

SEVENTH FDITION

# Windows Internals Part 1

System architecture, processes, threads, memory management, and more

😧 Professional

Pavel Yosifovich Alex Ionescu Mark E. Russinovich David A. Solomon

From the Library of Octavian Mustafa



# Windows Internals Seventh Edition

Part 1

System architecture, processes, threads, memory management, and more

Pavel Yosifovich, Alex Ionescu, Mark E. Russinovich, and David A. Solomon

From the Library of Octavian Mustafa

To my family–my wife Idit and our children Danielle, Amit, and Yoav– thank you for your patience and encouragement during this demanding work. Pavel Yosifovich

To my parents, who guided and inspired me to follow my dreams, and to my family, who stood by me all those countless nights.

Alex Ionescu

To our parents, who guided and inspired us to follow our dreams. Mark E. Russinovich and David A. Solomon

#### PUBLISHED BY

Microsoft Press A division of Microsoft Corporation One Microsoft Way Redmond, Washington 98052-6399

Copyright © 2017 by Pavel Yosifovich, Alex Ionescu, Mark E. Russinovich and David A. Solomon All rights reserved. No part of the contents of this book may be reproduced or transmitted in any form or by any means without the written permission of the publisher.

Library of Congress Control Number: 2014951935

ISBN: 978-0-7356-8418-8

Printed and bound in the United States of America.

**First Printing** 

Microsoft Press books are available through booksellers and distributors worldwide. If you need support related to this book, email Microsoft Press Support at *mspinput@microsoft.com*. Please tell us what you think of this book at *https://aka.ms/tellpress*.

This book is provided "as-is" and expresses the author's views and opinions. The views, opinions and information expressed in this book, including URL and other Internet website references, may change without notice.

Some examples depicted herein are provided for illustration only and are fictitious. No real association or connection is intended or should be inferred.

Microsoft and the trademarks listed at *https://www.microsoft.com* on the "Trademarks" webpage are trademarks of the Microsoft group of companies. All other marks are property of their respective owners.

Acquisitions Editor: Devon Musgrave Editorial Production: Polymath Publishing Technical Reviewer: Christophe Nasarre Layout Services: Shawn Morningstar Indexing Services: Kelly Talbot Editing Services Proofreading Services: Corina Lebegioara Cover: Twist Creative • Seattle

# Contents

	Introduction	ci
Chapter 1	Concepts and tools	1
-	Windows operating system versions.	1
	Windows 10 and future Windows versions	3
	Windows 10 and OneCore	3
	Foundation concepts and terms	4
	Windows API	4
	Services, functions, and routines.	7
	Processes.	8
	Threads	8
	Jobs2	0
	Virtual memory	1
	Kernel mode vs. user mode2	3
	Hypervisor	7
	Firmware	9
	Terminal Services and multiple sessions2	9
	Objects and handles3	0
	Security	1
	Registry	2
	Unicode3	3
	Digging into Windows internals3	5
	Performance Monitor and Resource Monitor	6
	Kernel debugging3	8
	Windows Software Development Kit4	3
	Windows Driver Kit4	3
	Sysinternals tools4	4
	Conclusion	4
Chapter 2	System architecture 4	5
	Requirements and design goals4	5
	Operating system model4	6

Requirements and design goals	
Operating system model	46
Architecture overview	
Portability	50
Symmetric multiprocessing	51
Scalability	53
Differences between client and server versions	54
Checked build	57
Virtualization-based security architecture overview	59

Key system components61
Environment subsystems and subsystem DLLs.
Other subsystems
Executive
Kernel
Hardware abstraction layer79
Device drivers
System processes
Conclusion

#### Chapter 3 Processes and jobs

#### CreateProcess\* functions arguments......102 Creating other kinds of processes......104 Protected Process Light (PPL). ..... 115 Trustlet structure 123 Isolated user-mode services......127 Stage 4: Creating the initial thread and its stack and context ......144 Stage 6: Starting execution of the initial thread......148 Stage 7: Performing process initialization in the context

Early process initialization157DLL name resolution and redirection160Loaded module database164Import parsing168Post-import process initialization170

	SwitchBack
	API Sets
Jobs	
	Job limits
	Working with a job178
	Nested jobs
	Windows containers (server silos)
Conclu	usion

# Chapter 4 Threads

#### 193

lineaus	195
Creating threads	
Thread internals	
Data structures	
Birth of a thread	
Examining thread activity	
Limitations on protected process threads	
Thread scheduling	
Overview of Windows scheduling	
Priority levels	
Thread states	
Dispatcher database	
Quantum	
Priority boosts	
Context switching	
Scheduling scenarios	
Idle threads	
Thread suspension	
(Deep) freeze	
Thread selection	
Multiprocessor systems	
Thread selection on multiprocessor systems	
Processor selection	
Heterogeneous scheduling (big.LITTLE)	
Group-based scheduling	
Dynamic fair share scheduling	
CPU rate limits	
Dynamic processor addition and replacement	
Worker factories (thread pools)	
Worker factory creation	
Conclusion	

#### Chapter 5 Memory management Introduction to the memory manage

ntroduction to the memory manager	
Memory manager components	
Large and small pages	

Examining memory usage	
Internal synchronization	
Services provided by the memory manager	
Page states and memory allocations	
Commit charge and commit limit	
Locking memory	
Allocation granularity	
Shared memory and mapped files	
Protecting memory	
Data Execution Prevention	
Copy-on-write	
Address Windowing Extensions	
Kernel-mode heaps (system memory pools)	
Pool sizes.	
Monitoring pool usage	
Look-aside lists	
Heap manager	
Process heaps	
Heap types	
The NT heap	
Heap synchronization.	
The low-fragmentation heap	
The segment heap	
Heap security features	
Heap debugging features	
Pageheap	
Fault-tolerant heap	
Virtual address space layouts	
x86 address space layouts	
x86 system address space layout	
x86 session space	
System page table entries	
ARM address space layout	
64-bit address space layout	
x64 virtual addressing limitations.	
Dynamic system virtual address space management	
System virtual address space quotas	
User address space layout	
Address translation	
x86 virtual address translation	
Translation look-aside buffer	
x64 virtual address translation	
ARM virtual address translation	
Page fault handling	
Invalid PTEs	
Prototype PTEs	
- ·	

In-paging I/O	
Collided page faults	
Clustered page faults	
Page files.	
Commit charge and the system commit limit	394
Commit charge and page file size	
Stacks	
User stacks	
Kernel stacks	
DPC stack	
Virtual address descriptors.	
Process VADs	
Rotate VADs.	
NUMA	
Section objects	
Working sets	
Demand paging	
Logical prefetcher and ReadyBoot	
Placement policy	
Working set management.	
Balance set manager and swapper	
System working sets	
Memory notification events	423
Page frame number database	
Page list dynamics	428
Page priority	436
Modified page writer and mapped page writer	438
PFN data structures	. 440
Page file reservation	. 443
Physical memory limits	. 446
Windows client memory limits	447
Memory compression	
Compression illustration	450
Compression architecture	
Memory partitions	
Memory combining	
The search phase	
The classification phase	
The page combining phase	
From private to shared PTE	
Combined pages release	
Memory enclaves	
Memory enclave initializations	
Enclave construction	
Loading data into an enclave	4/1

Initializing an enclave	
Proactive memory management (SuperFetch)	
Components	
Tracing and logging	
Scenarios	
Page priority and rebalancing	
Robust performance	
ReadyBoost	
ReadyDrive	
Process reflection	
Conclusion	

# Chapter 6 I/O system

I/O system components	
The I/O manager	
Typical I/O processing	
Interrupt Request Levels and Deferred Procedure Calls	
Interrupt Request Levels	
Deferred Procedure Calls	
Device drivers	
Types of device drivers	
Structure of a driver	
Driver objects and device objects	
Opening devices	
I/O processing	
Types of I/O	511
I/O request packets	513
I/O request to a single-layered hardware-based driver	
I/O requests to layered drivers	533
Thread-agnostic I/O	536
I/O cancellation	537
I/O completion ports	
I/O prioritization	
Container notifications	
Driver Verifier	
I/O-related verification options	
Memory-related verification options	
The Plug and Play manager	
Level of Plug and Play support	
Device enumeration	561
Device stacks	
Driver support for Plug and Play	
Plug-and-play driver installation	
General driver loading and installation	
Driver loading	
Driver installation	

The	e Windows Driver Foundation	
	Kernel-Mode Driver Framework	
	User-Mode Driver Framework	
The	e power manager	
	Connected Standby and Modern Standby	
	Power manager operation	
	Driver power operation	
	Driver and application control of device power	
	Power management framework	600
	Power availability requests	602
Со	nclusion	

# Chapter 7 Security

Security	605
Security ratings.	
Trusted Computer System Evaluation Criteria	605
The Common Criteria	607
Security system components	
Virtualization-based security	611
Credential Guard	
Device Guard	
Protecting objects	619
Access checks.	
Security identifiers	
Virtual service accounts	
Security descriptors and access control	650
Dynamic Access Control.	
The AuthZ API	
Conditional ACEs	
Account rights and privileges	
Account rights	
Privileges.	670
Super privileges	
Access tokens of processes and threads.	
Security auditing	
Object access auditing	679
Global audit policy	
Advanced Audit Policy settings	
AppContainers	
Overview of UWP apps	
The AppContainer	
Logon	
Winlogon initialization	
User logon steps	
Assured authentication	
Windows Biometric Framework	
Windows Hello	

User Account Control and virtualization	722
File system and registry virtualization	722
Elevation	
Exploit mitigations	735
Process-mitigation policies	735
Control Flow Integrity	740
Security assertions	752
Application Identification	756
AppLocker	
Software Restriction Policies	
Kernel Patch Protection	
PatchGuard	
HyperGuard	
Conclusion	

Index

# Introduction

Windows Internals, Seventh Edition is intended for advanced computer professionals (developers, security researchers, and system administrators) who want to understand how the core components of the Microsoft Windows 10 and Windows Server 2016 operating systems work internally. With this knowledge, developers can better comprehend the rationale behind design choices when building applications specific to the Windows platform. Such knowledge can also help developers debug complex problems. System administrators can benefit from this information as well, because understanding how the operating system works "under the hood" facilitates an understanding of the performance behavior of the system and makes troubleshooting system problems much easier when things go wrong. Security researchers can figure out how software applications and the operating system can misbehave and be misused, causing undesirable behavior, while also understanding the mitigations and security features modern Windows offers against such scenarios. After reading this book, you should have a better understanding of how Windows works and why it behaves as it does.

### History of the book

This is the seventh edition of a book that was originally called *Inside Windows NT* (Microsoft Press, 1992), written by Helen Custer (prior to the initial release of Microsoft Windows NT 3.1). *Inside Windows NT* was the first book ever published about Windows NT and provided key insights into the architecture and design of the system. *Inside Windows NT, Second Edition* (Microsoft Press, 1998) was written by David Solomon. It updated the original book to cover Windows NT 4.0 and had a greatly increased level of technical depth.

Inside Windows 2000, Third Edition (Microsoft Press, 2000) was authored by David Solomon and Mark Russinovich. It added many new topics, such as startup and shutdown, service internals, registry internals, file-system drivers, and networking. It also covered kernel changes in Windows 2000, such as the Windows Driver Model (WDM), Plug and Play, power management, Windows Management Instrumentation (WMI), encryption, the job object, and Terminal Services. *Windows Internals, Fourth Edition* (Microsoft Press, 2004) was the Windows XP and Windows Server 2003 update and added more content focused on helping IT professionals make use of their knowledge of Windows internals, such as using key tools from Windows SysInternals and analyzing crash dumps.

*Windows Internals, Fifth Edition* (Microsoft Press, 2009) was the update for Windows Vista and Windows Server 2008. It saw Mark Russinovich move on to a full-time job at

Microsoft (where he is now the Azure CTO) and the addition of a new co-author, Alex lonescu. New content included the image loader, user-mode debugging facility, Advanced Local Procedure Call (ALPC), and Hyper-V. The next release, *Windows Internals, Sixth Edition* (Microsoft Press, 2012), was fully updated to address the many kernel changes in Windows 7 and Windows Server 2008 R2, with many new hands-on experiments to reflect changes in the tools as well.

#### Seventh edition changes

Since this book's last update, Windows has gone through several releases, coming up to Windows 10 and Windows Server 2016. Windows 10 itself, being the current going-forward name for Windows, has had several releases since its initial release to manufac-turing (RTM). Each is labeled with a four-digit version number indicating the year and month of release, such as *Windows 10, version 1703*, which was completed in March 2017. This implies that Windows has gone through at least six versions since Windows 7 (at the time of this writing).

Starting with Windows 8, Microsoft began a process of OS convergence, which is beneficial from a development perspective as well as for the Windows engineering team. Windows 8 and Windows Phone 8 had converged kernels, with modern app convergence arriving in Windows 8.1 and Windows Phone 8.1. The convergence story was complete with Windows 10, which runs on desktops/laptops, servers, XBOX One, phones (Windows Mobile 10), HoloLens, and various Internet of Things (IoT) devices.

With this grand unification completed, the time was right for a new edition of the series, which could now finally catch up with almost half a decade of changes in what will now be a more stable kernel architecture going forward. As such, this latest book covers aspects of Windows from Windows 8 to Windows 10, version 1703. Additionally, this edition welcomes Pavel Yosifovich as its new co-author.

### **Hands-on experiments**

Even without access to the Windows source code, you can glean much about Windows internals from the kernel debugger, tools from SysInternals, and the tools developed specifically for this book. When a tool can be used to expose or demonstrate some aspect of the internal behavior of Windows, the steps for trying the tool yourself are listed in special "EXPERIMENT" sections. These appear throughout the book, and we encourage you to try them as you're reading. Seeing visible proof of how Windows works internally will make much more of an impression on you than just reading about it will.

## **Topics not covered**

Windows is a large and complex operating system. This book doesn't cover everything relevant to Windows internals but instead focuses on the base system components. For example, this book doesn't describe COM+, the Windows distributed object-oriented programming infrastructure, or the Microsoft .NET Framework, the foundation of managed code applications. Because this is an "internals" book and not a user, programming, or system-administration book, it doesn't describe how to use, program, or configure Windows.

# A warning and a caveat

Because this book describes undocumented behavior of the internal architecture and the operation of the Windows operating system (such as internal kernel structures and functions), this content is subject to change between releases.

By "subject to change," we don't necessarily mean that details described in this book will change between releases, but you can't count on them not changing. Any software that uses these undocumented interfaces, or insider knowledge about the operating system, might not work on future releases of Windows. Even worse, software that runs in kernel mode (such as device drivers) and uses these undocumented interfaces might experience a system crash when running on a newer release of Windows, resulting in potential loss of data to users of such software.

In short, you should never use any internal Windows functionality, registry key, behavior, API, or other undocumented detail mentioned in this book during the development of any kind of software designed for end-user systems, or for any other purpose other than research and documentation. Always check with the Microsoft Software Development Network (MSDN) for official documentation on a particular topic first.

# Assumptions about you

The book assumes the reader is comfortable with working on Windows at a power-user level, and has a basic understanding of operating system and hardware concepts, such as CPU registers, memory, processes, and threads. Basic understanding of functions, pointers, and similar C programming language constructs is beneficial in some sections.

# **Organization of this book**

The book is divided into two parts (as was the sixth edition), the first of which you're holding in your hands.

- Chapter 1, "Concepts and tools," provides a general introduction to Windows internals concepts and introduces the main tools used throughout the book. It's critical to read this chapter first, as it provides the necessary background needed for the rest of the book.
- Chapter 2, "System architecture," shows the architecture and main components that comprise Windows and discusses them in some depth. Several of these concepts are dealt with in greater detail in subsequent chapters.
- Chapter 3, "Processes and jobs," details how processes are implemented in Windows and the various ways of manipulating them. Jobs are also discussed as a means for controlling a set of processes and enabling Windows Container support.
- Chapter 4, "Threads," details how threads are managed, scheduled, and otherwise manipulated in Windows.
- Chapter 5, "Memory management," shows how the memory manager uses physical and virtual memory, and the various ways that memory can be manipulated and used by processes and drivers alike.
- Chapter 6, "I/O system," shows how the I/O system in Windows works and integrates with device drivers to provide the mechanisms for working with I/O peripherals.
- Chapter 7, "Security," details the various security mechanisms built into Windows, including mitigations that are now part of the system to combat exploits.

# Conventions

The following conventions are used in this book:

- Boldface type is used to indicate text that you type as well as interface items that you are instructed to click or buttons that you are instructed to press.
- Italic type is used to indicate new terms.
- Code elements appear in a monospaced font.

- The first letters of the names of dialog boxes and dialog box elements are capitalized—for example, the Save As dialog box.
- Keyboard shortcuts are indicated by a plus sign (+) separating the key names.
   For example, Ctrl+Alt+Delete mean that you press Ctrl, Alt, and Delete keys at the same time.

### About the companion content

We have included companion content to enrich your learning experience. The companion content for this book can be downloaded from the following page:

#### https://aka.ms/winint7ed/downloads

We have also placed the source code for the tools written specifically for this book at *https://github.com/zodiacon/windowsinternals.* 

### **Acknowledgments**

First, thanks to Pavel Yosifovich for joining us on this project. His involvement with the book was crucial to its release, and his many nights spent studying Windows details and writing about six releases' worth of changes is the reason this book exists.

This book wouldn't contain the depth of technical detail or the level of accuracy it has without the review, input, and support of key members of the Microsoft Windows development team and other experts at Microsoft. Therefore, we want to thank the following people, who provided technical review and/or input to the book, or were simply a source of support and help to the authors: Akila Srinivasan, Alessandro Pilotti, Andrea Allievi, Andy Luhrs, Arun Kishan, Ben Hillis, Bill Messmer, Chris Kleynhans, Deepu Thomas, Eugene Bak, Jason Shirk, Jeremiah Cox, Joe Bialek, John Lambert, John Lento, Jon Berry, Kai Hsu, Ken Johnson, Landy Wang, Logan Gabriel, Luke Kim, Matt Miller, Matthew Woolman, Mehmet Iyigun, Michelle Bergeron, Minsang Kim, Mohamed Mansour, Nate Warfield, Neeraj Singh, Nick Judge, Pavel Lebedynskiy, Rich Turner, Saruhan Karademir, Simon Pope, Stephen Finnigan, and Stephen Hufnagel.

We would like to again thank Ilfak Guilfanov of Hex-Rays (*http://www.hex-rays.com*) for the IDA Pro Advanced and Hex-Rays licenses they granted to Alex Ionescu more than a decade ago, so that he could speed up his reverse engineering of the Windows kernel, and for the continued support and development of decompiler features which make writing such a book possible without source code access.

Finally, the authors would like to thank the great staff at Microsoft Press who have been behind turning this book into a reality. Devon Musgrave served his last tour as our acquisitions editor, while Kate Shoup oversaw the title as its project editor. Shawn Morningstar, Kelly Talbot, and Corina Lebegioara also contributed to the quality of this book.

#### **Errata and book support**

We have made every effort to ensure the accuracy of this book and its companion content. Any errors that have been reported since this book was published are listed on our Microsoft Press site at:

https://aka.ms/winint7ed/errata

If you find an error that is not already listed, you can report it to us through the same page.

If you need additional support, email Microsoft Press Book Support at *mspinput@ microsoft.com*.

Please note that product support for Microsoft software is not offered through the addresses above.

#### We want to hear from you

At Microsoft Press, your satisfaction is our top priority and your feedback our most valuable asset. Please tell us what you think of this book at:

https://aka.ms/tellpress

The survey is short, and we read every one of your comments and ideas. Thanks in advance for your input!

### Stay in touch

Let's keep the conversation going! We're on Twitter: @MicrosoftPress.

# **Concepts and tools**

n this chapter, we'll introduce the key Microsoft Windows operating system (OS) concepts and terms we'll be using throughout this book, such as the Windows API, processes, threads, virtual memory, kernel mode and user mode, objects, handles, security, and the registry. We'll also introduce the tools that you can use to explore Windows internals, such as the kernel debugger, the Performance Monitor, and key tools from Windows Sysinternals (*http://www.microsoft.com/technet/sysinternals*). In addition, we'll explain how you can use the Windows Driver Kit (WDK) and the Windows Software Development Kit (SDK) as resources for finding further information on Windows internals.

Be sure that you understand everything in this chapter; the remainder of the book is written assuming that you do.

# Windows operating system versions

This book covers the most recent version of the Microsoft Windows client and server operating systems: Windows 10 (32-bit on x86 and ARM, and 64-bit version on x64) and Windows Server 2016 (which exists as 64-bit version only). Unless specifically stated, the text applies to all versions. As background information, Table 1-1 lists the Windows product names, their internal version number, and their release date.

Product Name	Internal Version Number	Release Date
Windows NT 3.1	3.1	July 1993
Windows NT 3.5	3.5	September 1994
Windows NT 3.51	3.51	May 1995
Windows NT 4.0	4.0	July 1996
Windows 2000	5.0	December 1999
Windows XP	5.1	August 2001
Windows Server 2003	5.2	March 2003

Product Name	Internal Version Number	Release Date (continued)
Windows Server 2003 R2	5.2	December 2005
Windows Vista	6.0	January 2007
Windows Server 2008	6.0 (Service Pack 1)	March 2008
Windows 7	6.1	October 2009
Windows Server 2008 R2	6.1	October 2009
Windows 8	6.2	October 2012
Windows Server 2012	6.2	October 2012
Windows 8.1	6.3	October 2013
Windows Server 2012 R2	6.3	October 2013
Windows 10	10.0 (build 10240)	July 2015
Windows 10 version 1511	10.0 (build 10586)	November 2015
Windows 10 version 1607 (Anniversary Update)	10.0 (build 14393)	July 2016
Windows Server 2016	10.0 (build 14393)	October 2016

The version numbers seem to have strayed from a well-defined path starting with Windows 7. Its version number was 6.1 and not 7. Because of the popularity of Windows XP, when Windows Vista bumped the version number to 6.0, some applications failed to detect the correct (OS) because developers checked major numbers greater than or equal to 5 and minor numbers greater than or equal to 1, which was not the case with Windows Vista. Having learned the lesson, Microsoft chose to leave the major version number as 6 and the minor version number as 2 (greater than 1) to minimize such incompatibilities. However, with Windows 10, the version number has been updated to 10.0.

**Note** Starting with Windows 8, the GetVersionEx Windows API function returns the OS version number as 6.2 (Windows 8) by default, regardless of the actual OS. (The function is also declared as deprecated.) This is done to minimize compatibility issues but also as an indicator that checking for the OS version is not the best approach in most cases. This is because some components can be installed out of band, without coinciding with an official Windows release. Still, if you need the actual OS version, you can obtain it indirectly by using the VerifyVersionInfo function or the newer version helper APIs, such as IsWindows80rGreater, IsWindows8Point10rGreater, IsWindows100rGreater, IsWindowsServer, and similar. Also, OS compatibility can be indicated in the executable's manifest, which changes the results of this function. (See the section "Image Loader," in Chapter 3 for details.)

You can view the Windows version information using the ver command-line tool or graphically by running winver. Here's a screenshot of winver on Windows 10 Enterprise version 1511:

	Windows 10
© 2015 Microsof The Windows 10 protected by tra	vs 3 Buid 10586.218) 1 Corporation. Al rights reserved. Enterprise operating system and its user interface are demark and other pending or existing intelectual property ed States and other countries/regions.
This product is lic Terms to: Microsoft Corp	ensed under the <u>Microsoft Software License</u> p.

The graphic also shows the Windows build number (10586.218 in this example), which could be useful for Windows Insiders (those who registered for getting earlier previews of Windows). It's also helpful for managing security updates because it shows which patch level is installed.

# Windows 10 and future Windows versions

With Windows 10, Microsoft declared it will update Windows at a faster cadence than before. There will not be an official "Windows 11"; instead, Windows Update (or another enterprise servicing model) will update the existing Windows 10 to a new version. At the time of writing, two such updates have occurred, in November 2015 (also known as *version 1511*, referring to the year and month of servicing) and July 2016 (*version 1607*, also known by the marketing name of *Anniversary Update*).

**Note** Internally, Microsoft still builds Windows versions in waves. For example, the initial Windows 10 release was code-named *Threshold 1*, while the November 2015 update was called *Threshold 2*. The next three phases of update are called *Redstone 1* (version 1607) to be followed by *Redstone 2* and *Redstone 3*.

# Windows 10 and OneCore

Over the years, several flavors of Windows have evolved. Apart from mainstream Windows running on PCs, there is the Xbox 360 game console that runs a fork off Windows 2000. Windows Phone 7 runs a variant based on Windows CE (Microsoft's real-time OS). Maintaining and extending all these code bases is clearly difficult. Therefore, Microsoft decided to converge the kernels and base platform support binaries into one. This started with Windows 8 and Windows Phone 8 having a shared kernel (and Windows 8.1 and Windows Phone 8.1 having a converged Windows Runtime API). With Windows 10, the convergence is complete; this shared platform is known as OneCore, and it runs on PCs, phones, the Xbox One game console, the HoloLens and Internet of Things (IoT) devices such as the Raspberry Pi 2.

Clearly, all these device form factors are very different from one another. Some features simply don't exist on some devices. For example, supporting a mouse or a physical keyboard on a HoloLens device may not make sense, so you can't expect those parts to be present on the Windows 10 version for such a device. But the kernel, drivers, and base platform binaries are essentially the same (with registry-based and/or policy-based settings where they make sense for performance or other reasons). You'll see one such policy example in the section "API Sets" in Chapter 3, "Processes and jobs."

This book delves into the internals of the OneCore kernel, on whatever device it's running on. The experiments in the book, however, are targeted to a desktop machine with a mouse and keyboard mostly for convenience, as it's not easy (and sometimes officially impossible) to perform the experiments on other devices such as phones or the Xbox One.

## Foundation concepts and terms

The following sections introduce the most fundamental concepts in Windows, which are essential to understanding the topics discussed in the rest of the book. Many of the concepts such as processes, threads, and virtual memory are discussed at length in subsequent chapters.

### Windows API

The Windows application programming interface (API) is the user-mode system programming interface to the Windows OS family. Prior to the introduction of 64-bit versions of Windows, the programming interface to the 32-bit versions of the Windows OS was called the *Win32 API* to distinguish it from the original 16-bit Windows API, which was the programming interface to the original 16-bit versions of Windows. In this book, the term *Windows API* refers to both the 32-bit and 64-bit programming interfaces to Windows.

+	+	÷	÷	~
				٦
	-	-	-	
-			=	1
- 2		_	=	1
	-	-	-	1
				J

**Note** We sometimes use the term *Win32 API* in lieu of *Windows API*. Either way, it still refers to the 32-bit and 64-bit variants.

4	+	+	+	~
	_	_		
	_			

**Note** The Windows API is described in the Windows SDK documentation. (See the section "Windows Software Development Kit" later in this chapter.) This documentation is available free online at *https://developer.microsoft.com/en-us/windows/desktop/develop*. It is also included with all subscription levels to the Microsoft Developer Network (MSDN), Microsoft's support program for developers. An excellent description of how to program the Windows base API is in the book *Windows via C/C++, Fifth Edition* by Jeffrey Richter and Christophe Nasarre (Microsoft Press, 2007).

#### Windows API flavors

The Windows API originally consisted of C-style functions only. Today, thousands of such functions exist for developers to use. C was the natural choice at the time of the inception of Windows because it was the lowest common denominator (that is, it could be accessed from other languages as well) and was low level enough to expose OS services. The downside was the sheer number of functions coupled with the lack of naming consistency and logical groupings (for example, C++ namespaces). One outcome of these difficulties resulted in some newer APIs using a different API mechanism: the Component Object Model (COM).

COM was originally created to enable Microsoft Office applications to communicate and exchange data between documents (such as embedding an Excel chart inside a Word document or a PowerPoint presentation). This ability is called Object Linking and Embedding (OLE). OLE was originally implemented using an old Windows messaging mechanism called Dynamic Data Exchange (DDE). DDE was inherently limited, which is why a new way of communication was developed: COM. In fact, COM initially was called OLE 2, released to the public circa 1993.

COM is based on two foundational principles. First, clients communicate with objects (sometimes called COM server objects) through interfaces—well-defined contracts with a set of logically related methods grouped under the virtual table dispatch mechanism, which is also a common way for C++ compilers to implement virtual functions dispatch. This results in binary compatibility and removal of compiler name mangling issues. Consequently, it is possible to call these methods from many languages (and compilers), such as C, C++, Visual Basic, .NET languages, Delphi and others. The second principle is that component implementation is loaded dynamically rather than being statically linked to the client.

The term *COM server* typically refers to a Dynamic Link Library (DLL) or an executable (EXE) where the COM classes are implemented. COM has other important features related to security, cross-process marshalling, threading model, and more. A comprehensive treatment of COM is beyond the scope of this book; an excellent treatment of COM can be found in the book *Essential COM* by Don Box (Addison-Wesley, 1998).

**Note** Examples of APIs accessed through COM include DirectShow, Windows Media Foundation, DirectX, DirectComposition, Windows Imaging Component (WIC), and the Background Intelligent Transfer Service (BITS).

#### The Windows Runtime

Windows 8 introduced a new API and supporting runtime called the *Windows Runtime* (sometimes abbreviated *WinRT*, not to be confused with Windows RT, the discontinued ARM-based Windows OS version). The Windows Runtime consists of platform services aimed particularly at app developers for the so-called *Windows Apps* (formerly known as *Metro Apps, Modern Apps, Immersive Apps*, and *Windows Store Apps*). Windows Apps may target multiple device form factors, from small IoT devices to phones, tablets, laptops, desktops, and even devices such as the Xbox One and Microsoft HoloLens. From an API perspective, WinRT is built on top of COM, adding various extensions to the base COM infrastructure. For example, complete type metadata is available in WinRT (stored in WINMD files and based on the .NET metadata format) that extends a similar concept in COM known as type libraries. From an API design perspective, it's much more cohesive than classic Windows API functions, with namespace hierarchies, consistent naming, and programmatic patterns.

Windows Apps are subject to new rules, unlike the normal Windows applications (now called *Windows desktop applications* or *Classic Windows applications*). These rules are described in Chapter 9, "Management mechanisms," in Part 2.

The relationship between the various APIs and applications is not straightforward. Desktop apps can use a subset of the WinRT APIs. Conversely, Windows Apps can use a subset of Win32 and COM APIs. Refer to the MSDN documentation for the details of which APIs are available from each application platform. Note, however, that at the basic binary level, the WinRT API is still based on top of the legacy Windows binaries and APIs, even though the availability of certain APIs may not be documented or supported. It is not a new "native" API for the system, much like .NET still leverages the traditional Windows API.

Applications written in C++, C# (or other .NET languages), and JavaScript can consume WinRT APIs easily thanks to language projections developed for these platforms. For C++, Microsoft created a non-standard extension known as C++/CX that makes it simpler to consume WinRT types. The normal COM interop layer for .NET (with some supporting run-time extensions) allows any .NET language to consume WinRT APIs naturally and simply just as if it were pure .NET. For JavaScript developers, an extension called *WinJS* was developed for accessing WinRT, although JavaScript developers must still use HTML to build their app's user interface.

**Note** Even though HTML can be used in Windows Apps, it's still a local client app and not a web application retrieved from a web server.

#### The .NET Framework

The .NET Framework is part of Windows. Table 1-2 shows the .NET Framework version installed as part of a given Windows version. However, a later version of the .NET Framework can be installed on older OS versions.

Windows Version	.NET Framework Version
Windows 8	4.5
Windows 8.1	4.5.1
Windows 10	4.6
Windows 10 version 1511	4.6.1
Windows 10 version 1607	4.6.2

TABLE 1-2	Default .NET Framework installations on Windows
-----------	---

The .NET Framework consists of two major components:

- The Common Language Runtime (CLR) This is the run-time engine for .NET and includes a Just In Time (JIT) compiler that translates Common Intermediate Language (CIL) instructions to the underlying hardware CPU machine language, a garbage collector, type verification, code access security, and more. It's implemented as a COM in-process server (DLL) and uses various facilities provided by the Windows API.
- The .NET Framework Class Library (FCL) This is a large collection of types that implement functionality typically needed by client and server applications, such as user interface services, networking, database access, and much more.

By offering these features and others, including new high-level programming languages (C#, Visual Basic, F#) and supporting tools, the .NET Framework improves developer productivity and increases safety and reliability within applications that target it. Figure 1-1 shows the relationship between the .NET Framework and the OS.




FIGURE 1-1 This diagram shows the relationship between .NET and the Windows OS.

# Services, functions, and routines

Several terms in the Windows user and programming documentation have different meanings in different contexts. For example, the word *service* can refer to a callable routine in the OS, a device driver, or a server process. The following list describes what certain terms mean in this book:

- Windows API functions These are documented, callable subroutines in the Windows API.
   Examples include CreateProcess, CreateFile, and GetMessage.
- Native system services (or system calls) These are the undocumented, underlying services in the OS that are callable from user mode. For example, NtCreateUserProcess is the internal system service the Windows CreateProcess function calls to create a new process.
- Kernel support functions (or routines) These are the subroutines inside the Windows OS that can be called only from kernel mode (defined later in this chapter). For example, ExAllocatePoolWithTag is the routine that device drivers call to allocate memory from the Windows system heaps (called *pools*).

- Windows services These are processes started by the Windows service control manager. For example, the Task Scheduler service runs in a user-mode process that supports the schtasks command (which is similar to the UNIX commands at and cron). (Note that although the registry defines Windows device drivers as "services," they are not referred to as such in this book.)
- Dynamic link libraries (DLLs) These are callable subroutines linked together as a binary file that can be dynamically loaded by applications that use the subroutines. Examples include Msvcrt.dll (the C run-time library) and Kernel32.dll (one of the Windows API subsystem libraries). Windows user-mode components and applications use DLLs extensively. The advantage DLLs provide over static libraries is that applications can share DLLs, and Windows ensures that there is only one in-memory copy of a DLL's code among the applications that are referencing it. Note that library .NET assemblies are compiled as DLLs but without any unmanaged exported subroutines. Instead, the CLR parses compiled metadata to access the corresponding types and members.

#### Processes

Although programs and processes appear similar on the surface, they are fundamentally different. A *program* is a static sequence of instructions, whereas a *process* is a container for a set of resources used when executing the instance of the program. At the highest level of abstraction, a Windows process comprises the following:

- A private virtual address space This is a set of virtual memory addresses that the process can use.
- An executable program This defines initial code and data and is mapped into the process's virtual address space.
- A list of open handles These map to various system resources such as semaphores, synchronization objects, and files that are accessible to all threads in the process.
- A security context This is an access token that identifies the user, security groups, privileges, attributes, claims, capabilities, User Account Control (UAC) virtualization state, session, and limited user account state associated with the process, as well as the AppContainer identifier and its related sandboxing information.
- A process ID This is a unique identifier, which is internally part of an identifier called a *client ID*.
- At least one thread of execution Although an "empty" process is possible, it is (mostly) not useful.

A number of tools for viewing (and modifying) processes and process information are available. The following experiments illustrate the various views of process information you can obtain with some of these tools. While many of these tools are included within Windows itself, and within the Debugging Tools for Windows and the Windows SDK, others are stand-alone tools from Sysinternals. Many of these tools show overlapping subsets of the core process and thread information, sometimes identified by different names.

Probably the most widely used tool to examine process activity is Task Manager. (Because there is no such thing as a "task" in the Windows kernel, the name of this tool, Task Manager, is a bit odd.) The following experiment shows some of the basic features of Task Manager.

#### **EXPERIMENT:** Viewing process information with Task Manager

The built-in Windows Task Manager provides a quick list of the processes on the system. You can start Task Manager in one of four ways:

- Press Ctrl+Shift+Esc.
- Right-click the taskbar and click Start Task Manager.
- Press Ctrl+Alt+Delete and click the Start Task Manager button.
- Start the executable Taskmgr.exe.

The first time Task Manager shows up, it's in "less details" mode, where only processes that have a visible top-level window are shown, as in the following screenshot:

igger		
	—	

There's little you can do from this window, so click the **More Details** expander button to show Task Manager's full view. The Processes tab should be selected by default:

File Options View					
Processes Performance Applicationy Star	tup Users	Details Servi	CRI		
Rame	2% CPU	36% Memory	0% plak	0% Network	
Apps (7)					í
Micresoft Edge	0%	12.1 MB	D MB/s	0 Mbps	
Microsoft Outlook (32 bit)	0%	35.4 MB	0.1MB/s	0 Mbps	
> 🚺 Microsoft Word (32 bit)	1.4%	96.5 MB	0 MB/s	© Mitiges	
) all Paint	0%	10.1 MB	© MB/S	0 Mbps	
) 👘 Tesk Manager	0.3%	10.3 MB	0 MB/s	@ Mbps	
> 🐂 Windows Explorer (7)	0%	39.1 MB	D MB/S	Ø Mbps	
🗧 📓 Windows GUI symbolic debugger	0%	12.4 MB	O MB/S	© Mitps	
Background processes (49)					
Application Frame Host	0%	E3 MB	D MB/s	0 Mbps	
) 💽 Borgour Service	0%	1.0 MB	D MB/s	0 Mbps	
🐨 Browser_Broker	0%	23 MB	0 MB/S	0 Mbps	
Coloulator	0%	0.3 MB	@ MB/s	© Mbps	

The Processes tab shows the list of processes, with four columns: CPU, Memory, Disk, and Network. You can show more columns by right-clicking the header. Available columns are Process (Image) Name, Process ID, Type, Status, Publisher, and Command Line. Some processes can be further expanded, showing top-level visible windows created by the process. To get even more process details, click the **Details** tab. Or, right-click a process and choose **Go to Details** to switch to the Details tab and select that specific process.

ſ	-	-	-	-	7
L	2	-	_	=	
L	Э	=	=	=	
L	3	-	-	=	
L					

**Note** The Windows 7 Task Manager's Processes tab is roughly equivalent to Windows 8+ Task Manager's Details tab. The Windows 7 Task Manager's Applications tab shows top-level visible Windows and not processes per se. This information is now contained in the Processes tab of the new Windows 8+ Task Manager.

1 Task Manager						-		<
Eile Options View Processes Performance	App histor	y Startup	Users	Details	Services			
Name	PID S	itatus	Use	r name	CPU	Memory (p	Description	
ApplicationFrameHo	1100 F	Running	Ad	ministr	00	3.000 K	Application	
audiodg.exe		tunning	LO	CAL SE.	00	3.696 K	Windows A.	
CSISS.exe		Running	SYS	TEM	00	512 K	Client Serve	
CSISS.exe		Running	SYS	TEM	00	244 K	Client Serve	
CSTSS.exe		Running	SYS	TEM	00	472 K	Client Serve	
dwm.exe	904 F	Running	DWM-1		00	1,644 K	Desktop Wi	
dwm.exe	2680 1	Running	DW	M-2	00	18,936 K	Desktop Wi	
explorer.exe	1320 #	Running	Adi	ministr	00	24,352 K	Windows Ex	
LogonUI.exe	896 #	Running	SYS	TEM	00	4,748 K	Windows Lo	
Isass.exe	612 8	Running	SYS	TEM	00	3,744 K	Local Securi	
MBAMAgent.exe	1944 8	Running	SYS	TEM	00	712 K	MBAMAgent	
MpCmdRun.exe	1356 8	tunning	NE	TWORK	00	1,328 K	Microsoft M	
MsMpEng.exe	2100 F	Running	SYS	TEM	00	48,800 K	Antimalwar	
MSOIDSVC.EXE	2020 8	Running	SYSTEM		00	1,360 K	Microsoft®	
MSOIDSVCM.EXE	2520 F	Running	SYSTEM		00	264 K Microsoft		
mspaint.exe	5464 F	Running	Ad	ministr	00	22,276 K	Paint	
NisSrv.exe	3028 8	Running	LOCAL SE		00	92 K	Microsoft N	
OfficeClickToRun.exe	1712 8	Running	SYSTEM		00	14,444 K	Microsoft O	
ConeDrive.exe	4224 8	Running	Administr		00	1,756 K	Microsoft O	
rdpclip.exe	352 F	Running	Administr		00	1,312 K	RDP Clipbo	
RuntimeBroker.exe	4016 F	Running	Ad	ministr	00	6,436 K	Runtime Br	
SearchFilterHost.exe	5064 F	Running	SYS	TEM	00	1,124 K	Microsoft W	
Q. Searchindever.eve	1780 8	Lunning	SVS	TEM	00	9 R20 K	Microsoft W	

The Details tab shows processes as well, but does so in a more compact manner. It does not show windows created by processes, and provides more diverse information columns.

Notice that processes are identified by the name of the image of which they are an instance. Unlike some objects in Windows, processes can't be given global names. To display additional details, right-click the header row and click **Select Columns**. A list of columns appears as shown here:

Package name	^
PID PID	
Status	
User name	
Session ID	
CPU CPU	
CPU time	
Cyde	
Working set (memory)	
Peak working set (memory)	
Working set delta (memory)	~

Some key columns are as follows:

- Threads The Threads column shows the number of threads in each process. This number should normally be at least one, as there's no direct way of creating a process with no threads (and such a process is pretty useless anyway). If a process shows zero threads, it usually means the process can't be deleted for some reason—probably because of some buggy driver code.
- Handles The Handles column shows the number of handles to kernel objects opened by threads running within the process. (This is described later in this chapter and in detail in Chapter 8 in Part 2.)
- **Status** The Status column is a little bit tricky. For processes that don't have any user interface, Running should be the normal case, although the threads may all be waiting for something, such as a kernel object being signaled or some I/O operation to complete. The other option for such processes is Suspended, and this happens if all the threads in the process are in a suspended state. This is unlikely to occur by the process itself, but can be achieved programmatically by calling the undocumented NtSuspendProcess native API on the process, typically through a tool (for example, Process Explorer, described later, has such an option). For processes that create a user interface, the Running status value means that the UI is responsive. In other words, the thread that created the window(s) is waiting for UI input (technically, the message queue associated with the thread). The Suspended state is possible just like in the non-UI case, but for Windows Apps (those hosting the Windows Runtime), Suspended normally occurs when the app loses its foreground status by being minimized by the user. Such processes are suspended after 5 seconds so that they don't consume any CPU or networking resources, thus allowing the new foreground app to get all machine resources. This is especially important for battery-powered devices, such as tablets and phones. This and other related mechanisms are described more fully in Chapter 9 in Part 2. The third possible value for Status is Not Responding. This can happen if a thread within the process that created the user interface has not checked its message queue for UI-related activity for at least 5 seconds. The process (actually the thread that owns the window) may be busy doing some CPU-intensive work or waiting on something else entirely (such as an I/O operation to complete). Either way, the UI freezes up, and Windows indicates that by fading the window(s) in question and appending "(Not Responding)" to its title.

Each process also points to its parent (which may be, but is not always, its creator process). If the parent no longer exists, this information is not updated. Therefore, it is possible for a process to refer to a nonexistent parent. This is not a problem, because nothing relies on this information being kept current. In the case of the Process Explorer tool, the start time of the parent process is taken into account to avoid attaching a child process based on a reused process ID. The following experiment illustrates this behavior.

**Note** Why would a parent process not be the same as its creator? In certain cases, some processes that appear to be created by a certain user application might involve the help of a broker, or helper, process, which is responsible for calling the process creation API. In such cases, it would be confusing (and sometimes incorrect, if handle or address space inheritance is needed) to display the broker process as the creator, and a "re-parenting" is done. You'll learn about one such example in Chapter 7, "Security."

#### **EXPERIMENT:** Viewing the process tree

One unique attribute about a process that most tools don't display is the parent or creator process ID. You can retrieve this value with the Performance Monitor (or programmatically) by querying the Creating Process ID. You can use the Tlist.exe tool in the Debugging Tools for Windows to show the process tree by using the /t switch. Here's an example of output from tlist/t:

```
System Process (0)
System (4)
 smss.exe (360)
csrss.exe (460)
wininit.exe (524)
  services.exe (648)
    svchost.exe (736)
      unsecapp.exe (2516)
      WmiPrvSE.exe (2860)
      WmiPrvSE.exe (2512)
      RuntimeBroker.exe (3104)
      SkypeHost.exe (2776)
      ShellExperienceHost.exe (3760) Windows Shell Experience Host
      ApplicationFrameHost.exe (2848) OleMainThreadWndName
      SearchUI.exe (3504) Cortana
      WmiPrvSE.exe (1576)
      TiWorker.exe (6032)
      wuapihost.exe (5088)
    svchost.exe (788)
    svchost.exe (932)
    svchost.exe (960)
    svchost.exe (976)
    svchost.exe (68)
    svchost.exe (380)
    VSSVC.exe (1124)
    svchost.exe (1176)
      sihost.exe (3664)
      taskhostw.exe (3032) Task Host Window
    svchost.exe (1212)
    svchost.exe (1636)
    spoolsv.exe (1644)
    svchost.exe (1936)
    OfficeClickToRun.exe (1324)
    MSOIDSVC.EXE (1256)
```

```
MSOIDSVCM.EXE (2264)
    MBAMAgent.exe (2072)
    MsMpEng.exe (2116)
    SearchIndexer.exe (1000)
      SearchProtocolHost.exe (824)
    svchost.exe (3328)
    svchost.exe (3428)
    svchost.exe (4400)
    svchost.exe (4360)
    svchost.exe (3720)
    TrustedInstaller.exe (6052)
  lsass.exe (664)
csrss.exe (536)
winlogon.exe (600)
  dwm.exe (1100) DWM Notification Window
explorer.exe (3148) Program Manager
  OneDrive.exe (4448)
  cmd.exe (5992) C:\windows\system32\cmd.exe - tlist /t
    conhost.exe (3120) CicMarshalWnd
    tlist.exe (5888)
SystemSettingsAdminFlows.exe (4608)
```

The list indents each process to show its parent/child relationship. Processes whose parents aren't alive are left-justified (as explorer.exe is in the preceding example) because even if a grandparent process exists, there's no way to find that relationship. Windows maintains only the creator process ID, not a link back to the creator of the creator, and so forth.

The number in parentheses is the process ID, and the text that follows some processes is the title of a window that was created by that process.

To prove that Windows doesn't keep track of more than just the parent process ID, follow these steps:

- 1. Press WinKey+R, type cmd, and press Enter to open a Command Prompt window.
- 2. Type title Parent to change the title of the window to Parent.
- 3. Type start cmd to open a second Command Prompt window.
- 4. Type title Child in the second Command Prompt window.
- 5. Type mspaint in the second Command Prompt window to start Microsoft Paint.
- 6. Go back to the second Command Prompt window and type exit. Notice that Paint remains.
- 7. Press Ctrl+Shift+Esc to open Task Manager.
- 8. If Task Manager is in "less details" mode, click More Details.
- 9. Click the Processes tab.

**10.** Find the Windows Command Processor app and expand its node. You should see the title *Parent*, as in the following screenshot:

Processes Performance Apphistory Sta	rtup Users	Details Servi	ces		
Name	6% CPU	32% Memory	2% Disk	0% Network	
Microsoft Edge	0%	22.3 MB	0 MB/s	0 Mbps	1
> 03 Microsoft Outlook (32 bit)	0%	153.6 MB	0.1 MB/s	0 Mbps	
> 📑 Microsoft Word (32 bit)	0.1%	100.2 MB	0 MB/s	0 Mbps	
> 🚮 Paint	0%	9.5 MB	0 MB/s	0 Mbps	
C Settings	0%	15.2 MB	0 MB/s	0 Mbps	
> 🧐 Skype (32 bit)	0%	91.5 MB	0 MB/s	0 Mbps	
> 👰 Task Manager	0.2%	14.8 MB	0 MB/s	0 Mbps	
<ul> <li>Windows Command Processor</li> <li>Parent</li> </ul>	0%	0.4 MB	0 MB/s	0 Mbps	
🗧 🎆 Windows Explorer (3)	0.1%	523.7 MB	0 MB/s	0 Mbps	
Background processes (123)					
> 👩 64-bit Synaptics Pointing Enhan	0%	0.8 MB	0 MB/s	0 Mbps	
💋 Adobe® Flash® Player Utility	0%	2.4 MB	0 MB/s	0 Mbps	
🗿 Alarms & Clock	0%	0.5 MB	0 MB/s	0 Mbps	
	200			1000	1

- 11. Right-click the Windows Command Processor entry and select Go to details.
- 12. Right-click this cmd.exe process and select End Process Tree.
- 13. Click End Process Tree in the Task Manager confirmation dialog box.

The first Command Prompt window will disappear, but you should still see the Paint window because it was the grandchild of the command prompt process you terminated. Because the intermediate process (the parent of Paint) was terminated, there was no link between the parent and the grandchild.

Process Explorer, from Sysinternals, shows more details about processes and threads than any other available tool, which is why you will see it used in a number of experiments throughout the book. Following are some of the unique things that Process Explorer shows or enables:

- A process security token, such as lists of groups and privileges and the virtualization state
- Highlighting to show changes in the process, thread, DLLs, and handles list
- A list of services inside service-hosting processes, including the display name and description

- A list of additional process attributes, such as mitigation policies and their process protection level
- Processes that are part of a job and job details
- Processes hosting .NET applications and .NET-specific details, such as the list of AppDomains, loaded assemblies, and CLR performance counters
- Processes that host the Windows Runtime (immersive processes)
- The start time for processes and threads
- A complete list of memory-mapped files (not just DLLs)
- The ability to suspend a process or a thread
- The ability to kill an individual thread
- Easy identification of which processes were consuming the most CPU over a period of time

C	+	+	+	+	h
	ŝ	=	=	Ξ	
	Ē				
t					J

**Note** The Performance Monitor can display process CPU utilization for a given set of processes, but it won't automatically show processes created after the performance-monitoring session has started. Only a manual trace in binary output format can do that.

Process Explorer also provides easy access to information in one place, such as the following:

- A process tree, with the ability to collapse parts of the tree
- Open handles in a process, including unnamed handles
- A list of DLLs (and memory-mapped files) in a process
- Thread activity within a process
- User-mode and kernel-mode thread stacks, including the mapping of addresses to names using the Dbghelp.dll that comes with the Debugging Tools for Windows
  - More accurate CPU percentage using the thread cycle count—an even better representation of precise CPU activity, as explained in Chapter 4, "Threads."
  - Integrity level
- Memory manager details such as peak commit charge and kernel memory paged and nonpaged pool limits (other tools show only current size)

An introductory experiment using Process Explorer follows.

#### **EXPERIMENT:** Viewing process details with Process Explorer

Download the latest version of Process Explorer from Sysinternals and run it. You can run it with standard user privileges. Alternatively, right-click the executable and select **Run as Administrator** to run it with administrator privileges. Running with admin privileges causes Process Explorer to install a driver that provides more features. The following description works the same regardless of how you launch Process Explorer.

The first time you run Process Explorer, you should configure symbols. If you don't, you will receive a message that symbols are not currently configured when you double-click a process and click the **Threads** tab. If properly configured, Process Explorer can access symbol information to display the symbolic name of the thread start function as well as functions on a thread's call stack. This is useful for identifying what threads are doing within a process. To access symbols, you must have Debugging Tools for Windows installed (described later in this chapter). Then click **Options**, choose **Configure Symbols**, and fill in the path to Dbghelp.dll in the Debugging Tools folder and a valid symbol path. For example, on a 64-bit system, this configuration is correct if Debugging Tools for Windows are installed in the default location as part of the WDK:

addresses and thread stack location dialog.	solve function names when displaying threa ns on the Threads tab of a process' propertie	ed start es
If you do not require that information	n you do not need to configure symbols.	
Dbghelp.dl path:		
	A de de de la California de la California de	1.00
C:\Program Files (x86)\Windows K	its (10/Liebuggers x64 (abgneip.ali	104
C:\Program Files (x86)\Windows K Symbols path:	its (10 \Debuggers \to+ \abgrep.all	100

In the preceding example, the on-demand symbol server is used to access symbols and a copy of the symbol files is stored on the local machine in the C:\symbols folder. (You can replace this folder with some other folder, such as on another drive, if free disk space is an issue.) For more information on configuring the use of the symbol server, see *https://msdn.microsoft.com/en-us/library/windows/desktop/ee416588.aspx*.

**Tip** You can configure the Microsoft symbol server by setting an environment variable named \_NT\_SYMBOL\_PATH to the value shown in the preceding graphic. Various tools look for this variable automatically, such as Process Explorer, the debuggers that are part of the Debugging Tools for Windows, Visual Studio, and others. This will help you avoid having to configure each tool separately.

When Process Explorer starts, it shows the process tree view by default. You can expand the lower pane to display open handles or mapped DLLs and memory-mapped files. (These are explored in Chapter 5, "Memory management," and in Chapter 8 in Part 2.) It also shows a tooltip for the process command line and path, which becomes visible when you hover the mouse over

the process name. For some types of processes, the tooltip also shows extra information, including the following:

- The services inside a service-hosting process (for example, Svchost.exe)
- The tasks inside a task-hosting process (for example, TaskHostw.exe)
- The target of a Rundll32.exe process, used for Control Panel items and other features
- The COM class information when being hosted inside a Dllhost.exe process (also known as the default COM+ surrogate)
- Provider information for Windows Management Instrumentation (WMI) host processes such as WMIPrvSE.exe (see Chapter 8 in Part 2 for more on WMI)
- Package information for Windows Apps processes (processes hosting the Windows Runtime, briefly discussed in "The Windows Runtime" section earlier in this chapter)

k	📔 🗏 🗄 🦉 🚰 🗡 🗛 🚱	-			-					A	N
Pro	cess	PID	CPU	9	tart Time	Private Bytes	Working Set	Description			
	services.exe	920	< 0.01	13:31:170	8-Feb-16	7,248 K	12,916 K	Services and Co	introller app		
1	SettingSyncHost.exe	7720		13:51:54 0	8-Feb-16	2,448 K	5,408 K	Host Process for	r Setting Synchronia	ation	
Ĩ	ShellExperienceHost.exe	2496	Suspended	13:51:04 0	8-Feb-16	35,100 K		Windows Shell 8			
1	shost exe	5380		13:49:41 0		8,296 K	25,912 K	Shell Infrastructu	ure Host		
. [	SkypeHost.exe	9836	Suspended	14:14:25 0	8-Feb-16	5,988 K	1,312 K	Microsoft Skype			
3	slack.exe	10960	< 0.01	13:53:06 0	8-Feb-16	49,148 K	79,972 K	Slack			
	slack exe	6956		13:53:19 0	8-Feb-16	24,900 K	36,336 K	Slack			
	slack exe	11184		13:53:19 0		3,848 K	11,764 K				
	slack.exe	6028		13:53:28 0	8-Feb-16	60,180 K	76,900 K	Slack			
1	slack exe	10800	< 0.01	13:53:41 0	8-Feb-16	91,828 K	116,100 K	Slack			
ĺ	smas.exe	524		13:30:47 0	8-Feb-16	368 K	1,220 K	Windows Sessio	n Manager		
ShippingTool.exe		21836		14:52:49 0	9-Feb-16	3,756 K		Snipping Tool			
		24100		12:11:14 0	9-Feb-16	4,952 K	16,552 K	Print driver host	for applications		
		1348		13:31:42 0	8-Feb-16	13.024 K		Spooler Sub Syst			
1	sqlwriter exe	2440		13:31:48 0	8-Feb-16	1,764 K	8,232 K	SQL Server VSS	Writer + 64 Bit		
E	StandardCollector,Service.exe	15176		15:56:40 0	8-Feb-16	6,456 K	13,976 K	Microsoft (R) Vis	ual Studio Standard	Collector	
	sublime_text exe	11284		16:02:34 0	8-Feb-16	20,908 K	35.840 K	Sublime Text			
a f	svchost.exe	104	< 0.01	13:31:22 0	8-Feb-16	9,848 K	23,996 K	Host Process for	Windows Services	ŝ.	
Ī	svchost.exe	616	0.01	13:31:22 0	8-Feb-16	9,460 K	15,740 K	Host Process for	Windows Services	i.	
1	svchost exe	1032	0.15	13:31:25 0	8-Feb-16	226,756 K	264,820 K	Host Process for	Windows Services	ŝ.	
ī	svchost exe	1080	0.07	13:31:26 0	8-Feb-16	97,484 K	109,668 K	Host Process for	Windows Services		
i	svchost.exe	1320	< 0.01	13:31:31 0	8-Feb-16	226.108 K	244,060 K	Host Process for	Windows Services	i i	
Î	svchost.exe	1352		13:31:31 0	8-Feb-16	14,764 K	37,568 K	Host Process for	Windows Services		
ī	svchost exe	1528	< 0.01	13:31:35 0	8-Feb-16	3.288 K	10,972 K	Host Process for	Windows Services		
i	sychost exe Command Line				-Feb-16	25.848 K	38,772 K	Host Process for	Windows Services	i.	
ī	svchost exe C:\WINDOWS\system32\svchost.	exe -k Loc	alSenrice (Loo	alService)	Feb-16	20.452 K	36.296 K	Host Process for	Windows Services	i.	
Ī	sychost exe Services:				-Feb-16	3,992 K	10,744 K	Host Process for	Windows Services	8	
COM+ Event System [EventSystem] Diagnostic Service Host [Wd/ServiceHost]			-Feb-16	4,508 K	11,548 K	Host Process for	Windows Services	ř.			
ľ	svchost exe Network Store Interface Service In	Lhagnostic Service Host (WdiServiceHost)				125,988 K	9,840 K	Host Process for	Windows Services		
Ī	sychost exe Network List Service [netprofm]	90 no se			-Feb-16	7,876 K	21,528 K	Host Process for	Windows Services	R.	
î	svchost.exe Secure Socket Tunneling Protocol Windows Font Cache Service (Fond		istpSvc]		Feb-16	11,320 K	38.284 K	Host Process for	Windows Services		

Here are a few steps to walk you through some basic capabilities of Process Explorer:

- Notice that processes hosting services are highlighted by default in pink. Your own processes are highlighted in blue. You can change these colors by opening the drop-down menu, selecting **Options**, and choosing **Configure Colors**.
- 2. Hover your mouse pointer over the image name for processes. Notice that the tooltip displays the full path. As noted, certain types of processes have additional details in the tooltip.

- 3. In the Process Image tab, click View, choose Select Columns, and add the image path.
- **4.** Click the **Process** column head to sort the processes. Notice that the tree view disappears. (You can either display the tree view or sort by any of the columns shown.) Click the **Process** column head again to sort from Z to A. Click it a third time to return the display to tree view.
- 5. Open the **View** menu and deselect **Show Processes from All Users** to show only your processes.
- 6. Click the **Options** menu, choose **Difference Highlight Duration**, and change the value to 3 seconds. Then launch a new process (anything). Notice that the new process is highlighted in green for 3 seconds. Exit this new process, and notice that the process is highlighted in red for 3 seconds before disappearing from the display. This can be useful for seeing processes being created and exiting on your system.
- **7.** Double-click a process and explore the various tabs available from the process properties display. (These will be referenced in various experiments throughout the book where the information being shown is being explained.)

# Threads

A *thread* is an entity within a process that Windows schedules for execution. Without it, the process's program can't run. A thread includes the following essential components:

- The contents of a set of CPU registers representing the state of the processor
- Two stacks—one for the thread to use while executing in kernel mode and one for executing in user mode
- A private storage area called *thread-local storage* (*TLS*) for use by subsystems, run-time libraries, and DLLs
- A unique identifier called a *thread ID* (part of an internal structure called a *client ID*; process IDs and thread IDs are generated out of the same namespace, so they never overlap)

In addition, threads sometimes have their own security context, or token, which is often used by multithreaded server applications that impersonate the security context of the clients that they serve.

The volatile and non-volatile registers as well as a private storage area are called the thread's context. Because this information is different for each machine architecture that Windows runs on, this structure, by necessity, is architecture-specific. The Windows GetThreadContext function provides access to this architecture specific information (called the CONTEXT block). Additionally, each thread has its own stack as well (pointed to by a stack register part of the thread's context).

Because switching execution from one thread to another involves the kernel scheduler, it can be an expensive operation, especially if two threads are often switching between each other. Windows implements two mechanisms to reduce this cost: *fibers* and *user-mode scheduling (UMS)*.

**Note** The threads of a 32-bit application running on a 64-bit version of Windows will contain both 32-bit and 64-bit contexts, which Wow64 (Windows on Windows 64-bit) will use to switch the application from running in 32-bit to 64-bit mode when required. These threads will have two user stacks and two CONTEXT blocks, and the usual Windows API functions will return the 64-bit context instead. The Wow64GetThreadContext function, however, will return the 32-bit context. See Chapter 8 in Part 2 for more information on Wow64.

#### **Fibers**

Fibers allow an application to schedule its own threads of execution rather than rely on the prioritybased scheduling mechanism built into Windows. Fibers are often called *lightweight threads*. In terms of scheduling, they're invisible to the kernel because they're implemented in user mode in Kernel32. dll. To use fibers, you first make a call to the Windows ConvertThreadToFiber function. This function converts the thread to a running fiber. Afterward, the newly converted fiber can create additional fibers via the CreateFiber function. (Each fiber can have its own set of fibers.) Unlike a thread, however, a fiber doesn't begin execution until it's manually selected through a call to the SwitchToFiber function. The new fiber runs until it exits or until it calls SwitchToFiber, again selecting another fiber to run. For more information, see the Windows SDK documentation on fiber functions.

**Note** Using fibers is usually not a good idea. This is because they are invisible to the kernel. They also have issues such as sharing thread local storage (TLS) because several fibers can be running on the same thread. Although fiber local storage (FLS) exists, this does not solve all sharing issues, and I/O-bound fibers will perform poorly regardless. Additionally, fibers cannot run concurrently on more than one processor, and are limited to cooperative multi-tasking only. In most scenarios, it's best to let the Windows kernel handle scheduling by using the appropriate threads for the task at hand.

#### User-mode scheduling threads

User-mode scheduling (UMS) threads, which are available only on 64-bit versions of Windows, provide the same basic advantages as fibers—and only a few of the disadvantages. UMS threads have their own kernel thread state and are therefore visible to the kernel, which allows multiple UMS threads to issue blocking system calls and share and contend on resources. Or, when two or more UMS threads need to perform work in user mode, they can periodically switch execution contexts (by yielding from one thread to another) in user mode rather than involving the scheduler. From the kernel's perspective, the same kernel thread is still running and nothing has changed. When a UMS thread performs an operation that requires entering the kernel (such as a system call), it switches to its dedicated kernel-mode thread (called a *directed context switch*). While concurrent UMS threads still cannot run on multiple processors, they do follow a pre-emptible model that's not solely cooperative.

Although threads have their own execution context, every thread within a process shares the process's virtual address space (in addition to the rest of the resources belonging to the process), meaning that all the threads in a process have full read-write access to the process virtual address space. Threads cannot accidentally reference the address space of another process, however, unless the other process makes available part of its private address space as a shared memory section (called a *file mapping object* in the Windows API) or unless one process has the right to open another process to use crossprocess memory functions, such as ReadProcessMemory and WriteProcessMemory (which a process that's running with the same user account, and not inside of an AppContainer or other type of sandbox, can get by default unless the target process has certain protections).

In addition to a private address space and one or more threads, each process has a security context and a list of open handles to kernel objects such as files, shared memory sections, or one of the synchronization objects such as mutexes, events, or semaphores, as illustrated in Figure 1-2.




FIGURE 1-2 A process and its resources.

Each process's security context is stored in an object called an *access token*. The process access token contains the security identification and credentials for the process. By default, threads don't have their own access token, but they can obtain one, thus allowing individual threads to impersonate the security context of another process—including processes on a remote Windows system—without affecting other threads in the process. (See Chapter 7 for more details on process and thread security.)

The *virtual address descriptors (VADs*) are data structures that the memory manager uses to keep track of the virtual addresses the process is using. These data structures are described in more depth in Chapter 5.

#### Jobs

Windows provides an extension to the process model called a *job*. A job object's main function is to allow the management and manipulation of groups of processes as a unit. A job object allows control of certain attributes and provides limits for the process or processes associated with the job. It also records basic accounting information for all processes associated with the job and for all processes that were associated with the job but have since terminated. In some ways, the job object compensates for the lack of a structured process tree in Windows—yet in many ways it is more powerful than a UNIX-style process tree.

ſ	+	+	+	+	
L	Ξ	_		=	
L	ŝ				
L	-	_	_	-	

**Note** Process Explorer can show processes managed by a job using a default color of brown, but it's not enabled by default (to enable it, open the **Options** menu and choose **Configure Colors**). Furthermore, the property pages of such a process have an additional Job tab that gives information on the job object itself.

You'll find out much more about the internal structure of processes and jobs in Chapter 3 and about threads and thread-scheduling algorithms in Chapter 4.

## Virtual memory

Windows implements a virtual memory system based on a flat (linear) address space that provides each process with the illusion of having its own large, private address space. Virtual memory provides a logical view of memory that might not correspond to its physical layout. At run time, the memory manager—with assistance from hardware—translates, or *maps*, the virtual addresses into physical addresses, where the data is actually stored. By controlling the protection and mapping, the OS can ensure that individual processes don't bump into each other or overwrite OS data.

Because most systems have much less physical memory than the total virtual memory in use by the running processes, the memory manager transfers, or *pages*, some of the memory contents to disk. Paging data to disk frees physical memory so that it can be used for other processes or for the OS itself. When a thread accesses a virtual address that has been paged to disk, the virtual memory manager loads the information back into memory from disk.

Applications don't have to be altered in any way to take advantage of paging because hardware support enables the memory manager to page without the knowledge or assistance of processes or threads. Figure 1-3 shows two processes using virtual memory in which parts are mapped to physical memory (RAM) while other parts are paged to disk. Notice that contiguous virtual memory chunks may be mapped to non-contiguous chunks in physical memory. These chunks are called pages, and have a default size of 4 KB.





FIGURE 1-3 Mapping virtual memory to physical memory with paging.

The size of the virtual address space varies for each hardware platform. On 32-bit x86 systems, the total virtual address space has a theoretical maximum of 4 GB. By default, Windows allocates the lower half of this address space (addresses 0x00000000 through 0x7FFFFFF) to processes for their unique private storage and the upper half (addresses 0x80000000 through 0xFFFFFFF) for its own protected OS memory utilization. The mappings of the lower half change to reflect the virtual address space of the currently executing process, but (most of) the mappings of the upper half always consist of the OS's virtual memory. Windows supports boot-time options, such as the increaseuserva qualifier in the Boot Configuration Database (described in Chapter 5), that give processes running specially marked programs the ability to use up to 3 GB of private address space, leaving 1 GB for the OS. (By "specially marked," we mean the large address space-aware flag must be set in the header of the executable image.) This option allows applications such as database servers to keep larger portions of a database in the process address space, thus reducing the need to map subset views of the database on disk and therefore increasing overall performance (although in certain cases, the loss of 1 GB for the system can cause more pronounced system-wide performance losses). Figure 1-4 shows the two typical virtual address space layouts supported by 32-bit Windows. (The increaseuserva option allows executable images marked with the large address space-aware flag to use anywhere from 2 to 3 GB.)





Although 3 GB is better than 2 GB, it's still not enough virtual address space to map very large (multi-gigabyte) databases. To address this need on 32-bit systems, Windows provides a mechanism called *Address Windowing Extensions (AWE*), which allows a 32-bit application to allocate up to 64 GB of physical memory and then map views, or windows, into its 2 GB virtual address space. Although using AWE puts the burden of managing the mapping of virtual to physical memory on the developer, it does address the need to directly access more physical memory than can be mapped at any one time in a 32-bit process address space.

64-bit Windows provides a much larger address space for processes: 128 TB on Windows 8.1, Server 2012 R2, and later systems. Figure 1-5 shows a simplified view of the 64-bit system address space layouts. (For a detailed description, see Chapter 5.) Note that these sizes do not represent the architectural limits for these platforms. Sixty-four bits of address space is 2 to the 64th power, or 16 EB (where 1 EB

equals 1,024 PB, or 1,048,576 TB), but current 64-bit hardware limits this to smaller values. The unmapped region marked in figure 1-5 is much larger than the possible mapped region (about one million times larger on Windows 8), which means the images are (by far) not to scale.




FIGURE 1-5 Address space layouts for 64-bit Windows.

Details of the implementation of the memory manager, including how address translation works and how Windows manages physical memory, are described in Chapter 5.

## Kernel mode vs. user mode

To protect user applications from accessing and/or modifying critical OS data, Windows uses two processor access modes (even if the processor on which Windows is running supports more than two): *user mode* and *kernel mode*. User application code runs in user mode, whereas OS code (such as system services and device drivers) runs in kernel mode. Kernel mode refers to a mode of execution in a processor that grants access to all system memory and all CPU instructions. Some processors differentiate between such modes by using the term *code privilege level* or *ring level*, while others use terms such as *supervisor mode* and *application mode*. Regardless of what it's called, by providing the operating system kernel with a higher privilege level than user mode applications have, the processor provides a necessary foundation for OS designers to ensure that a misbehaving application can't disrupt the stability of the system as a whole.

**Note** The architectures of the x86 and x64 processors define four privilege levels (or rings) to protect system code and data from being overwritten either inadvertently or maliciously by code of lesser privilege. Windows uses privilege level 0 (or ring 0) for kernel mode and privilege level 3 (or ring 3) for user mode. The reason Windows uses only two levels is that some hardware architectures, such as ARM today and MIPS/Alpha in the past, implemented only two privilege levels. Settling on the lowest minimum bar allowed for a more efficient and portable architecture, especially as the other x86/x64 ring levels do not provide the same guarantees as the ring 0/ring 3 divide.

Although each Windows process has its own private memory space, the kernel-mode OS and device-driver code share a single virtual address space. Each page in virtual memory is tagged to indicate what access mode the processor must be in to read and/or write the page. Pages in system space can be accessed only from kernel mode, whereas all pages in the user address space are accessible from user mode and kernel mode. Read-only pages (such as those that contain static data) are not writable from any mode. Additionally, on processors that support no-execute memory protection, Windows marks pages containing data as non-executable, thus preventing inadvertent or malicious code execution in data areas (if this feature, Data Execution Prevention [DEP] is enabled).

Windows doesn't provide any protection for private read/write system memory being used by components running in kernel mode. In other words, once in kernel mode, OS and device-driver code has complete access to system-space memory and can bypass Windows security to access objects. Because the bulk of the Windows OS code runs in kernel mode, it is vital that components that run in kernel mode be carefully designed and tested to ensure they don't violate system security or cause system instability.

This lack of protection also emphasizes the need to remain vigilant when loading a third-party device driver, especially if it's unsigned, because once in kernel mode, the driver has complete access to all OS data. This risk was one of the reasons behind the driver-signing mechanism introduced in Windows 2000, which warns (and, if configured as such, blocks) the user if an attempt is made to add an unsigned plug-and-play driver (see Chapter 6, "I/O system," for more information on driver signing), but does not affect other types of drivers. Also, a mechanism called Driver Verifier helps device-driver writers find bugs, such as buffer overruns or memory leaks, that can cause security or reliability issues. (Chapter 6 also discusses Driver Verifier.)

On 64-bit and ARM versions of Windows 8.1, the kernel-mode code-signing (KMCS) policy dictates that all device drivers (not just plug-and-play) must be signed with a cryptographic key assigned by one of the major code certification authorities. The user cannot explicitly force the installation of an unsigned driver, even as an administrator. As a one-time exception, however, this restriction can be disabled manually. This allows drivers to be self-signed and tested, places a watermark on the desktop wallpaper labeled "Test Mode," and disables certain digital rights management (DRM) features.

On Windows 10, Microsoft implemented an even more significant change, which was enforced starting one year after release as part of the July Anniversary Update (version 1607). As of that time, all new Windows 10 drivers must be signed by only two of the accepted certification authorities with a SHA-2 Extended Validation (EV) Hardware certificate instead of the regular file-based SHA-1 certificate and its 20 authorities. Once EV-signed, the hardware driver must be submitted to Microsoft through the System Device (SysDev) portal for attestation signing, which will see the driver receive a Microsoft signature. As such, the kernel will sign only Microsoft-signed Windows 10 drivers with no exemptions except the aforementioned Test Mode. Drivers signature for the release date of Windows 10 (July 2015) can continue to load with their regular signature for the time being.

With Windows Server 2016, the operating system takes its strongest stance yet. On top of the aforementioned EV requirements, mere attestation signing is insufficient. For a Windows 10 driver to load on a server system, it must pass through stringent Windows Hardware Quality Labs (WHQL) certification as part of the Hardware Compatibility Kit (HCK) and be submitted for formal evaluation. Only WHQL-signed drivers which provide certain compatibility, security, performance, and stability assurances to system administrators —will be allowed to load on such systems. All in all, the reduction of third-party drivers that are allowed to load in kernel mode memory should result in significant stability and security improvements.

Certain vendors, platforms, and even enterprise configurations of Windows can have any number of these signing policies customized, such as through the Device Guard technology, which we'll briefly describe in the upcoming "Hypervisor" section, and later in Chapter 7. As such, an enterprise might require WHQL signatures even on Windows 10 client systems, or might request the omission of this requirement on a Windows Server 2016 system.

As you'll see in Chapter 2, "System architecture," user applications switch from user mode to kernel mode when they make a system service call. For example, a Windows ReadFile function eventually needs to call the internal Windows routine that actually handles reading data from a file. That routine, because it accesses internal system data structures, must run in kernel mode. The use of a special processor instruction triggers the transition from user mode to kernel mode and causes the processor to enter the system service dispatching code in the kernel. This in turn calls the appropriate internal function in Ntoskrnl.exe or Win32k.sys. Before returning control to the user thread, the processor mode is switched back to user mode. In this way, the OS protects itself and its data from perusal and modification by user processes.

**Note** A transition from user mode to kernel mode (and back) does not affect thread scheduling *per se*. A mode transition is *not* a context switch. Further details on system service dispatching are included in Chapter 2.

Thus, it's normal for a user thread to spend part of its time executing in user mode and part in kernel mode. In fact, because the bulk of the graphics and windowing system also runs in kernel mode, graphics-intensive applications spend more of their time in kernel mode than in user mode. An easy way to test this is to run a graphics-intensive application such as Microsoft Paint and watch the time split between user mode and kernel mode using one of the performance counters listed in Table 1-3. More advanced applications can use newer technologies such as Direct2D and DirectComposition, which perform bulk computations in user mode and send only the raw surface data to the kernel. This reduces the time spent transitioning between user and kernel modes.

Object: Counter	Function
Processor: % Privileged Time	Percentage of time that an individual CPU (or all CPUs) has run in kernel mode during a specified interval
Processor: % User Time	Percentage of time that an individual CPU (or all CPUs) has run in user mode during a specified interval
Process: % Privileged Time	Percentage of time that the threads in a process have run in kernel mode during a specified interval
Process: % User Time	Percentage of time that the threads in a process have run in user mode during a speci- fied interval
Thread: % Privileged Time	Percentage of time that a thread has run in kernel mode during a specified interval
Thread: % User Time	Percentage of time that a thread has run in user mode during a specified interval


#### TABLE 1-3 Mode-related performance counters

\_

#### EXPERIMENT: Kernel mode vs. user mode

You can use the Performance Monitor to see how much time your system spends executing in kernel mode versus in user mode. Follow these steps:

- 1. Open the **Start** menu and type **Run Performance Monitor** (it should be suggested before you finish typing) to run Performance Monitor.
- 2. Select the **Performance Monitor** node under Performance/Monitoring Tools in the tree on the left side.
- **3.** To delete the default counter showing the total CPU time, click the **Delete** button on the toolbar or press the **Delete** key on the keyboard.
- 4. Click the Add (+) button on the toolbar.
- 5. Expand the **Processor** counter section, click the **% Privileged Time** counter, and, while holding down the **Ctrl** key, click the **% User Time** counter.
- 6. Click Add, and then click OK.
- **7.** Open a command prompt and type **dir \\%computername%\c\$ /s** to run a directory scan of your C drive.



8. When you're finished, close the tool.

You can also quickly see this by using Task Manager. Just click the **Performance** tab, rightclick the CPU graph, and select **Show Kernel Times**. The CPU usage bar will show kernel-mode CPU time usage in a darker shade of light blue.

To see how the Performance Monitor itself uses kernel time and user time, run it again, but add the individual process counters % User Time and % Privileged Time for every process in the system:

- If it's not already running, run the Performance Monitor again. (If it is already running, start with a blank display by right-clicking in the graph area and selecting **Remove All Counters**.)
- 2. Click the Add button on the toolbar.
- 3. In the available counters area, expand the **Process** section.
- 4. Select the % Privileged Time and % User Time counters.
- 5. Select a few processes in the Instance box (such as mmc, csrss, and Idle).
- 6. Click Add, and then click OK.
- 7. Move the mouse rapidly back and forth.
- 8. Press **Ctrl+H** to turn on highlighting mode. This highlights the currently selected counter in black.
- **9.** Scroll through the counters at the bottom of the display to identify the processes whose threads were running when you moved the mouse, and note whether they were running in user mode or kernel mode.

When you move the mouse, you should see the kernel-mode *and* user-mode time increase in the Instance column of the mmc process in the Process Monitor. This is because the process is executing application code in user mode and calling Windows functions that run in kernel mode. You'll also notice kernel-mode thread activity in a process named *csrss* when you move the mouse. This activity occurs because the Windows subsystem's kernel-mode raw input thread, which handles keyboard and mouse input, is attached to this process. (See Chapter 2 for more information about system threads and subsystems.) Finally, the Idle process that you see spending nearly 100 percent of its time in kernel mode isn't really a process—it's a fake process used to account for idle CPU cycles. As you can observe from the mode in which the threads in the Idle process run, when Windows has nothing to do, it does it in kernel mode.

## Hypervisor

Recent shifts in application and software models, such as the introduction of cloud-based services and the pervasiveness of IoT devices, have resulted in the need for operating systems and hardware vendors to figure out more efficient ways to virtualize other OS guests on the host hardware of the machine,

whether to allow for hosting multiple tenants on a server farm and run 100 isolated websites on a single server or to permit developers to test dozens of different OS varieties without buying dedicated hardware. The need for fast, efficient, and secure virtualization has driven new models of computing and reasoning about software. In fact, today, certain software—such as Docker, which is supported in Windows 10 and Server 2016—runs in containers, which provide fully isolated virtual machines solely designed for running a single application stack or framework, pushing the boundaries of a guest/host even further.

To provide such virtualization services, almost all modern solutions employ the use of a *hypervisor*, which is a specialized and highly privileged component that allows for the virtualization and isolation of all resources on the machine, from virtual to physical memory, to device interrupts, and even to PCI and USB devices. Hyper-V is an example of such a hypervisor, which powers the Hyper-V client functionality exposed in Windows 8.1 and later. Competing products such as Xen, KVM, VMware, and VirtualBox all implement their own hypervisors, each with their own strengths and weaknesses.

Due to its highly privileged nature, and because it has access even greater than the kernel itself, a hypervisor has a distinct advantage that goes beyond merely running multiple guest instances of other operating systems: It can protect and monitor a single host instance to offer assurances and guarantees beyond what the kernel provides. In Windows 10, Microsoft now leverages the Hyper-V hypervisor to provide a new set of services known as *virtualization-based security (VBS)*:

- Device Guard This provides Hypervisor Code Integrity (HVCI) for stronger code-signing guarantees over KMCS alone, and allows for the customization of the signature policy of the Windows OS, for both user-mode and kernel-mode code.
- Hyper Guard This protects key kernel-related and hypervisor-related data structures and code.
- Credential Guard This prevents unauthorized access to domain account credentials and secrets, combined with secure biometrics.
- **Application Guard** This provides an even stronger sandbox for the Microsoft Edge browser.
- Host Guardian and Shielded Fabric These leverage a virtual TPM (v-TPM) to protect a virtual machine from the infrastructure it's running on.

Additionally, the Hyper-V hypervisor enables certain key kernel mitigations against exploits and other attackers. The key advantage of all these technologies is that unlike previous kernel-based security improvements, they are not vulnerable to malicious or badly written drivers, regardless of whether they are signed or not. This makes them highly resilient against today's advanced adversaries. This is possible due to the hypervisor's implementation of Virtual Trust Levels (VTLs). Because the normal operating system and its components are in a less privileged mode (VTL 0), but these VBS technologies run at VTL 1 (a higher privilege), they cannot be affected even by kernel mode code. As such, code remains within the realm of the VTL 0 privilege space. In this way, you can think of VTLs as orthogonal to the processor's privilege levels: kernel and user mode exist *within* each VTL, and the hypervisor manages privileges *across* VTLs. Chapter 2 covers additional details on the hypervisor-assisted architecture, and Chapter 7 discusses these VBS security mechanisms in detail.

## Firmware

Windows components increasingly rely on the security of the operating system and its kernel, and the latter now relies on the protection of the hypervisor. A question arises of what can ensure these components are loaded securely and can authenticate their contents. This is typically the job of the boot loader, but it, too, needs the same level of authenticity checking, creating an increasingly complicated hierarchy of trust.

What, then, provides a root chain of trust that can guarantee an unencumbered boot process? In modern Windows 8 and later systems, this falls under the purview of the system firmware, which must be UEFI-based on certified systems. As part of the UEFI standard, which Windows dictates (UEFI 2.3.1b; see *http://www.uefi.org* for more information), a secure boot implementation with strong guarantees and requirements around the signature qualities of the boot-related software must be present. Through this verification process, Windows components are guaranteed to load securely from the very beginning of the boot process. In addition, technologies such as Trusted Platform Module (TPM) can measure the process to provide attestation (both local and remote). Through partnerships with the industry, Microsoft manages the whitelist and blacklist of the UEFI secure boot component in case of boot software errors or compromise, and Windows updates now include firmware updates as well. Although we won't talk about firmware again until Chapter 11, "Startup and shutdown," in Part 2, it's important now to state its significance in modern Windows architecture, through the guarantees its meant to provide.

## Terminal Services and multiple sessions

*Terminal Services* refers to the support in Windows for multiple interactive user sessions on a single system. With Windows Terminal Services, a remote user can establish a session on another machine, log in, and run applications on the server. The server transmits the graphical user interface (GUI) to the client (as well as other configurable resources such as audio and clipboard), and the client transmits the user's input back to the server. (Similar to the X Window System, Windows permits running individual applications on a server system with the display remoted to the client instead of remoting the entire desktop.)

The first session is considered the services session, or session zero, and contains system service hosting processes (explained in further detail in Chapter 9 in Part 2). The first login session at the physical console of the machine is session one, and additional sessions can be created through the use of the remote desktop connection program (Mstsc.exe) or through the use of fast user switching.

Windows client editions permit a single remote user to connect to the machine, but if someone is logged in at the console, the workstation is locked. That is, someone can be using the system either locally or remotely, but not at the same time. Windows editions that include Windows Media Center allow one interactive session and up to four Windows Media Center Extender sessions.

Windows server systems support two simultaneous remote connections. This is to facilitate remote management—for example, using management tools that require you to be logged in to the machine being managed. They also support more than two remote sessions if appropriately licensed and configured as a terminal server.

All Windows client editions support multiple sessions, created locally through a feature called *fast user switching*, that can be used one at a time. When a user chooses to disconnect their session instead of log off (for example, by clicking the **Start** button, clicking the current user, and choosing **Switch Account** from the submenu that appears or by holding down the **Windows** key, pressing **L**, and then clicking a different user in the bottom-left corner of the screen), the current session—that is, the processes running in that session and all the session-wide data structures that describe the session—remains active in the system and the system returns to the main logon screen (if it's not already there). If a new user logs in, a new session is created.

For applications that want to be aware of running in a terminal server session, there are a set of Windows APIs for programmatically detecting that as well as for controlling various aspects of Terminal Services. (See the Windows SDK and the Remote Desktop Services API for details.)

Chapter 2 briefly describes how sessions are created and contains some experiments showing how to view session information with various tools, including the kernel debugger. The "Object manager" section in Chapter 8 in Part 2 describes how the system namespace for objects is instantiated on a per-session basis and how applications that need to be aware of other instances of themselves on the same system can accomplish that. Finally, Chapter 5 covers how the memory manager sets up and manages session-wide data.

## **Objects and handles**

In the Windows OS, a *kernel object* is a single, run-time instance of a statically defined object type. An *object type* comprises a system-defined data type, functions that operate on instances of the data type, and a set of object attributes. If you write Windows applications, you might encounter process, thread, file, and event objects, to name just a few examples. These objects are based on lower-level objects that Windows creates and manages. In Windows, a *process* is an instance of the process object type, a *file* is an instance of the file object type, and so on.

An *object attribute* is a field of data in an object that partially defines the object's state. An object of type *process*, for example, would have attributes that include the process ID, a base scheduling priority, and a pointer to an access token object. *Object methods*, the means for manipulating objects, usually read or change object attributes. For example, the *open* method for a process would accept a process identifier as input and return a pointer to the object as output.

**Note** There is a parameter named ObjectAttributes that a caller supplies when creating an object using the kernel object manager APIs. That parameter shouldn't be confused with the more general meaning of the term as used in this book, however.

The most fundamental difference between an object and an ordinary data structure is that the internal structure of an object is opaque. You must call an object service to get data out of or put data into an object. You can't directly read or change data inside an object. This difference separates the underlying implementation of the object from code that merely uses it, a technique that allows object implementations to be changed easily over time.

Objects, through the help of a kernel component called the *object manager*, provide a convenient means for accomplishing the following four important OS tasks:

- Providing human-readable names for system resources
- Sharing resources and data among processes
- Protecting resources from unauthorized access
- Reference tracking, which allows the system to recognize when an object is no longer in use so that it can be automatically deallocated

Not all data structures in the Windows OS are objects. Only data that needs to be shared, protected, named, or made visible to user-mode programs (via system services) is placed in objects. Structures used by only one component of the OS to implement internal functions are not objects. Objects and handles (references to objects) are discussed in more detail in Chapter 8 in Part 2.

## Security

Windows was designed from the start to be secure and to meet the requirements of various formal government and industry security ratings, such as the Common Criteria for Information Technology Security Evaluation (CCITSE) specification. Achieving a government-approved security rating allows an OS to compete in that arena. Of course, many of these capabilities are advantageous features for any multiuser system.

The core security capabilities of Windows include:

- Discretionary (need-to-know) and mandatory protection for all shareable system objects, such as files, directories, processes, threads, and so forth
- Security auditing for accountability of subjects, or users, and the actions they initiate
- User authentication at logon
- The prevention of one user from accessing uninitialized resources, such as free memory or disk space, that another user has deallocated

Windows has three forms of access control over objects:

Discretionary access control This is the protection mechanism that most people think of when they think of OS security. It's the method by which owners of objects (such as files or printers) grant or deny access to others. When users log in, they are given a set of security credentials, or a security context. When they attempt to access objects, their security context is compared to the access control list on the object they are trying to access to determine whether they have permission to perform the requested operation. With Windows Server 2012 and Windows 8, this form of discretionary control is further improved by implementing attribute-based access control (also called Dynamic Access Control). However, a resource's access control list does not necessarily identify individual users and groups. Instead, it identifies required

attributes or claims that grant access to a resource, such as "Clearance Level: Top Secret" or "Seniority: 10 Years." With the ability to populate such attributes automatically by parsing SQL databases and schemas through Active Directory, this significantly more elegant and flexible security model helps organizations avoid cumbersome manual group management and group hierarchies.

- Privileged access control This is necessary for those times when discretionary access control is not enough. It's a method of ensuring that someone can get to protected objects if the owner isn't available. For example, if an employee leaves a company, the administrator needs a way to gain access to files that might have been accessible only to that employee. In that case, under Windows, the administrator can take ownership of the file so that they can manage its rights as necessary.
- Mandatory integrity control This is required when an additional level of security control is needed to protect objects that are being accessed from within the same user account. It's used for everything from providing part of the sandboxing technology for Windows Apps (see the upcoming discussion), to isolating Protected Mode Internet Explorer (and other browsers) from a user's configuration, to protecting objects created by an elevated administrator account from access by a non-elevated administrator account. (See Chapter 7 for more information on User Account Control.)

Starting with Windows 8, a sandbox called an *AppContainer* is used to host Windows Apps, which provides isolation with relation to other AppContainers and non–Windows Apps processes. Code in AppContainers can communicate with brokers (non-isolated processes running with the user's credentials) and sometimes other AppContainers or processes through well-defined contracts provided by the Windows Runtime. A canonical example is the Microsoft Edge browser that runs inside an AppContainer and thus provides better protection against malicious code running within its boundaries. Additionally, third-party developers can leverage AppContainers to isolate their own non–Windows Apps applications in similar ways. The AppContainer model forces a significant shift in traditional programming paradigms, moving from the traditional multithreaded single-process application implementation to a multi-process one.

Security pervades the interface of the Windows API. The Windows subsystem implements objectbased security in the same way the OS does: protecting shared Windows objects from unauthorized access by placing Windows security descriptors on them. The first time an application tries to access a shared object, the Windows subsystem verifies the application's right to do so. If the security check succeeds, the Windows subsystem allows the application to proceed.


For a comprehensive description of Windows security, see Chapter 7.

## Registry

If you've worked with Windows operating systems, you've probably heard about or looked at the registry. You can't talk much about Windows internals without referring to the registry because it's the system database that contains the information required to boot and configure the system, system-wide software settings that control the operation of Windows, the security database, and per-user

configuration settings such as which screen saver to use. In addition, the registry provides a window into in-memory volatile data, such as the current hardware state of the system (what device drivers are loaded, the resources they are using, and so on) as well as the Windows performance counters. The performance counters, which aren't actually *in* the registry, can be accessed through the registry functions (although there is a newer, better API for accessing performance counters). See Chapter 9 in Part 2 for more on how performance counter information is accessed from the registry.

Although many Windows users and administrators will never need to look directly into the registry (because you can view or change most configuration settings with standard administrative utilities), it is still a useful source of Windows internals information because it contains many settings that affect system performance and behavior. You'll find references to individual registry keys throughout this book as they pertain to the component being described. Most registry keys referred to in this book are under the system-wide configuration hive, HKEY\_LOCAL\_MACHINE, which we'll abbreviate throughout as *HKLM*.



For further information on the registry and its internal structure, see Chapter 9 in Part 2.

## Unicode

Windows differs from most other operating systems in that most internal text strings are stored and processed as 16-bit-wide Unicode characters (technically UTF-16LE; when Unicode is mentioned in this book it refers to UTF-16LE unless otherwise stated). Unicode is an international character set standard that defines unique values for most of the world's known character sets, and provides 8, 16, and even 32-bit encodings for each character.

Because many applications deal with 8-bit (single-byte) ANSI character strings, many Windows functions that accept string parameters have two entry points: a Unicode (wide, 16-bit) version and an ANSI (narrow, 8-bit) version. If you call the narrow version of a Windows function, there is a slight performance impact as input string parameters are converted to Unicode before being processed by the system and output parameters are converted from Unicode to ANSI before being returned to the application. Thus, if you have an older service or piece of code that you need to run on Windows but this code is written using ANSI character text strings, Windows will convert the ANSI characters into Unicode for its own use. However, Windows never converts the *data* inside files—it's up to the application to decide whether to store data as Unicode or as ANSI.

Regardless of language, all versions of Windows contain the same functions. Instead of having separate language versions, Windows has a single worldwide binary so that a single installation can support multiple languages (through the addition of various language packs). Applications can also take advantage of Windows functions that allow single worldwide application binaries that can support multiple languages.

**Note** The old Windows 9x operating systems did not support Unicode natively. This was yet another reason for the creation of two functions for ANSI and Unicode. For example, the Windows API function CreateFile is not a function at all; instead, it's a macro that expands to one of two functions: CreateFileA (ANSI) or CreateFileW (Unicode, where W stands for *wide*). The expansion is based on a compilation constant named UNICODE. It's defined by default in Visual Studio C++ projects because it's more beneficial to work with the Unicode functions. However, the explicit function name can be used in lieu of the appropriate macro. The following experiment shows these pairs of functions.

#### **EXPERIMENT:** Viewing exported functions

In this experiment, you'll use the Dependency Walker tool to view exported functions from a Windows subsystem DLL.

- Download Dependency Walker from http://www.dependencywalker.com. If you have a 32-bit system, download the 32-bit version of Download Dependency. Or, if you have a 64-bit system, download the 64-bit version. Then extract the downloaded ZIP file to a folder of your choice.
- Run the tool (depends.exe). Then open the File menu and choose Open, navigate to the C:\Windows\System32 folder (assuming Windows is installed on your C drive), locate the kernel32.dll file and click Open.
- **3.** Dependency Walker may show a warning message box. Disregard it and dismiss the message box.
- **4.** You'll see several views with vertical and horizontal splitter bars. Make sure the item selected in the top-left tree view is kernel32.dll.
- 5. Look at the second view from the top on the right side. This view lists the exported functions available in kernel32.dll. Click the **Function** list header to sort by name. Then locate the function CreateFileA. You'll find CreateFileW not much farther down, as shown here:

E - KERNEL32.DLL	PI	Ordinal ^	Hint	Function	Entry Point
	E	Ordinal	Hint	Function ^	Entry Point
	<b>C</b>	182 (0x00B6)	181 (0x00B5)	CreateFiber	0x0002DEF0
	C	183 (0x00B7)	182 (0x00B6)	CreateFiberEx	0x0002DF00
	C	184 (0x00B8)	183 (0x00B7)	CreateFile2	0x0002D890
	6		184 (0x00 B8)	CreateFileA	0x000208A0
	C	186 (0x00BA)	185 (0x00B9)	CreateFileMappingA	0x00021810
	103	187 (0x00BB)	186 (0x00BA)	CreateFileMappingFromApp	api-ms-win-core-memory-I1-1-1.Crea
	C	188 (0x00BC)	187 (0x00BB)	CreateFileMappingNumaA	0x00040C70
	C	189 (0x00BD)	188 (0x00BC)	CreateFileMappingNumaW	0x00045980
	C	190 (0x00BE)	189 (0x00BD)	CreateFileMappingW	0x00023AF0
	C	191 (0x00BF)	190 (0x00BE)	CreateFileTransactedA	0x00042020
	C	192 (0x00C0)	191 (0x00BF)	CreateFileTransactedW	0x0002C640
	6	193 (0x00C1).	192 (0x0 0 C0)	CreateFileW	0x00020880
	C	194 (0x00 C2)	193 (0x00 C1)	CreateHardLinkA	0x00045990

- 6. As you can see, most functions that have at least one string type argument are in fact pairs of functions. In the preceding graphic, the following are visible: CreateFileMappingA/W, CreateFileTransactedA/W, and CreateFileMappingNumaA/W.
- 7. You can scroll the list to locate others. You can also open other system files, such as user32.dll and advapi32.dll.

**Note** The COM-based APIs in Windows typically use Unicode strings, sometimes typed as *BSTR*. This is essentially a null-terminated array of Unicode characters with the length of the string in bytes stored 4 bytes before the start of the array of characters in memory. The Windows Runtime APIs use Unicode strings only, typed as *HSTRING*, which is an immutable array of Unicode characters.

For more information about Unicode, see *http://www.unicode.org* and the programming documentation in the MSDN Library.

## **Digging into Windows internals**

Although much of the information in this book is based on reading Windows source code and talking to developers, you don't have to take *everything* on faith. Many details about the internals of Windows can be exposed and demonstrated by using a variety of available tools, such as those that come with Windows and the Windows debugging tools. These tool packages are briefly described later in this section.

To encourage your exploration of Windows internals, we've included "Experiment" sidebars throughout the book that describe steps you can take to examine a particular aspect of Windows internal behavior. (You already saw a few of these sidebars earlier in this chapter.) We encourage you to try these experiments so you can see in action many of the internals topics described in this book.

Table 1-4 shows a list of the principal tools used in this book and where they come from.

Tool	Image Name	Origin
Startup Programs Viewer	AUTORUNS	Sysinternals
Access Check	ACCESSCHK	Sysinternals
Dependency Walker	DEPENDS	www.dependencywalker.com
Global Flags	GFLAGS	Debugging tools
Handle Viewer	HANDLE	Sysinternals

TABLE 1-4 Tools for viewing Windows internals

Continues...

**TABLE 1-4** Tools for viewing Windows internals (continued)

Tool	Image Name	Origin
Kernel debuggers	WINDBG, KD	WDK, Windows SDK
Object Viewer	WINOBJ	Sysinternals
Performance Monitor	PERFMON.MSC	Windows built-in tool
Pool Monitor	POOLMON	WDK
Process Explorer	PROCEXP	Sysinternals
Process Monitor	PROCMON	Sysinternals
Task (Process) List	TLIST	Debugging tools
Task Manager	TASKMGR	Windows built-in tool

## Performance Monitor and Resource Monitor

We refer to Performance Monitor—which you can access from the Administrative Tools folder in the Control Panel or by typing **perfmon** in the Run dialog box—throughout this book. Specifically, we focus on Performance Monitor and Resource Monitor.

٢	+	+	+	+	٦
	2	_	_	=	
	E	-	-		
	Ξ	-	-		
L					J

**Note** Performance Monitor has three functions: system monitoring, viewing performance counter logs, and setting alerts (by using data collector sets, which also contain performance counter logs and trace and configuration data). For simplicity, when we refer to Performance Monitor, we mean the system-monitoring function within that tool.

Performance Monitor provides more information about how your system is operating than any other single utility. It includes hundreds of base and extensible counters for various objects. For each major topic described in this book, a table of the relevant Windows performance counters is included. Performance Monitor contains a brief description for each counter. To see the descriptions, select a counter in the Add Counters window and select the **Show Description** check box.

Although all the low-level system monitoring we'll do in this book can be done with Performance Monitor, Windows also includes a Resource Monitor utility (accessible from the Start menu or from the Task Manager Performance tab) that shows four primary system resources: CPU, disk, network, and memory. In their basic states, these resources are displayed with the same level of information that you would find in Task Manager. However, they also provide sections that can be expanded for more information. Here's a typical view of Resource Monitor:

🔕 Resource Moni														
File Monitor He	elp													
Overview CPU	Memory	/ Disk	Network											
CPU			8% CPU Usag	e			<b>#</b> 37	% Maxim	um Freque	ncy		•	•	Views
Image		PID	Descrip	Status	Threads		CPU A	verag	Operating	Syste	Platform	^	CPU	100% -
SkypeHost.exe		4960	Micros	Suspe	13		0	0.00	- Startmannerski -		32 8it		B A	
ShellExperiencel	lost.exe	1928	Windo	Suspe	27		0	0.00	* -		64 Bit			
SearchULexe		5308	Search	Suspe	39		D	0.00			64 Bit		A A	
SystemSettings.e	axe.	6608	Settings	Suspe	25		0	0.00			64 Bit		60 Seconds	0% -
Calculator.exe		5380	Calcula	Suspe-	21		0	0.00			64 Bit		Disk	100 KB/sec -
WINWORD.EXE		6204	Micros	Runni	46		1	2.43	10		32 Bit	Y		
<												>		
Disk			25 KB/sec Dis	k 1/0			29	6 Highest	Active Tim	e		•		
Image	PID	File			Re	ad	Write	Total	VO Pr	Respon	ise	^	Network	10 Kbps -
WINWORD.EXE	6204	C:\SLogFil	e (NTFS Volum	ne Logi		0	100	100	Nor		17			
MsMpEng.exe	2640	C:\Users\P	avel AppData	Roaming	Micr	768	0	768	Nor		16			A
System	4	C:\SLogFil	e (NTFS Volum	ne Log)		0	5,642	5,642	Nor		13			AAAAA.
System	4	C:\Program	mData\Micros	oft\Window	¥5\	0	4,274	4,274	Nor		10			0 -
System	4	C:\Windo	ws\System32\I	LogFiles\WI	MI\T	0	118	118	Nor	2	1	~	Memory	100 Hard Faults/sec
Network	_		1 Kbps Netwo	ork I/O			01	6 Networ	k Utilizatio	n	_	$\odot$		
Memory			6 Hard Faults	/sec			<b>#</b> 40	% Used F	Physical Me	mory	_			
Image		PID	Hard Faults	sec Co	mmit (KB)	Share	able	Workin	g Set (KB)	Private	(KB)	^		150
MicrosoftEdgeCP.ex	e	9040		0	209,220	1	62,128		242,892	180	764			
OneDrive.exe	-17	6740		0	153,120		25,156		171,524	146	368			
WINWORD.EXE		6204		0	154,828	1	10,116		219,932	109	816			
MicrosoftEdgeCP.ex	e	5696		0	118,892		75,268		168,848	93	580			
dwm.exe		408		0	100,884		29,544		108,168	78	,624			
SearchUI.exe		5308		0	81,576		63,716		133,900	70	,184			
MsMpEng.exe		2640		4	113,904	8	44,820		108,992	64	,172			
MicrosoftEdgeCP.ex	œ	8356		0	54,908	10	49,416		92,172	42	,756			
explorer.exe		5616		0	69,704		58,824		101,184	42	360	~		

When expanded, the CPU tab displays information about per-process CPU usage, just like Task Manager. However, it adds a column for average CPU usage, which can give you a better idea of which processes are most active. The CPU tab also includes a separate display of services and their associated CPU usage and average. Each service-hosting process is identified by the service group it is hosting. As with Process Explorer, selecting a process (by clicking its associated check box) will display a list of named handles opened by the process, as well as a list of modules (such as DLLs) that are loaded in the process address space. The Search Handles box can also be used to search for which processes have opened a handle to a given named resource.

The Memory tab displays much of the same information that one can obtain with Task Manager, but it is organized for the entire system. A physical memory bar graph displays the current organization of physical memory into either hardware-reserved, in-use, modified, standby, or free memory. See Chapter 5 for the exact meaning of these terms.

The Disk tab, on the other hand, displays per-file information for I/O in a way that makes it easy to identify the most-accessed, the most-written to, or the most-read from files on the system. These results can be further filtered down by process.

The Network tab displays the active network connections, the processes that own them, and how much data is going through them. This information makes it possible to see background network activity that might be hard to detect otherwise. In addition, it shows the TCP connections that are active on the system, organized by process, with data such as the remote and local port and address and packet latency. Finally, it displays a list of listening ports by process, allowing an administrator to see which services or applications are currently waiting for connections on a given port. The protocol and firewall policy for each port and process is also shown. **Note** All Windows performance counters are accessible programmatically. For more information, search for "performance counters" in the MSDN documentation.

## Kernel debugging

*Kernel debugging* means examining internal kernel data structures and/or stepping through functions in the kernel. It is a useful way to investigate Windows internals because you can display internal system information not available through any other tools and get a clearer idea of code flows within the kernel. Before describing the various ways in which you can debug the kernel, let's examine a set of files that you'll need in order to perform any type of kernel debugging.

#### Symbols for kernel debugging

Symbol files contain the names of functions and variables and the layout and format of data structures. They are generated by the linker and used by debuggers to reference and display these names during a debug session. This information is not usually stored in the binary image because it is not needed to execute the code. This means binaries are smaller and faster. However, it also means that when debugging, you must make sure the debugger can access the symbol files associated with the images you are referencing during a debugging session.

To use any of the kernel-debugging tools to examine internal Windows kernel data structures such as the process list, thread blocks, loaded driver list, memory usage information, and so on, you must have the correct symbol files for at least the kernel image, Ntoskrnl.exe. (You can learn more about this file in the section "Architecture overview" in Chapter 2.) Symbol table files must match the version of the image from which they were taken. For example, if you install a Windows service pack or hot fix that updates the kernel, you must obtain the matching updated symbol files.

While it is possible to download and install symbols for various versions of Windows, updated symbols for hot fixes are not always available. The easiest way to obtain the correct version of symbols for debugging is to employ the Microsoft on-demand symbol server by using a special syntax for the symbol path that you specify in the debugger. For example, the following symbol path causes the debugging tools to load required symbols from the Internet symbol server and keep a local copy in the C:\symbols folder:

srv\*c:\symbols\*http://msdl.microsoft.com/download/symbols

## **Debugging Tools for Windows**

The Debugging Tools for Windows package contains advanced debugging tools, which are used in this book to explore Windows internals. The latest version is included as part of the Windows SDK. (See *https://msdn.microsoft.com/en-us/library/windows/hardware/ff551063.aspx* for more details about the different installation types.) These tools can be used to debug user-mode processes as well as the kernel.

There are four debuggers included in the tools: cdb, ntsd, kd, and WinDbg. All are based on a single debugging engine implemented in DbgEng.dll, which is documented fairly well in the help file for the tools. Here's a brief overview of the debuggers:

- cdb and ntsd are user-mode debuggers based on a console user interface. The only difference between them is that ntsd opens a new console window if activated from an existing console window, while cdb does not.
- kd is a kernel-mode debugger based on a console user interface.
- WinDbg can be used as a user-mode or kernel-mode debugger, but not both at the same time.
   It provides a GUI for the user.
- The user-mode debuggers (cdb, ntsd, and WinDbg, when used as such) are essentially equivalent. Usage of one or the other is a matter of preference.
- The kernel-mode debuggers (kd and WinDbg, when used as such) are equivalent as well.

**User-mode debugging** The debugging tools can also be used to attach to a user-mode process and to examine and/or change process memory. There are two options when attaching to a process:

- Invasive Unless specified otherwise, when you attach to a running process, you use the DebugActiveProcess Windows function to establish a connection between the debugger and the debugee. This permits you to examine and/or change process memory, set breakpoints, and perform other debugging functions. Windows allows you to stop debugging without killing the target process as long as the debugger is detached, not killed.
- Noninvasive With this option, the debugger simply opens the process with the OpenProcess function. It does not attach to the process as a debugger. This allows you to examine and/or change memory in the target process, but you cannot set breakpoints. This also means it's possible to attach noninvasively even if another debugger is attached invasively.

You can also open user-mode process dump files with the debugging tools. User-mode dump files are explained in Chapter 8 in Part 2 in the section on exception dispatching.

**Kernel-mode debugging** As mentioned, there are two debuggers that can be used for kernel debugging: a command-line version (Kd.exe) and a GUI version (Windbg.exe). You can perform three types of kernel debugging with these tools:

- Open a crash dump file created as a result of a Windows system crash. (See Chapter 15, "Crash dump analysis," in Part 2 for more information on kernel crash dumps.)
- Connect to a live, running system and examine the system state (or set breakpoints if you're debugging device driver code). This operation requires two computers: a target (the system being debugged) and a host (the system running the debugger). The target system can be connected to the host via a null modem cable, an IEEE 1394 cable, a USB 2.0/3.0 debugging cable, or the local network. The target system must be booted in debugging mode. You can configure the system to boot in debugging mode using Bcdedit.exe or Msconfig.exe. (Note that you may

have to disable secure boot in the UEFI BIOS settings.) You can also connect through a named pipe—which is useful when debugging Windows 7 or earlier versions through a virtual machine product such as Hyper-V, Virtual Box, or VMWare Workstation—by exposing the guest operating system's serial port as a named pipe device. For Windows 8 and later guests, you should instead use local network debugging by exposing a host-only network using a virtual NIC in the guest operating system. This will result in 1,000x performance gain.

Windows systems also allow you to connect to the local system and examine the system state. This is called *local kernel debugging*. To initiate local kernel debugging with WinDbg, first make sure the system is set to debug mode (for example, by running msconfig.exe, clicking the **Boot** tab, selecting **Advanced Options**, selecting **Debug**, and restarting Windows). Launch WinDbg with admin privileges and open the **File** menu, choose **Kernel Debug**, click the **Local** tab, and then click **OK** (or use bcdedit.exe). Figure 1-6 shows a sample output screen on a 64-bit Windows 10 machine. Some kernel debugger commands do not work when used in local kernel debugging mode, such as setting breakpoints or creating a memory dump with the .dump command. However, the latter can be done with LiveKd, described later in this section.

😨 Local kernel - WinDbg:10.0.10240.9 AMD64			
File Edit View Debug Window Help			
Command		2	3
Microsoft (R) Windows Debugger Version 10.0.10240.9 AMD64 Copyright (c) Microsoft Corporation. All rights reserved.			
Connected to Windows 10 10586 x64 target at (Thu Feb 11 17:41:	56.379 2016 (UTC + 2:00)), ptr64 TRUE		
<pre>************************************</pre>	: symbols for ntkrnlmp.exe - 100°claelcf0	ols	
llid>			
Ln 0, Col	Sys 0: «None» Proc 000:0 Thrd 000:0 ASM OVR	CAPS N	UN

FIGURE 1-6 Local kernel debugging.

Once connected in kernel-debugging mode, you can use one of the many debugger extension commands—also known as *bang* commands, which are commands that begin with an exclamation point (!)—to display the contents of internal data structures such as threads, processes, I/O request packets, and memory management information. Throughout this book, the relevant kernel debugger commands and output are included as they apply to each topic being discussed. An excellent companion reference is the Debugger.chm help file, contained in the WinDbg installation folder, which documents all the kernel debugger functionality and extensions. In addition, the dt (display type) command can format more than 1,000 kernel structures because the kernel symbol files for Windows contain type information that the debugger can use to format structures.

#### **EXPERIMENT:** Displaying type information for kernel structures

To display the list of kernel structures whose type information is included in the kernel symbols, type **dt nt!\_\*** in the kernel debugger. A sample partial output is shown here. (ntkrnlmp is the internal file name of the 64-bit kernel. For more details, see Chapter 2.)

```
lkd> dt nt!_*
```

```
ntkrnlmp!_KSYSTEM_TIME
ntkrnlmp!_NT_PRODUCT_TYPE
ntkrnlmp!_ALTERNATIVE_ARCHITECTURE_TYPE
ntkrnlmp!_KUSER_SHARED_DATA
ntkrnlmp!_ULARGE_INTEGER
ntkrnlmp!_TP_POOL
ntkrnlmp!_TP_CLEANUP_GROUP
ntkrnlmp!_ACTIVATION_CONTEXT
ntkrnlmp!_TP_CALLBACK_INSTANCE
ntkrnlmp!_TP_CALLBACK_ENVIRON_V3
ntkrnlmp!_TEB
```

You can also use the dt command to search for specific structures by using its wildcard lookup capability. For example, if you were looking for the structure name for an interrupt object, you could type **dt nt!\_\*interrupt\***:

```
lkd> dt nt!_*interrupt*
```

```
ntkrnlmp!_KINTERRUPT_MODE
ntkrnlmp!_KINTERRUPT_POLARITY
ntkrnlmp!_PEP_ACPI_INTERRUPT_RESOURCE
ntkrnlmp!_KINTERRUPT
ntkrnlmp!_UNEXPECTED_INTERRUPT
ntkrnlmp!_INTERRUPT_CONNECTION_DATA
ntkrnlmp!_INTERRUPT_VECTOR_DATA
ntkrnlmp!_INTERRUPT_HT_INTR_INFO
ntkrnlmp!_INTERRUPT_REMAPPING_INFO
```

Then you can use dt to format a specific structure as shown next (the debugger treats structures as case insensitive):

```
lkd> dt nt!_KINTERRUPT
```

```
+0x000Type: Int2B+0x002Size: Int2B+0x008InterruptListEntry: _LIST_ENTRY+0x018ServiceRoutine: Ptr64unsigned char+0x020MessageServiceRoutine: Ptr64unsigned char+0x028MessageIndex: Uint4B+0x030ServiceContext: Ptr64 Void+0x038SpinLock: Uint8B+0x040TickCount: Uint4B+0x050DispatchAddress: Ptr64+0x058Vector: Uint4B+0x055Irql: UChar
```

+0x05d	SynchronizeIrql	:	UChar
+0x05e	FloatingSave	:	UChar
+0x05f	Connected	:	UChar
+0x060	Number	:	Uint4B
+0x064	ShareVector	:	UChar
+0x065	EmulateActiveBoth		: UChar
+0x066	ActiveCount	:	Uint2B
+0x068	InternalState		
+0x06c	Mode	:	_KINTERRUPT_MODE
+0x070	Polarity	:	_KINTERRUPT_POLARITY
+0x074	ServiceCount	:	Uint4B
+0x078	DispatchCount	:	Uint4B
+0x080	PassiveEvent	:	Ptr64 _KEVENT
+0x088	TrapFrame	:	Ptr64 _KTRAP_FRAME
+0x090	DisconnectData	:	Ptr64 Void
+0x098	ServiceThread	:	Ptr64 _KTHREAD
+0x0a0	ConnectionData	:	Ptr64 _INTERRUPT_CONNECTION_DATA
	IntTrackEntry		
+0x0b0	IsrDpcStats	:	_ISRDPCSTATS
+0x0f0	RedirectObject	;	Ptr64 Void
+0x0f8	Padding	:	[8] UChar

Note that dt does not show substructures (structures within structures) by default. To show substructures, use the -r or -b switches. For example, using one of these switches to display the kernel interrupt object shows the format of the \_LIST\_ENTRY structure stored in the Interrupt-ListEntry field. (See the documentation for the exact differences between the -r and -b switches.)

```
1kd> dt nt!_KINTERRUPT -r
+0x000 Type : Int2B
+0x002 Size : Int2B
+0x008 InterruptListEntry : _LIST_ENTRY
+0x000 Flink : Ptr64 _LIST_ENTRY
+0x000 Flink : Ptr64 _LIST_ENTRY
+0x008 Blink : Ptr64 _LIST_ENTRY
+0x008 Blink : Ptr64 _LIST_ENTRY
+0x000 Flink : Ptr64 _LIST_ENTRY
+0x008 Blink : Ptr64 _LIST_ENTRY
+0x008 Blink : Ptr64 _LIST_ENTRY
+0x008 Blink : Ptr64 _LIST_ENTRY
+0x018 ServiceRoutine : Ptr64 unsigned char
```

The dt command even lets you specify the level of recursion of structures by appending a number to the -r switch. The following example means one level of recursion:

lkd> dt nt!\_KINTERRUPT -r1

The Debugging Tools for Windows help file explains how to set up and use kernel debuggers. For additional details on using kernel debuggers aimed primarily at device-driver writers, see the WDK documentation.

#### LiveKd tool

LiveKd is a free tool from Sysinternals that enables you to use the standard Microsoft kernel debuggers just described to examine the running system without booting the system in debugging mode. This approach might be useful when kernel-level troubleshooting is required on a machine that wasn't booted in debugging mode. Certain issues might be hard to reproduce reliably, so a reboot with the *debug* option enabled might not readily exhibit the error.

You run LiveKd just as you would WinDbg or kd. LiveKd passes any command-line options you specify to the debugger you select. By default, LiveKd runs the command-line kernel debugger (kd). To have it run WinDbg, use the -w switch. To see the help files for LiveKd switches, use the -? switch.

LiveKd presents a simulated crash dump file to the debugger so you can perform any operations in LiveKd that are supported on a crash dump. Because LiveKd relies on physical memory to back the simulated dump, the kernel debugger might run into situations in which data structures are in the middle of being changed by the system and are inconsistent. Each time the debugger is launched, it starts with a fresh view of the system state. If you want to refresh the snapshot, enter the **q** command to quit the debugger. LiveKd will ask you whether you want to start it again. If the debugger enters a loop in printing output, press **Ctrl+C** to interrupt the output and quit. If it hangs, press **Ctrl+Break**, which will terminate the debugger process. LiveKd will then ask you whether you want to run the debugger again.

## Windows Software Development Kit

The Windows Software Development Kit (SDK) is available as part of the MSDN subscription program. You can also download it for free from *https://developer.microsoft.com/en-US/windows/downloads/ windows-10-sdk*. Visual Studio also provides the option of installing the SDK as part of VS installation. The versions contained in the Windows SDK always match the latest version of the Windows operating system, whereas the version that comes with Visual Studio might be an older version that was current when that version was released. Besides the Debugging Tools for Windows, it contains the C header files and the libraries necessary to compile and link Windows applications. From a Windows internals perspective, items of interest in the Windows SDK include the Windows API header files—for example, C:\Program Files (x86)\Windows Kits\10\Include—and the SDK tools (search for the Bin folder). Also of interest is the documentation. It's available online or can be downloaded for offline access. A few of these tools are also shipped as sample source code in both the Windows SDK and the MSDN Library.

## Windows Driver Kit

The Windows Driver Kit (WDK) is also available through the MSDN subscription program. Just like the Windows SDK, it is available for free download. The WDK documentation is included in the MSDN Library.

Although the WDK is aimed at developers of device drivers, it is an abundant source of Windows internals information. For example, although Chapter 6 describes the I/O system architecture, driver model, and basic device driver data structures, it does not describe the individual kernel support functions in detail. The WDK documentation contains a comprehensive description of all the Windows kernel support functions and mechanisms used by device drivers in both tutorial and reference form.

In addition to including the documentation, the WDK contains header files (in particular, ntddk.h, ntifs.h, and wdm.h) that define key internal data structures and constants as well as interfaces to many internal system routines. These files are useful when exploring Windows internal data structures with the kernel debugger because although the general layout and content of these structures are shown in this book, detailed field-level descriptions (such as size and data types) are not. A number of these data structures—such as object dispatcher headers, wait blocks, events, mutants, semaphores, and so on—are, however, fully described in the WDK.

If you want to dig into the I/O system and driver model beyond what is presented in this book, read the WDK documentation—especially the *Kernel-Mode Driver Architecture Design Guide* and *Kernel-Mode Driver Reference* manuals. You might also find useful *Programming the Microsoft Windows Driver Model, Second Edition* by Walter Oney (Microsoft Press, 2002) and *Developing Drivers with the Windows Driver Foundation* by Penny Orwick and Guy Smith (Microsoft Press, 2007).

## Sysinternals tools

Many experiments in this book use freeware tools that you can download from Sysinternals. Mark Russinovich, coauthor of this book, wrote most of these tools. The most popular tools include Process Explorer and Process Monitor. Note that many of these utilities involve the installation and execution of kernel-mode device drivers and thus require administrator, or elevated, privileges—although some of them can run with limited functionality and output on a standard, or non-elevated, user account.

Because the Sysinternals tools are updated frequently, be make sure you have the latest version. To be notified of tool updates, you can follow the Sysinternals Site Blog (which has an RSS feed). For a description of all the tools, a description of how to use them, and case studies of problems solved, see *Windows Sysinternals Administrator's Reference* by Mark Russinovich and Aaron Margosis (Microsoft Press, 2011). For questions and discussions on the tools, use the Sysinternals Forums.

## Conclusion

This chapter introduced key Windows technical concepts and terms that will be used throughout the book. It also offered a glimpse of the many useful tools available for digging into Windows internals. Now you're ready to begin your exploration of the internal design of the system, beginning with an overall view of the system architecture and its key components.

# System architecture

N ow that you've learned the terms, concepts, and tools you need to be familiar with, it's time to start exploring the internal design goals and structure of the Microsoft Windows operating system (OS). This chapter explains the overall architecture of the system—the key components, how they interact with each other, and the context in which they run. To provide a framework for understanding the internals of Windows, let's first review the requirements and goals that shaped the original design and specification of the system.

## **Requirements and design goals**

The following requirements drove the specification of Windows NT back in 1989:

- Provide a true 32-bit, preemptive, reentrant, virtual memory OS.
- Run on multiple hardware architectures and platforms.
- Run and scale well on symmetric multiprocessing systems.
- Be a great distributed computing platform, both as a network client and as a server.
- Run most existing 16-bit MS-DOS and Microsoft Windows 3.1 applications.
- Meet government requirements for POSIX 1003.1 compliance.
- Meet government and industry requirements for OS security.
- Be easily adaptable to the global market by supporting Unicode.

To guide the thousands of decisions that had to be made to create a system that met these requirements, the Windows NT design team adopted the following design goals at the beginning of the project:

- Extensibility The code must be written to comfortably grow and change as market requirements change.
- Portability The system must be able to run on multiple hardware architectures and must be able to move with relative ease to new ones as market demands dictate.
- **Reliability and robustness** The system should protect itself from both internal malfunction and external tampering. Applications should not be able to harm the OS or other applications.

- Compatibility Although Windows NT should extend existing technology, its user interface and APIs should be compatible with older versions of Windows and with MS-DOS. It should also interoperate well with other systems, such as UNIX, OS/2, and NetWare.
- **Performance** Within the constraints of the other design goals, the system should be as fast and responsive as possible on each hardware platform.

As we explore the details of the internal structure and operation of Windows, you'll see how these original design goals and market requirements were woven successfully into the construction of the system. But before we start that exploration, let's examine the overall design model for Windows and compare it with other modern operating systems.

## **Operating system model**

In most multiuser operating systems, applications are separated from the OS itself. The OS kernel code runs in a privileged processor mode (referred to as *kernel mode* in this book), with access to system data and to the hardware. Application code runs in a non-privileged processor mode (called *user mode*), with a limited set of interfaces available, limited access to system data, and no direct access to hardware. When a user-mode program calls a system service, the processor executes a special instruction that switches the calling thread to kernel mode. When the system service completes, the OS switches the thread context back to user mode and allows the caller to continue.

Windows is similar to most UNIX systems in that it's a monolithic OS in the sense that the bulk of the OS and device driver code shares the same kernel-mode protected memory space. This means that any OS component or device driver can potentially corrupt data being used by other OS system components. However, as you saw in Chapter 1, "Concepts and tools," Windows addresses this through attempts to strengthen the quality and constrain the provenance of third-party drivers through programs such as WHQL and enforcement through KMCS, while also incorporating additional kernel protection technologies such as virtualization-based security and the Device Guard and Hyper Guard features. Although you'll see how these pieces fit together in this section, more details will follow in Chapter 7, "Security," and in Chapter 8, "System mechanisms," in *Windows Internals Part 2*.

All these OS components are, of course, fully protected from errant applications because applications don't have direct access to the code and data of the privileged part of the OS (although they can quickly call other kernel services). This protection is one of the reasons that Windows has the reputation for being both robust and stable as an application server and as a workstation platform, yet fast and nimble from the perspective of core OS services, such as virtual memory management, file I/O, networking, and file and print sharing.

The kernel-mode components of Windows also embody basic object-oriented design principles. For example, in general they don't reach into one another's data structures to access information maintained by individual components. Instead, they use formal interfaces to pass parameters and access and/or modify data structures. Despite its pervasive use of objects to represent shared system resources, Windows is not an objectoriented system in the strict sense. Most of the kernel-mode OS code is written in C for portability. The C programming language doesn't directly support object-oriented constructs such as polymorphic functions or class inheritance. Therefore, the C-based implementation of objects in Windows borrows from, but doesn't depend on, features of particular object-oriented languages.

## **Architecture overview**

With this brief overview of the design goals and packaging of Windows, let's take a look at the key system components that make up its architecture. A simplified version of this architecture is shown in Figure 2-1. Keep in mind that this diagram is basic. It doesn't show everything. For example, the networking components and the various types of device driver layering are not shown.




FIGURE 2-1 Simplified Windows architecture.

In Figure 2-1, first notice the line dividing the user-mode and kernel-mode parts of the Windows OS. The boxes above the line represent user-mode processes, and the components below the line are kernel-mode OS services. As mentioned in Chapter 1, user-mode threads execute in a private process address space (although while they are executing in kernel mode, they have access to system space). Thus, system processes, service processes, user processes, and environment subsystems each have their own private process address space. A second dividing line between kernel-mode parts of Windows and the hypervisor is also visible. Strictly speaking, the hypervisor still runs with the same CPU privilege level (0) as the kernel, but because it uses specialized CPU instructions (VT-x on Intel, SVM on AMD), it can both isolate itself from the kernel while also monitoring it (and applications). For these reasons, you may often hear the term *ring -1* thrown around (which is inaccurate).

The four basic types of user-mode processes are described as follows:

- User processes These processes can be one of the following types: Windows 32-bit or 64-bit (Windows Apps running on top of the Windows Runtime in Windows 8 and later are included in this category), Windows 3.1 16-bit, MS-DOS 16-bit, or POSIX 32-bit or 64-bit. Note that 16-bit applications can be run only on 32-bit Windows, and that POSIX applications are no longer supported as of Windows 8.
- Service processes These are processes that host Windows services, such as the Task Scheduler and Print Spooler services. Services generally have the requirement that they run independently of user logons. Many Windows server applications, such as Microsoft SQL Server and Microsoft Exchange Server, also include components that run as services. Chapter 9, "Management mechanisms," in Part 2 describes services in detail.
- System processes These are fixed, or hardwired, processes, such as the logon process and the Session Manager, that are not Windows services. That is, they are not started by the Service Control Manager.
- Environment subsystem server processes These implement part of the support for the OS environment, or personality, presented to the user and programmer. Windows NT originally shipped with three environment subsystems: Windows, POSIX, and OS/2. However, the OS/2 subsystem last shipped with Windows 2000 and POSIX last shipped with Windows XP. The Ultimate and Enterprise editions of Windows 7 client as well as all of the server versions of Windows 2008 R2 include support for an enhanced POSIX subsystem called Subsystem for UNIX-based Applications (SUA). The SUA is now discontinued and is no longer offered as an optional part of Windows (either client or server).

**Note** Windows 10 Version 1607 includes a Windows Subsystem for Linux (WSL) in beta state for developers only. However, this is not a true subsystem as described in this section. This chapter will discuss WSL and the related Pico providers in more detail. For information about Pico processes, see Chapter 3, "Processes and jobs."

In Figure 2-1, notice the Subsystem DLLs box below the Service Processes and User Processes boxes. Under Windows, user applications don't call the native Windows OS services directly. Rather, they go through one or more *subsystem dynamic-link libraries* (*DLLs*). The role of subsystem DLLs is to translate a documented function into the appropriate internal (and generally undocumented) native system service calls implemented mostly in Ntdll.dll. This translation might or might not involve sending a message to the environment subsystem process that is serving the user process.

The kernel-mode components of Windows include the following:

**Executive** The Windows executive contains the base OS services, such as memory management, process and thread management, security, I/O, networking, and inter-process communication.

- The Windows kernel This consists of low-level OS functions, such as thread scheduling, interrupt and exception dispatching, and multiprocessor synchronization. It also provides a set of routines and basic objects that the rest of the executive uses to implement higher-level constructs.
- Device drivers This includes both hardware device drivers, which translate user I/O function calls into specific hardware device I/O requests, and non-hardware device drivers, such as file system and network drivers.
- The Hardware Abstraction Layer (HAL) This is a layer of code that isolates the kernel, the device drivers, and the rest of the Windows executive from platform-specific hardware differences (such as differences between motherboards).
- The windowing and graphics system This implements the graphical user interface (GUI) functions (better known as the Windows USER and GDI functions), such as dealing with windows, user interface controls, and drawing.
- The hypervisor layer This is composed of a single component: the hypervisor itself. There are no drivers or other modules in this environment. That being said, the hypervisor is itself composed of multiple internal layers and services, such as its own memory manager, virtual processor scheduler, interrupt and timer management, synchronization routines, partitions (virtual machine instances) management and inter-partition communication (IPC), and more.

Table 2-1 lists the file names of the core Windows OS components. (You'll need to know these file names because we'll be referring to some system files by name.) Each of these components is covered in greater detail both later in this chapter and in the chapters that follow.

File Name	Components
Ntoskrnl.exe	Executive and kernel
Hal.dll	HAL
Win32k.sys	Kernel-mode part of the Windows subsystem (GUI)
Hvix64.exe (Intel), Hvax64.exe (AMD)	Hypervisor
.sys files in \SystemRoot\System32\Drivers	Core driver files, such as Direct X, Volume Manager, TCP/IP, TPM, and ACPI support
Ntdll.dll	Internal support functions and system service dispatch stubs to ex- ecutive functions
Kernel32.dll, Advapi32.dll, User32.dll, Gdi32.dll	Core Windows subsystem DLLs

 TABLE 2-1
 Core Windows System Files

Before we dig into the details of these system components, though, let's examine some basics about the Windows kernel design, starting with how Windows achieves portability across multiple hardware architectures.

# Portability

Windows was designed to run on a variety of hardware architectures. The initial release of Windows NT supported the x86 and MIPS architectures. Support for the Digital Equipment Corporation (which was bought by Compaq, which later merged with Hewlett-Packard) Alpha AXP was added shortly thereafter. (Although Alpha AXP was a 64-bit processor, Windows NT ran in 32-bit mode. During the development of Windows 2000, a native 64-bit version was running on Alpha AXP, but this was never released.) Support for a fourth processor architecture, the Motorola PowerPC, was added in Windows NT 3.51. Because of changing market demands, however, support for the MIPS and PowerPC architectures was dropped before development began on Windows 2000. Later, Compaq withdrew support for the Alpha AXP architecture, resulting in Windows 2000 being supported only on the x86 architecture. Windows XP and Windows Server 2003 added support for two 64-bit processor families: the Intel Itanium IA-64 family and the AMD64 family with its equivalent Intel 64-bit Extension Technology (EM64T). These latter two implementations are called *64-bit extended systems* and in this book are referred to as *x64*. (How Windows runs 32-bit applications on 64-bit Windows is explained in Chapter 8 in Part 2.) Additionally, as of Server 2008 R2, IA-64 systems are no longer supported by Windows.

Newer editions of Windows support the ARM processor architecture. For example, Windows RT was a version of Windows 8 that ran on ARM architecture, although that edition has since been discontinued. Windows 10 Mobile—the successor for Windows Phone 8.*x* operating systems—runs on ARM based processors, such as Qualcomm Snapdragon models. Windows 10 IoT runs on both x86 and ARM devices such as Raspberry Pi 2 (which uses an ARM Cortex-A7 processor) and Raspberry Pi 3 (which uses the ARM Cortex-A53). As ARM hardware has advanced to 64-bit, a new processor family called *AArch64*, or *ARM64*, may also at some point be supported, as an increasing number of devices run on it.

Windows achieves portability across hardware architectures and platforms in two primary ways:

- By using a layered design Windows has a layered design, with low-level portions of the system that are processor-architecture-specific or platform-specific isolated into separate modules so that upper layers of the system can be shielded from the differences between architectures and among hardware platforms. The two key components that provide OS portability are the kernel (contained in Ntoskrnl.exe) and the HAL (contained in Hal.dll). Both these components are described in more detail later in this chapter. Functions that are architecture-specific, such as thread context switching and trap dispatching, are implemented in the kernel. Functions that can differ among systems within the same architecture (for example, different motherboards) are implemented in the HAL. The only other component with a significant amount of architecture-specific code is the memory manager, but even that is a small amount compared to the system as a whole. The hypervisor follows a similar design, with most parts shared between the AMD (SVM) and Intel (VT-x) implementation, and some specific parts for each processor—hence the two file names on disk you saw in Table 2-1.
- **By using C** The vast majority of Windows is written in C, with some portions in C++. Assembly language is used only for those parts of the OS that need to communicate directly with system hardware (such as the interrupt trap handler) or that are extremely performance-sensitive (such as context switching). Assembly language code exists not only in the kernel and the HAL but also in a few other places within the core OS (such as the routines that implement interlocked

instructions as well as one module in the local procedure call facility), in the kernel-mode part of the Windows subsystem, and even in some user-mode libraries, such as the process startup code in Ntdll.dll (a system library explained later in this chapter).

## Symmetric multiprocessing

*Multitasking* is the OS technique for sharing a single processor among multiple threads of execution. When a computer has more than one processor, however, it can execute multiple threads simultaneously. Thus, whereas a multitasking OS only appears to execute multiple threads at the same time, a multiprocessing OS actually does it, executing one thread on each of its processors.

As mentioned at the beginning of this chapter, one of the key design goals for Windows was that it had to run well on multiprocessor computer systems. Windows is a *symmetric multiprocessing* (*SMP*) OS. There is no master processor—the OS as well as user threads can be scheduled to run on any processor. Also, all the processors share just one memory space. This model contrasts with *asymmetric multiprocessing* (*ASMP*), in which the OS typically selects one processor to execute OS kernel code while other processors run only user code. The differences in the two multiprocessing models are illustrated in Figure 2-2.




FIGURE 2-2 Symmetric vs. asymmetric multiprocessing.

Windows also supports four modern types of multiprocessor systems: multicore, simultaneous multi-threaded (SMT), heterogeneous, and non-uniform memory access (NUMA). These are briefly mentioned in the following paragraphs. (For a complete, detailed description of the scheduling support for these systems, see the section on thread scheduling in Chapter 4, "Threads.")

SMT was first introduced to Windows systems by adding support for Intel's Hyper-Threading Technology, which provides two logical processors for each physical core. Newer AMD processors under the Zen micro-architecture implement a similar SMT technology, also doubling the logical processor count.

From the Library of Octavian Mustafa

Each logical processor has its own CPU state, but the execution engine and onboard cache are shared. This permits one logical CPU to make progress while the other logical CPU is stalled (such as after a cache miss or branch misprediction). Confusingly, the marketing literature for both companies refers to these additional cores as *threads*, so you'll often see claims such as "four cores, eight threads." This indicates that up to eight threads can be scheduled, hence, the existence of eight logical processors. The scheduling algorithms are enhanced to make optimal use of SMT-enabled machines, such as by scheduling threads on an idle physical processor versus choosing an idle logical processor on a physical processor whose other logical processors are busy. For more details on thread scheduling, see Chapter 4.

In NUMA systems, processors are grouped in smaller units called *nodes*. Each node has its own processors and memory and is connected to the larger system through a cache-coherent interconnect bus. Windows on a NUMA system still runs as an SMP system, in that all processors have access to all memory. It's just that node-local memory is faster to reference than memory attached to other nodes. The system attempts to improve performance by scheduling threads on processors that are in the same node as the memory being used. It attempts to satisfy memory-allocation requests from within the node, but it will allocate memory from other nodes if necessary.

Naturally, Windows also natively supports multicore systems. Because these systems have real physical cores (simply on the same package), the original SMP code in Windows treats them as discrete processors, except for certain accounting and identification tasks (such as licensing, described shortly) that distinguish between cores on the same processor and cores on different sockets. This is especially important when dealing with cache topologies to optimize data-sharing.

Finally, ARM versions of Windows also support a technology known as *heterogeneous multi-processing*, whose implementation on such processors is called *big.LITTLE*. This type of SMP-based design differs from traditional ones in that not all processor cores are identical in their capabilities, yet unlike pure heterogeneous multi-processing, they are still able to execute the same instructions. The difference, then, comes from the clock speed and respective full load/idle power draws, allowing for a collection of slower cores to be paired with faster ones.

Think of sending an e-mail on an older dual-core 1 GHz system connected to a modern Internet connection. It's unlikely this will be any slower than on an eight-core 3.6 GHz machine because bottle-necks are mostly caused by human input typing speed and network bandwidth, not raw processing power. Yet even in its deepest power-saving mode, such a modern system is likely to use significantly more power than the legacy system. Even if it could regulate itself down to 1 GHz, the legacy system has probably set itself to 200 MHz, for example.

By being able to pair such legacy mobile processors with top-of-the-line ones, ARM-based platforms paired with a compatible OS kernel scheduler can maximize processing power when needed (by turning on all cores), strike a balance (by having certain big cores online and other little ones for other tasks), or run in extremely low power modes (by having only a single little core online—enough for SMS and push e-mail). By supporting what are called *heterogeneous scheduling policies*, Windows 10 allows threads to pick and choose between a policy that satisfies their needs, and will interact with the scheduler and power manager to best support it. You'll learn more about these policies in Chapter 4.

Windows was not originally designed with a specific processor number limit in mind, other than the licensing policies that differentiate the various Windows editions. However, for convenience and

efficiency, Windows does keep track of processors (total number, idle, busy, and other such details) in a bitmask (sometimes called an *affinity mask*) that is the same number of bits as the native data type of the machine (32-bit or 64-bit). This allows the processor to manipulate bits directly within a register. Due to this fact, Windows systems were originally limited to the number of CPUs in a native word, because the affinity mask couldn't arbitrarily be increased. To maintain compatibility, as well as support larger processor systems, Windows implements a higher-order construct called a *processor group*. The processor group is a set of processors that can all be defined by a single affinity bitmask, and the kernel as well as the applications can choose which group they refer to during affinity updates. Compatible applications can query the number of supported groups (currently limited to 20; the maximum number of logical processors is currently limited to 640) and then enumerate the bitmask for each group. Meanwhile, legacy applications continue to function by seeing only their current group. For more information on how exactly Windows assigns processors to groups (which is also related to NUMA) and legacy processes to groups, see Chapter 4.

As mentioned, the actual number of supported *licensed* processors depends on the edition of Windows being used. (See Table 2-2 later in this chapter.) This number is stored in the system license policy file (essentially a set of name/value pairs) %SystemRoot%\ServiceProfiles\LocalService\AppData\Local Microsoft\WSLicense\tokens.dat in the variable kerne1-RegisteredProcessors.

## Scalability

One of the key issues with multiprocessor systems is *scalability*. To run correctly on an SMP system, OS code must adhere to strict guidelines and rules. Resource contention and other performance issues are more complicated in multiprocessing systems than in uniprocessor systems and must be accounted for in the system's design. Windows incorporates several features that are crucial to its success as a multiprocessor OS:

- The ability to run OS code on any available processor and on multiple processors at the same time
- Multiple threads of execution within a single process, each of which can execute simultaneously on different processors
- Fine-grained synchronization within the kernel (such as spinlocks, queued spinlocks, and pushlocks, described in Chapter 8 in Part 2) as well as within device drivers and server processes, which allows more components to run concurrently on multiple processors
- Programming mechanisms such as I/O completion ports (described in Chapter 6, "I/O system") that facilitate the efficient implementation of multithreaded server processes that can scale well on multiprocessor systems

The scalability of the Windows kernel has evolved over time. For example, Windows Server 2003 introduced per-CPU scheduling queues with a fine-grained lock, permitting thread-scheduling decisions to occur in parallel on multiple processors. Windows 7 and Windows Server 2008 R2 eliminated global scheduler locking during wait-dispatching operations. This stepwise improvement of the granularity of locking has also occurred in other areas, such as the memory manager, cache manager, and object manager.

## Differences between client and server versions

Windows ships in both client and server retail packages. There are six desktop client versions of Windows 10: Windows 10 Home, Windows 10 Pro, Windows 10 Education, Windows 10 Pro Education, Windows 10 Enterprise, and Windows 10 Enterprise Long Term Servicing Branch (LTSB). Other non-desktop editions include Windows 10 Mobile, Windows 10 Mobile Enterprise, and Windows 10 IoT Core, IoT Core Enterprise, and IoT Mobile Enterprise. Still more variants exist that target world regions with specific needs, such as the N series.

There are six different versions of Windows Server 2016: Windows Server 2016 Datacenter, Windows Server 2016 Standard, Windows Server 2016 Essentials, Windows Server 2016 MultiPoint Premium Server, Windows Storage Server 2016, and Microsoft Hyper-V Server 2016.

These versions differ as follows:

- Core-based (rather than socket-based) pricing for the Server 2016 Datacenter and Standard edition
- The number of total logical processors supported
- For server systems, the number of Hyper-V containers allowed to run (client systems support only namespace-based Windows containers)
- The amount of physical memory supported (actually highest physical address usable for RAM; see Chapter 5, "Memory management," for more information on physical memory limits)
- The number of concurrent network connections supported (for example, a maximum of 10 concurrent connections are allowed to the file and print services in client versions)
- Support for multi-touch and Desktop Composition
- Support for features such as BitLocker, VHD booting, AppLocker, Hyper-V, and more than 100 other configurable licensing policy values
- Layered services that come with Windows Server editions that don't come with the client editions (for example, directory services, Host Guardian, Storage Spaces Direct, shielded virtual machines, and clustering)

Table 2-2 lists the differences in memory and processor support for some Windows 10, Windows Server 2012 R2, and Windows Server 2016 editions. For a detailed comparison chart of the different editions of Windows Server 2012 R2, see *https://www.microsoft.com/en-us/download/details.aspx?id=41703*. For Windows 10 and Server 2016 editions and earlier OS memory limits, see *https://msdn.microsoft.com/en-us/library/windows/desktop/aa366778.aspx*.

Although there are several client and server retail packages of the Windows OS, they share a common set of core system files, including the kernel image, Ntoskrnl.exe (and the PAE version, Ntkrnlpa.exe), the HAL libraries, the device drivers, and the base system utilities and DLLs.

TABLE 2-2 Processor and memory limits for some Windows editions

	Number of Sockets Supported (32-Bit Edition)	Physical Memory Supported (32-Bit Edition)	Number of Logical Processors/Sockets Supported (64-Bit Edition)	Physical Memory Supported (x64 Editions)
Windows 10 Home	1	4 GB	1 socket	128 GB
Windows 10 Pro	2	4 GB	2 sockets	2 TB
Windows 10 Enterprise	2	4 GB	2 sockets	2 TB
Windows Server 2012 R2 Essentials	Not available	Not available	2 sockets	64 GB
Windows Server 2016 Standard	Not available	Not available	512 logical processors	24 TB
Windows Server 2016 Datacenter	Not available	Not available	512 logical processors	24 TB

With so many different editions of Windows and each having the same kernel image, how does the system know which edition is booted? By querying the registry values ProductType and ProductSuite under the HKLM\SYSTEM\CurrentControlSet\Control\ProductOptions key. ProductType is used to distinguish whether the system is a client system or a server system (of any flavor). These values are loaded into the registry based on the licensing policy file described earlier. The valid values are listed in Table 2-3. This can be queried from the user-mode VerifyVersionInfo function or from a device driver using the kernel-mode support function RtlGetVersion and RtlVerifyVersionInfo, both documented in the Windows Driver Kit (WDK).

#### TABLE 2-3 ProductType registry values

Edition of Windows	Value of ProductType
Windows client	WinNT
Windows server (domain controller)	LanmanNT
Windows server (server only)	ServerNT

A different registry value, ProductPolicy, contains a cached copy of the data inside the tokens.dat file, which differentiates between the editions of Windows and the features that they enable.

So if the core files are essentially the same for the client and server versions, how do the systems differ in operation? In short, server systems are optimized by default for system throughput as high-performance application servers, whereas the client version (although it has server capabilities) is optimized for response time for interactive desktop use. For example, based on the product type, several resource-allocation decisions are made differently at system boot time, such as the size and number of OS heaps (or pools), the number of internal system worker threads, and the size of the system data cache. Also, run-time policy decisions, such as the way the memory manager trades off system and process memory demands, differ between the server and client editions. Even some thread-scheduling

details have different default behavior in the two families (the default length of the time slice, or thread *quantum*; see Chapter 4 for details). Where there are significant operational differences in the two products, these are highlighted in the pertinent chapters throughout the rest of this book. Unless otherwise noted, everything in this book applies to both the client and server versions.

### **EXPERIMENT:** Determining features enabled by licensing policy

As mentioned, Windows supports more than 100 different features that can be enabled through the software licensing mechanism. These policy settings determine the various differences not only between a client and server installation, but also between each edition (or SKU) of the OS, such as BitLocker support (available on Windows server as well as the Pro and Enterprise editions of Windows client). You can use the SIPolicy tool from the downloads available for the book to display many of these policy values.

Policy settings are organized by a *facility*, which represents the owner module for which the policy applies. You can display a list of all facilities known to the tool by running Slpolicy.exe with the –f switch:

```
C:\>SlPolicy.exe -f
Software License Policy Viewer Version 1.0 (C)2016 by Pavel Yosifovich
Desktop Windows Manager
Explorer
Fax
Kernel
IIS
```

You can then add the name of any facility after the switch to display the policy value for that facility. For example, to look at the limitations on CPUs and available memory, use the Kernel facility. Here's the expected output on a machine running Windows 10 Pro:

```
C:\>SlPolicy.exe -f Kernel
Software License Policy Viewer Version 1.0 (C)2016 by Pavel Yosifovich
Kernel
------
Maximum allowed processor sockets: 2
Maximum memory allowed in MB (x86): 4096
Maximum memory allowed in MB (x64): 2097152
Maximum memory allowed in MB (ARM64): 2097152
Maximum physical page in bytes: 4096
Device Family ID: 3
Native VHD boot: Yes
Dynamic Partitioning supported: No
Virtual Dynamic Partitioning supported: No
Memory Mirroring supported: No
Persist defective memory list: No
```

As another example, the output for the kernel facility for a Windows Server 2012 R2 Datacenter edition would look something like this:

```
Kernel
-----
Maximum allowed processor sockets: 64
Maximum memory allowed in MB (x86): 4096
Maximum memory allowed in MB (x64): 4194304
Add physical memory allowed: Yes
Add VM physical memory allowed: Yes
Maximum physical page in bytes: 0
Native VHD boot: Yes
Dynamic Partitioning supported: Yes
Virtual Dynamic Partitioning supported: Yes
Memory Mirroring supported: Yes
Persist defective memory list: Yes
```

# Checked build

There is a special internal debug version of Windows called the *checked build* (externally available only for Windows 8.1 and earlier with an MSDN Operating Systems subscription). It is a recompilation of the Windows source code with a compile-time flag defined called *DBG*, which causes compile time, conditional debugging, and tracing code to be included. Also, to make it easier to understand the machine code, the post-processing of the Windows binaries to optimize code layout for faster execution is not performed. (See the section "Debugging performance-optimized code" in the Debugging Tools for Windows help file.)

The checked build was provided primarily to aid device driver developers because it performs more stringent error-checking on kernel-mode functions called by device drivers or other system code. For example, if a driver (or some other piece of kernel-mode code) makes an invalid call to a system function that is checking parameters (such as acquiring a spinlock at the wrong interrupt request level), the system will stop execution when the problem is detected rather than allow some data structure to be corrupted and the system to possibly crash at a later time. Because a full checked build was often unstable and impossible to run in most environments, Microsoft provides a checked kernel and HAL only for Windows 10 and later. This enables developers to obtain the same level of usefulness from the kernel and HAL code they interact with without dealing with the issues that a full checked build would cause. This checked kernel and HAL pair is freely available through the WDK, in the \Debug directory of the root installation path. For detailed instructions on how to do this, see the section "Installing Just the Checked Operating System and HAL" in the WDK documentation.

### EXPERIMENT: Determining if you are running the checked build

There is no built-in tool to display whether you are running the checked build or the retail build (called the *free build*) of the kernel. However, this information is available through the Debug property of the Windows Management Instrumentation (WMI) Win32\_OperatingSystem class.

The following PowerShell script displays this property. (You can try this by opening a PowerShell script host.)

```
PS C:\Users\pavely> Get-WmiObject win32_operatingsystem | select debug
debug
```

False

This system is not running the checked build, because the Debug property shown here says False.

Much of the additional code in the checked-build binaries is a result of using the ASSERT and/or NT\_ASSERT macros, which are defined in the WDK header file Wdm.h and documented in the WDK documentation. These macros test a condition, such as the validity of a data structure or parameter. If the expression evaluates to FALSE, the macros either call the kernel-mode function Rt1Assert, which calls DbgPrintEx to send the text of the debug message to a debug message buffer, or issue an assertion interrupt, which is interrupt 0x2B on x64 and x86 systems. If a kernel debugger is attached and the appropriate symbols are loaded, this message is displayed automatically followed by a prompt asking the user what to do about the assertion failure (breakpoint, ignore, terminate process, or terminate thread). If the system wasn't booted with the kernel debugger (using the debug option in the Boot Configuration Database) and no kernel debugger is currently attached, failure of an assertion test will bug-check (crash) the system. For a small list of assertion checks made by some of the kernel support routines, see the section "Checked Build ASSERTs" in the WDK documentation (although note this list is unmaintained and outdated).

The checked build is also useful for system administrators because of the additional detailed informational tracing that can be enabled for certain components. (For detailed instructions, see the Microsoft Knowledge Base Article number 314743, titled "HOWTO: Enable Verbose Debug Tracing in Various Drivers and Subsystems.") This information output is sent to an internal debug message buffer using the DbgPrintEx function referred to earlier. To view the debug messages, you can either attach a kernel debugger to the target system (which requires booting the target system in debugging mode), use the !dbgprint command while performing local kernel debugging, or use the Dbgview.exe tool from Sysinternals. Most recent versions of Windows have moved away from this type of debug output, however, and use a combination of either Windows preprocessor (WPP) tracing or TraceLogging technology, both of which are built on top of Event Tracing for Windows (ETW). The advantage of these new logging mechanisms is that they are not solely limited to the checked versions of components (especially useful now that a full checked build is no longer available), and can be seen by using tools such as the Windows Performance Analyzer (WPA), formerly known as XPerf or Windows Performance Toolkit, TraceView (from the WDK), or the !wmiprint extension command in the kernel debugger.

Finally, the checked build can also be useful for testing user-mode code only because the timing of the system is different. (This is because of the additional checking taking place within the kernel and the fact that the components are compiled without optimizations.) Often, multithreaded synchronization bugs are related to specific timing conditions. By running your tests on a system running the checked build (or at least the checked kernel and HAL), the fact that the timing of the whole system is different might cause latent timing bugs to surface that do not occur on a normal retail system.

# Virtualization-based security architecture overview

As you saw in Chapter 1 and again in this chapter, the separation between user mode and kernel mode provides protection for the OS from user-mode code, whether malicious or not. However, if an unwanted piece of kernel-mode code makes it into the system (because of some yet-unpatched kernel or driver vulnerability or because the user was tricked into installing a malicious or vulnerable driver), the system is essentially compromised because all kernel-mode code has complete access to the entire system. The technologies outlined in Chapter 1, which leverage the hypervisor to provide additional guarantees against attacks, make up a set of virtualization-based security (VBS) capabilities, extending the processor's natural privilege-based separation through the introduction of Virtual Trust Levels (VTLs). Beyond simply introducing a new orthogonal way of isolating access to memory, hardware, and processor resources, VTLs also require new code and components to manage the higher levels of trust. The regular kernel and drivers, running in VTL 0, cannot be permitted to control and define VTL 1 resources; this would defeat the purpose.

Figure 2-3 shows the architecture of Windows 10 Enterprise and Server 2016 when VBS is active. (You'll also sometimes see the term *Virtual Secure Mode*, or *VSM*, used.) With Windows 10 version 1607 and Server 2016 releases, it's always active by default if supported by hardware. For older versions of Windows 10, you can activate it by using a policy or with the Add Windows Features dialog box (select the Isolated User Mode option).




FIGURE 2-3 Windows 10 and Server 2016 VBS architecture.

As shown in Figure 2-3, the user/kernel code discussed earlier is running on top of a Hyper-V hypervisor, just like in Figure 2-1. The difference is that with VBS enabled, a VTL of 1 is now present, which contains its own secure kernel running in the privileged processor mode (that is, ring 0 on x86/x64). Similarly, a run-time user environment mode, called the Isolated User Mode (IUM), now exists, which runs in unprivileged mode (that is, ring 3). In this architecture, the secure kernel is its own separate binary, which is found under the name securekernel.exe on disk. As for IUM, it's both an environment that restricts the allowed system calls that regular user-mode DLLs can make (thus limiting which of these DLLs can be loaded) and a framework that adds special secure system calls that can execute only under VTL 1. These additional system calls are exposed in a similar way as regular system calls: through an internal system library named *lumdll.dll* (the VTL 1 version of Ntdll.dll) and a Windows subsystem–facing library named *lumbase.dll* (the VTL 1 version of Kernelbase.dll). This implementation of IUM, mostly sharing the same standard Win32 API libraries, allows for the reduction of the memory overhead of VTL 1 user-mode applications because essentially, the same user-mode code is present as in their VTL 0 counterparts. As an important note, copy-on-write mechanisms, which you'll learn more about in Chapter 5, prevent VTL 0 applications from making changes to binaries used by VTL 1.

With VBS, the regular user versus kernel rules apply, but are now augmented by VTL considerations. In other words, kernel-mode code running at VTL 0 cannot touch user mode running at VTL 1 because VTL 1 is more privileged. Yet, user-mode code running at VTL 1 cannot touch kernel mode running at VTL 0 either because user (ring 3) cannot touch kernel (ring 0). Similarly, VTL 1 user-mode applications must still go through regular Windows system calls and their respective access checks if they wish to access resources.

A simple way of thinking about this is as follows: privilege levels (user versus kernel) enforce *power*. VTLs, on the other hand, enforce *isolation*. Although a VTL 1 user-mode application is not more powerful than a VTL 0 application or driver, it is isolated from it. In fact, VTL 1 applications aren't just *not* more powerful; in many cases, they're much less so. Because the secure kernel does not implement a full range of system capabilities, it hand-picks which system calls it will forward to the VTL 0 kernel. (Another name for secure kernel is *proxy kernel*.) Any kind of I/O, including file, network, and registry-based, is completely prohibited. Graphics, as another example, are out of the question. Not a single driver is allowed to be communicated with.

The secure kernel however, by both running at VTL 1 and being in kernel mode, does have complete access to VTL 0 memory and resources. It can use the hypervisor to limit the VTL 0 OS access to certain memory locations by leveraging CPU hardware support known as Second Level Address Translation (SLAT). SLAT is the basis of Credential Guard technology, which can store secrets in such locations. Similarly, the secure kernel can use SLAT technology to interdict and control execution of memory locations, a key covenant of Device Guard.

To prevent normal device drivers from leveraging hardware devices to directly access memory, the system uses another piece of hardware known as the *I/O memory management unit (MMU)*, which effectively virtualizes memory access for devices. This can be used to prevent device drivers from using direct memory access (DMA) to directly access the hypervisor or secure kernel's physical regions of memory. This would bypass SLAT because no virtual memory is involved.

Because the hypervisor is the first system component to be launched by the boot loader, it can program the SLAT and I/O MMU as it sees fit, defining the VTL 0 and 1 execution environments. Then, while in VTL 1, the boot loader runs again, loading the secure kernel, which can configure the system further to its needs. Only then is the VTL dropped, which will see the execution of the normal kernel, now living in its VTL 0 jail, unable to escape. Because user-mode processes running in VTL 1 are isolated, potentially malicious code—while not able to exert greater influence over the system—could run surreptitiously, attempt secure system calls (which would allow it to seal/sign its own secrets), and potentially cause bad interactions with other VTL 1 processes or the smart kernel. As such, only a special class of specially signed binaries, called *Trustlets*, are allowed to execute in VTL 1. Each Trustlet has a unique identifier and signature, and the secure kernel has hard-coded knowledge of which Trustlets have been created so far. As such, it is impossible to create new Trustlets without access to the secure kernel (which only Microsoft can touch), and existing Trustlets cannot be patched in any way (which would void the special Microsoft signature). For more information on Trustlets, see Chapter 3.

The addition of the secure kernel and VBS is an exciting step in modern OS architecture. With additional hardware changes to various buses such as PCI and USB, it will soon be possible to support an entire class of secure devices, which, when combined with a minimalistic secure HAL, secure Plug-and-Play manager, and secure User-Mode Device Framework, could allow certain VTL 1 applications direct and segregated access to specially designated devices, such as for biometric or smartcard input. New versions of Windows 10 are likely to leverage such advances.

# Key system components

Now that we've looked at the high-level architecture of Windows, let's delve deeper into the internal structure and the role each key OS component plays. Figure 2-4 is a more detailed and complete diagram of the core Windows system architecture and components than was shown in Figure 2-1. Note that it still does not show all components (networking in particular, which is explained in Chapter 10, "Networking," in Part 2).




FIGURE 2-4 Windows architecture.

The following sections elaborate on each major element of this diagram. Chapter 8 in Part 2 explains the primary control mechanisms the system uses (such as the object manager, interrupts, and so forth). Chapter 11, "Startup and shutdown," in Part 2 describes the process of starting and shutting down Windows, and Chapter 9 in Part 2 details management mechanisms such as the registry, service processes and WMI. Other chapters explore in even more detail the internal structure and operation of key areas such as processes and threads, memory management, security, the I/O manager, storage management, the cache manager, the Windows file system (NTFS), and networking.

# **Environment subsystems and subsystem DLLs**

The role of an environment subsystem is to expose some subset of the base Windows executive system services to application programs. Each subsystem can provide access to different subsets of the native services in Windows. That means that some things can be done from an application built on one subsystem that can't be done by an application built on another subsystem. For example, a Windows application can't use the SUA fork function.

Each executable image (.exe) is bound to one and only one subsystem. When an image is run, the process creation code examines the subsystem type code in the image header so that it can notify the proper subsystem of the new process. This type code is specified with the /SUBSYSTEM linker option of the Microsoft Visual Studio linker (or through the SubSystem entry in the Linker/System property page in the project's properties).

As mentioned, user applications don't call Windows system services directly. Instead, they go through one or more subsystem DLLs. These libraries export the documented interface that the programs linked to that subsystem can call. For example, the Windows subsystem DLLs (such as Kernel32.dll, Advapi32.dll, User32.dll, and Gdi32.dll) implement the Windows API functions. The SUA subsystem DLL (Psxdll.dll) is used to implement the SUA API functions (on Windows versions that supported POSIX).

#### EXPERIMENT: Viewing the image subsystem type

You can see the image subsystem type by using the Dependency Walker tool (Depends.exe). For example, notice the image types for two different Windows images, Notepad.exe (the simple text editor) and Cmd.exe (the Windows command prompt):

		dp 8 2 2 1 1 1	2						- 8
Module ^	File Time Stamp	Link Time Stamp	File Size	Attr.	Link Checksum	Real Checksum	CPU	Subsystem	Symbols
NCRYPT.DLL	19-02-2016 15:40 19-02-2016 15:40 19-02-2016 15:40 19-02-2016 15:40 19-02-2016 15:40	19-02-2016 11:40 19-02-2016 11:40 19-02-2016 11:40 19-02-2016 11:40 19-02-2016 11:34	142,568 76,456 39,232 510,464	AA	0x0002978A 0x0001881A 0x0000ED7C 0x00086433	0x000297BA 0x0001881A 0x0000ED7C 0x00086433	x64 x64 x64 x64	Console Console Console Console	CV,Unknown CV,Unknown CV,Unknown CV,Unknown
NOTEPAD.EXE NSI.DLL NTASN1.DLL	19-02-2016 15:41 19-02-2016 15:40 19-02-2016 15:40 19-02-2016 15:40 19-02-2016 15:40	19-02-2016 11:29 19-02-2016 11:36 19-02-2016 11:40 19-02-2016 11:28	238,592 20,136 238,560 1,855,800	A	0x000429F1 0x0000D1C6 0x0004101A 0x001D0760	0x000429F1 0x0000D1C6 0x0004101A 0x001D0760	x64 x64 x64 x64	GUI Console GUI Console	CV.Unknown CV,Unknown CV,Unknown CV,Unknown

<b>1</b>	Eile Edit View Options Profile Windo	w <u>H</u> elp								-	5 :
<b>F</b>	🖬 🔎 陀 여 🔤 🛺 📾 🚇 🚇	到國  28  28  28  28  28  28  28  28  28  2									
	Module ^	File Time Stamp	Link Time Stamp	File Size	Attr.	Link Checksum	Real Checksum	CPU	Subsystem	Symbols	
00	API-MS-WIN-EVENTING-PROVIDER-L1-1-0. API-MS-WIN-SECURITY-BASE-L1-2-0.DLL		The system cannot fir The system cannot fir								
6	CMD.EXE		19-02-2016 11:33	232,960		0x0003CFFE	0x0003CFFE	x64	Console	CV, Unkno	nwo
000	EXT-MS-WIN-ADVAPI32-NPUSERNAME-L1 EXT-MS-WIN-ADVAPI32-NTMARTA-L1-1-0 EXT-MS-WIN-ADVAPI32-REGISTRY-L1-1-0.1	Error opening file.	The system cannot fir	d the file spe	cified (2)						
e											3

This shows that Notepad is a GUI program, while Cmd is a console, or character-based, program. Although this implies there are two different subsystems for GUI and character-based programs, there is just one Windows subsystem, and GUI programs can have consoles (by calling the AllocConsole function), just like console programs can display GUIs.

When an application calls a function in a subsystem DLL, one of three things can occur:

- The function is entirely implemented in user mode inside the subsystem DLL. In other words, no message is sent to the environment subsystem process, and no Windows executive system services are called. The function is performed in user mode, and the results are returned to the caller. Examples of such functions include GetCurrentProcess (which always returns -1, a value that is defined to refer to the current process in all process-related functions) and GetCurrentProcessId. (The processID doesn't change for a running process, so this ID is retrieved from a cached location, thus avoiding the need to call into the kernel.)
- The function requires one or more calls to the Windows executive. For example, the Windows ReadFile and WriteFile functions involve calling the underlying internal (and undocumented for user-mode use) Windows I/O system services NtReadFile and NtWriteFile, respectively.
- The function requires some work to be done in the environment subsystem process. (The environment subsystem processes, running in user mode, are responsible for maintaining the state of the client applications running under their control.) In this case, a client/server request is made to the environment subsystem via an ALPC (described in Chapter 8 in Part 2) message sent to the subsystem to perform some operation. The subsystem DLL then waits for a reply before returning to the caller.

Some functions can be a combination of the second and third items just listed, such as the Windows CreateProcess and ExitWindowsEx functions.

#### Subsystem startup

Subsystems are started by the Session Manager (Smss.exe) process. The subsystem startup information is stored under the registry key HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\SubSystems. Figure 2-5 shows the values under this key (Windows 10 Pro snapshot).

Eile Edit	¥iew Favor	rites <u>H</u> elp			
(init) is 5th		ServiceAggregateEvi A ServiceGroupOrder ServiceGroupOrder Session Manager AppCompatCachi Configuration Ma DOS Devices Environment Executive FileBenameOperat V/O System kernel KnownDLLs Memory Manager NamespaceSepare Power Quota System SubSystems WPA SMMP SQMServiceList Sro	Name Default) Cobug Nonde Optional Required Windows	Type REG_SZ REG_EXPAND_SZ REG_MULTI_SZ REG_MULTI_SZ REG_MULTI_SZ REG_EXPAND_SZ	Data mmmsnvc \SystemRoot\System32\win32k.sys Debug Windows %SystemRoot%\system32\csrss.exe ObjectDirectory=\V
c		aic	(		>

FIGURE 2-5 Registry Editor showing Windows subsystem information.

The Required value lists the subsystems that load when the system boots. The value has two strings: Windows and Debug. The Windows value contains the file specification of the Windows subsystem, Csrss.exe, which stands for *Client/Server Runtime Subsystem*. Debug is blank (this value has not been needed since Windows XP, but the registry value is kept for compatibility) and therefore does nothing. The Optional value indicates optional subsystems, which in this case is blank as well because SUA is no longer available on Windows 10. If it was, a data value of Posix would point to another value pointing to Psxss.exe (the POSIX subsystem process). A value of Optional means "loaded on demand," which means the first time a POSIX image is encountered. The registry value Kmode contains the file name of the kernel-mode portion of the Windows subsystem, Win32k.sys (explained later in this chapter).

Let's take a closer look at the Windows environment subsystems.

#### Windows subsystem

Although Windows was designed to support multiple independent environment subsystems, from a practical perspective, having each subsystem implement all the code to handle windowing and display I/O would result in a large amount of duplication of system functions that, ultimately, would negatively affect both system size and performance. Because Windows was the primary subsystem, the Windows designers decided to locate these basic functions there and have the other subsystems call on the Windows subsystem to perform display I/O. Thus, the SUA subsystem calls services in the Windows subsystem to perform display I/O.

As a result of this design decision, the Windows subsystem is a required component for any Windows system, even on server systems with no interactive users logged in. Because of this, the process is marked as a critical process (which means if it exits for any reason, the system crashes).

The Windows subsystem consists of the following major components:

- For each session, an instance of the environment subsystem process (Csrss.exe) loads four DLLs (Basesrv.dll, Winsrv.dll, Sxssrv.dll, and Csrsrv.dll) that contain support for the following:
  - Various housekeeping tasks related to creating and deleting processes and threads
  - Shutting down Windows applications (through the ExitWindowsEx API)
  - Containing .ini file to registry location mappings for backward compatibility
  - Sending certain kernel notification messages (such as those from the Plug-and-Play manager) to Windows applications as Window messages (WM\_DEVICECHANGE)
  - Portions of the support for 16-bit virtual DOS machine (VDM) processes (32-bit Windows only)
  - Side-by-Side (SxS)/Fusion and manifest cache support
  - Several natural language support functions, to provide caching

**Note** Perhaps most critically, the kernel mode code that handles the raw input thread and desktop thread (responsible for the mouse cursor, keyboard input, and handling of the desktop window) is hosted inside threads running inside Winsrv.dll. Additionally, the Csrss.exe instances associated with interactive user sessions contain a fifth DLL called the Canonical Display Driver (Cdd.dll). CDD is responsible for communicating with the DirectX support in the kernel (see the upcoming discussion) on each vertical refresh (VSync) to draw the visible desktop state without traditional hardware-accelerated GDI support.

- A kernel-mode device driver (Win32k.sys) that contains the following:
  - The window manager, which controls window displays; manages screen output; collects input from keyboard, mouse, and other devices; and passes user messages to applications
  - The Graphics Device Interface (GDI), which is a library of functions for graphics output devices and includes functions for line, text, and figure drawing and for graphics manipulation
  - Wrappers for DirectX support that is implemented in another kernel driver (Dxgkrnl.sys)
- The console host process (Conhost.exe), which provides support for console (character cell) applications
- The Desktop Window Manager (Dwm.exe), which allows for compositing visible window rendering into a single surface through the CDD and DirectX
- Subsystem DLLs (such as Kernel32.dll, Advapi32.dll, User32.dll, and Gdi32.dll) that translate documented Windows API functions into the appropriate and undocumented (for user-mode) kernel-mode system service calls in Ntoskrnl.exe and Win32k.sys
- Graphics device drivers for hardware-dependent graphics display drivers, printer drivers, and video miniport drivers

**Note** As part of a refactoring effort in the Windows architecture called *MinWin*, the subsystem DLLs are now generally composed of specific libraries that implement API Sets, which are then linked together into the subsystem DLL and resolved using a special redirection scheme. For more information on this refactoring, see the "Image loader" section in Chapter 3.

#### Windows 10 and Win32k.sys

The basic window-management requirements for Windows 10–based devices vary considerably depending on the device in question. For example, a full desktop running Windows needs all the window manager's capabilities, such as resizable windows, owner windows, child windows and so forth. Windows Mobile 10 running on phones or small tablets doesn't need many of these features because there's only one window in the foreground and it cannot be minimized or resized, etc. The same goes for IoT devices, which may not even have a display at all.

For these reasons, the functionality of Win32K.sys has been split among several kernel modules so that not all modules may be required on a specific system. This significantly reduces the attack surface of the window manager by reducing the complexity of the code and eliminating many of its legacy pieces. Here are some examples:

- On phones (Windows Mobile 10) Win32k.sys loads Win32kMin.sys and Win32kBase.sys.
- On full desktop systems Win32k.sys loads Win32kBase.sys and Win32kFull.sys.
- On certain IoT systems, Win32k.sys might only need Win32kBase.sys.

Applications call the standard USER functions to create user-interface controls, such as windows and buttons, on the display. The window manager communicates these requests to the GDI, which passes them to the graphics device drivers, where they are formatted for the display device. A display driver is paired with a video miniport driver to complete video display support.

The GDI provides a set of standard two-dimensional functions that let applications communicate with graphics devices without knowing anything about the devices. GDI functions mediate between applications and graphics devices such as display drivers and printer drivers. The GDI interprets application requests for graphic output and sends the requests to graphics display drivers. It also provides a standard interface for applications to use varying graphics output devices. This interface enables application code to be independent of the hardware devices and their drivers. The GDI tailors its messages to the capabilities of the device, often dividing the request into manageable parts. For example, some devices can understand directions to draw an ellipse; others require the GDI to interpret the command as a series of pixels placed at certain coordinates. For more information about the graphics and video driver architecture, see the "Design Guide" section of the "Display (Adapters and Monitors)" chapter in the WDK.

Because much of the subsystem—in particular, display I/O functionality—runs in kernel mode, only a few Windows functions result in sending a message to the Windows subsystem process: process and thread creation and termination and DOS device drive letter mapping (such as through subst.exe).

In general, a running Windows application won't cause many, if any, context switches to the Windows subsystem process, except as needed to draw the new mouse cursor position, handle keyboard input, and render the screen through CDD.

# Console window host

In the original Windows subsystem design, the subsystem process (Csrss.exe) was responsible for managing console windows and each console application (such as Cmd.exe, the command prompt) communicated with Csrss.exe. Starting with Windows 7, a separate process is used for each console window on the system: the console window host (Conhost.exe). (A single console window can be shared by multiple console applications, such as when you launch a command prompt from the command prompt. By default, the second command prompt shares the console window of the first.) The details of the Windows 7 console host are explained in Chapter 2 of the sixth edition of this book.

With Windows 8 and later, the console architecture changed yet again. The Conhost.exe process remains, but is now spawned from the console-based process (rather than from Csrss.exe, as in Windows 7) by the console driver (\Windows\System32\Drivers\ConDrv.sys). The process in question communicates with Conhost.exe using the console driver (ConDrv.sys), by sending read, write, I/O control and other I/O request types. Conhost.exe is designated as a server and the process using the console is the client. This change obviates the need for Csrss.exe to receive keyboard input (as part of the raw input thread), send it through Win32k.sys to Conhost.exe, and then use ALPC to send it to Cmd.exe. Instead, the command-line application can directly receive input from the console driver through read/write I/Os, avoiding needless context switching.

The following Process Explorer screen shows the handle Conhost.exe holds open to the device object exposed by ConDrv.sys named \Device\ConDrv. (For more details on device names and I/O, see Chapter 6.)

Eile Options View Process Find H		<u>H</u> elp					
Process	PID	CPU	Private Bytes	Working Set	Integrity	Description	Compa *
🖃 📷 cmd.exe	9276		2,468 K 6,264 K High	High	Windows Command Pro	ocessor Microso	
conhost.exe	18172	-	11.312 K	15,576 K	High	Console Window Host	Microso
mconnect.exe	16280 <	16280 0.09 207.012 K 213.780 K Hinh				Virtual Machine Conner	tion Micman
Handle Type	Name					0	bject Address
0x4 File	\Device\ConDrv					0xFFFFE00	OCD10BE10 F
0x8 Directory	\KnownDlls					0xFFFFC00	000C688D60 C
OxC Event						0xFFFFE00	00D478E6E0 F
Ox10 Event						0xFFFFE00	ODODGAFOO F
¢							,

Notice that Conhost.exe is a child process of the console process (in this case, Cmd.exe). Conhost creation is initiated by the image loader for Console subsystem images or on demand if a GUI subsystem image calls the AllocConsole Windows API. (Of course, GUI and Console are essentially the same in the sense both are variants of the Windows subsystem type.) The real workhorse of Conhost.exe is a DLL it loads (\Windows\System32\ConhostV2.dll) that includes the bulk of code that communicates with the console driver.

# Other subsystems

As mentioned, Windows originally supported POSIX and OS/2 subsystems. Because these subsystems are no longer provided with Windows, they are not covered in this book. The general concept of subsystems remains, however, making the system extensible to new subsystems if such a need arises in the future.

### Pico providers and the Windows subsystem for Linux

The traditional subsystem model, while extensible and clearly powerful enough to have supported POSIX and OS/2 for a decade, has two important technical disadvantages that made it hard to reach broad usage of non-Windows binaries beyond a few specialized use cases:

- As mentioned, because subsystem information is extracted from the Portable Executable (PE) header, it requires the source code of the original binary to rebuild it as a Windows PE executable file (.exe). This will also change any POSIX-style dependencies and system calls into Windows-style imports of the Psxdll.dll library.
- It is limited by the functionality provided either by the Win32 subsystem (on which it sometimes piggybacks) or the NT kernel. Therefore, the subsystem wraps, instead of emulates, the behavior required by the POSIX application. This can sometimes lead to subtle compatibility flaws.

Finally, it's also important to point out, that as the name says, the POSIX subsystem/SUA was designed with POSIX/UNIX applications in mind, which dominated the server market decades ago, not true Linux applications, which are common today.

Solving these issues required a different approach to building a subsystem—one that did not require the traditional user-mode wrapping of the other environments' system call and the execution of traditional PE images. Luckily, the Drawbridge project from Microsoft Research provided the perfect vehicle for an updated take on subsystems. It resulted in the implementation of the Pico model.


Under this model, the idea of a *Pico provider* is defined, which is a custom kernel-mode driver that receives access to specialized kernel interfaces through the PsRegisterPicoProvider API. The benefits of these specialized interfaces are two-fold:

- They allow the provider to create Pico processes and threads while customizing their execution contexts, segments, and store data in their respective EPROCESS and ETHREAD structures (see Chapter 3 and Chapter 4 for more on these structures).
- They allow the provider to receive a rich set of notifications whenever such processes or threads engage in certain system actions such as system calls, exceptions, APCs, page faults, termination, context changes, suspension/resume, etc.

With Windows 10 version 1607, one such Pico provider is present: Lxss.sys and its partner Lxcore.sys. As the name suggests, this refers to the Windows Subsystem for Linux (WSL) component, and these drivers make up the Pico provider interface for it.

Because the Pico provider receives almost all possible transitions to and from user and kernel mode (be they system calls or exceptions, for example), as long as the Pico process (or processes) running underneath it has an address space that it can recognize, and has code that can natively execute within it, the "true" kernel below doesn't really matter as long as these transitions are handled in a fully transparent way. As such, Pico processes running under the WSL Pico provider, as you'll see in Chapter 3, are very different from normal Windows processes—lacking, for example, the Ntdll.dll that is always loaded into normal processes. Instead, their memory contains structures such as a vDSO, a special image seen only on Linux/BSD systems.

Furthermore, if the Linux processes are to run transparently, they must be able to execute without requiring recompilation as PE Windows executables. Because the Windows kernel does not know how to map other image types, such images cannot be launched through the CreateProcess API by a Windows process, nor do they ever call such APIs themselves (because they have no idea they are running on Windows). Such interoperability support is provided both by the Pico provider and the LXSS Manager, which is a user-mode service. The former implements a private interface that it uses to communicate with the LXSS Manager. The latter implements a COM-based interface that it uses to communicate with a specialized launcher process, currently known as *Bash.exe*, and with a management process, called *Lxrun.exe*. The following diagram shows an overview of the components that make up WSL.



Providing support for a wide variety of Linux applications is a massive undertaking. Linux has hundreds of system calls—about as many as the Windows kernel itself. Although the Pico provider can leverage existing features of Windows—many of which were built to support the original POSIX subsystem, such as fork() support—in some cases, it must re-implement functionality on its own. For example, even though NTFS is used to store the actual file system (and not EXTFS), the Pico provider has an entire implementation of the Linux Virtual File System (VFS), including support for inodes, inotify(), and /sys, /dev, and other similar Linux-style file-system–based namespaces with corresponding behaviors. Similarly, while the Pico provider can leverage Windows Sockets for Kernel (WSK) for networking, it has complex wrapping around actual socket behavior, such that it can support UNIX domain sockets, Linux NetLink sockets, and standard Internet sockets.

In other cases, existing Windows facilities were simply not adequately compatible, sometimes in subtle ways. For example, Windows has a named pipe driver (Npfs.sys) that supports the traditional pipe IPC mechanism. Yet, it's subtly different enough from Linux pipes that applications would break. This required a from-scratch implementation of pipes for Linux applications, without using the kernel's Npfs.sys driver.

As the feature is still officially in beta at the time of this writing and subject to significant change, we won't cover the actual internals of the subsystem in this book. We will, however, take another look at Pico processes in Chapter 3. When the subsystem matures beyond beta, you will probably see official documentation on MSDN and stable APIs for interacting with Linux processes from Windows.

### Ntdll.dll

Ntdll.dll is a special system support library primarily for the use of subsystem DLLs and native applications. (*Native* in this context refers to images that are not tied to any particular subsystem.) It contains two types of functions:

- System service dispatch stubs to Windows executive system services
- Internal support functions used by subsystems, subsystem DLLs, and other native images

The first group of functions provides the interface to the Windows executive system services that can be called from user mode. There are more than 450 such functions, such as NtCreateFile, Nt-SetEvent, and so on. As noted, most of the capabilities of these functions are accessible through the Windows API. (A number are not, however, and are for use only by specific OS-internal components.)

For each of these functions, Ntdll.dll contains an entry point with the same name. The code inside the function contains the architecture-specific instruction that causes a transition into kernel mode to invoke the system service dispatcher. (This is explained in more detail in Chapter 8 in Part 2.) After verifying some parameters, this system service dispatcher calls the actual kernel-mode system service that contains the real code inside Ntoskrnl.exe. The following experiment shows what these functions look like.

## EXPERIMENT: Viewing the system service dispatcher code

Open the version of WinDbg that corresponds to your system's architecture (for example the x64 version bit on 64 bit Windows). Then open the **File** menu and select **Open Executable**. Navigate to **%SystemRoot%\System32** and select **Notepad.exe**.

Notepad should launch and the debugger should break in the initial breakpoint. This is very early in the life of the process, which you can witness by executing the k (call stack) command. You should see a few functions starting with Ldr, which indicates the image loader. The main function for Notepad has not executed yet, which means you won't see Notepad's window.

Set a breakpoint in the NtCreateFile inside Ntdll.dll (the debuggers are not case sensitive):

bp ntdll!ntcreatefile

Enter the **g** (go) command or press **F5** to let Notepad continue execution. The debugger should break almost immediately, showing something like this (x64):

Breakpoint 0 hit ntdll!NtCreateFile: 00007ffa'9f4e5b10 4c8bd1 mov r10,rcx You may see the function name as ZwCreateFile. ZwCreateFile and NtCreateFile refer to the same symbol in user mode. Now enter the **u** (unassembled) command to see a few instructions ahead:

00007ffa'9f4e5b10 4c8bd1	mov	r10,rcx
00007ffa'9f4e5b13 b855000000	mov	eax,55h
00007ffa'9f4e5b18 f604250803fe7f0	1 test	byte ptr [SharedUserData+0x308
(0000000'7ffe0308)],1		
00007ffa'9f4e5b20 7503	jne	ntdll!NtCreateFile+0x15
(00007ffa'9f4e5b25)		
00007ffa'9f4e5b22 0f05	syscall	
00007ffa'9f4e5b24 c3	ret	
00007ffa'9f4e5b25 cd2e	int	2Eh
00007ffa'9f4e5b27 c3	ret	

The EAX register is set with the system service number (55 hex in this case). This is the system service number on this OS (Windows 10 Pro x64). Then notice the syscall instruction. This is the one causing the processor to transition to kernel mode, jumping to the system service dispatcher, where that EAX is used to select the NtCreateFile executive service. You'll also notice a check for a flag (1) at offset 0x308 in the Shared User Data (more information on this structure is available in Chapter 4). If this flag is set, execution will take another path, by using the int 2Eh instruction instead. If you enable the specific Credential Guard VBS feature that is described in Chapter 7, this flag will be set on your machine, because the hypervisor can react to the int instruction in a more efficient fashion than the syscall instruction, and this behavior is beneficial to Credential Guard.

As mentioned, more details about this mechanism (and the behavior of both syscall and int) are provided in Chapter 8 in Part 2. For now, you can try to locate other native services such as NtReadFile, NtWriteFile and NtClose.

You saw in the "Virtualization-based security architecture overview" section that IUM applications can leverage another binary similar to Ntdll.dll, called *lumDll.dll*. This library also contains system calls, but their indices will be different. If you have a system with Credential Guard enabled, you can repeat the preceding experiment by opening the **File** menu in WinDbg, choosing **Open Crash Dump**, and choosing **lumDll.dll** as the file. Note how in the following output, the system call index has the high bit set, and no SharedUserData check is done; syscall is always the instruction used for these types of system calls, which are called *secure system calls*:

0:000> u iumdll!Iu	umCrypto		
<pre>iumdll!IumCrypto:</pre>			
00000001'80001130	4c8bd1	mov	r10,rcx
00000001'80001133	b802000008	mov	eax,8000002h
00000001'80001138	0f05	syscall	
00000001'8000113a	c3	ret	

Ntdll.dll also contains many support functions, such as the image loader (functions that start with Ldr), the heap manager, and Windows subsystem process communication functions (functions that

start with Csr). Ntdll.dll also includes general run-time library routines (functions that start with Rt1), support for user-mode debugging (functions that start with DbgUi), Event Tracing for Windows (functions starting in Etw), and the user-mode asynchronous procedure call (APC) dispatcher and exception dispatcher. (APCs are explained briefly in Chapter 6 and in more detail in Chapter 8 in Part 2, as well as exceptions.)

Finally, you'll find a small subset of the C Run-Time (CRT) routines in Ntdll.dll, limited to those routines that are part of the string and standard libraries (such as memcpy, strcpy, sprintf, and so on); these are useful for native applications, described next.

#### Native images

Some images (executables) don't belong to any subsystem. In other words, they don't link against a set of subsystem DLLs, such as Kernel32.dll for the Windows subsystem. Instead, they link only to Ntdll.dll, which is the lowest common denominator that spans subsystems. Because the native API exposed by Ntdll.dll is mostly undocumented, these kind of images are typically built only by Microsoft. One example is the Session Manager process (Smss.exe, described in more detail later in this chapter). Smss.exe is the first user-mode process created (directly by the kernel), so it cannot be dependent on the Windows subsystem because Csrss.exe (the Windows subsystem process) has not started yet. In fact, Smss.exe is responsible for launching Csrss.exe. Another example is the Autochk utility that sometimes runs at system startup to check disks. Because it runs relatively early in the boot process (launched by Smss.exe, in fact), it cannot depend on any subsystem.

Here is a screenshot of Smss.exe in Dependency Walker, showing its dependency on Ntdll.dll only. Notice the subsystem type is indicated by Native.

<b>n</b> ¢ (	Eile Edit 3	(iew Options Pro	ofile Window Help									-	8 )
6	🖬 🔎 k	: c:1 📴 🖓 🛙	8 3 4 3	880	<b>N</b> ?								
8	SMSS.E			PI	Ordinal	^ Hint	Function	Entry Point					
		TDLL.DLL		E	Ordinal	Hint	Function	Entry Point					
	Module ^	File Time Stamp	Link Time Stamp	File Size	Attr.	Link Chec	ksum Re	al Checksum	CPU	Subsystem	Symbols	Preferred Base	Acti
	NTDLL.DLL	19-02-2016 15:40	19-02-2016 11:28	1,855,800	A	0x001D0	760 Obd	0100760	х64	Console	CV,Unknown	0x00000018000000	Unk
	SMSS.EXE	19-02-2016 15:40	19-02-2016 11:33	132,736			50C 0		x64	Native	CV Linknown	0x0000000140000000	Unk

# Executive

The Windows executive is the upper layer of Ntoskrnl.exe. (The kernel is the lower layer.) The executive includes the following types of functions:

Functions that are exported and callable from user mode These functions are called system services and are exported via Ntdll.dll (such as NtCreateFile from the previous experiment). Most of the services are accessible through the Windows API or the APIs of another environment subsystem. A few services, however, aren't available through any documented subsystem function. (Examples include ALPC and various query functions such as NtQuery-InformationProcess, specialized functions such as NtCreatePagingFile, and so on.)

- Device driver functions that are called through the DeviceloControl function This provides a general interface from user mode to kernel mode to call functions in device drivers that are not associated with a read or write. The driver used for Process Explorer and Process Monitor from Sysinternals are good examples of that as is the console driver (ConDrv.sys) mentioned earlier.
- Functions that can be called only from kernel mode that are exported and documented in the WDK These include various support routines, such as the I/O manager (start with Io), general executive functions (Ex) and more, needed for device driver developers.
- Functions that are exported and can be called from kernel mode but are not documented in the WDK These include the functions called by the boot video driver, which start with Inbv.
- Functions that are defined as global symbols but are not exported These include internal support functions called within Ntoskrnl.exe, such as those that start with Iop (internal I/O manager support functions) or Mi (internal memory management support functions).
- Functions that are internal to a module that are not defined as global symbols These functions are used exclusively by the executive and kernel.

The executive contains the following major components, each of which is covered in detail in a subsequent chapter of this book:

- **Configuration manager** The configuration manager, explained in Chapter 9 in Part 2, is responsible for implementing and managing the system registry.
- Process manager The process manager, explained in Chapter 3 and Chapter 4, creates and terminates processes and threads. The underlying support for processes and threads is implemented in the Windows kernel; the executive adds additional semantics and functions to these lower-level objects.
- Security Reference Monitor (SRM) The SRM, described in Chapter 7, enforces security policies on the local computer. It guards OS resources, performing run-time object protection and auditing.
- **I/O manager** The I/O manager, discussed in Chapter 6, implements device-independent I/O and is responsible for dispatching to the appropriate device drivers for further processing.
- Plug and Play (PnP) manager The PnP manager, covered in Chapter 6, determines which drivers are required to support a particular device and loads those drivers. It retrieves the hardware resource requirements for each device during enumeration. Based on the resource requirements of each device, the PnP manager assigns the appropriate hardware resources such as I/O ports, IRQs, DMA channels, and memory locations. It is also responsible for sending proper event notification for device changes (the addition or removal of a device) on the system.
- Power manager The power manager (explained in Chapter 6), processor power management (PPM), and power management framework (PoFx) coordinate power events and generate power management I/O notifications to device drivers. When the system is idle, the PPM can be configured to reduce power consumption by putting the CPU to sleep. Changes in power

consumption by individual devices are handled by device drivers but are coordinated by the power manager and PoFx. On certain classes of devices, the terminal timeout manager also manages physical display timeouts based on device usage and proximity.

- Windows Driver Model (WDM) Windows Management Instrumentation (WMI) routines These routines, discussed in Chapter 9 in Part 2, enable device drivers to publish performance and configuration information and receive commands from the user-mode WMI service. Consumers of WMI information can be on the local machine or remote across the network.
- Memory manager The memory manager, discussed in Chapter 5, implements virtual memory, a memory management scheme that provides a large private address space for each process that can exceed available physical memory. The memory manager also provides the underlying support for the cache manager. It is assisted by the prefetcher and Store Manager, also explained in Chapter 5.
- Cache manager The cache manager, discussed in Chapter 14, "Cache manager," in Part 2, improves the performance of file-based I/O by causing recently referenced disk data to reside in main memory for quick access. It also achieves this by deferring disk writes by holding the updates in memory for a short time before sending them to the disk. As you'll see, it does this by using the memory manager's support for mapped files.

In addition, the executive contains four main groups of support functions that are used by the executive components just listed. About a third of these support functions are documented in the WDK because device drivers also use them. These are the four categories of support functions:

- Object manager The object manager creates, manages, and deletes Windows executive objects and abstract data types that are used to represent OS resources such as processes, threads, and the various synchronization objects. The object manager is explained in Chapter 8 in Part 2.
- Asynchronous LPC (ALPC) facility The ALPC facility, explained in Chapter 8 in Part 2, passes messages between a client process and a server process on the same computer. Among other things, ALPC is used as a local transport for *remote procedure call (RPC)*, the Windows implementation of an industry-standard communication facility for client and server processes across a network.
- Run-time library functions These include string processing, arithmetic operations, data type conversion, and security structure processing.
- Executive support routines These include system memory allocation (paged and non-paged pool), interlocked memory access, as well as special types of synchronization mechanisms such as executive resources, fast mutexes, and pushlocks.

The executive also contains a variety of other infrastructure routines, some of which are mentioned only briefly in this book:

Kernel debugger library This allows debugging of the kernel from a debugger supporting KD, a portable protocol supported over a variety of transports such as USB, Ethernet, and IEEE 1394, and implemented by WinDbg and the Kd.exe debuggers.

- User-Mode Debugging Framework This is responsible for sending events to the user-mode debugging API and allowing breakpoints and stepping through code to work, as well as for changing contexts of running threads.
- Hypervisor library and VBS library These provide kernel support for the secure virtual machine environment and optimize certain parts of the code when the system knows it's running in a client partition (virtual environment).
- **Errata manager** The errata manager provides workarounds for nonstandard or noncompliant hardware devices.
- **Driver Verifier** The Driver Verifier implements optional integrity checks of kernel-mode drivers and code (described in Chapter 6).
- **Event Tracing for Windows (ETW)** ETW provides helper routines for system-wide event tracing for kernel-mode and user-mode components.
- Windows Diagnostic Infrastructure (WDI) The WDI enables intelligent tracing of system activity based on diagnostic scenarios.
- Windows Hardware Error Architecture (WHEA) support routines These routines provide a common framework for reporting hardware errors.
- File-System Runtime Library (FSRTL) The FSRTL provides common support routines for file system drivers.
- **Kernel Shim Engine (KSE)** The KSE provides driver-compatibility shims and additional device errata support. It leverages the shim infrastructure and database described in Chapter 8 in Part 2.

# Kernel

The kernel consists of a set of functions in Ntoskrnl.exe that provides fundamental mechanisms. These include thread-scheduling and synchronization services, used by the executive components, and low-level hardware architecture–dependent support, such as interrupt and exception dispatching, which is different on each processor architecture. The kernel code is written primarily in C, with assembly code reserved for those tasks that require access to specialized processor instructions and registers not easily accessible from C.

Like the various executive support functions mentioned in the preceding section, a number of functions in the kernel are documented in the WDK (and can be found by searching for functions beginning with Ke) because they are needed to implement device drivers.

### **Kernel objects**

The kernel provides a low-level base of well-defined, predictable OS primitives and mechanisms that allow higher-level components of the executive to do what they need to do. The kernel separates itself from the rest of the executive by implementing OS mechanisms and avoiding policy making. It leaves nearly all policy decisions to the executive, with the exception of thread scheduling and dispatching, which the kernel implements.

Outside the kernel, the executive represents threads and other shareable resources as objects. These objects require some policy overhead, such as object handles to manipulate them, security checks to protect them, and resource quotas to be deducted when they are created. This overhead is eliminated in the kernel, which implements a set of simpler objects, called *kernel objects*, that help the kernel control central processing and support the creation of executive objects. Most executive-level objects encapsulate one or more kernel objects, incorporating their kernel-defined attributes.

One set of kernel objects, called *control objects*, establishes semantics for controlling various OS functions. This set includes the Asynchronous Procedure Call (APC) object, the Deferred Procedure Call (DPC) object, and several objects the I/O manager uses, such as the interrupt object.

Another set of kernel objects, known as *dispatcher objects*, incorporates synchronization capabilities that alter or affect thread scheduling. The dispatcher objects include the kernel thread, mutex (called *mutant* in kernel terminology), event, kernel event pair, semaphore, timer, and waitable timer. The executive uses kernel functions to create instances of kernel objects, to manipulate them, and to construct the more complex objects it provides to user mode. Objects are explained in more detail in Chapter 8 in Part 2, and processes and threads are described in Chapter 3 and Chapter 4, respectively.

#### Kernel processor control region and control block

The kernel uses a data structure called the *kernel processor control region (KPCR)* to store processorspecific data. The KPCR contains basic information such as the processor's interrupt dispatch table (IDT), task state segment (TSS), and global descriptor table (GDT). It also includes the interrupt controller state, which it shares with other modules, such as the ACPI driver and the HAL. To provide easy access to the KPCR, the kernel stores a pointer to it in the fs register on 32-bit Windows and in the gs register on an x64 Windows system.

The KPCR also contains an embedded data structure called the *kernel processor control block* (*KPRCB*). Unlike the KPCR, which is documented for third-party drivers and other internal Windows kernel components, the KPRCB is a private structure used only by the kernel code in Ntoskrnl.exe. It contains the following:

- Scheduling information such as the current, next, and idle threads scheduled for execution on the processor
- The dispatcher database for the processor, which includes the ready queues for each priority level
- The DPC queue
- CPU vendor and identifier information, such as the model, stepping, speed, and feature bits
- CPU and NUMA topology, such as node information, cores per package, logical processors per core, and so on
- Cache sizes
- Time accounting information, such as the DPC and interrupt time.

The KPRCB also contains all the statistics for the processor, such as:

- I/O statistics
- Cache manager statistics (see Chapter 14 in Part 2 for a description of these)
- DPC statistics
- Memory manager statistics (see Chapter 5 for more information)

Finally, the KPRCB is sometimes used to store cache-aligned, per-processor structures to optimize memory access, especially on NUMA systems. For example, the non-paged and paged-pool system look-aside lists are stored in the KPRCB.

## **EXPERIMENT:** Viewing the KPCR and KPRCB

You can view the contents of the KPCR and KPRCB by using the !pcr and !prcb kernel debugger commands. For the latter, if you don't include flags, the debugger will display information for CPU 0 by default. Otherwise, you can specify a CPU by adding its number after the command—for example, !prcb 2. The former command, on the other hand, will always display information on the current processor, which you can change in a remote debugging session. If doing local debugging, you can obtain the address of the KPCR by using the !pcr extension, followed by the CPU number, then replacing @\$pcr with that address. Do not use any of the other output shown in the !pcr command. This extension is deprecated and shows incorrect data. The following example shows what the output of the dt nt!\_KPCR @\$pcr and !prcb commands looks like (Windows 10 x64):

```
      1kd> dt nt!_KPCR @$pcr

      +0x000 NtTib
      : _NT_TIB

      +0x000 GdtBase
      : 0xfffff802'a5f4bfb0 _KGDTENTRY64

      +0x008 TssBase
      : 0xfffff802'a5f4a000 _KTSS64

      +0x010 UserRsp
      : 0x000009b'1a47b2b8

      +0x020 CurrentPrcb
      : 0xfffff802'a280a180 _KPRCB

      +0x030 Used_Self
      : 0x000009b'1a200000 Void

      +0x030 IdtBase
      : 0xfffff802'a5f49000 _KIDTENTRY64

      +0x030 Used_Self
      : 0x000009b'1a200000 Void

      +0x030 IdtBase
      : 0xfffff802'a5f49000 _KIDTENTRY64

      +0x040 Unused
      : [2] 0

      +0x050 Irql
      : 0 ''

      +0x051 SecondLevelCacheAssociativity : 0x10 ''

      +0x052 ObsoleteNumber
      : 0 ''

      +0x053 Fill0
      : [3] 0

      +0x064 Unused0
      : [3] 0

      +0x064 StallScaleFactor : 0x8a0

      +0x068 Unused1
      : [3] (null)

      +0x068 KernelReserved : [15] 0

      +0x064 StallScaleFactor : 0x400000

      +0x065 SecondLevelCacheSize : 0x400000

      +0x066 KernelReserved : [16] 0x839b6800
```

```
+0x110 Unused3 : (null)
+0x118 PcrAlign1 : [24] 0
+0x180 Prcb : _KPRCB
lkd> !prcb
PRCB for Processor 0 at fffff803c3b23180:
Current IRQL -- 0
Threads-- Current ffffe0020535a800 Next 0000000000000 Idle fffff803c3b99740
Processor Index 0 Number (0, 0) GroupSetMember 1
Interrupt Count -- 0010d637
Times -- Dpc 000000f4 Interrupt 00000119
Kernel 0000d952 User 0000425d
```

You can also use the dt command to directly dump the \_KPRCB data structures because the debugger command gives you the address of the structure (shown in bold for clarity in the previous output). For example, if you wanted to determine the speed of the processor as detected at boot, you could look at the MHz field with the following command:

```
lkd> dt nt!_KPRCB fffff803c3b23180 MHz
+0x5f4 MHz : 0x893
lkd> ? 0x893
Evaluate expression: 2195 = 00000000'00000893
```

On this machine, the processor was running at about 2.2 GHz during boot-up.

#### Hardware support

The other major job of the kernel is to abstract or isolate the executive and device drivers from variations between the hardware architectures supported by Windows. This job includes handling variations in functions such as interrupt handling, exception dispatching, and multiprocessor synchronization.

Even for these hardware-related functions, the design of the kernel attempts to maximize the amount of common code. The kernel supports a set of interfaces that are portable and semantically identical across architectures. Most of the code that implements these portable interfaces is also identical across architectures.

Some of these interfaces are implemented differently on different architectures or are partially implemented with architecture-specific code. These architecturally independent interfaces can be called on any machine, and the semantics of the interface will be the same regardless of whether the code varies by architecture. Some kernel interfaces, such as spinlock routines, described in Chapter 8 in Part 2, are actually implemented in the HAL (described in the next section) because their implementation can vary for systems within the same architecture family.

The kernel also contains a small amount of code with x86-specific interfaces needed to support old 16-bit MS-DOS programs (on 32-bit systems). These x86 interfaces aren't portable in the sense that they can't be called on a machine based on any other architecture; they won't be present. This x86-specific code, for example, supports calls to use Virtual 8086 mode, required for the emulation of certain real-mode code on older video cards.

Other examples of architecture-specific code in the kernel include the interfaces to provide translation buffer and CPU cache support. This support requires different code for the different architectures because of the way caches are implemented.

Another example is context switching. Although at a high level the same algorithm is used for thread selection and context switching (the context of the previous thread is saved, the context of the new thread is loaded, and the new thread is started), there are architectural differences among the implementations on different processors. Because the context is described by the processor state (registers and so on), what is saved and loaded varies depending on the architecture.

# Hardware abstraction layer

As mentioned at the beginning of this chapter, one of the crucial elements of the Windows design is its portability across a variety of hardware platforms. With OneCore and the myriad device form factors available, this is more important than ever. The hardware abstraction layer (HAL) is a key part of making this portability possible. The HAL is a loadable kernel-mode module (Hal.dll) that provides the low-level interface to the hardware platform on which Windows is running. It hides hardware-dependent details such as I/O interfaces, interrupt controllers, and multiprocessor communication mechanisms—any functions that are both architecture-specific and machine-dependent.

So rather than access hardware directly, Windows internal components and user-written device drivers maintain portability by calling the HAL routines when they need platform-dependent information. For this reason, many HAL routines are documented in the WDK. To find out more about the HAL and its use by device drivers, refer to the WDK.

Although a couple of x86 HALs are included in a standard desktop Windows installation (as shown in Table 2-4), Windows has the ability to detect at boot-up time which HAL should be used, eliminating the problem that existed on earlier versions of Windows when attempting to boot a Windows installation on a different kind of system.

HAL File Name	Systems Supported
Halacpi.dll	Advanced Configuration and Power Interface (ACPI) PCs. Implies uniprocessor-only machine, without APIC support. (The presence of either one would make the system use the HAL below instead.)
Halmacpi.dll	Advanced Programmable Interrupt Controller (APIC) PCs with an ACPI. The existence of an APIC implies SMP support.

TABLE 2-4	List of x86 HALs
-----------	------------------

On x64 and ARM machines, there is only one HAL image, called Hal.dll. This results from all x64 machines having the same motherboard configuration, because the processors require ACPI and APIC support. Therefore, there is no need to support machines without ACPI or with a standard PIC. Similarly, all ARM systems have ACPI and use interrupt controllers, which are similar to a standard APIC. Once again, a single HAL can support this.

On the other hand, although such interrupt controllers are similar, they are not identical. Additionally, the actual timer and memory/DMA controllers on some ARM systems are different from others. Finally, in the IoT world, certain standard PC hardware such as the Intel DMA controller may not be present and might require support for a different controller, even on PC-based systems. Older versions of Windows handled this by forcing each vendor to ship a custom HAL for each possible platform combination. This is no longer realistic, however, and results in significant amounts of duplicated code. Instead, Windows now supports modules known as *HAL extensions*, which are additional DLLs on disk that the boot loader may load if specific hardware requiring them is needed (usually through ACPI and registrybased configuration). Your desktop Windows 10 system is likely to include a HalExtPL080.dll and HalExtIntcLpioDMA.dll, the latter of which is used on certain low-power Intel platforms, for example.

Creating HAL extensions requires collaboration with Microsoft, and such files must be custom signed with a special HAL extension certificate available only to hardware vendors. Additionally, they are highly limited in the APIs they can use and interact through a limited import/export table mechanism that does not use the traditional PE image mechanism. For example, the following experiment will not show you any functions if you try to use it on a HAL extension.

### **EXPERIMENT:** Viewing Ntoskrnl.exe and HAL image dependencies

You can view the relationship of the kernel and HAL images by using the Dependency Walker tool (Depends.exe) to examine their export and import tables. To examine an image in the Dependency Walker, open the **File** menu, choose **Open**, and select the desired image file.

Here is a sample of output you can see by viewing the dependencies of Ntoskrnl.exe using this tool (for now, disregard the errors displayed by Dependency Walker's inability to parse the API sets):

- TOSKRNL.EXE ---- ? EXT-MS-WIN-NTOS-WERKERNEL-L1-1-0.DLL ---- ? EXT-MS-WIN-NTOS-TM-L1-1-0.DLL HAL.DLL KDCOM.DLL SI PSHED.DLL E SHED.DLL BOOTVID.DLL H- CALL ..... (?) EXT-MS-WIN-NTOS-KCMINITCFG-L1-1-0.DLL ..... (?) EXT-MS-WIN-NTOS-KSR-L1-1-0.DLL ---- ? EXT-MS-WIN-NTOS-KSECURITY-L1-1-1.DLL ..... (?) EXT-MS-WIN-NTOS-KSIGNINGPOLICY-L1-1-0.DLL EXT-MS-WIN-NTOS-UCODE-L1-1-0.DLL - ? EXT-MS-WIN-FS-CLFS-L1-1-0.DLL ..... ? EXT-MS-WIN-NTOS-IUM-L1-1-0.DLL IT- CI.DLL MSRPC.SYS ..... (?) EXT-MS-WIN-NTOS-CLIPSP-L1-1-0.DLL

Notice that Ntoskrnl.exe is linked against the HAL, which is in turn linked against Ntoskrnl.exe. (They both use functions in each other.) Ntoskrnl.exe is also linked to the following binaries:

Pshed.dll The Platform-Specific Hardware Error Driver (PSHED) provides an abstraction of the hardware error reporting facilities of the underlying platform. It does this by hiding the details of a platform's error-handling mechanisms from the OS and exposing a consistent interface to the Windows OS.

- Bootvid.dll The Boot Video Driver on x86 systems (Bootvid) provides support for the VGA commands required to display boot text and the boot logo during startup.
- **Kdcom.dll** This is the Kernel Debugger Protocol (KD) communications library.
- **Ci.dll** This is the integrity library. (See Chapter 8 in Part 2 for more information on code integrity.)
- Msrpc.sys The Microsoft Remote Procedure Call (RPC) client driver for kernel mode allows the kernel (and other drivers) to communicate with user-mode services through RPC or to marshal MES-encoded assets. For example, the kernel uses this to marshal data to and from the user-mode Plug-and-Play service.

For a detailed description of the information displayed by this tool, see the Dependency Walker help file (Depends.hlp).

We asked you to disregard the errors that Dependency Walker has parsing API Sets because its authors have not updated it to correctly handle this mechanism. While the implementation of API Sets will be described in Chapter 3 in the "Image loader" section, you should still use the Dependency Walker output to review what other dependencies the kernel may potentially have, depending on SKU, as these API Sets may indeed point to real modules. Note that when dealing with API Sets, they are described in terms of contracts, not DLLs or libraries. It's important to realize that any number (or even all) of these contracts might be absent from your machine. Their presence depends on a combination of factors: SKU, platform, and vendor.

- Werkernel contract This provides support for Windows Error Reporting (WER) in the kernel, such as with live kernel dump creation.
- **Tm contract** This is the kernel transaction manager (KTM), described in Chapter 8 in Part 2.
- **Kcminitcfg contract** This is responsible for the custom initial registry configuration that may be needed on specific platforms.
- **Ksr contract** This handles Kernel Soft Reboot (KSR) and the required persistence of certain memory ranges to support it, specifically on certain mobile and IoT platforms.
- Ksecurity contract This contains additional policies for AppContainer processes (that is, Windows Apps) running in user mode on certain devices and SKUs.
- Ksigningpolicy contract This contains additional policies for user-mode code integrity (UMCI) to either support non-AppContainer processes on certain SKUs or FURTHER configure Device Guard and/or App Locker security features on certain platforms/SKUs.
- **Ucode contract** This is the microcode update library for platforms that can support processor microcode updates, such as Intel and AMD.
- **Clfs contract** This is the Common Log File System driver, used by (among other things) the Transactional Registry (TxR). For more information on TxR, see Chapter 8 in Part 2.

Ium Contract These are additional policies for IUM Trustlets running on the system, which may be needed on certain SKUs, such as for providing shielded VMs on Datacenter Server. Trustlets are described further in Chapter 3.

# **Device drivers**

Although device drivers are explained in detail in Chapter 6, this section provides a brief overview of the types of drivers and explains how to list the drivers installed and loaded on your system.

Windows supports kernel-mode and user-mode drivers, but this section discussed the kernel drivers only. The term *device driver* implies a hardware device, but there are other device driver types that are not directly related to hardware (listed momentarily). This section focuses on device drivers that are related to controlling a hardware device.

Device drivers are loadable kernel-mode modules (files typically ending with the .sys extension) that interface between the I/O manager and the relevant hardware. They run in kernel mode in one of three contexts:

- In the context of the user thread that initiated an I/O function (such as a read operation)
- In the context of a kernel-mode system thread (such as a request from the Plug and Play manager)
- As a result of an interrupt and therefore not in the context of any particular thread but rather of whichever thread was current when the interrupt occurred

As stated in the preceding section, device drivers in Windows don't manipulate hardware directly. Rather, they call functions in the HAL to interface with the hardware. Drivers are typically written in C and/or C++. Therefore, with proper use of HAL routines, they can be source-code portable across the CPU architectures supported by Windows and binary portable within an architecture family.

There are several types of device drivers:

- Hardware device drivers These use the HAL to manipulate hardware to write output to or retrieve input from a physical device or network. There are many types of hardware device drivers, such as bus drivers, human interface drivers, mass storage drivers, and so on.
- **File system drivers** These are Windows drivers that accept file-oriented I/O requests and translate them into I/O requests bound for a particular device.
- File system filter drivers These include drivers that perform disk mirroring and encryption or scanning to locate viruses, intercept I/O requests, and perform some added-value processing before passing the I/O to the next layer (or in some cases rejecting the operation).
- Network redirectors and servers These are file system drivers that transmit file system I/O requests to a machine on the network and receive such requests, respectively.
- Protocol drivers These implement a networking protocol such as TCP/IP, NetBEUI, and IPX/SPX.

- **Kernel streaming filter drivers** These are chained together to perform signal processing on data streams, such as recording or displaying audio and video.
- Software drivers These are kernel modules that perform operations that can only be done in kernel mode on behalf of some user-mode process. Many utilities from Sysinternals such as Process Explorer and Process Monitor use drivers to get information or perform operations that are not possible to do from user-mode APIs.

### Windows driver model

The original driver model was created in the first NT version (3.1) and did not support the concept of Plug and Play (PnP) because it was not yet available. This remained the case until Windows 2000 came along (and Windows 95/98 on the consumer Windows side).

Windows 2000 added support for PnP, Power Options, and an extension to the Windows NT driver model called the Windows Driver Model (WDM). Windows 2000 and later can run legacy Windows NT 4 drivers, but because these don't support PnP and Power Options, systems running these drivers will have reduced capabilities in these two areas.

Originally, WDM provided a common driver model that was (almost) source compatible between Windows 2000/XP and Windows 98/ME. This was done to make it easier to write drivers for hardware devices, since a single code base was needed instead of two. WDM was simulated on Windows 98/ME. Once these operating systems were no longer used, WDM remained the base model for writing drivers for hardware devices for Windows 2000 and later versions.

From the WDM perspective, there are three kinds of drivers:

- Bus drivers A bus driver services a bus controller, adapter, bridge, or any device that has child devices. Bus drivers are required drivers, and Microsoft generally provides them. Each type of bus (such as PCI, PCMCIA, and USB) on a system has one bus driver. Third parties can write bus drivers to provide support for new buses, such as VMEbus, Multibus, and Futurebus.
- Function drivers A function driver is the main device driver and provides the operational interface for its device. It is a required driver unless the device is used raw, an implementation in which I/O is done by the bus driver and any bus filter drivers, such as SCSI PassThru. A function driver is by definition the driver that knows the most about a particular device, and it is usually the only driver that accesses device-specific registers.
- Filter drivers A filter driver is used to add functionality to a device or existing driver, or to modify I/O requests or responses from other drivers. It is often used to fix hardware that provides incorrect information about its hardware resource requirements. Filter drivers are optional and can exist in any number, placed above or below a function driver and above a bus driver. Usually, system original equipment manufacturers (OEMs) or independent hardware vendors (IHVs) supply filter drivers.

In the WDM driver environment, no single driver controls all aspects of a device. A bus driver is concerned with reporting the devices on its bus to PnP manager, while a function driver manipulates the device.

In most cases, lower-level filter drivers modify the behavior of device hardware. For example, if a device reports to its bus driver that it requires 4 I/O ports when it actually requires 16 I/O ports, a lower-level, device-specific function filter driver could intercept the list of hardware resources reported by the bus driver to the PnP manager and update the count of I/O ports.

Upper-level filter drivers usually provide added-value features for a device. For example, an upper-level device filter driver for a disk can enforce additional security checks.

Interrupt processing is explained in Chapter 8 in Part 2 and in the narrow context of device drivers, in Chapter 6. Further details about the I/O manager, WDM, Plug and Play, and power management are also covered in Chapter 6.

#### **Windows Driver Foundation**

The Windows Driver Foundation (WDF) simplifies Windows driver development by providing two frameworks: the Kernel-Mode Driver Framework (KMDF) and the User-Mode Driver Framework (UMDF). Developers can use KMDF to write drivers for Windows 2000 SP4 and later, while UMDF supports Windows XP and later.

KMDF provides a simple interface to WDM and hides its complexity from the driver writer without modifying the underlying bus/function/filter model. KMDF drivers respond to events that they can register and call into the KMDF library to perform work that isn't specific to the hardware they are managing, such as generic power management or synchronization. (Previously, each driver had to implement this on its own.) In some cases, more than 200 lines of WDM code can be replaced by a single KMDF function call.

UMDF enables certain classes of drivers—mostly USB-based or other high-latency protocol buses, such as those for video cameras, MP3 players, cell phones, and printers—to be implemented as usermode drivers. UMDF runs each user-mode driver in what is essentially a user-mode service, and it uses ALPC to communicate to a kernel-mode wrapper driver that provides actual access to hardware. If a UMDF driver crashes, the process dies and usually restarts. That way, the system doesn't become unstable; the device simply becomes unavailable while the service hosting the driver restarts.

UMDF has two major versions: version 1.x is available for all OS versions that support UMDF, the latest and last being version 1.11, available in Windows 10. This version uses C++ and COM for driver writing, which is rather convenient for user-mode programmers, but it makes the UMDF model different from KMDF. Version 2.0 of UMDF, introduced in Windows 8.1, is based around the same object model as KMDF, making the two frameworks very similar in their programming model. Finally, WDF has been open-sourced by Microsoft, and at the time of this writing is available on GitHub at *https://github.com/Microsoft/Windows-Driver-Frameworks*.

### **Universal Windows drivers**

Starting with Windows 10, the term *Universal Windows drivers* refers to the ability to write device drivers once that share APIs and Device Driver Interfaces (DDIs) provided by the Windows 10 common core. These drivers are binary-compatible for a specific CPU architecture (x86, x64, ARM) and can be used as is on a variety of form factors, from IoT devices, to phones, to the HoloLens and Xbox One, to laptops and desktops. Universal drivers can use KMDF, UMDF 2.*x*, or WDM as their driver model.

### **EXPERIMENT:** Viewing the installed device drivers

To list the installed drivers, run the System Information tool (Msinfo32.exe). To launch this tool, click **Start** and then type **Msinfo32** to locate it. Under System Summary, expand **Software Environment** and open **System Drivers**. Here's an example output of the list of installed drivers:

File Edit View Help							
System Summary	Name	Description	File	Туре	Started	Start Mode	State
Hardware Resources	1394ohci	1394 OHCI Compliant Host Co	c:\windows\s	Kernel Driver	No	Manual	Stopped
Components	3ware	3ware	c:\windows\s	Kernel Driver	No	Manual	Stopped
Software Environment	acpi	Microsoft ACPI Driver	c:\windows\s	Kernel Driver	Yes	Boot	Running
Environment Variable Print Jobs Network Connection: Running Tasks Loaded Mcdules Services Program Groups	acpiex	Microsoft ACPIEx Driver	c:\windows\s	Kernel Driver	Yes	Boot	Running
	acpipagr	ACPI Processor Aggregator Dr	c:\windows\s	Kernel Driver	No	Manual	Stopped
	acpipmi	ACPI Power Meter Driver	c:\windows\s	Kernel Driver	No	Manual	Stopped
	acpitime	ACPI Wake Alarm Driver	c:\windows\s	Kernel Driver	No	Manual	Stopped
	adp80xx	ADPSOXX	c:\windows\s	Kernel Driver	No	Manual	Stopped
	afd	Ancillary Function Driver for Wi	c:\windows\s	Kernel Driver	Yes	System	Running
	agp440	Intel AGP Bus Filter	c:\windows\s	Kernel Driver	No	Manual	Stopped
- Startup Programs	ahcache	Application Compatibility Cache	c:\windows\s	Kernel Driver	Yes	System	Running
OLE Registration	amdkB	AMD K8 Processor Driver	c:\windows\s	Kernel Driver	No	Manual	Stopped
	amdkmdag	amdkmdag	c:\windows\s	Kernel Driver	Yes	Manual	Running
	amdkmdap	amdkmdap	c:\windows\s	Kernel Driver	Yes	Manual	Running
	amdkmpfd	AMD PCI Root Bus Lower Filter	c:\windows\s	Kernel Driver	Yes	Boot	Running
	amdppm	AMD Processor Driver	c:\windows\s	Kernel Driver	No	Manual	Stopped
	amdsata	amdsata	c:\windows\s	Kernel Driver	No	Manual	Stopped
	amdsbs	amdsbs	c:\windows\s	Kernel Driver	No	Manual	Stopped
	amdxata	amdxata	c:\windows\s	Kernel Driver	No	Manual	Stopped
	apfiltrservice	Alps Touch Pad Filter Driver fo	c:\windows\s	Kernel Driver	Yes	Manual	Running
	appid	AppID Driver	c:\windows\s	Kernel Driver	Yes	Manual	Running
	arcsas	Adaptec SAS/SATA-II RAID Stor	c:\windows\s	Kernel Driver	No	Manual	Stopped
c >	<			2.4		1 ×	>
Find what:					Find	Close Find	

This window displays the list of device drivers defined in the registry, their type, and their state (Running or Stopped). Device drivers and Windows service processes are both defined in the same place: HKLM\SYSTEM\CurrentControlSet\Services. However, they are distinguished by a type code. For example, type 1 is a kernel-mode device driver. For a complete list of the information stored in the registry for device drivers, see Chapter 9 in Part 2.

Alternatively, you can list the currently loaded device drivers by selecting the **System** process in Process Explorer and opening the DLL view. Here's a sample output. (To get the extra columns, right-click a column header and click **Select Columns** to see all the available columns for modules in the DLL tab.)

File Options V	/iew Process Fin	d DLL U	iers Help				A										
Process		PID	CPU	Private Bytes	Working Set	Integrity	Description	Company	Name	Window Title							
System Idle P	rocess	0	87.93	0K	4 K												
System	Contractor of the second s	4	0.37	184 K	25.044 K	System											
Interrupts	ist one	< <sup>1</sup>	0.00	0.17						>							
Name	Description			10.0	Base	Image Base	Size	Company Name	Path								
ACPLeve	ACPI Driver for NT			OxFFFFF801	09810000	Ox0	0x90000	Microsoft Corporation	C:\WINDOWS\System	m32\drivers\ACPLays							
acpiex.sys	ACPIEx Driver			0xFFFFF801	09A30000	Ox0	0x23000	Microsoft Corporation	C:\WINDOWS\System	m32\Drivers\acpiex.sys							
fd sys	Ancillary Function Dr	river for WinSo	ick	0xFFFFF801	0C400000	Ox0	0x92000	Microsoft Corporation	C:\WINDOWS\syster	m32\drivers\afd.sys							
shcache sys	Application Compatib	bility Cache		OxFFFFF801	0C710000	Ox0	0x3C000	Microsoft Corporation	C:\WINDOWS\syster	m32\DRIVERS\ahcachr							
mdkmpfd.øys	AMD PCI Root Bus I	Lower Filter		0xFFFFF801	0xFFFFF8010A9E0000		0x13000	Advanced Micro Devices	C:\WINDOWS\System	m32\drivers\amdkmpfd.							
Apfiltr.sys	Alps Touch Pad Driv	/er		0xFFFFF801	0xFFFFF801102B0000		0x9C000	Alps Electric Co., Ltd.		m32\DRIVERS\Apfiltr.sy							
sppid.sys	AppID Driver			0xFFFFF801	0xFFFFF801104D0000		0x27000	Microsoft Corporation	C:\WINDOWS\system	m32\drivers\appid.sys							
AtihdWT6.sys	AMD High Definition	Audio Functio	n Driver	DxFFFFF801	0DC60000	Ox0	0x1E000	Advanced Micro Devices	C:\WINDOWS\system32\drivers\AtihdWT6								
stikmdag sys	ATI Radeon Kernel	Mode Driver		0xFFFF6010E850000									OxO	0x1507000	Advanced Micro Devices,	C:\WINDOWS\syster	m32\DRIVERS\atikmda
atikmpag sys	AMD multi-vendor M	Iniport Driver		0xFFFFF801	0CA20000	0x0	0xA8000	Advanced Micro Devices,	C:\WINDOWS\system32\DRIVERS\atik								
Basic Display sys	Microsoft Basic Disp	lay Driver		0xFFFFF8010C3D0000 0x0 0xFFFFF8010CEC0000 0x0	0xFFFFF8010C3D0000	Ox0	0x14000	Microsoft Corporation	C:\WINDOWS\System32\drivers\BasicDisp								
Basic Render.sys	Microsoft Basic Ren	der Driver			*FFFFF8010CEC0000	0x12000	0x12000 Microsoft Corporation	C:\WINDOWS\System	m32\drivers\BasicRend								
BATTC.SYS	Battery Class Driver			OxFFFFF80		Ox0	0xE000	Microsoft Corporation	C:\WINDOWS\System	m32\drivers\BATTC.SY							
Beep.SYS	BEEP Driver			0xFFFFF8010C3C0000		OcO	0xA000	0xA000 Microsoft Corporation	C:\WINDOWS\Syster	m32\Drivers\Beep.SYS							
Ib CIVTOOB	VGA Boot Driver			OxFFFFF801	096C0000	Ox0	0x8000	Microsoft Corporation	C:\WINDOWS\syster	m32\BOOTVID.dll							
bowser.sys	NT Lan Manager Da	anager Datagram Receiver Driver 0xFFFF80110B10000 0x0		0xFFFFF80110B10000		CbcO	0x23000	Microsoft Corporation	C:\WINDOWS\syster	m32\DRIVERS\bowser:							
bridge.eys	MAC Bridge Driver			OxFFFFF801	0DC10000	Ox0	0x24000	Mcrosoft Corporation	C:\WINDOWS\System32\drivers\bridge.st								
b.bb:	Canonical Display D	river		OxFFFFF96	92920000	OxO	0x3C000	Microsoft Corporation	C:\WINDOWS\System	m32\cdd.dl							
cdrom.sys	SCSI CD-ROM Drive	ar .		OxFFFFF801	BDC0000	OxO	0x31000	Microsoft Corporation	C:\WINDOWS\System	m32\drivers\cdrom.sys							
CEA.sys	Event Aggregation P	Kernel Mode L	brary	0xFFFFF801	09D00000	Ox0	0x19000	Mcrosoft Corporation	C:\WINDOWS\syster	m32\drivers\CEA.sys							
Cl.dl	Code Integrity Modu			0xFFFFF80	096F0000	Ox0	Dx99000	Mcrosoft Corporation	C:\WINDOWS\system								
CLASSPNP SYS	SCSI Class System [	DI		0xFFFFF801	0A060000	Ox0	0x60000	Microsoft Corporation	C:\WINDOWS\Syster	m32\drivers\CLASSPNF							
<	re la Tellie				*******	+(+)		0. 3.*.	# /11/10/1# #///# #								

### Peering into undocumented interfaces

Examining the names of the exported or global symbols in key system images (such as Ntoskrnl. exe, Hal.dll, or Ntdll.dll) can be enlightening—you can get an idea of the kinds of things Windows can do versus what happens to be documented and supported today. Of course, just because you know the names of these functions doesn't mean that you can or should call them—the interfaces are undocumented and are subject to change. We suggest that you look at these functions purely to gain more insight into the kinds of internal functions Windows performs, not to bypass supported interfaces.

For example, looking at the list of functions in Ntdll.dll gives you the list of all the system services that Windows provides to user-mode subsystem DLLs versus the subset that each subsystem exposes. Although many of these functions map clearly to documented and supported Windows functions, several are not exposed via the Windows API.

Conversely, it's also interesting to examine the imports of Windows subsystem DLLs (such as Kernel32.dll or Advapi32.dll) and which functions they call in Ntdll.dll.

Another interesting image to dump is Ntoskrnl.exe—although many of the exported routines that kernel-mode device drivers use are documented in the WDK, quite a few are not. You might also find it interesting to take a look at the import table for Ntoskrnl.exe and the HAL; this table shows the list of functions in the HAL that Ntoskrnl.exe uses and vice versa.

Table 2-5 lists most of the commonly used function name prefixes for the executive components. Each of these major executive components also uses a variation of the prefix to denote internal functions—either the first letter of the prefix followed by an i (for *internal*) or the full prefix followed by a p (for *private*). For example, Ki represents internal kernel functions, and Psp refers to internal process support functions.

#### TABLE 2-5 Commonly Used Prefixes

Prefix	Component
Alpc	Advanced Local Procedure Calls
Cc	Common Cache
Cm	Configuration manager
Dbg	Kernel debug support
Dbgk	Debugging Framework for user mode
Em	Errata manager
Etw	Event Tracing for Windows
Ex	Executive support routines
FsRt1	File System Runtime Library
Ηv	Hive library
Hv1	Hypervisor library
Io	I/O manager
Kd	Kernel debugger
Ке	Kernel
Kse	Kernel Shim Engine
Lsa	Local Security Authority
Mm	Memory manager
Nt	NT system services (accessible from user mode through system calls)
Ob	Object manager
Pf	Prefetcher
Ро	Power manager
PoFx	Power framework
Рр	PnP manager
Ppm	Processor power manager
Ps	Process support
Rtl	Run-time library
Se	Security Reference Monitor
Sm	Store Manager
Tm	Transaction manager
Ttm	Terminal timeout manager
Vf	Driver Verifier

TABLE 2-5	Commonly	y Used Prefixes	(Continued)
-----------	----------	-----------------	-------------

	-
Prefix	Component
Vs1	Virtual Secure Mode library
Wdi	Windows Diagnostic Infrastructure
Wfp	Windows FingerPrint
Whea	Windows Hardware Error Architecture
Wmi	Windows Management Instrumentation
Zw	Mirror entry point for system services (beginning with Nt) that sets previous access mode to kernel, which eliminates parameter validation, because Nt system services validate parameters only if previous access mode is user

You can decipher the names of these exported functions more easily if you understand the naming convention for Windows system routines. The general format is

#### <Prefix><Operation><Object>

In this format, *Prefix* is the internal component that exports the routine, *Operation* tells what is being done to the object or resource, and *Object* identifies what is being operated on.

For example, ExAllocatePoolWithTag is the executive support routine to allocate from a paged or non-paged pool. KeInitializeThread is the routine that allocates and sets up a kernel thread object.

# System processes

The following system processes appear on every Windows 10 system. One of these (Idle) is not a process at all, and three of them—System, Secure System, and Memory Compression—are not full processes because they are not running a user-mode executable. These types of processes are called *minimal processes* and are described in Chapter 3.

- Idle process This contains one thread per CPU to account for idle CPU time.
- **System process** This contains the majority of the kernel-mode system threads and handles.
- Secure System process This contains the address space of the secure kernel in VTL 1, if running.
- Memory Compression process This contains the compressed working set of user-mode processes, as described in Chapter 5.
- Session manager (Smss.exe).
- Windows subsystem (Csrss.exe).
- Session 0 initialization (Wininit.exe).
- Logon process (Winlogon.exe).

- Service Control Manager (Services.exe) and the child service processes it creates such as the system-supplied generic service-host process (Svchost.exe).
- Local Security Authentication Service (Lsass.exe), and if Credential Guard is active, the Isolated Local Security Authentication Server (Lsaiso.exe).

To understand how these processes are related, it is helpful to view the process tree—that is, the parent/child relationship between processes. Seeing which process created each process helps to understand where each process comes from. Figure 2-6 shows the process tree following a Process Monitor boot trace. To conduct a boot trace, open the Process Monitor **Options** menu and select **Enable Boot Logging**. Then restart the system, open Process Monitor again, and open the **Tools** menu and choose **Process Tree** or press **Ctrl+T**. Using Process Monitor enables you to see processes that have since exited, indicated by the faded icon.

Process	Description	^
<ul> <li>de (0)</li> </ul>	ide	
🖃 🔳 System (4)	System	
Image:	Windows Session C:\windows\Syste	Microe
autochk.exe (372)	Auto Check Utility C:\windows\syste	Microt
smss.exe (448)	Windows Session C:\windows\Syste	Moroe
Carea.exe (456)	Client Server Runt C:\windows\øyste	Microe
winint.exe (520)	Windows Start-Up C:\windows\syste	Mcros
E services.exe (644)	Services and Cont C:\windows\syste	Microe
Isaes exe (652)	Local Security Aut C:\windows\syste	Micros
- III smss.exe (512)	Windows Session C:\windows\Syste	Moree
Cares exe (532)	Client Server Runt C:\windows\syste	Micror
😑 💽 winlogon exe (596)	Windows Logon A., C:\windows\syste	Moroe
dwm.exe (900)	Desktop Window C:\windows\syste	Microe
LogonULexe (908)	Windows Logon C:\windows\syste	Micros
Image: Signature (2004)	Windows Session C:\windows\Syste	Moree
Cares.exe (2012)	Client Server Runt C:\windows\avate	Micror
🖂 💽 winlogon exe (720)	Windows Logon A., C:\windows\syste	Moroe
LogonUlexe (2504)	Windows Logon C.\windows\syste	Moree
dwm.exe (2512)	Desktop Window C:\windows\syste	Morot
E userinit.exe (4032)	Userinit Logon Ap C:\Windows\syst	Morot
Explorer EXE (4108)	Windows Explorer C:\windows\Explo	Moror
ConeDrive exe (5680)	Microsoft OneDrive C:\Users\Administ	More: Y
Procmon exe (5820)	C PROFESSION CONTRACTOR CONTRACTOR	
besorption: Company: hath: Idle command: Iser: ID: 0 Started: 09-Mar-16 11:38:	ц	

FIGURE 2-6 The initial system process tree.

The next sections explain the key system processes shown in Figure 2-6. Although these sections briefly indicate the order of process startup, Chapter 11 in Part 2, contains a detailed description of the steps involved in booting and starting Windows.

### System idle process

The first process listed in Figure 2-6 is the Idle process. As discussed in Chapter 3, processes are identified by their image name. However, this process—as well as the System, Secure System, and Memory Compression processes—isn't running a real user-mode image. That is, there is no "System Idle Process.exe" in the \Windows directory. In addition, because of implementation details, the name shown for this process differs from utility to utility. The Idle process accounts for idle time. That's why the number of "threads" in this "process" is the number of logical processors on the system. Table 2-6 lists several of the names given to the Idle process (process ID 0). The Idle process is explained in detail in Chapter 3. 
 TABLE 2-6
 Names for process ID 0 in various utilities

Utility	Name for Process ID 0
Task Manager	System Idle process
Process Status (Pstat.exe)	Idle process
Process Explorer (Procexp.exe)	System Idle process
Task List (Tasklist.exe)	System Idle process
Tlist (Tlist.exe)	System process

Now let's look at system threads and the purpose of each of the system processes that are running real images.

#### System process and system threads

The System process (process ID 4) is the home for a special kind of thread that runs only in kernel mode: a *kernel-mode system thread*. System threads have all the attributes and contexts of regular user-mode threads such as a hardware context, priority, and so on, but differ in that they run only in kernel-mode executing code loaded in system space, whether that is in Ntoskrnl.exe or in any other loaded device driver. In addition, system threads don't have a user process address space and hence must allocate any dynamic storage from OS memory heaps, such as a paged or non-paged pool.

**Note** On Windows 10 Version 1511, Task Manager calls the System process *System and Compressed Memory*. This is because of a new feature in Windows 10 that compresses memory to save more process information in memory rather than page it out to disk. This mechanism is further described in Chapter 5. Just remember that the term *System process* refers to this one, no matter the exact name displayed by this tool or another. Windows 10 Version 1607 and Server 2016 revert the name of the System process to *System*. This is because a new process called *Memory Compression* is used for compressing memory. Chapter 5 discusses this process in more detail.

System threads are created by the PsCreateSystemThread or IoCreateSystemThread functions, both documented in the WDK. These threads can be called only from kernel mode. Windows, as well as various device drivers, create system threads during system initialization to perform operations that require thread context, such as issuing and waiting for I/Os or other objects or polling a device. For example, the memory manager uses system threads to implement such functions as writing dirty pages to the page file or mapped files, swapping processes in and out of memory, and so forth. The kernel creates a system thread called the *balance set manager* that wakes up once per second to possibly initiate various scheduling and memory-management related events. The cache manager also uses system threads to implement both read-ahead and write-behind I/Os. The file server device driver (Srv2.sys) uses system threads to respond to network I/O requests for file data on disk partitions shared to the network. Even the floppy driver has a system thread to poll the floppy device. (Polling is more efficient in this case because an interrupt-driven floppy driver consumes a large amount of system

resources.) Further information on specific system threads is included in the chapters in which the corresponding component is described.

By default, system threads are owned by the System process, but a device driver can create a system thread in any process. For example, the Windows subsystem device driver (Win32k.sys) creates a system thread inside the Canonical Display Driver (Cdd.dll) part of the Windows subsystem process (Csrss.exe) so that it can easily access data in the user-mode address space of that process.

When you're troubleshooting or going through a system analysis, it's useful to be able to map the execution of individual system threads back to the driver or even to the subroutine that contains the code. For example, on a heavily loaded file server, the System process will likely consume considerable CPU time. But knowing that when the System process is running, "some system thread" is running isn't enough to determine which device driver or OS component is running.

So if threads in the System process are running, first determine which ones are running (for example, with the Performance Monitor or Process Explorer tools). Once you find the thread (or threads) that is running, look up in which driver the system thread began execution. This at least tells you which driver likely created the thread. For example, in Process Explorer, right-click the **System** process and select **Properties**. Then, in the Threads tab, click the **CPU** column header to view the most active thread at the top. Select this thread and click the **Module** button to see the file from which the code on the top of stack is running. Because the System process is protected in recent versions of Windows, Process Explorer is unable to show a call stack.

#### Secure System process

The Secure System process (variable process ID) is technically the home of the VTL 1 secure kernel address space, handles, and system threads. That being said, because scheduling, object management, and memory management are owned by the VTL 0 kernel, no such actual entities will be associated with this process. Its only real use is to provide a visual indicator to users (for example, in tools such as Task Manager and Process Explorer) that VBS is currently active (providing at least one of the features that leverages it).

#### Memory Compression process

The Memory Compression process uses its user-mode address space to store the compressed pages of memory that correspond to standby memory that's been evicted from the working sets of certain processes, as described in Chapter 5. Unlike the Secure System process, the Memory Compression process does actually host a number of system threads, usually seen as SmKmStoreHelperWorker and SmStReadThread. Both of these belong to the Store Manager that manages memory compression.

Additionally, unlike the other System processes in this list, this process actually stores its memory in the user-mode address space. This means it is subject to working set trimming and will potentially have large visible memory usage in system-monitoring tools. In fact, if you view the Performance tab in Task Manager, which now shows both in-use and compressed memory, you should see that the size of the Memory Compression process's working set is equal to the amount of compressed memory.

#### **Session Manager**

The Session Manager (%SystemRoot%\System32\Smss.exe) is the first user-mode process created in the system. The kernel-mode system thread that performs the final phase of the initialization of the executive and kernel creates this process. It is created as a Protected Process Light (PPL), as described in Chapter 3.

When Smss.exe starts, it checks whether it is the first instance (the master Smss.exe) or an instance of itself that the master Smss.exe launched to create a session. If command-line arguments are present, it is the latter. By creating multiple instances of itself during boot-up and Terminal Services session creation, Smss.exe can create multiple sessions at the same time—as many as four concurrent sessions, plus one more for each extra CPU beyond one. This ability enhances logon performance on Terminal Server systems where multiple users connect at the same time. Once a session finishes initializing, the copy of Smss.exe terminates. As a result, only the initial Services and multiple sessions" in Chapter 1.)

The master Smss.exe performs the following one-time initialization steps:

- 1. It marks the process and the initial thread as critical. If a process or thread marked critical exits for any reason, Windows crashes. See Chapter 3 for more information.
- 2. It causes the process to treat certain errors as critical, such as invalid handle usage and heap corruption, and enables the Disable Dynamic Code Execution process mitigation.
- 3. It increases the process base priority to 11.
- **4.** If the system supports hot processor add, it enables automatic processor affinity updates. That way, if new processors are added, new sessions will take advantage of the new processors. For more information about dynamic processor additions, see Chapter 4.
- 5. It initializes a thread pool to handle ALPC commands and other work items.
- 6. It creates an ALPC port named \SmApiPort to receive commands.
- 7. It initializes a local copy of the NUMA topology of the system.
- 8. It creates a mutex named PendingRenameMutex to synchronize file-rename operations.
- 9. It creates the initial process environment block and updates the Safe Mode variable if needed.
- **10.** Based on the ProtectionMode value in the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager key, it creates the security descriptors that will be used for various system resources.
- Based on the ObjectDi rectories value in the HKLM\SYSTEM\CurrentControlSet\Control\ Session Manager key, it creates the object manager directories that are described, such as \ RPC Control and \Windows. It also saves the programs listed under the values BootExecute, BootExecuteNoPnpSync, and SetupExecute.
- 12. It saves the program path listed in the SOInitialCommand value under the HKLM\SYSTEM\ CurrentControlSet\Control\Session Manager key.

- **13.** It reads the NumberOfInitialSessions value from the HKLM\SYSTEM\CurrentControlSet\ Control\Session Manager key, but ignores it if the system is in manufacturing mode.
- 14. It reads the file rename operations listed under the PendingFileRenameOperations and PendingFileRenameOperations2 values from the HKLM\SYSTEM\CurrentControlSet\Control\ Session Manager key.
- **15.** It reads the values of the AllowProtectedRenames, ClearTempFiles, TempFileDirectory, and DisableWpbtExecution values in the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager key.
- **16.** It reads the list of DLLs in the ExcludeFromKnownDllList value found under the HKLM\SYSTEM\ CurrentControlSet\Control\Session Manager key.
- 17. It reads the paging file information stored in the HKLM\SYSTEM\CurrentControlSet\Control Session Manager\Memory Management key, such as the PagingFiles and ExistingPageFiles list values and the PagefileOnOsVolume and WaitForPagingFiles configuration values.
- **18.** It reads and saves the values stored in the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\ DOS Devices key.
- **19.** It reads and saves the KnownDlls value list stored in the HKLM\SYSTEM\CurrentControlSet\ Control\Session Manager key.
- **20.** It creates system-wide environment variables as defined in HKLM\SYSTEM\CurrentControlSet\ Control\Session Manager\Environment.
- 21. It creates the \KnownDlls directory, as well as \KnownDlls32 on 64-bit systems with WoW64.
- **22.** It creates symbolic links for devices defined in HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\DOS Devices under the \Global?? directory in the object manager namespace.
- 23. It creates a root \Sessions directory in the object manager namespace.
- **24.** It creates protected mailslot and named pipe prefixes to protect service applications from spoofing attacks that could occur if a malicious user-mode application executes before a service does.
- **25.** It runs the programs part of the BootExecute and BootExecuteNoPnpSync lists parsed earlier. (The default is Autochk.exe, which performs a disk check.)
- 26. It initializes the rest of the registry (HKLM software, SAM, and security hives).
- **27.** Unless disabled by the registry, it executes the Windows Platform Binary Table (WPBT) binary registered in the respective ACPI table. This is often used by anti-theft vendors to force the execution of a very early native Windows binary that can call home or set up other services for execution, even on a freshly installed system. These processes must link with Ntdll.dll only (that is, belong to the native subsystem).
- **28.** It processes pending file renames as specified in the registry keys seen earlier unless this is a Windows Recovery Environment boot.

- 29. It initializes paging file(s) and dedicated dump file information based on the HKLM\System\ CurrentControlSet\Control\Session Manager\Memory Management and HKLM\System\CurrentControlSet\Control\CrashControl keys.
- **30.** It checks the system's compatibility with memory cooling technology, used on NUMA systems.
- **31.** It saves the old paging file, creates the dedicated crash dump file, and creates new paging files as needed based on previous crash information.
- 32. It creates additional dynamic environment variables, such as PROCESSOR\_ARCHITECTURE, PROCESSOR\_LEVEL, PROCESSOR\_IDENTIFIER, and PROCESSOR\_REVISION, which are based on registry settings and system information queried from the kernel.
- **33.** It runs the programs in HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\SetupExecute. The rules for these executables are the same as for BootExecute in step 11.
- **34.** It creates an unnamed section object that is shared by child processes (for example, Csrss.exe) for information exchanged with Smss.exe. The handle to this section is passed to child processes via handle inheritance. For more on handle inheritance, see Chapter 8 in Part 2.
- **35.** It opens known DLLs and maps them as permanent sections (mapped files) except those listed as exclusions in the earlier registry checks (none listed by default).
- **36.** It creates a thread to respond to session create requests.
- 37. It creates the Smss.exe instance to initialize session 0 (non-interactive session).
- **38.** It creates the Smss.exe instance to initialize session 1 (interactive session) and, if configured in the registry, creates additional Smss.exe instances for extra interactive sessions to prepare itself in advance for potential future user logons. When Smss.exe creates these instances, it requests the explicit creation of a new session ID using the PROCESS\_CREATE\_NEW\_SESSION flag in NtCreateUserProcess each time. This has the effect of calling the internal memory manager function MiSessionCreate, which creates the required kernel-mode session data structures (such as the Session object) and sets up the Session Space virtual address range that is used by the kernel-mode part of the Windows subsystem (Win32k.sys) and other session-space device drivers. See Chapter 5 for more details.

After these steps have been completed, Smss.exe waits forever on the handle to the session 0 instance of Csrss.exe. Because Csrss.exe is marked as a critical process (and is also a protected process; see Chapter 3), if Csrss.exe exits, this wait will never complete because the system will crash.

A session startup instance of Smss.exe does the following:

- It creates the subsystem process(es) for the session (by default, the Windows subsystem Csrss.exe).
- It creates an instance of Winlogon (interactive sessions) or the Session 0 Initial Command, which is Wininit (for session 0) by default unless modified by the registry values seen in the preceding steps. See the upcoming paragraphs for more information on these two processes.

Finally, this intermediate Smss.exe process exits, leaving the subsystem processes and Winlogon or Wininit as parent-less processes.

#### Windows initialization process

The Wininit.exe process performs the following system initialization functions:

- 1. It marks itself and the main thread critical so that if it exits prematurely and the system is booted in debugging mode, it will break into the debugger. (Otherwise, the system will crash.)
- 2. It causes the process to treat certain errors as critical, such as invalid handle usage and heap corruption.
- 3. It initializes support for state separation, if the SKU supports it.
- 4. It creates an event named Global\FirstLogonCheck (this can be observed in Process Explorer or WinObj under the \BaseNamedObjects directory) for use by Winlogon processes to detect which Winlogon is first to launch.
- 5. It creates a WinlogonLogoff event in the BasedNamedObjects object manager directory to be used by Winlogon instances. This event is signaled (set) when a logoff operation starts.
- 6. It increases its own process base priority to high (13) and its main thread's priority to 15.
- 7. Unless configured otherwise with the NoDebugThread registry value in the HKLM\Software\ Microsoft\Windows NT\CurrentVersion\Winlogon key, it creates a periodic timer queue, which will break into any user-mode process as specified by the kernel debugger. This enables remote kernel debuggers to cause Winlogon to attach and break into other user-mode applications.
- **8.** It sets the machine name in the environment variable COMPUTERNAME and then updates and configures TCP/IP-related information such as the domain name and host name
- **9.** It sets the default profile environment variables USERPROFILE, ALLUSERSPROFILE, PUBLIC, and ProgramData.
- **10.** It creates the temp directory by expanding %SystemRoot%\Temp (for example, C:\Windows\ Temp).
- 11. It sets up font loading and DWM if session 0 is an interactive session, which depends on the SKU.
- **12.** It creates the initial terminal, which is composed of a window station (always named *Winsta0*) and two desktops (Winlogon and Default) for processes to run on in session 0.
- **13.** It initializes the LSA machine encryption key, depending on whether it's stored locally or if it must be entered interactively. See Chapter 7 for more information on how local authentication keys are stored.
- **14.** It creates the Service Control Manager (SCM or Services.exe). See the upcoming paragraphs for a brief description and Chapter 9 in Part 2 for more details.

- **15.** It starts the Local Security Authentication Subsystem Service (Lsass.exe) and, if Credential Guard is enabled, the Isolated LSA Trustlet (Lsaiso.exe). This also requires querying the VBS provision-ing key from UEFI. See Chapter 7 for more information on Lsass.exe and Lsaiso.exe.
- **16.** If Setup is currently pending (that is, if this is the first boot during a fresh install or an update to a new major OS build or Insider Preview), it launches the setup program.
- **17.** It waits forever for a request for system shutdown or for one of the aforementioned system processes to terminate (unless the DontWatchSysProcs registry value is set in the Winlogon key mentioned in step 7). In either case, it shuts down the system.

#### Service control manager

Recall that with Windows, *services* can refer to either a server process or a device driver. This section deals with services that are user-mode processes. Services are like Linux daemon processes in that they can be configured to start automatically at system boot time without requiring an interactive logon. They can also be started manually, such as by running the Services administrative tool, using the sc.exe tool, or calling the Windows StartService function. Typically, services do not interact with the logged-on user, although there are special conditions when this is possible. Additionally, while most services run in special service accounts (such as SYSTEM or LOCAL SERVICE), others can run with the same security context as logged-in user accounts. (For more, see Chapter 9 in Part 2.)

The Service Control Manager (SCM) is a special system process running the image %SystemRoot% System32\Services.exe that is responsible for starting, stopping, and interacting with service processes. It is also a protected process, making it difficult to tamper with. Service programs are really just Windows images that call special Windows functions to interact with the SCM to perform such actions as registering the service's successful startup, responding to status requests, or pausing or shutting down the service. Services are defined in the registry under HKLM\SYSTEM\CurrentControlSet\Services.

Keep in mind that services have three names: the process name you see running on the system, the internal name in the registry, and the display name shown in the Services administrative tool. (Not all services have a display name—if a service doesn't have a display name, the internal name is shown.) Services can also have a description field that further details what the service does.

To map a service process to the services contained in that process, use the tlist/s (from Debugging Tools for Windows) or tasklist/svc (built-in Windows tool) command. Note that there isn't always one-to-one mapping between service processes and running services, however, because some services share a process with other services. In the registry, the Type value under the service's key indicates whether the service runs in its own process or shares a process with other services in the image.

A number of Windows components are implemented as services, such as the Print Spooler, Event Log, Task Scheduler, and various networking components. For more details on services, see Chapter 9 in Part 2.

#### **EXPERIMENT:** Listing installed services

To list the installed services, open the Control Panel, select **Administrative Tools**, and select **Services**. Alternatively, click **Start** and run **services.msc**. You should see output like this:

File Action V	iew Help						
Services (Loca							_
	Select an item to view its description.	Name	Description	Status	Startup Type	Log On As	
	Select an item to view its description.			510103			
		ActiveX Installer (AxInstSV)	Provides Us		Manual	Local Syste	
		Alloyn Router Service	Routes AllJo Monitor Hl	No.	Manual (Trig	Local Service	
		Alps HID Monitor Service	Monitor Hi	Running	Automatic	Local Syste	
		AMD External Events Utility		Running	Automatic	Local Syste	
		App Readiness	Gets apps re		Automatic	Local System	
		Application Host Helper Ser		Running	1000	Local Syste Local Service	
		Application Identity	Determines	Running	Automatic (T		
		Application Information	Facilitates t	Running	Manual (Trig	Local Syste	
		Application Layer Gateway	Provides su		Manual	Local Service	
		Application Management	Processes in		Manual	Local Syste	
		AppX Deployment Service (	Provides inf Provides su		Manual	Local Syste	
		ASP.NET State Service				Network S	
		Auto Time Zone Updater	Automatica		Disabled	Local Service	
		Background Intelligent Tran		Running	Automatic (D	Local Syste	
		Background Tasks Infrastru	Windows in	Running	Automatic	Local Syste	
		Base Filtering Engine	The Base Fil	Running	Automatic	Local Service	
		BitLocker Drive Encryption	BDESVC hos	Running	Manual (Trig	Local Syste	
		BitLocker Management Clie		Running	Automatic	Local Syste	
		Block Level Backup Engine	The WBENG		Manual	Local Syste	
		Bluetooth Handsfree Service	Enables wir		Manual (Trig	Local Service	
		Bluetooth Support Service	The Bluetoo		Manual (Trig	Local Service	
		BranchCache	This service		Manual	Network S	
		Certificate Propagation	Copies user	Running	Automatic	Local Syste	
		Q Client License Service (ClipS	Provides inf		Manual (Trig	Local Syste	_

To see the detailed properties of a service, right-click the service and select **Properties**. For example, here are the properties of the Windows Update service:

General	Log On	Recovery	Depen	dencies		
Service	name:	wuauslerv				
Display	name:	Windows	Update			
Descrip	tion;			ion, download, an ws and other progr		~ ~
	executab DOWS\ø	and the second second	chost.exe	+k netsvcs		
Startup	type:	Manual				~
Service	status:	Stopped				-
9	(tart	Sta	P/	Paure	Besume	
You car from he		he start para	ameters ti	nat apply when yo	u start the servi	28
Start pa	ra <u>m</u> eters:					

Notice that the Path to Executable field identifies the program that contains this service and its command line. Remember that some services share a process with other services. Mapping isn't always one-to-one.

#### **EXPERIMENT:** Viewing service details inside service processes

Process Explorer highlights processes hosting one service or more. (These processes are shaded pink color by default, but you can change this by opening the **Options** menu and choosing **Configure Colors**.) If you double-click a service-hosting process, you will see a Services tab that lists the services inside the process, the name of the registry key that defines the service, the display name seen by the administrator, the description text for that service (if present), and for Svchost. exe services, the path to the DLL that implements the service. For example, listing the services in one of the Svchost.exe processes running under the System account appears as follows:

Services         Threads         TCP/IP         Security         Environment         Strings           Services registered in this process:         Services registered in this process:         Service         Display Name         Path           Brokenk/finat/control         DCOM Service         Display Name         Path           DoomLaunch         DCOM Serve Procees Launc.         C:WINDOW'S Vignem 32/bars rdl         C:WINDOW'S Vignem 32/bars rdl           LSM         Local Second Manager         C:WINDOW'S Vignem 32/bars rdl         C:WINDOW'S Vignem 32/bars rdl           Power         Pug and Play         C:WINDOW'S Vignem 32/bars rdl         C:WINDOW'S Vignem 32/bars rdl           Power         Power         C:WINDOW'S Vignem 32/bars rdl         C:WINDOW'S Vignem 32/bars rdl           SystemEventsBroker         System Events Broker         C:WINDOW'S Vignem 32/bars rdl         System 22/bars rdl           V         Windows infrastructure service that controls which background tasks can run on the system.         2         2	Image	Performance	Performance	Graph	Disk and Network	GPU Grap
Service Display Name Path Bencherhartstuck Background Tarks Hinduck C:WINDOWS System32/barv dl DeonLaunch DCOM Server Process Launc. C:WINDOWS System32/barv dl Local Sestion Manager C:WINDOWS System32/bard dl Local Sestion Manager C:WINDOWS System32/bard dl Power Power C:WINDOWS System32/bard dl C:WINDOWS System32/bard dl C:WINDOWS System32/bard dl SystemEventaBroker System Eventa Broker C:WINDOWS System32/bard dl C:WINDOWS System32/bard	Services	Threads	TCP/IP	Security	Environmen	nt String
Bioketh/Instructure         Eacloground Traks Ministruct         C:WINDOW/SS/system32/boxed           DcomLaunch         DCOM Server Process Launca         C:WINDOWS/system32/boxed           LSM         Local Seeson Manager         C:WINDOWS/system32/boxed           PlugPlay         Plug and Play         C:WINDOWS/system32/boxed           Power         C:WINDOWS/system32/boxed         C:WINDOWS/system32/boxed           SystemEventsBroker         System Events Broker         C:WINDOWS/System32/systemEventsE	Se se	ervices registered	in this process:			
DeomLaunch DCOM Server Process Launc. C:/WINDOWS/system32/tpcod dl LSM Local Session Manager C:/WINDOWS/System32/umong.dl PlugPlay Plug and Play C:/WINDOWS/System32/umonping.dl SystemEventsBroker System Events Broker C:/WINDOWS/System32/SystemEventsBroker SystemEventsBroker 2:///interest Broker 2://interest Broker 2:///interest Broker 2://interest Broker	Service	Display	Name	Path		
LSM Local Session Manager C:\WINDOWS\System32\windl PlugPlay Plug and Play C:\WINDOWS\system32\windl Power Power C:\WINDOWS\system32\windl SystemEventsBroker System Events Broker C:\WINDOWS\System32\SystemEventsB \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$ \$		ructure Backgrow	und Tasks Infras	truct C.\WI		
Plug Plug and Play         C:\WINDOWS'wystem32umpnong.dl           Power         C:\WINDOWS'wystem32umpnong.dl           SystemEventsBroker         System Events Broker						
Power Power C://WINDOWS?vpatem32/umpo.dl SystemEventsBroker System Events Broker C://WINDOWS/System32/SystemEventsB						
SystemEventsBroker System Events Broker C:\WINDOWS\System32\SystemEventsB			riay			
٤						
	SystemEvent		Events Broker			
			Events Broker			
	č	tsBroker System E		C:\WI	NDOWS\System3;	2\SystemEvents
Permissions Stop Restart Pouse Resume	ک Windows infra	toBroker System E astructure service		C:\WI	NDOWS (System); d tasks can run on	2\SystemEvents

#### Winlogon, LogonUI, and Userinit

The Windows logon process (%SystemRoot%\System32\Winlogon.exe) handles interactive user logons and logoffs. Winlogon.exe is notified of a user logon request when the user enters the secure attention sequence (SAS) keystroke combination. The default SAS on Windows is Ctrl+Alt+Delete. The reason for the SAS is to protect users from password-capture programs that simulate the logon process because this keyboard sequence cannot be intercepted by a user-mode application.

The identification and authentication aspects of the logon process are implemented through DLLs called *credential providers*. The standard Windows credential providers implement the default Windows authentication interfaces: password and smartcard. Windows 10 provides a biometric credential provider: face recognition, known as *Windows Hello*. However, developers can provide their own credential providers to implement other identification and authentication mechanisms instead of the standard Windows user name/password method, such as one based on a voice print or a biometric device such as a fingerprint reader. Because Winlogon.exe is a critical system process on which the system depends, credential providers and the UI to display the logon dialog box run inside a child process of Winlogon.exe

called *LogonUI.exe*. When Winlogon.exe detects the SAS, it launches this process, which initializes the credential providers. When the user enters their credentials (as required by the provider) or dismisses the logon interface, the LogonUI.exe process terminates. Winlogon.exe can also load additional network provider DLLs that need to perform secondary authentication. This capability allows multiple network providers to gather identification and authentication information all at one time during normal logon.

After the user name and password (or another information bundle as the credential provider requires) have been captured, they are sent to the Local Security Authentication Service process (Lsass. exe, described in Chapter 7) to be authenticated. Lsass.exe calls the appropriate authentication package, implemented as a DLL, to perform the actual verification, such as checking whether a password matches what is stored in the Active Directory or the SAM (the part of the registry that contains the definition of the local users and groups). If Credential Guard is enabled, and this is a domain logon, Lsass.exe will communicate with the Isolated LSA Trustlet (Lsaiso.exe, described in Chapter 7) to obtain the machine key required to authenticate the legitimacy of the authentication request.

Upon successful authentication, Lsass.exe calls a function in the SRM (for example, NtCreateToken) to generate an access token object that contains the user's security profile. If User Account Control (UAC) is used and the user logging on is a member of the administrators group or has administrator privileges, Lsass.exe will create a second, restricted version of the token. This access token is then used by Winlogon to create the initial process(es) in the user's session. The initial process(es) are stored in the Userinit registry value under the HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Winlogon registry key. The default is Userinit.exe, but there can be more than one image in the list.

Userinit.exe performs some initialization of the user environment, such as running the login script and reestablishing network connections. It then looks in the registry at the Shell value (under the same Winlogon key mentioned previously) and creates a process to run the system-defined shell (by default, Explorer.exe). Then Userinit exits. This is why Explorer is shown with no parent. Its parent has exited, and as explained in Chapter 1, tlist.exe and Process Explorer left-justify processes whose parent isn't running. Another way of looking at it is that Explorer is the grandchild of Winlogon.exe.

Winlogon.exe is active not only during user logon and logoff, but also whenever it intercepts the SAS from the keyboard. For example, when you press Ctrl+Alt+Delete while logged on, the Windows Security screen comes up, providing the options to log off, start the Task Manager, lock the workstation, shut down the system, and so forth. Winlogon.exe and LogonUI.exe are the processes that handle this interaction.

For a complete description of the steps involved in the logon process, see Chapter 11 in Part 2. For more details on security authentication, see Chapter 7. For details on the callable functions that interface with Lsas.exe (the functions that start with Lsa), see the documentation in the Windows SDK.

### Conclusion

This chapter takes a broad look at the overall system architecture of Windows. It examines the key components of Windows and shows how they interrelate. In the next chapter, we'll look in more detail at processes, which are one of the most basic entities in Windows.

This page intentionally left blank

# **Processes and jobs**

n this chapter, we'll explain the data structures and algorithms that deal with processes and jobs in Windows. First we'll take a general look at process creation. Then we'll examine the internal structures that make up a process. Next we'll look at protected processes and how they differ from non-protected ones. After that we outline the steps involved in creating a process (and its initial thread). The chapter concludes with a description of jobs.

Because processes touch so many components in Windows, a number of terms and data structures (such as working sets, threads, objects and handles, system memory heaps, and so on) are referred to in this chapter but are explained in detail elsewhere in the book. To fully understand this chapter, you need to be familiar with the terms and concepts explained in Chapter 1, "Concepts and tools," and Chapter 2, "System architecture," such as the difference between a process and a thread, the Windows virtual address space layout, and the difference between user mode and kernel mode.

#### **Creating a process**

The Windows API provides several functions for creating processes. The simplest is CreateProcess, which attempts to create a process with the same access token as the creating process. If a different token is required, CreateProcessAsUser can be used, which accepts an extra argument (the first)—a handle to a token object that was already somehow obtained (for example, by calling the LogonUser function).

Other process creation functions include CreateProcessWithTokenW and CreateProcessWithLogonW (both part of advapi32.Dll). CreateProcessWithTokenW is similar to CreateProcessAsUser, but the two differ in the privileges required for the caller. (Check the Windows SDK documentation for the specifics.) CreateProcessWithLogonW is a handy shortcut to log on with a given user's credentials and create a process with the obtained token in one stroke. Both call the Secondary Logon service (seclogon.dll, hosted in a SvcHost.Exe) by making a Remote Procedure Call (RPC) to do the actual process creation. SecLogon executes the call in its internal SIrCreateProcessWithLogon function, and if all goes well, eventually calls CreateProcessAsUser. The SecLogon service is configured by default to start manually, so the first time CreateProcessWithTokenW or CreateProcessWithLogonW is called, the service is started. If the service fails to start (for example, an administrator can configure the service to be disabled), these functions will fail. The runas command-line utility, which you may be familiar with, makes use of these functions.

Figure 3-1 shows the call graph described above.




FIGURE 3-1 Process creation functions. Functions marked with dotted boxes are internal.

All the above documented functions expect a proper Portable Executable (PE) file (although the EXE extension is not strictly required), batch file, or 16-bit COM application. Beyond that, they have no knowledge of how to connect files with certain extensions (for example, .txt) to an executable (for example, Notepad). This is something that is provided by the Windows Shell, in functions such as ShellExecute and ShellExecuteEx. These functions can accept any file (not just executables) and try to locate the executable to run based on the file extensions and the registry settings at HKEY\_CLASSES\_ROOT. (See Chapter 9, "Management mechanisms," in *Windows Internals Part 2* for more on this.) Eventually, ShellExecute(Ex) calls CreateProcess with a proper executable and appends appropriate arguments on the command line to achieve the user's intention (such as editing a TXT file by appending the file name to Notepad.exe).

Ultimately, all these execution paths lead to a common internal function, CreateProcessInternal, which starts the actual work of creating a user-mode Windows process. Eventually (if all goes well), CreateProcessInternal calls NtCreateUserProcess in Ntdll.dll to make the transition to kernel mode and continue the kernel-mode part of process creation in the function with the same name (NtCreateUserProcess), part of the Executive.

### CreateProcess\* functions arguments

It's worthwhile to discuss the arguments to the CreateProcess\* family of functions, some of which will be referred to in the section on the flow of CreateProcess. A process created from user mode is always created with one thread within it. This is the thread that eventually will execute the main function of the executable. Here are the important arguments to the CreateProcess\* functions:

For CreateProcessAsUser and CreateProcessWithTokenW, the token handle under which the new process should execute. Similarly, for CreateProcessWithLogonW, the username, domain and password are required.

- The executable path and command-line arguments.
- Optional security attributes applied to the new process and thread object that's about to be created.
- A Boolean flag indicating whether all handles in the current (creating) process that are marked inheritable should be inherited (copied) to the new process. (See Chapter 8, "System mechanisms," in Part 2 for more on handles and handle inheritance.)
- Various flags that affect process creation. Here are some examples. (Check the Windows SDK documentation for a complete list.)
  - **CREATE\_SUSPENDED** This creates the initial thread of the new process in the suspended state. A later call to ResumeThread will cause the thread to begin execution.
  - **DEBUG\_PROCESS** The creating process is declaring itself to be a debugger, creating the new process under its control.
  - **EXTENDED\_STARTUPINFO\_PRESENT** The extended STARTUPINFOEX structure is provided instead of STARTUPINFO (described below).
- An optional environment block for the new process (specifying environment variables). If not specified, it will be inherited from the creating process.
- An optional current directory for the new process. (If not specified, it uses the one from the creating process.) The created process can later call SetCurrentDirectory to set a different one. The current directory of a process is used in various non-full path searches (such as when loading a DLL with a filename only).
- A STARTUPINFO or STARTUPINFOEX structure that provides more configuration for process creation. STARTUPINFOEX contains an additional opaque field that represents a set of process and thread attributes that are essentially an array of key/value pairs. These attributes are filled by calling UpdateProcThreadAttributes once for each attribute that's needed. Some of these attributes are undocumented and used internally, such as when creating store apps, as described in the next section.
- A PROCESS\_INFORMATION structure that is the output of a successful process creation. This structure holds the new unique process ID, the new unique thread ID, a handle to the new process and a handle to the new thread. The handles are useful for the creating process if it wants to somehow manipulate the new process or thread in some way after creation.

### **Creating Windows modern processes**

Chapter 1 described the new types of applications available starting from Windows 8 and Windows Server 2012. The names of these apps have changed over time, but we'll refer to them as modern apps, UWP apps, or immersive processes, to distinguish them from the classic, also known as desktop, applications. Creating a modern application process requires more than just calling CreateProcess with the correct executable path. There are some required command-line arguments. Yet another requirement is adding an undocumented process attribute (using UpdateProcThreadAttribute) with a key named PROC\_THREAD\_ATTRIBUTE\_PACKAGE\_FULL\_NAME with the value set to the full store app package name. Although this attribute is undocumented, there are other ways (from an API perspective) to execute a store app. For example, the Windows API includes a COM interface called IApplicationActivation-Manager that is implemented by a COM class with a CLSID named CLSID\_ApplicationActivation-Manager. One of the methods in the interface is ActivateApplication, which can be used to launch a store app after obtaining something known as *AppUserModelId* from the store app full package name by calling GetPackageApplicationIds. (See the Windows SDK for more information on these APIs.)

Package names and the way a store app is typically created, from a user tapping on a modern app tile, eventually leading to CreateProcess, is discussed in Chapter 9 in Part 2.

### Creating other kinds of processes

Although Windows applications launch either classic or modern applications, the Executive includes support for additional kinds of processes that must be started by bypassing the Windows API, such as native processes, minimal processes, or Pico processes. For example, we described in Chapter 2 the existence of Smss, the Session Manager, which is an example of a native image. Since it is created directly by the kernel, it obviously does not use the CreateProcess API, but instead calls directly into NtCreateUserProcess. Similarly, when Smss creates Autochk (the check disk utility) or Csrss (the Windows subsystem process), the Windows API is also not available, and NtCreateUserProcess must be used. Additionally, native processes cannot be created from Windows applications, as the CreateProcessInternal function will reject images with the native subsystem image type. To alleviate these complications, the native library, Ntdll.dll, includes an exported helper function called Rt1CreateUserProcess.

As its name suggests, NtCreateUserProcess is used for the creation of user-mode processes. However, as we saw in Chapter 2, Windows also includes a number of kernel-mode processes, such as the System process and the Memory Compression processes (which are minimal processes), plus the possibility of Pico processes managed by a provider such as the Windows Subsystem for Linux. The creation of such processes is instead provided by the NtCreateProcessEx system call, with certain capabilities reserved solely for kernel-mode callers (such as the creation of minimal processes).

Finally, Pico providers call a helper function, which takes care of both creating the minimal process as well as initializing its Pico provider context—PspCreatePicoProcess. This function is not exported, and is only available to Pico providers through their special interface.

As we'll see in the flow section later in this chapter, although NtCreateProcessEx and NtCreate-UserProcess are different system calls, the same internal routines are used to perform the work: PspAllocateProcess and PspInsertProcess. All the possible ways we've enumerated so far to create a process, and any ways you can imagine, from a WMI PowerShell cmdlet to a kernel driver, will end up there.

#### **Process internals**

This section describes the key Windows process data structures maintained by various parts of the system and describes different ways and tools to examine this data.

Each Windows process is represented by an executive process (EPROCESS) structure. Besides containing many attributes relating to a process, an EPROCESS contains and points to a number of other related data structures. For example, each process has one or more threads, each represented by an executive thread (ETHREAD) structure. (Thread data structures are explained in Chapter 4, "Threads".)

The EPROCESS and most of its related data structures exist in system address space. One exception is the Process Environment Block (PEB), which exists in the process (user) address space (because it contains information accessed by user-mode code). Additionally, some of the process data structures used in memory management, such as the working set list, are valid only within the context of the current process, because they are stored in process-specific system space. (See Chapter 5, "Memory management," for more information on process address space.)

For each process that is executing a Windows program, the Windows subsystem process (Csrss) maintains a parallel structure called the CSR\_PROCESS. Additionally, the kernel-mode part of the Windows subsystem (Win32k.sys) maintains a per-process data structure, W32PROCESS, which is created the first time a thread calls a Windows USER or GDI function that is implemented in kernel mode. This happens as soon as the User32.dll library is loaded. Typical functions that cause this library to be loaded are CreateWindow(Ex) and GetMessage.

Since the kernel-mode Windows subsystem makes heavy use of DirectX-based hardware accelerated graphics, the Graphics Device Interface (GDI) component infrastructure causes the DirectX Graphics Kernel (Dxgkrnl.sys) to initialize a structure of its own, DXGPROCESS. This structure contains information for DirectX objects (surfaces, shaders, etc.) and the GPGPU-related counters and policy settings for both computational and memory management–related scheduling.

Except for the idle process, every EPROCESS structure is encapsulated as a process object by the executive object manager (described in Chapter 8 in Part 2). Because processes are not named objects, they are not visible in the WinObj tool (from Sysinternals). You can, however, see the Type object called *Process* in the \ObjectTypes directory (in WinObj). A handle to a process provides, through use of the process-related APIs, access to some of the data in the EPROCESS structure and in some of its associated structures.

Many other drivers and system components, by registering process-creation notifications, can choose to create their own data structures to track information they store on a per-process basis. (The executive functions PsSetCreateProcessNotifyRoutine(Ex, Ex2) allow this and are documented in the WDK.) When one discusses the overhead of a process, the size of such data structures must often be taken into consideration, although it is nearly impossible to obtain an accurate number. Additionally, some of these functions allow such components to disallow, or block, the creation of processes. This provides anti-malware vendors with an architectural way to add security enhancements to the operating system, either through hash-based blacklisting or other techniques.

First let's focus on the Process object. Figure 3-2 shows the key fields in an EPROCESS structure.




FIGURE 3-2 Important fields of the executive process structure.

Similar to the way the kernel's APIs and components are divided into isolated and layered modules with their own naming conventions, the data structures for a process follow a similar design. As shown in Figure 3-2, the first member of the executive process structure is called *Pcb (Process Control Block)*. It is a structure of type KPROCESS, for *kernel process*. Although routines in the executive store information in the EPROCESS, the dispatcher, scheduler, and interrupt/time accounting code—being part of the operating system kernel—use the KPROCESS instead. This allows a layer of abstraction to exist between the executive's high-level functionality and its underlying low-level implementation of certain functions, and helps prevent unwanted dependencies between the layers. Figure 3-3 shows the key fields in a KPROCESS structure.




FIGURE 3-3 Important fields of the kernel process structure.

#### **EXPERIMENT:** Displaying the format of an EPROCESS structure

For a list of the fields that make up an EPROCESS structure and their offsets in hexadecimal, type **dt nt!\_eprocess** in the kernel debugger. (See Chapter 1 for more information on the kernel debugger and how to perform kernel debugging on the local system.) The output (truncated for the sake of space) on a 64-bit Windows 10 system looks like this:

```
lkd> dt nt!_eprocess
  +0x000 Pcb
                       : _KPROCESS
  +0x2d8 ProcessLock : _EX_PUSH_LOCK
  +0x2e0 RundownProtect : _EX_RUNDOWN_REF
  +0x2e8 UniqueProcessId : Ptr64 Void
  +0x2f0 ActiveProcessLinks : _LIST_ENTRY
  +0x3a8 Win32Process : Ptr64 Void
  +0x3b0 Job : Ptr64 _EJOB
  +0x418 ObjectTable : Ptr64 _HANDLE_TABLE
  +0x420 DebugPort
                       : Ptr64 Void
  +0x428 WoW64Process
                       : Ptr64 _EWOW64PROCESS
  +0x758 SharedCommitCharge : Uint8B
  +0x760 SharedCommitLock : _EX_PUSH_LOCK
  +0x768 SharedCommitLinks : _LIST_ENTRY
```

```
+0x778 AllowedCpuSets : Uint8B
+0x780 DefaultCpuSets : Uint8B
+0x778 AllowedCpuSetsIndirect : Ptr64 Uint8B
+0x780 DefaultCpuSetsIndirect : Ptr64 Uint8B
```

The first member of this structure (Pcb) is an embedded structure of type KPROCESS. This is where scheduling and time-accounting data is stored. You can display the format of the kernel process structure in the same way as the EPROCESS:

```
1kd> dt nt!_kprocess
+0x000 Header : _DISPATCHER_HEADER
+0x018 ProfileListHead : _LIST_ENTRY
+0x028 DirectoryTableBase : Uint8B
+0x030 ThreadListHead : _LIST_ENTRY
+0x040 ProcessLock : Uint4B
...
+0x26c KernelTime : Uint4B
+0x270 UserTime : Uint4B
+0x270 UserTime : Uint4B
+0x274 LdtFreeSelectorHint : Uint2B
+0x276 LdtTableLength : Uint2B
+0x278 LdtSystemDescriptor : _KGDTENTRY64
+0x288 LdtBaseAddress : Ptr64 Void
+0x290 LdtProcessLock : _FAST_MUTEX
+0x2c8 InstrumentationCallback : Ptr64 Void
+0x200 SecurePid : Uint8B
```

The dt command also enables you to view the specific contents of one field or multiple fields by typing their names following the structure name. For example, typing **dt nt!\_eprocess UniqueProcessId** displays the process ID field. In the case of a field that represents a structure such as the Pcb field of EPROCESS, which contains the KPROCESS substructure—adding a period after the field name will cause the debugger to display the substructure. For example, an alternative way to see the KPROCESS is to type **dt nt!\_eprocess Pcb**. You can continue to recurse this way by adding more field names (within KPROCESS) and so on. Finally, the –r switch of the dt command allows you to recurse through all the substructures. Adding a number after the switch controls the depth of recursion the command will follow.

The dt command used as shown earlier shows the format of the selected structure, not the contents of any particular instance of that structure type. To show an instance of an actual process, you can specify the address of an EPROCESS structure as an argument to the dt command. You can get the addresses of almost all of the EPROCESS structures in the system by using the !process 0 0 command (the exception being the system idle process). Because the KPROCESS is the first thing in the EPROCESS, the address of an EPROCESS will also work as the address of a KPROCESS with dt \_kprocess.

#### EXPERIMENT: Using the kernel debugger !process command

The kernel debugger !process command displays a subset of the information in a process object and its associated structures. This output is arranged in two parts for each process. First you see the information about the process, as shown here. When you don't specify a process address or ID, !process lists information for the process owning the thread currently running on CPU 0, which will be WinDbg itself (or livekd if it's used in lieu of WinDbg) on a single-processor system.

Image: windbg.exe	f2f1de000 ParentCid: Of08 fc000a2b22200 HandleCount: <data accessible="" not=""> Clone O Private 3563. Modified 228. Locked 1.</data>
Token	ffffc000a13f39a0
ElapsedTime	00:00:20.772
UserTime	00:00:00.000
KernelTime	00:00.015
QuotaPoolUsage[PagedPool]	299512
QuotaPoolUsage[NonPagedPool]	16240
Working Set Sizes (now,min,max)	(9719, 50, 345) (38876KB, 200KB, 1380KB)
PeakWorkingSetSize	9947
VirtualSize	2097319 Mb
PeakVirtualSize	2097321 Mb
PageFaultCount	13603
MemoryPriority	FOREGROUND
BasePriority	8
CommitCharge	3994
Job	ffffe0011b853690

After the basic process output comes a list of the threads in the process. That output is explained in the "Experiment: Using the kernel debugger !thread command" section in Chapter 4.

Other commands that display process information include !handle, which dumps the process handle table (described in more detail in the section "Object handles and the process handle table" in Chapter 8 in Part 2). Process and thread security structures are described in Chapter 7, "Security."

Note that the output gives the address of the PEB. You can use this with the !peb command shown in the next experiment to see a friendly view of the PEB of an arbitrary process or you can use the regular dt command with the \_PEB structure. However, because the PEB is in the user-mode address space, it is valid only within the context of its own process. To look at the PEB of another process, you must first switch WinDbg to that process. You can do this with the .process /P command, followed by the EPROCESS pointer.

If you're using the latest Windows 10 SDK, the updated version of WinDbg will include an intuitive hyperlink under the PEB address, which you can click to automatically execute both the .process command and the !peb command.

The PEB lives in the user-mode address space of the process it describes. It contains information needed by the image loader, the heap manager, and other Windows components that need to access it from user mode; it would be too expensive to expose all that information through system calls. The EPROCESS and KPROCESS structures are accessible only from kernel mode. The important fields of the PEB are illustrated in Figure 3-4 and are explained in more detail later in this chapter.




FIGURE 3-4 Important fields of the Process Environment Block.

#### **EXPERIMENT: Examining the PEB**

You can dump the PEB structure with the !peb command in the kernel debugger, which displays the PEB of the process that owns the currently running thread on CPU 0. By using the information in the previous experiment, you can also use the PEB pointer as an argument to the command.

```
1kd> .process /P ffffe0011c3243c0 ; !peb 5f2f1de000
PEB at 0000003561545000
   InheritedAddressSpace:
                            No
   ReadImageFileExecOptions: No
   BeingDebugged:
                           No
   ImageBaseAddress: 00007ff64fa70000
   Ldr
                           00007ffdf52f5200
   Ldr.Initialized:
                            Yes
   Ldr.InInitializationOrderModuleList: 000001d3d22b3630 . 000001d3d6cddb60
   Ldr.InLoadOrderModuleList: 000001d3d22b3790 . 000001d3d6cddb40
   Ldr.InMemoryOrderModuleList: 000001d3d22b37a0 . 000001d3d6cddb50
                   Base TimeStamp
                                                    Module
           7ff64fa70000 56ccafdd Feb 23 21:15:41 2016 C:\dbg\x64\windbg.exe
           7ffdf51b0000 56cbf9dd Feb 23 08:19:09 2016 C:\WINDOWS\SYSTEM32\ntdll.dll
           7ffdf2c10000 5632d5aa Oct 30 04:27:54 2015 C:\WINDOWS\system32\KERNEL32.DLL
    . . .
```

The CSR\_PROCESS structure contains information about processes that is specific to the Windows subsystem (Csrss). As such, only Windows applications have a CSR\_PROCESS structure associated with them (for example, Smss does not). Additionally, because each session has its own instance of the Windows subsystem, the CSR\_PROCESS structures are maintained by the Csrss process within each individual session. The basic structure of the CSR\_PROCESS is illustrated in Figure 3-5 and is explained in more detail later in this chapter.




FIGURE 3-5 Fields of the CSR process structure.

#### **EXPERIMENT: Examining the CSR\_PROCESS**

Csrss processes are protected (see later in this chapter for more on protected processes), so it's not possible to attach a user mode debugger to a Csrss process (not even with elevated privileges or non-invasively). Instead, we'll use the kernel debugger.

First, list the existing Csrss processes:

```
lkd> !process 0 0 csrss.exe
PROCESS ffffe00077ddf080
SessionId: 0 Cid: 02c0 Peb: c4e3fc0000 ParentCid: 026c
DirBase: ObjectTable: ffffc0004d15d040 HandleCount: 543.
Image: csrss.exe
```

PROCESS ffffe00078796080

SessionId: 1 Cid: 0338 Peb: d4b4db4000 ParentCid: 0330 DirBase: ObjectTable: ffffc0004ddff040 HandleCount: 514. Image: csrss.exe

Next, take any one of them and change the debugger context to point to the particular process so that its user mode modules are visible:

```
lkd> .process /r /P ffffe00078796080
Implicit process is now ffffe000'78796080
Loading User Symbols
```

. . . . . . . . . . . . .

The /p switch changes the process context of the debugger to the provided process object (EPROCESS, mostly needed in live debugging) and /r requests loading of user mode symbols. Now you can look at the modules themselves using the 1m command or look at the CSR\_PROCESS structure:

```
1kd> dt csrss!_csr_process
  +0x000 ClientId : _CLIENT_ID
+0x010 ListLink : _LIST_ENTRY
+0x020 ThreadList : _LIST_ENTRY
  +0x030 NtSession : Ptr64 _CSR_NT_SESSION
+0x038 ClientPort : Ptr64 Void
  +0x040 ClientViewBase : Ptr64 Char
  +0x048 ClientViewBounds : Ptr64 Char
  +0x050 ProcessHandle : Ptr64 Void
  +0x058 SequenceNumber : Uint4B
  +0x05c Flags : Uint4B
+0x060 DebugFlags : Uint4B
  +0x064 ReferenceCount : Int4B
  +0x068 ProcessGroupId : Uint4B
  +0x06c ProcessGroupSequence : Uint4B
  +0x070 LastMessageSequence : Uint4B
  +0x074 NumOutstandingMessages : Uint4B
  +0x078 ShutdownLevel : Uint4B
  +0x07c ShutdownFlags : Uint4B
  +0x080 Luid : _LUID
  +0x088 ServerDllPerProcessData : [1] Ptr64 Void
```

The W32PROCESS structure is the final system data structure associated with processes that we'll look at. It contains all the information that the Windows graphics and window management code in the kernel (Win32k) needs to maintain state information about GUI processes (which were defined earlier as processes that have done at least one USER/GDI system call). The basic structure of the W32PROCESS is illustrated in Figure 3-6. Unfortunately, since type information for Win32k structures is not available in public symbols, we can't easily show you an experiment displaying this information. Either way, discussion of graphics-related data structures and concepts is beyond the scope of this book.




FIGURE 3-6 Fields of the Win32k Process structure.

### **Protected processes**

In the Windows security model, any process running with a token containing the debug privilege (such as an administrator's account) can request any access right that it desires to any other process running on the machine. For example, it can read and write arbitrary process memory, inject code, suspend and resume threads, and query information on other processes. Tools such as Process Explorer and Task Manager need and request these access rights to provide their functionality to users.

This logical behavior (which helps ensure that administrators will always have full control of the running code on the system) clashes with the system behavior for digital rights management requirements imposed by the media industry on computer operating systems that need to support playback of advanced, high-quality digital content such as Blu-ray media. To support reliable and protected playback of such content, Windows Vista and Windows Server 2008 introduced protected processes. These processes exist alongside normal Windows processes, but they add significant constraints to the access rights that other processes on the system (even when running with administrative privileges) can request.

Protected processes can be created by any application. However, the operating system will allow a process to be protected only if the image file has been digitally signed with a special Windows Media Certificate. The Protected Media Path (PMP) in Windows makes use of protected processes to provide protection for high-value media, and developers of applications such as DVD players can make use of protected processes by using the Media Foundation (MF) API.

The Audio Device Graph process (Audiodg.exe) is a protected process because protected music content can be decoded through it. Related to this is the Media Foundation Protected Pipeline (Mfpmp.exe), which is also a protected process for similar reasons (it does not run by default). Similarly, the Windows Error Reporting (WER; discussed in Chapter 8 in Part 2) client process (Werfaultsecure.exe) can also run protected because it needs to have access to protected processes in case one of them crashes. Finally, the System process itself is protected because some of the decryption information is generated by the Ksecdd.sys driver and stored in its user-mode memory. The System process is also protected to protect the integrity of all kernel handles (because the System process's handle table contains all the kernel handles on the system). Since other drivers may also sometimes map memory inside the user-mode address space of the System process (such as Code Integrity certificate and catalog data), it's yet another reason for keeping the process protected.

At the kernel level, support for protected processes is twofold. First, the bulk of process creation occurs in kernel mode to avoid injection attacks. (The flow for both protected and standard process creation is described in detail in the next section.) Second, protected processes (and their extended cousin, Protected Processes Light [PPL], described in the next section) have special bits set in their EPROCESS structure that modify the behavior of security-related routines in the process manager to deny certain access rights that would normally be granted to administrators. In fact, the only access rights that are granted for protected processes are PROCESS\_QUERY/SET\_LIMITED\_INFORMATION, PROCESS\_TERMINATE and PROCESS\_SUSPEND\_RESUME. Certain access rights are also disabled for threads running inside protected processes. We will look at those access rights in Chapter 4 in the section "Thread internals."

Because Process Explorer uses standard user-mode Windows APIs to query information on process internals, it is unable to perform certain operations on such processes. On the other hand, a tool like WinDbg in kernel-debugging mode, which uses kernel-mode infrastructure to obtain this information, will be able to display complete information. See the experiment in the "Thread internals" section in Chapter 4 on how Process Explorer behaves when confronted with a protected process such as Audiodg.exe.

**Note** As mentioned in Chapter 1, to perform local kernel debugging, you must boot in debugging mode (enabled by using bcdedit /debug on or by using the Msconfig advanced boot options). This mitigates against debugger-based attacks on protected processes and the PMP. When booted in debugging mode, high-definition content playback will not work.

Limiting these access rights reliably allows the kernel to sandbox a protected process from usermode access. On the other hand, because a protected process is indicated by a flag in the EPROCESS structure, an administrator can still load a kernel-mode driver that modifies this flag. However, this would be a violation of the PMP model and considered malicious, and such a driver would likely eventually be blocked from loading on a 64-bit system because the kernel-mode, code-signing policy prohibits the digital signing of malicious code. Additionally, kernel-mode patch protection, known as PatchGuard (described in Chapter 7), as well as the Protected Environment and Authentication Driver (Peauth.sys), will recognize and report such attempts. Even on 32-bit systems, the driver has to be recognized by PMP policy or the playback may be halted. This policy is implemented by Microsoft and not by any kernel detection. This block would require manual action from Microsoft to identify the signature as malicious and update the kernel.

### **Protected Process Light (PPL)**

As we just saw, the original model for protected processes focused on DRM-based content. Starting with Windows 8.1 and Windows Server 2012 R2, an extension to the protected process model was introduced, called Protected Process Light (PPL).

PPLs are protected in the same sense as classic protected processes: User-mode code (even running with elevated privileges) cannot penetrate these processes by injecting threads or obtaining detailed information about loaded DLLs. However, the PPL model adds an additional dimension to the quality of being protected: attribute values. The different Signers have differing trust levels, which in turn results in certain PPLs being more, or less, protected than other PPLs.

Because DRM evolved from merely multimedia DRM to also Windows licensing DRM and Windows Store DRM, standard protected processes are now also differentiated based on the Signer value. Finally, the various recognized Signers also define which access rights are denied to lesser protected processes. For example, normally, the only access masks allowed are PROCESS\_QUERY/SET\_LIMITED\_INFORMATION and PROCESS\_SUSPEND\_RESUME. PROCESS\_TERMINATE is not allowed for certain PPL signers.

Table 3-1 shows the legal values for the protection flag stored in the EPROCESS structure.

Internal Protection Process Level Symbol	Protection Type	Signer
PS_PROTECTED_SYSTEM (0x72)	Protected	WinSystem
PS_PROTECTED_WINTCB (0x62)	Protected	WinTcb
PS_PROTECTED_WINTCB_LIGHT (0x61)	Protected Light	WinTcb
PS_PROTECTED_WINDOWS (0x52)	Protected	Windows
PS_PROTECTED_WINDOWS_LIGHT (0x51)	Protected Light	Windows
PS_PROTECTED_LSA_LIGHT (0x41)	Protected Light	Lsa
PS_PROTECTED_ANTIMALWARE_LIGHT (0x31)	Protected Light	Anti-malware
PS_PROTECTED_AUTHENTICODE (0x21)	Protected	Authenticode
PS_PROTECTED_AUTHENTICODE_LIGHT (0x11)	Protected Light	Authenticode
PS_PROTECTED_NONE (0x00)	None	None

**TABLE 3-1** Valid protection values for processes

As shown in Table 3-1, there are several signers defined, from high to low power. WinSystem is the highest-priority signer and used for the System process and minimal processes such as the Memory Compression process. For user-mode processes, WinTCB (Windows Trusted Computer Base) is the highest-priority signer and leveraged to protect critical processes that the kernel has intimate knowledge

of and might reduce its security boundary toward. When interpreting the power of a process, keep in mind that first, protected processes always trump PPLs, and that next, higher-value signer processes have access to lower ones, but not vice versa. Table 3-2 shows the signer levels (higher values denote the signer is more powerful) and some examples of their usage. You can also dump these in the debugger with the \_PS\_PROTECTED\_SIGNER type.

Signer Name (PS_PROTECTED_SIGNER)	Level	Used For
PsProtectedSignerWinSystem	7	System and minimal processes (including Pico processes).
PsProtectedSignerWinTcb	6	Critical Windows components. PROCESS_TERMINATE is denied.
PsProtectedSignerWindows	5	Important Windows components handling sensitive data.
PsProtectedSignerLsa	4	Lsass.exe (if configured to run protected).
PsProtectedSignerAntimalware	3	Anti-malware services and processes, including third party. PROCESS_TERMINATE is denied.
PsProtectedSignerCodeGen	2	NGEN (.NET native code generation).
PsProtectedSignerAuthenticode	1	Hosting DRM content or loading user-mode fonts.
PsProtectedSignerNone	0	Not valid (no protection).

TABLE 3-2	Signers and	levels
-----------	-------------	--------

At this point you may be wondering what prohibits a malicious process from claiming it is a protected process and shielding itself from anti-malware (AM) applications. Because the Windows Media DRM Certificate is no longer necessary to run as a protected process, Microsoft extended its Code Integrity module to understand two special enhanced key usage (EKU) OIDs that can be encoded in a digital code signing certificate: 1.3.6.1.4.1.311.10.3.22 and 1.3.6.1.4.1.311.10.3.20. Once one of these EKUs is present, hardcoded Signer and Issuer strings in the certificate, combined with additional possible EKUs, are then associated with the various Protected Signer values. For example, the Microsoft Windows Issuer can grant the PsProtectedSignerWindows protected signer value, but only if the EKU for Windows System Component Verification (1.3.6.1.4.1.311.10.3.6) is also present. As an example, Figure 3-7 shows the certificate for Smss.exe, which is permitted to run as WinTcb-Light.

Finally, note that the protection level of a process also impacts which DLLs it will be allowed to load—otherwise, either through a logic bug or simple file replacement or plating, a legitimate protected process could be coerced into loading a third party or malicious library, which would now execute with the same protection level as the process. This check is implemented by granting each process a "Signature Level," which is stored in the SignatureLevel field of EPROCESS, and then using an internal lookup table to find a corresponding "DLL Signature Level," stored as SectionSignatureLevel in EPROCESS. Any DLL loading in the process will be checked by the Code Integrity component in the same way that the main executable is verified. For example, a process with "WinTcb" as its executable signer will only load "Windows" or higher signed DLLs.

eneral	Details Ce	rtification Path		
Show:	<all></all>		~	
Field	1		Value	^
Pu	blic key paran	neters	05 00	
En	hanced Key U	sage	Code Signing (1.3.6.1.5.5.7.3	
Su	bject Key Ide	ntifier	71 8f ba 8e 97 70 20 1c 55 ba	
Su	bject Alternat	ive Name	Directory Address:SERIALNUM	
_	thority Key Id		KeyID=a9 29 02 39 8e 16 c4 9	
	L Distribution		[1]CRL Distribution Point: Distr	
	5	nation Access		5
Ra	sic Constraint	2	Subject Type=End Entity Pat	
Windov Protect	ed Process Li	mponent Verifi ght Verification onent (1.3.6.1	ication (1.3.6.1.4.1.311.10.3.6) n (1.3.6.1.4.1.311.10.3.22) l.4.1.311.10.3.23) dit Properties	
		15	Copy to File.	

FIGURE 3-7 Smss certificate.

On Windows 10 and Windows Server 2016, the following processes are PPL signed with WinTcb-Lite: smss.exe, csrss.exe, services.exe, and wininit.exe. Lsass.exe is running as PPL on ARM-based Windows (such as Windows mobile 10) and can run as PPL on x86/x64 if configured as such by a registry setting or by policy (see Chapter 7 for more information). Additionally, certain services are configured to run as Windows PPL or protected processes, such as sppsvc.exe (Software Protection Platform). You may also notice certain service-hosting processes (Svchost.exe) running with this protection level, since many services, such as the AppX Deployment Service and the Windows Subsystem for Linux Service, also run protected. More information on such protected services will be described in Chapter 9 in Part 2.

The fact that these core system binaries run as TCB is critical to the security of the system. For example, Csrss.exe has access to certain private APIs implemented by the Window Manager (Win32k.sys), which could give an attacker with Administrator rights access to sensitive parts of the kernel. Similarly, Smss. exe and Wininit.exe implement system startup and management logic that is critical to perform without possible interference from an administrator. Windows guarantees that these binaries will always run as WinTcb-Lite such that, for example, it is not possible for someone to launch them without specifying the correct process protection level in the process attributes when calling CreateProcess. This guarantee is known as the *minimum TCB list* and forces any processes with the names in Table 3-3 that are in a System path to have a minimum protection level and/or signing level regardless of the caller's input.

#### TABLE 3-3 Minimum TCB

Process Name	Minimum Signature Level	Minimum Protection Level
Smss.exe	Inferred from protection level	WinTcb-Lite
Csrss.exe	Inferred from protection level	WinTcb-Lite
Wininit.exe	Inferred from protection level	WinTcb-Lite
Services.exe	Inferred from protection level	WinTcb-Lite
Werfaultsecure.exe	Inferred from protection level	WinTcb-Full
Sppsvc.exe	Inferred from protection level	Windows-Full
Genvalobj.exe	Inferred from protection level	Windows-Full
Lsass.exe	SE_SIGNING_LEVEL_WINDOWS	0
Userinit.exe	SE_SIGNING_LEVEL_WINDOWS	0
Winlogon.exe	SE_SIGNING_LEVEL_WINDOWS	0
Autochk.exe	SE_SIGNING_LEVEL_WINDOWS*	0

\*Only on UEFI firmware systems

#### **EXPERIMENT:** Viewing protected processes in Process Explorer

In this experiment, we'll look at how Process Explorer shows protected processes (of either type). Run Process Explorer and select the **Protection** check box in the Process Image tab to view the Protection column:

Process Network Pro	cess Disk	Pro	cess Me	mory
Process GPU Handle	DLL	.NET	State	us Bar
Process Image Proces	ss Performa	nce	Proces	s I/O
Select the columns that will a Process Explorer.	appear on th	e Proces	ss view of	
Process Name	W	ndow Tit	le	
PID (Process Identifier)	DW	ndow St	atus	
User Name	Se Se	ssion		
Description	Co	mmand I	Line	
Company Name		mment		
Verified Signer	Au	tostart L	ocation	
Version	Vir	usTotal		
Image Path	DE	P Statu	5	
Image Type (64 vs 32-bit)	Int	egrity Le	vel	
Package Name	Vir	tualized		
DPI Awareness	AS	LR Enal	bled	
Protection		Access		
Control Flow Guard	010524154			

Now sort by the Protection column in descending order and scroll to the top. You should see all protected processes with their protection type. Here's a screenshot from a Windows 10 x64 machine:

Process	PID	CPU	Protection	F
🖃 💽 System	4	0.19	PsProtectedSignerWinTcb	
wininit.exe	784		PsProtectedSignerWinTcb-Light	
smss.exe	488		PsProtectedSignerWinTcb-Light	
services.exe	868		PsProtectedSignerWinTcb-Light	
CSISS.exe	648		PsProtectedSignerWinTcb-Light	
CSISS.exe	792	0.06	PsProtectedSignerWinTcb-Light	
NisSrv.exe	4988		PsProtectedSignerAntimalware-Light	
MsMpEng.exe	3284	0.05	PsProtectedSignerAntimalware-Light	
WUDFHost.exe	2692			
WUDFHost.exe	2808			
WUDFHost.exe	2892			
WmiPrySE eve	5292	0.01		

If you select a protected process and look at the lower part when configured to view DLLs, you'll see nothing. That's because Process Explorer uses user-mode APIs to query the loaded modules and that requires access that is not granted for accessing protected processes. The notable exception is the System process, which is protected, but Process Explorer instead shows the list of loaded kernel modules (mostly drivers) since there are no DLLs in system processes. This is done using the EnumDeviceDrivers API, which is a system API that does not require a process handle.

If you switch to Handle view, you'll see complete handle information. The reason is similar: Process Explorer uses an undocumented API that returns all handles on the system, which does not require a specific process handle. Process Explorer can identify the process simply because this information returns the PID associated with each handle.

## **Third-party PPL support**

The PPL mechanism extends the protection possibilities for processes beyond executables created solely by Microsoft. A common example is anti-malware (AM) software. A typical AM product consists of three main components:

- A kernel driver that intercepts I/O requests to the file system and/or the network, and implements blocking capabilities using object, process, and thread callbacks
- A user-mode service (typically running under a privileged account) that configures the driver's policies, receives notifications from the driver regarding "interesting" events (for example, infected file), and may communicate with a local server or the Internet
- A user-mode GUI process that communicates information to the user and optionally allows the user to make decisions where applicable.

One possible way malware can attack a system is by managing to inject code inside a process running with elevated privileges, or better, inject code specifically inside an anti-malware service and thus tamper with it or disable its operation. If, however, the AM service could run as a PPL, no code injection would be possible, and no process termination would be allowed, meaning that the AM software would be better protected from malware that does not employ kernel-level exploits.

To enable this use, the AM kernel driver described above needs to have a corresponding Early-Launch Anti Malware (ELAM) driver. While ELAM is further described in Chapter 7, the key distinction is that such drivers require a special anti-malware certificate provided by Microsoft (after proper verification of the software's publisher). Once such a driver is installed, it can contain a custom resource section in its main executable (PE) file called ELAMCERTIFICATEINFO. This section can describe three additional Signers (identified by their public key), each having up to three additional EKUs (identified by OID). Once the Code Integrity system recognizes any file signed by one of the three Signers, containing one of the three EKUs, it permits the process to request a PPL of PS\_PROTECTED\_ANTIMALWARE\_LIGHT (0x31). A canonical example of this is Microsoft's own AM known as Windows Defender. Its service on Windows 10 (MsMpEng.exe) is signed with the anti-malware certificate for better protection against malware attacking the AM itself, as is its Network Inspection Server (NisSvc.exe).

### **Minimal and Pico processes**

The types of processes we've looked at so far, and their data structures, seem to imply that their use is the execution of user-mode code, and that they contain a great deal of related data structures in memory to achieve this. Yet, not all processes are used for this purpose. For example, as we've seen, the System process is merely used as a container of most of the system threads, such that their execution time doesn't pollute arbitrary user-mode processes, as well as being used as a container of drivers' handles (called kernel handles), such that these don't end up owned by an arbitrary application either.

## **Minimal processes**

When a specific flag is given to the NtCreateProcessEx function, and the caller is kernel-mode, the function behaves slightly differently and causes the execution of the PsCreateMinimalProcess API. In turn, this causes a process to be created without many of the structures that we saw earlier, namely:

- No user-mode address space will be set up, so no PEB and related structures will exist.
- No NTDLL will be mapped into the process, nor will any loader/API Set information.
- No section object will be tied to the process, meaning no executable image file is associated to its execution or its name (which can be empty, or an arbitrary string).
- The Minimal flag will be set in the EPROCESS flags, causing all threads to become minimal threads, and also avoid any user-mode allocations such as their TEB or user-mode stack. (See Chapter 4 for more information on the TEB.)

As we saw in Chapter 2, Windows 10 has at least two minimal processes—the System process and Memory Compression process—and can have a third, the Secure System process, if Virtualization-Based Security is enabled, which is described further in Chapter 2 and Chapter 7.

Finally, the other way to have minimal processes running on a Windows 10 system is to enable the Windows Subsystem for Linux (WSL) optional feature that was also described in Chapter 2. This will install an inbox Pico Provider composed of the Lxss.sys and LxCore.sys drivers.

# Pico processes

While minimal processes have a limited use in terms of allowing access to user-mode virtual address space from kernel components and protecting it, Pico processes take on a more important role by permitting a special component, called a *Pico Provider*, to control most aspects of their execution from an operating system perspective. This level of control ultimately allows such a provider to emulate the behavior of a completely different operating system kernel, without the underlying user-mode binary being aware that it is running on a Windows-based operating system. This is essentially an implementation of the Drawbridge project from Microsoft Research, which is also used to support SQL Server for Linux in a similar way (albeit with a Windows-based Library OS on top of the Linux kernel).

To support the existence of Pico processes on the system, a provider must first be present. Such a provider can be registered with the PsRegisterPicoProvider API, but subject to a very specific rule: A Pico provider must be loaded before any other third-party drivers are loaded (including boot drivers). In fact, only one of the limited set of a dozen or so core drivers are allowed to call this API before the functionality is disabled, and these core drivers must be signed with a Microsoft Signer Certificate and Windows Component EKU. On Windows systems with the optional WSL component enabled, this core driver is called Lxss.sys, and serves as a stub driver until another driver, LxCore.sys, loads a bit later and takes over the Pico provider responsibilities by transferring the various dispatch tables over to itself. Additionally, note that at the time of this writing, only one such core driver can register itself as a Pico provider.

When a Pico provider calls the registration API, it receives a set of function pointers, which allow it to create and manage Pico processes:

- One function to create a Pico process and one to create a Pico thread.
- One function to get the context (an arbitrary pointer that the provider can use to store specific data) of a Pico process, one to set it, and another pair of functions to do the same for Pico threads. This will populate the PicoContext field in ETHREAD and/or EPROCESS.
- One function to get the CPU context structure (CONTEXT) of a Pico thread and one to set it.
- A function to change the FS and/or GS segments of a Pico thread, which are normally used by user-mode code to point to some thread local structure (such as the TEB on Windows).
- One function to terminate a Pico thread and one to do the same to a Pico process.
- One function to suspend a Pico thread and one to resume it.

As you can see, through these functions, the Pico provider can now create fully custom processes and threads for whom it controls the initial starting state, segment registers, and associate data. However, this alone would not allow the ability to emulate another operating system. A second set of function pointers is transferred, this time from the provider to the kernel, which serve as callbacks whenever certain activities of interest will be performed by a Pico thread or process.

- A callback whenever a Pico thread makes a system call using the SYSCALL instruction
- A callback whenever an exception is raised from a Pico thread

- A callback whenever a fault during a probe and lock operation on a memory descriptor list (MDL) occurs inside a Pico thread
- A callback whenever a caller is requesting the name of a Pico process
- A callback whenever Event Tracing for Windows (ETW) is requesting the user-mode stack trace of a Pico process
- A callback whenever an application attempts to open a handle to a Pico process or Pico thread
- A callback whenever someone requests the termination of a Pico process
- A callback whenever a Pico thread or Pico process terminates unexpectedly

Additionally, a Pico provider also leverages Kernel Patch Protection (KPP), described in Chapter 7, to both protect its callbacks and system calls as well as prevent fraudulent or malicious Pico providers from registering on top of a legitimate Pico provider.

It now becomes clear that with such unparalleled access to any possible user-kernel transition or visible kernel-user interactions between a Pico process/thread and the world, it can be fully encapsulated by a Pico provider (and relevant user-mode libraries) to wrap a completely different kernel implementation than that of Windows (with some exceptions, of course, as thread scheduling rules and memory management rules, such as commit, still apply). Correctly written applications are not supposed to be sensitive to such internal algorithms, as they are subject to change even within the operating system they normally execute on.

Therefore, Pico providers are essentially custom-written kernel modules that implement the necessary callbacks to respond to the list of possible events (shown earlier) that a Pico process can cause to arise. This is how WSL is capable of running unmodified Linux ELF binaries in user-mode, limited only by the completeness of its system call emulation and related functionality.

To complete the picture on regular NT processes versus minimal processes versus Pico processes, we present Figure 3-8, showing the different structures for each.




FIGURE 3-8 Process types.

As covered in Chapter 2, Windows contains new virtualization-based security (VBS) features such as Device Guard and Credential Guard, which enhance the safety of the operating system and user data by leveraging the hypervisor. We saw how one such feature, Credential Guard (which is discussed at length in Chapter 7), runs in a new Isolated User Mode environment, which, while still unprivileged (ring 3), has a virtual trust level of 1 (VTL 1), granting it protection from the regular VTL 0 world in which both the NT kernel (ring 0) and applications (ring 3) live. Let's investigate how the kernel sets up such processes for execution, and the various data structures such processes use.

### **Trustlet structure**

To begin with, although Trustlets are regular Windows Portable Executables (PE) files, they contain some IUM-specific properties:

- They can import only from a limited set of Windows system DLLs (C/C++ Runtime, KernelBase, Advapi, RPC Runtime, CNG Base Crypto, and NTDLL) due to the restricted number of system calls that are available to Trustlets. Note that mathematical DLLs that operate only on data structures (such as NTLM, ASN.1, etc.) are also usable, as they don't perform any system calls.
- They can import from an IUM-specific system DLL that is made available to them, called Iumbase, which provides the Base IUM System API, containing support for mailslots, storage boxes, cryptography, and more. This library ends up calling into lumdll.dll, which is the VTL 1 version of Ntdll.dll, and contains secure system calls (system calls that are implemented by the Secure Kernel, and not passed on to the Normal VTL 0 Kernel).
- They contain a PE section named .tPolicy with an exported global variable named s\_IumPolicyMetadata. This serves as metadata for the Secure Kernel to implement policy settings around permitting VTL 0 access to the Trustlet (such as allowing debugging, crash dump support, etc.).
- They are signed with a certificate that contains the Isolated User Mode EKU (1.3.6.1.4.1.311.10.3.37). Figure 3-9 shows the certificate data for Lsalso.exe, showing its IUM EKU.

Additionally, Trustlets must be launched by using a specific process attribute when using CreateProcess—both to request their execution in IUM as well as to specify launch properties. We will describe both the policy metadata and the process attributes in the following sections.




FIGURE 3-9 Trustlet EKU in the certificate.

#### Trustlet policy metadata

The policy metadata includes various options for configuring how "accessible" the Trustlet will be from VTL 0. It is described by a structure present at the s\_IumPolicyMetadata export mentioned earlier, and contains a version number (currently set to 1) as well as the Trustlet ID, which is a unique number that identifies this specific Trustlet among the ones that are known to exist (for example, Biolso.exe is Trustlet ID 4). Finally, the metadata has an array of policy options. Currently, the options listed in Table 3-4 are supported. It should be obvious that as these policies are part of the signed executable data, attempting to modify them would invalidate the IUM signature and prohibit execution.

Policy	Meaning	More Information
ETW	Enables or Disables ETW	
Debug	Configures debugging	Debug can be enabled at all times, only when SecureBoot is disabled, or using an on-demand challenge/response mechanism.
Crash Dump	Enables or disables crash dump	
Crash Dump Key	Specifies Public Key for Encrypting Crash Dump	Dumps can be submitted to Microsoft Product Team, which has the private key for decryption
Crash Dump GUID	Specifies identifier for crash dump key	This allows multiple keys to be used/identified by the product team.

**TABLE 3-4** Trustlet policy options

TABLE 3-4	Trustlet policy options	(continued)
-----------	-------------------------	-------------

Policy	Meaning	More Information
Parent Security Descriptor	SDDL format	This is used to validate that the owner/parent process is expected.
Parent Security Descriptor Revision	SDDL format revision ID	This is used to validate that the owner/parent process is expected.
SVN	Security version	This is a unique number that can be used by the Trustlet (along its identity) when encrypting AES256/GCM messages.
Device ID	Secure device PCI identifier	The Trustlet can only communicate with a Secure Device whose PCI ID matches.
Capability	Enables powerful VTL 1 capabilities	This enables access to the Create Secure Section API, DMA and user-mode MMIO access to Secure Devices, and Secure Storage APIs.
Scenario ID	Specifies the scenario ID for this binary	Encoded as a GUID, this must be specified by Trustlets when creating secure image sections to ensure it is for a known scenario.

### **Trustlet attributes**

Launching a Trustlet requires correct usage of the PS\_CP\_SECURE\_PROCESS attribute, which is first used to authenticate that the caller truly wants to create a Trustlet, as well as to verify that the Trustlet the caller *thinks* its executing is actually the Trustlet being executed. This is done by embedding a Trustlet identifier in the attribute, which must match the Trustlet ID contained in the policy metadata. Then, one or more attributes can be specified, which are shown in Table 3-5.

TABLE 3-5 Trustlet attributes

Attribute	Meaning	More Information
Mailbox Key	Used to retrieve mailbox data	Mailboxes allow the Trustlet to share data with the VTL 0 world as long as the Trustlet key is known.
Collaboration ID	Sets the collaboration ID to use when using the Secure Storage IUM API	Secure Storage allows Trustlets to share data among each other, as long as they have the same collaboration ID. If no collaboration ID is present, the Trustlet instance ID will be used instead.
TK Session ID	Identifies the session ID used during Crypto	

## System built-in Trustlets

At the time of this writing, Windows 10 contains five different Trustlets, which are identified by their identity numbers. They are described in Table 3-6. Note that Trustlet ID 0 represents the Secure Kernel itself.

Binary Name (Trustlet ID)	Description	Policy Options
Lsalso.exe (1)	Credential and Key Guard Trustlet	Allow ETW, Disable Debugging, Allow Encrypted Crash Dump
Vmsp.exe (2)	Secure Virtual Machine Worker (vTPM Trustlet)	Allow ETW, Disable Debugging, Disable Crash Dump, Enable Secure Storage Capability, Verify Parent Security Descriptor is S-1-5-83-0 (NT VIRTUAL MACHINE\Virtual Machines)
Unknown (3)	vTPM Key Enrollment Trustlet	Unknown
Biolso.exe (4)	Secure Biometrics Trustlet	Allow ETW, Disable Debugging, Allow Encrypted Crash Dump
Fslso.exe (5)	Secure Frame Server Trustlet	Disable ETW, Allow Debugging, Enable Create Secure Section Capability, Use Scenario ID { AE53FC6E-8D89-4488-9D2E-4D008731C5FD}

#### **TABLE 3-6** Built-in Trustlets

#### **Trustlet identity**

Trustlets have multiple forms of identity that they can use on the system:

- Trustlet identifier or Trustlet ID This is a hard-coded integer in the Trustlet's policy metadata, which also must be used in the Trustlet process-creation attributes. It ensures that the system knows there are only a handful of Trustlets, and that the callers are launching the expected one.
- Trustlet instance This is a cryptographically secure 16-byte random number generated by the Secure Kernel. Without the use of a collaboration ID, the Trustlet instance is what's used to guarantee that Secure Storage APIs will only allow this one instance of the Trustlet to get/put data into its storage blob.
- Collaboration ID This is used when a Trustlet would like to allow other Trustlets with the same ID, or other instances of the same Trustlet, to share access to the same Secure Storage blob. When this ID is present, the instance ID of the Trustlet will be ignored when calling the Get or Put APIs.
- Security version (SVN) This is used for Trustlets that require strong cryptographic proof of provenance of signed or encrypted data. It is used when encrypting AES256/GCM data by Credential and Key Guard, and is also used by the Cryptograph Report service.
- Scenario ID This is used for Trustlets that create named (identity-based) secure kernel objects, such as secure sections. This GUID validates that the Trustlet is creating such objects as part of a predetermined scenario, by tagging them in the namespace with this GUID. As such, other Trustlets wishing to open the same named objects would thus have to have the same scenario ID. Note that more than one scenario ID can actually be present, but no Trustlets currently use more than one.

### Isolated user-mode services

The benefits of running as a Trustlet not only include protection from attacks from the normal (VTL 0) world, but also access to privileged and protected secure system calls that are only offered by the Secure Kernel to Trustlets. These include the following services:

- Secure Devices (IumCreateSecureDevice, IumDmaMapMemory, IumGetDmaEnabler, IumMap-SecureIo, IumProtectSecureIo, IumQuerySecureDeviceInformation, IopUnmapSecureIo, IumUpdateSecureDeviceState) These provide access to secure ACPI and/or PCI devices, which cannot be accessed from VTL 0 and are exclusively owned by the Secure Kernel (and its ancillary Secure HAL and Secure PCI services). Trustlets with the relevant capabilities (see the "Trustlet policy metadata" section earlier in this chapter) can map the registers of such a device in VTL 1 IUM, as well as potentially perform Direct Memory Access (DMA) transfers. Additionally, Trustlets can serve as user-mode device drivers for such hardware by using the Secure Device Framework (SDF) located in SDFHost.dll. This functionality is leveraged for Secure Biometrics for Windows Hello, such as Secure USB Smartcard (over PCI) or Webcam/Fingerprint Sensors (over ACPI).
- Secure Sections (IumCreateSecureSection, IumFlushSecureSectionBuffers, IumGetExposed-SecureSection, IumOpenSecureSection) These provide the ability to both share physical pages with a VTL 0 driver (which would use Vs1CreateSecureSection) through exposed secure sections, as well as share data solely within VTL 1 as named secured sections (leveraging the identity-based mechanism described earlier in the "Trustlet identity" section) with other Trustlets or other instances of the same Trustlet. Trustlets require the Secure Section capability described in the "Trustlet policy metadata" section to use these features.
- Mailboxes (IumPostMailbox) This enables a Trustlet to share up to eight slots of about up to 4 KB of data with a component in the normal (VTL 0) kernel, which can call VslRetrieveMailbox passing in the slot identifier and secret mailbox key. For example, Vid.sys in VTL 0 uses this to retrieve various secrets used by the vTPM feature from the Vmsp.exe Trustlet.
- Identity Keys (IumGetIdk) This allows a Trustlet to obtain either a unique identifying decryption key or signing key. This key material is unique to the machine and can be obtained only from a Trustlet. It is an essential part of the Credential Guard feature to uniquely authenticate the machine and that credentials are coming from IUM.
- Cryptographic Services (IumCrypto) This allows a Trustlet to encrypt and decrypt data with a local and/or per-boot session key generated by the Secure Kernel that is only available to IUM, to obtain a TPM binding handle, to get the FIPS mode of the Secure Kernel, and to obtain a random number generator (RNG) seed only generated by the Secure Kernel for IUM. It also enables a Trustlet to generate an IDK-signed, SHA-2 hashed, and timestamped report with the identity and SVN of the Trustlet, a dump of its policy metadata, whether or not it was ever attached to a debugger, and any other Trustlet-controlled data requested. This can be used as a sort of TPM-like measurement of the Trustlet to prove that it was not tampered with.

Secure Storage (IumSecureStorageGet, IumSecureStoragePut) This allows Trustlets that have the Secure Storage capability (described earlier in the "Trustlet policy metadata" section) to store arbitrarily sized storage blobs and to later retrieve them, either based on their unique Trustlet instance or by sharing the same collaboration ID as another Trustlet.

## Trustlet-accessible system calls

As the Secure Kernel attempts to minimize its attack surface and exposure, it only provides a subset (less than 50) of all of the hundreds of system calls that a normal (VTL 0) application can use. These system calls are the strict minimum necessary for compatibility with the system DLLs that Trustlets can use (refer to the section "Trustlet structure" to see these), as well as the specific services required to support the RPC runtime (Rpcrt4.dll) and ETW tracing.

- Worker Factory and Thread APIs These support the Thread Pool API (used by RPC) and TLS Slots used by the Loader.
- Process Information API This supports TLS Slots and Thread Stack Allocation.
- Event, Semaphore, Wait, and Completion APIs These support Thread Pool and Synchronization.
- Advanced Local Procedure Call (ALPC) APIs These support Local RPC over the ncalrpc transport.
- System Information API This supports reading Secure Boot information, basic and NUMA system information for Kernel32.dll and Thread Pool scaling, performance, and subsets of time information.
- **Token API** This provides minimal support for RPC impersonation.
- Virtual Memory Allocation APIs These support allocations by the User-Mode Heap Manager.
- Section APIs These support the Loader (for DLL Images) as well as the Secure Section functionality (once created/exposed through secure system calls shown earlier).
- Trace Control API This supports ETW.
- **Exception and Continue API** This supports Structured Exception Handling (SEH).

It should be evident from this list that support for operations such as Device I/O, whether on files or actual physical devices, is not possible (there is no CreateFile API, to begin with), as is also the case for Registry I/O. Nor is the creation of other processes, or any sort of graphics API usage (there is no Win32k.sys driver in VTL 1). As such, Trustlets are meant to be isolated workhorse back-ends (in VTL 1) of their complex front-ends (in VTL 0), having only ALPC as a communication mechanism, or exposed secure sections (whose handle would have to had been communicated to them through ALPC). In Chapter 7 (Security), we'll look in more detail into the implementation of a specific Trustlet—Lsalso.exe, which provides Credential and Key Guard.

#### Experiment: Identifying secure processes

Secure processes, other than being known by their name, can be identified in the kernel debugger in two ways. First, each secure process has a secure PID, which represents its handle in the Secure Kernel's handle table. This is used by the normal (VTL 0) kernel when creating threads in the process or requesting its termination. Secondly, the threads themselves have a thread cookie associated with them, which represents their index in the Secure Kernel's thread table.

You can try the following in a kernel debugger:

```
lkd> !for_each_process .if @@(((nt!_EPROCESS*)${@#Process})->Pcb.SecurePid) {
.printf "Trustlet: %ma (%p)\n", @@(((nt!_EPROCESS*)) {@#Process})->ImageFileName),
@#Process }
Trustlet: Secure System (ffff9b09d8c79080)
Trustlet: LsaIso.exe (ffff9b09e2ba9640)
Trustlet: BioIso.exe (ffff9b09e61c4640)
1kd> dt nt!_EPROCESS ffff9b09d8c79080 Pcb.SecurePid
  +0x000 Pcb :
     +0x2d0 SecurePid : 0x00000001'40000004
1kd> dt nt!_EPROCESS ffff9b09e2ba9640 Pcb.SecurePid
  +0x000 Pcb :
     +0x2d0 SecurePid : 0x00000001'40000030
lkd> dt nt! EPROCESS ffff9b09e61c4640 Pcb.SecurePid
  +0x000 Pcb :
     +0x2d0 SecurePid : 0x00000001'40000080
1kd> !process ffff9b09e2ba9640 4
PROCESS ffff9b09e2ba9640
   SessionId: 0 Cid: 0388 Peb: 6cdc62b000 ParentCid: 0328
   DirBase: 2f254000 ObjectTable: ffffc607b59b1040 HandleCount: 44.
   Image: LsaIso.exe
      THREAD ffff9b09e2ba2080 Cid 0388.038c Teb: 0000006cdc62c000 Win32Thread:
000000000000000 WAIT
1kd> dt nt! ETHREAD ffff9b09e2ba2080 Tcb.SecureThreadCookie
  +0x000 Tcb :
     +0x31c SecureThreadCookie : 9
```

## **Flow of CreateProcess**

We've shown the various data structures involved in process-state manipulation and management and how various tools and debugger commands can inspect this information. In this section, we'll see how and when those data structures are created and filled out, as well as the overall creation and termination behaviors behind processes. As we've seen, all documented process-creation functions eventually end up calling CreateProcessInternalW, so this is where we start.

Creating a Windows process consists of several stages carried out in three parts of the operating system: the Windows client-side library Kernel32.dll (the real work starting with CreateProcessInternalW), the Windows executive, and the Windows subsystem process (Csrss). Because of the multiple-environment subsystem architecture of Windows, creating an executive process object (which other subsystems can use) is separated from the work involved in creating a Windows subsystem process. So, although the following description of the flow of the Windows CreateProcess function is complicated, keep in mind that part of the work is specific to the semantics added by the Windows subsystem as opposed to the core work needed to create an executive process object.

The following list summarizes the main stages of creating a process with the Windows CreateProcess\* functions. The operations performed in each stage are described in detail in the subsequent sections.

**Note** Many steps of CreateProcess are related to the setup of the process virtual address space and therefore refer to many memory-management terms and structures that are defined in Chapter 5.

- 1. Validate parameters; convert Windows subsystem flags and options to their native counterparts; parse, validate, and convert the attribute list to its native counterpart.
- 2. Open the image file (.exe) to be executed inside the process.
- 3. Create the Windows executive process object.

- 4. Create the initial thread (stack, context, and Windows executive thread object).
- 5. Perform post-creation, Windows subsystem–specific process initialization.
- 6. Start execution of the initial thread (unless the CREATE\_SUSPENDED flag was specified).
- 7. In the context of the new process and thread, complete the initialization of the address space (for example, load required DLLs) and begin execution of the program's entry point.

Figure 3-10 shows an overview of the stages Windows follows to create a process.




FIGURE 3-10 The main stages of process creation.

# Stage 1: Converting and validating parameters and flags

Before opening the executable image to run, CreateProcessInternalW performs the following steps:

1. The priority class for the new process is specified as independent bits in the CreationFlags parameter to the CreateProcess\* functions. Thus, you can specify more than one priority class for a single CreateProcess\* call. Windows resolves the question of which priority class to assign to the process by choosing the lowest-priority class set.

There are six process priority classes defined, each value mapped to a number:

- Idle or Low, as Task Manager displays it (4)
- Below Normal (6)
- Normal (8)
- Above Normal (10)
- High (13)
- Real-time (24)

The priority class is used as the base priority for threads created in that process. This value does not directly affect the process itself—only the threads inside it. A description of process priority class and its effects on thread scheduling appears in Chapter 4.

- 2. If no priority class is specified for the new process, the priority class defaults to Normal. If a Real-time priority class is specified for the new process and the process's caller doesn't have the Increase Scheduling Priority privilege (SE\_INC\_BASE\_PRIORITY\_NAME), the High priority class is used instead. In other words, process creation doesn't fail just because the caller has insufficient privileges to create the process in the Real-time priority class; the new process just won't have as high a priority as Real-time.
- If the creation flags specify that the process will be debugged, Kernel32 initiates a connection to the native debugging code in Ntdll.dll by calling DbgUiConnectToDbg and gets a handle to the debug object from the current thread's environment block (TEB).
- 4. Kernel32.dll sets the default hard error mode if the creation flags specified one.
- **5.** The user-specified attribute list is converted from Windows subsystem format to native format and internal attributes are added to it. The possible attributes that can be added to the attribute list are listed in Table 3-7, including their documented Windows API counterparts, if any.

٢	+	+	+	+	٦
L	Ē				
L	-	-	-		

**Note** The attribute list passed on CreateProcess\* calls permits passing back to the caller information beyond a simple status code, such as the TEB address of the initial thread or information on the image section. This is necessary for protected processes because the parent cannot query this information after the child is created.

Native Attribute	Equivalent Win32 Attribute	Туре	Description
PS_CP_PARENT_PROCESS	PROC_THREAD_ATTRIBUTE_ PARENT_PROCESS. Also used when elevating.	Input	Handle to the parent process.
PS_CP_DEBUG_OBJECT	N/A. Used when using DEBUG_ PROCESS as a flag.	Input	Debug object if process is being started debugged.
PS_CP_PRIMARY_TOKEN	N/A. Used when using CreateProcessAsUser/ WithTokenW.	Input	Process token if CreateProcessAsUser was used.
PS_CP_CLIENT_ID	N/A. Returned by Win32 API as a parameter (PROCESS_ INFORMATION).	Output	Returns the TID and PID of the initial thread and the process.
PS_CP_TEB_ADDRESS	N/A. Internally used and not exposed.	Output	Returns the address of the TEB for the initial thread.
PS_CP_FILENAME	N/A. Used as a parameter in CreateProcess APIs.	Input	The name of the process that should be created.
PS_CP_IMAGE_INFO	N/A. Internally used and not exposed.	Output	Returns SECTION_IMAGE_ INFORMATION, which contains in- formation on the version, flags, and subsystem of the executable, as well as the stack size and entry point.
PS_CP_MEM_RESERVE	N/A. Internally used by SMSS and CSRSS.	Input	An array of virtual memory reserva- tions that should be made during initial process address space cre- ation, allowing guaranteed availabil- ity because no other allocations have taken place yet.
PS_CP_PRIORITY_CLASS	N/A. Passed in as a parameter to the CreateProcess API.	Input	Priority class that the process should be given.
PS_CP_ERROR_MODE	N/A. Passed in through the CREATE_DEFAULT_ERROR_MODE flag.	Input	Hard error-processing mode for the process.
PS_CP_STD_HANDLE_INFO	None. Used internally.	Input	Specifies whether standard handles should be duplicated or new handles should be created.
PS_CP_HANDLE_LIST	PROC_THREAD_ATTRIBUTE_ HANDLE_LIST	Input	A list of handles belonging to the parent process that should be inherited by the new process.
PS_CP_GROUP_AFFINITY	PROC_THREAD_ATTRIBUTE_ GROUP_AFFINITY	Input	Processor group(s) the thread should be allowed to run on.
PS_CP_PREFERRED_NODE	PROC_THREAD_ATTRIBUTES_ PRFERRED_NODE	Input	The preferred (ideal) NUMA node that should be associated with the process. It affects the node on which the initial process heap and thread stack will be created (see Chapter 5).
PS_CP_IDEAL_PROCESSOR	PROC_THREAD_ATTTRIBUTE_ IDEAL_PROCESSOR	Input	The preferred (ideal) processor that the thread should be scheduled on.
PS_CP_UMS_THREAD	PROC_THREAD_ATTRIBUTE_ UMS_THREAD	Input	Contains the UMS attributes, completion list, and context.

#### **TABLE 3-7** Process attributes

PS_CP_MITIGATION_ OPTIONS	PROC_THREAD_MITIGATION_ POLICY	Input	Contains information on which miti- gations (SEHOP, ATL Emulation, NX) should be enabled/disabled for the process.
PS_CP_PROTECTION_LEVEL	PROC_THREAD_ATTRIBUTE_ PROTECTION_LEVEL	Input	Must point to one of the allowed process protection values shown in Table 3-1 or the value PROTECT_ LEVEL_SAME to indicate the same protection level as the parent.
PS_CP_SECURE_PROCESS	None. Used internally.	Input	Indicates the process should run as an Isolated User Mode (IUM) Trustlet. See Chapter 8 in Part 2 for more details.
PS_CP_JOB_LIST	None. Used internally.	Input	Assigns the process to a list of jobs.
PS_CP_CHILD_PROCESS_ POLICY	PROC_THREAD_ATTRIBUTE_ CHILD_PROCESS_POLICY	Input	Specifies whether the new process is allowed to create child processes, either directly or indirectly (such as by using WMI).
PS_CP_ALL_APPLICATION_ PACKAGES_POLICY	PROC_THREAD_ATTRIBUTE_ ALL_APPLICATION_PACKAGES_ POLICY	Input	Specifies if the AppContainer token should be excluded from ACL checks that include the ALL APPLICATION PACKAGES group. The ALL RESTRICTED APPLICATION PACKAGES group will be used in- stead.
PS_CP_WIN32K_FILTER	PROC_THREAD_ATTRIBUTE_ WIN32K_FILTER	Input	Indicates if the process will have many of its GDI/USER system calls to Win32k.sys filtered out (blocked), or if they will be permitted but audited. Used by the Microsoft Edge browser to reduce attack surface.
PS_CP_SAFE_OPEN_PROMPT_ ORIGIN_CLAIM	None. Used internally.	Input	Used by the Mark of the Web func- tionality to indicate the file came from an untrusted source.
PS_CP_BNO_ISOLATION	PROC_THREAD_ATTRIBUTE_ BNO_ISOLATION	Input	Causes the primary token of the pro- cess to be associated with an isolated BaseNamedObjects directory. (See Chapter 8 in Part 2 for more informa- tion on named objects.)
PS_CP_DESKTOP_APP_ POLICY	PROC_THREAD_ATTRIBUTE_ DESKTOP_APP_POLICY	Input	Indicates if the modern application will be allowed to launch legacy desktop applications, and if so, in what way.
None—used internally	PROC_THREAD_ATTRIBUTE_ SECURITY_CAPABILITIES	Input	Specifies a pointer to a SECURITY_ CAPABILITIES structure, which is used to create the AppContainer token for the process before calling NtCreateUserProcess.

**6.** If the process is part of a job object, but the creation flags requested a separate virtual DOS machine (VDM), the flag is ignored.

- The security attributes for the process and initial thread that were supplied to the CreateProcess function are converted to their internal representation (OBJECT\_ATTRIBUTES structures, documented in the WDK).
- 8. CreateProcessInternalW checks whether the process should be created as modern. The process is to be created modern if specified so by an attribute (PROC\_THREAD\_ATTRIBUTE\_ PACKAGE\_FULL\_NAME) with the full package name or the creator is itself modern (and a parent process has not been explicitly specified by the PROC\_THREAD\_ATTRIBUTE\_PARENT\_PROCESS attribute). If so, a call is made to the internal BasepAppXExtension to gather more contextual information on the modern app parameters described by a structure called APPX\_PROCESS\_CONTEXT. This structure holds information such as the package name (internally referred to as *package moniker*), the capabilities associated with the app, the current directory for the process, and whether the app should have full trust. The option of creating full trust modern apps is not publicly exposed, and is reserved for apps that have the modern look and feel but perform system-level operations. A canonical example is the Settings app in Windows 10 (SystemSettings.exe).
- 9. If the process is to be created as modern, the security capabilities (if provided by PROC\_THREAD\_ATTRIBUTE\_SECURITY\_CAPABILITIES) are recorded for the initial token creation by calling the internal BasepCreateLowBox function. The term *LowBox* refers to the sandbox (AppContainer) under which the process is to be executed. Note that although creating modern processes by directly calling CreateProcess is not supported (instead, the COM interfaces described earlier should be used), the Windows SDK and MSDN do document the ability to create AppContainer legacy desktop applications by passing this attribute.
- 10. If a modern process is to be created, then a flag is set to indicate to the kernel to skip embedded manifest detection. Modern processes should never have an embedded manifest as it's simply not needed. (A modern app has a manifest of its own, unrelated to the embedded manifest referenced here.)
- 11. If the debug flag has been specified (DEBUG\_PROCESS), then the Debugger value under the Image File Execution Options registry key (discussed in the next section) for the executable is marked to be skipped. Otherwise, a debugger will never be able to create its debuggee process because the creation will enter an infinite loop (trying to create the debugger process over and over again).
- **12.** All windows are associated with desktops, the graphical representation of a workspace. If no desktop is specified in the STARTUPINFO structure, the process is associated with the caller's current desktop.

**Note** The Windows 10 Virtual Desktop feature does not use multiple desktop objects (in the kernel object sense). There is still one desktop, but windows are shown and hidden as required. This is in contrast to the Sysinternals desktops.exe tool, which really creates up to four desktop objects. The difference can be felt when trying to move a window from one desktop to another. In the case of desktops.exe, it can't be done, as such an operation is not supported in Windows. On the other hand, Windows 10's Virtual Desktop allows it, since there is no real "moving" going on.

- 13. The application and command-line arguments passed to CreateProcessInternalWare analyzed. The executable path name is converted to the internal NT name (for example, c:\temp\a.exe turns into something like \device\harddiskvolume1\temp\a.exe) because some functions require it in that format.
- **14.** Most of the gathered information is converted to a single large structure of type RTL\_USER\_ PROCESS\_PARAMETERS.

Once these steps are completed, CreateProcessInternalW performs the initial call to NtCreate-UserProcess to attempt creation of the process. Because Kernel32.dll has no idea at this point whether the application image name is a real Windows application or a batch file (.bat or .cmd), 16-bit, or DOS application, the call might fail, at which point CreateProcessInternalW looks at the error reason and attempts to correct the situation.

## Stage 2: Opening the image to be executed

At this point, the creating thread has switched into kernel mode and continues the work within the NtCreateUserProcess system call implementation.

- 1. NtCreateUserProcess first validates arguments and builds an internal structure to hold all creation information. The reason for validating arguments again is to make sure the call to the executive did not originate from a hack that managed to simulate the way Ntdll.dll makes the transition to the kernel with bogus or malicious arguments.
- 2. As illustrated in Figure 3-11, the next stage in NtCreateUserProcess is to find the appropriate Windows image that will run the executable file specified by the caller and to create a section object to later map it into the address space of the new process. If the call fails for any reason, it returns to CreateProcessInternalW with a failure state (look ahead to Table 3-8) that causes CreateProcessInternalW to attempt execution again.




FIGURE 3-11 Choosing a Windows image to activate.

- 3. If the process needs to be created protected, it also checks the signing policy.
- 4. If the process to be created is modern, a licensing check is done to make sure it's licensed and allowed to run. If the app is inbox (preinstalled with Windows), it's allowed to run regardless of license. If sideloading apps is allowed (configured through the Settings app), then any signed app can be executed, not just from the store.
- 5. If the process is a Trustlet, the section object must be created with a special flag that allows the secure kernel to use it.
- 6. If the executable file specified is a Windows EXE, NtCreateUserProcess tries to open the file and create a section object for it. The object isn't mapped into memory yet, but it is opened. Just because a section object has been successfully created doesn't mean the file is a valid Windows image, however. It could be a DLL or a POSIX executable. If the file is a POSIX executable, the call fails, because POSIX is no longer supported. If the file is a DLL, CreateProcessInternalW fails as well.
- 7. Now that NtCreateUserProcess has found a valid Windows executable image, as part of the process creation code described in the next section, it looks in the registry under HKLM\ SOFTWARE\Microsoft\Windows NT\CurrentVersion\Image File Execution Options to see whether a subkey with the file name and extension of the executable image (but without the directory and path information—for example, Notepad.exe) exists there. If it does, PspAllocate-Process looks for a value named Debugger for that key. If this value is present, the image to be run becomes the string in that value and CreateProcessInternalW restarts at stage 1.

**Tip** You can take advantage of this process-creation behavior and debug the startup code of Windows services processes before they start rather than attach the debugger after starting a service, which doesn't allow you to debug the startup code.

8. On the other hand, if the image is not a Windows EXE (for example, if it's an MS-DOS or a Win16 application), CreateProcessInternalW goes through a series of steps to find a Windows support image to run it. This process is necessary because non-Windows applications aren't run directly. Windows instead uses one of a few special support images that, in turn, are responsible for actually running the non-Windows program. For example, if you attempt to run an MS-DOS or a Win16 executable (32-bit Windows only), the image to be run becomes the Windows executable Ntvdm.exe. In short, you can't directly create a process that is not a Windows process. If Windows can't find a way to resolve the activated image as a Windows process (as shown in Table 3-8), CreateProcessInternalW fails.

If the Image	Create State Code	This Image Will Run	and This Will Happen
Is an MS-DOS application with an .exe, .com, or .pif extension	PsCreateFailOnSectionCreate	Ntvdm.exe	CreateProcessInternalW restarts stage 1.
Is a Win16 application	PsCreateFailOnSectionCreate	Ntvdm.exe	CreateProcessInternalW restarts stage 1.
Is a Win64 application on a 32-bit system (or a PPC, MIPS, or Alpha binary)	PsCreateFailMachineMismatch	N/A	CreateProcessInternalW will fail.
Has a Debugger value with another image name	PsCreateFailExeName	Name speci- fied in the Debugger value	CreateProcessInternalW restarts stage 1.
Is an invalid or dam- aged Windows EXE	PsCreateFailExeFormat	N/A	CreateProcessInternalW will fail.
Cannot be opened	PsCreateFailOnFileOpen	N/A	CreateProcessInternalW will fail.
Is a command pro- cedure (application with a .bat or .cmd extension)	PsCreateFailOnSectionCreate	Cmd.exe	CreateProcessInternalW restarts Stage 1.

#### TABLE 3-8 Decision tree for stage 1 of CreateProcess

Specifically, the decision tree that CreateProcessInternalW goes through to run an image is as follows:

- If it's x86 32-bit Windows, and the image is an MS-DOS application with an .exe, .com, or .pif extension, a message is sent to the Windows subsystem to check whether an MS-DOS support process (Ntvdm.exe, specified in the HKLM\SYSTEM\CurrentControlSet\Control\WOW\ cmdline registry value) has already been created for this session. If a support process has been created, it is used to run the MS-DOS application. (The Windows subsystem sends the message to the virtual DOS machine [VDM] process to run the new image.) Then Create-ProcessInternalW returns. If a support process has't been created, the image to be run changes to Ntvdm.exe and CreateProcessInternalW restarts at stage 1.
- If the file to run has a .bat or .cmd extension, the image to be run becomes Cmd.exe, the Windows command prompt, and CreateProcessInternalWrestarts at stage 1. (The name of the batch file is passed as the second parameter to Cmd.exe after the /c switch.)
- For an x86 Windows system, if the image is a Win16 (Windows 3.1) executable, CreateProcess-InternalW must decide whether a new VDM process must be created to run it or whether it should use the default session-wide shared VDM process (which might not yet have been created). The CreateProcess flags CREATE\_SEPARATE\_WOW\_VDM and CREATE\_SHARED\_WOW\_ VDM control this decision. If these flags aren't specified, the HKLM\SYSTEM\CurrentControlSet\ Control\WOW\DefaultSeparateVDM registry value dictates the default behavior. If the

application is to be run in a separate VDM, the image to be run changes to Ntvdm.exe followed by some configuration parameters and the 16-bit process name, and CreateProcess-InternalW restarts at stage 1. Otherwise, the Windows subsystem sends a message to see whether the shared VDM process exists and can be used. (If the VDM process is running on a different desktop or isn't running under the same security as the caller, it can't be used, and a new VDM process must be created.) If a shared VDM process can be used, the Windows subsystem sends a message to it to run the new image and CreateProcessInternalW returns. If the VDM process hasn't yet been created (or if it exists but can't be used), the image to be run changes to the VDM support image and CreateProcessInternalW restarts at stage 1.

## Stage 3: Creating the Windows executive process object

At this point, NtCreateUserProcess has opened a valid Windows executable file and created a section object to map it into the new process address space. Next, it creates a Windows executive process object to run the image by calling the internal system function PspAllocateProcess. Creating the executive process object (which is done by the creating thread) involves the following sub-stages:

- 3A. Setting up the EPROCESS object
- 3B. Creating the initial process address space
- 3C. Initializing the kernel process structure (KPROCESS)
- **3D.** Concluding the setup of the process address space
- 3E. Setting up the PEB
- 3F. Completing the setup of the executive process object

**Note** The only time there won't be a parent process is during system initialization (when the System process is created). After that point, a parent process is always required to provide a security context for the new process.

#### Stage 3A: Setting up the EPROCESS object

This sub-stage involves the following steps:

- 1. Inherit the affinity of the parent process unless it was explicitly set during process creation (through the attribute list).
- 2. Choose the ideal NUMA node that was specified in the attribute list, if any.
- **3.** Inherit the I/O and page priority from the parent process. If there is no parent process, the default page priority (5) and I/O priority (Normal) are used.
- 4. Set the new process exit status to STATUS\_PENDING.

- 5. Choose the hard error processing mode selected by the attribute list. Otherwise, inherit the parent's processing mode if none was given. If no parent exists, use the default processing mode, which is to display all errors.
- 6. Store the parent process's ID in the InheritedFromUniqueProcessId field in the new process object.
- 7. Query the Image File Execution Options (IFEO) key to check if the process should be mapped with large pages (UseLargePages value in the IFEO key), unless the process is to run under Wow64, in which case large pages will not be used. Also, query the key to check if NTDLL has been listed as a DLL that should be mapped with large pages within this process.
- 8. Query the performance options key in IFEO (PerfOptions, if it exists), which may consist of any number of the following possible values: IoPriority, PagePriority, CpuPriorityClass, and WorkingSetLimitInKB.
- **9.** If the process would run under Wow64, then allocate the Wow64 auxiliary structure (EWOW64PROCESS) and set it in the WoW64Process member of the EPROCESS structure.
- **10.** If the process is to be created inside an AppContainer (in most cases a modern app), validate that the token was created with a LowBox. (See Chapter 7 for more on AppContainers.)
- **11.** Attempt to acquire all the privileges required for creating the process. Choosing the Real-time process priority class, assigning a token to the new process, mapping the process with large pages, and creating the process within a new session are all operations that require the appropriate privilege.
- 12. Create the process's primary access token (a duplicate of its parent's primary token). New processes inherit the security profile of their parents. If the CreateProcessAsUser function is being used to specify a different access token for the new process, the token is then changed appropriately. This change might happen only if the parent token's integrity level dominates the integrity level of the access token, and if the access token is a true child or sibling of the parent token. Note that if the parent has the SeAssignPrimaryToken privilege, this will bypass these checks.
- **13.** The session ID of the new process token is now checked to determine if this is a cross-session create. If so, the parent process temporarily attaches to the target session to correctly process quotas and address space creation.
- 14. Set the new process's quota block to the address of its parent process's quota block, and increment the reference count for the parent's quota block. If the process was created through CreateProcessAsUser, this step won't occur. Instead, the default quota is created, or a quota matching the user's profile is selected.
- 15. The process minimum and maximum working set sizes are set to the values of PspMinimum-WorkingSet and PspMaximumWorkingSet, respectively. These values can be overridden if performance options were specified in the PerfOptions key part of Image File Execution Options, in which case the maximum working set is taken from there. Note that the default working set limits are soft limits and are essentially hints, while the PerfOptions working set maximum is a hard limit. (That is, the working set will not be allowed to grow past that number.)

- **16.** Initialize the address space of the process. (See stage 3B.) Then detach from the target session if it was different.
- 17. The group affinity for the process is now chosen if group-affinity inheritance was not used. The default group affinity will either inherit from the parent if NUMA node propagation was set earlier (the group owning the NUMA node will be used) or be assigned round-robin. If the system is in forced group-awareness mode and group 0 was chosen by the selection algorithm, group 1 is chosen instead, as long as it exists.
- 18. Initialize the KPROCESS part of the process object. (See Stage 3C.)
- **19.** The token for the process is now set.
- **20.** The process's priority class is set to normal unless the parent was using idle or the Below Normal process priority class, in which case the parent's priority is inherited.
- 21. The process handle table is initialized. If the inherit handles flag is set for the parent process, any inheritable handles are copied from the parent's object handle table into the new process. (For more information about object handle tables, see Chapter 8 in Part 2.) A process attribute can also be used to specify only a subset of handles, which is useful when you are using CreateProcessAsUser to restrict which objects should be inherited by the child process.
- 22. If performance options were specified through the PerfOptions key, these are now applied. The PerfOptions key includes overrides for the working set limit, I/O priority, page priority, and CPU priority class of the process.
- 23. The final process priority class and the default quantum for its threads are computed and set.
- 24. The various mitigation options provided in the IFEO key (as a single 64-bit value named Mitigation) are read and set. If the process is under an AppContainer, add the TreatAs-AppContainer mitigation flag.
- **25.** All other mitigation flags are now applied.

#### Stage 3B: Creating the initial process address space

The initial process address space consists of the following pages:

- Page directory (it's possible there'll be more than one for systems with page tables more than two levels, such as x86 systems in PAE mode or 64-bit systems)
- Hyperspace page
- VAD bitmap page
- Working set list

To create these pages, the following steps are taken:

- 1. Page table entries are created in the appropriate page tables to map the initial pages.
- 2. The number of pages is deducted from the kernel variable MmTotalCommittedPages and added to MmProcessCommit.
- 3. The system-wide default process minimum working set size (PsMinimumWorkingSet) is deducted from MmResidentAvailablePages.
- **4.** The page table pages for the global system space (that is, other than the process-specific pages we just described, and except session-specific memory) are created.

#### Stage 3C: Creating the kernel process structure

The next stage of PspAllocateProcess is the initialization of the KPROCESS structure (the Pcb member of the EPROCESS). This work is performed by KeInitializeProcess, which does the following:

- 1. The doubly linked list, which connects all threads part of the process (initially empty), is initialized.
- 2. The initial value (or reset value) of the process default quantum (which is described in more detail in the "Thread scheduling" section in Chapter 4) is hard-coded to 6 until it is initialized later (by PspComputeQuantumAndPriority).

**Note** The default initial quantum differs between Windows client and server systems. For more information on thread quantums, turn to the discussion in the section "Thread scheduling" in Chapter 4.

- 3. The process's base priority is set based on what was computed in stage 3A.
- **4.** The default processor affinity for the threads in the process is set, as is the group affinity. The group affinity was calculated in stage 3A or inherited from the parent.
- 5. The process-swapping state is set to resident.
- 6. The thread seed is based on the ideal processor that the kernel has chosen for this process (which is based on the previously created process's ideal processor, effectively randomizing this in a round-robin manner). Creating a new process will update the seed in KeNodeBlock (the initial NUMA node block) so that the next new process will get a different ideal processor seed.
- 7. If the process is a secure process (Windows 10 and Server 2016), then its secure ID is created now by calling Hv1CreateSecureProcess.

### Stage 3D: Concluding the setup of the process address space

Setting up the address space for a new process is somewhat complicated, so let's look at what's involved one step at a time. To get the most out of this section, you should have some familiarity with the internals of the Windows memory manager, described in Chapter 5.

The routine that does most of the work in setting the address space is MmInitializeProcess-AddressSpace. It also supports cloning an address space from another process. This capability was useful at the time to implement the POSIX fork system call. It may also be leveraged in the future to support other Unix-style fork (this is how fork is implemented in Windows Subsystem for Linux in Redstone 1). The following steps do not describe the address space cloning functionality, but rather focus on normal process address space initialization.

- The virtual memory manager sets the value of the process's last trim time to the current time. The working set manager (which runs in the context of the balance set manager system thread) uses this value to determine when to initiate working set trimming.
- 2. The memory manager initializes the process's working set list. Page faults can now be taken.
- **3.** The section (created when the image file was opened) is now mapped into the new process's address space, and the process section base address is set to the base address of the image.
- 4. The Process Environment Block (PEB) is created and initialized (see the section stage 3E).
- Ntdll.dll is mapped into the process. If this is a Wow64 process, the 32-bit Ntdll.dll is also mapped.
- **6.** A new session, if requested, is now created for the process. This special step is mostly implemented for the benefit of the Session Manager (Smss) when initializing a new session.
- **7.** The standard handles are duplicated and the new values are written in the process parameters structure.
- 8. Any memory reservations listed in the attribute list are now processed. Additionally, two flags allow the bulk reservation of the first 1 or 16 MB of the address space. These flags are used internally for mapping, for example, real-mode vectors and ROM code (which must be in the low ranges of virtual address space, where normally the heap or other process structures could be located).
- **9.** The user process parameters are written into the process, copied, and fixed up (that is, they are converted from absolute form to a relative form so that a single memory block is needed).
- 10. The affinity information is written into the PEB.
- **11.** The *MinWin* API redirection set is mapped into the process and its pointer is stored in the PEB.
- 12. The process unique ID is now determined and stored. The kernel does not distinguish between unique process and thread IDs and handles. The process and thread IDs (handles) are stored in a global handle table (PspCidTable) that is not associated with any process.
- **13.** If the process is secure (that is, it runs in IUM), the secure process is initialized and associated with the kernel process object.

## Stage 3E: Setting up the PEB

NtCreateUserProcess calls MmCreatePeb, which first maps the system-wide National Language Support (NLS) tables into the process's address space. It next calls MiCreatePebOrTeb to allocate a page for the PEB and then initializes a number of fields, most of them based on internal variables that were configured through the registry, such as MmHeap\* values, MmCriticalSectionTimeout, and MmMinimum-StackCommitInBytes. Some of these fields can be overridden by settings in the linked executable image, such as the Windows version in the PE header or the affinity mask in the load configuration directory of the PE header.

If the image header characteristics IMAGE\_FILE\_UP\_SYSTEM\_ONLY flag is set (indicating that the image can run only on a uniprocessor system), a single CPU (MmRotatingUniprocessorNumber) is chosen for all the threads in this new process to run on. The selection process is performed by simply cycling through the available processors. Each time this type of image is run, the next processor is used. In this way, these types of images are spread evenly across the processors.

#### Stage 3F: Completing the setup of the executive process object

Before the handle to the new process can be returned, a few final setup steps must be completed, which are performed by PspInsertProcess and its helper functions:

- 1. If system-wide auditing of processes is enabled (because of either local policy settings or group policy settings from a domain controller), the process's creation is written to the Security event log.
- 2. If the parent process was contained in a job, the job is recovered from the job level set of the parent and then bound to the session of the newly created process. Finally, the new process is added to the job.
- 3. The new process object is inserted at the end of the Windows list of active processes (PsActive-ProcessHead). Now the process is accessible via functions like EnumProcesses and OpenProcess.
- 4. The process debug port of the parent process is copied to the new child process unless the NoDebugInherit flag is set (which can be requested when creating the process). If a debug port was specified, it is attached to the new process.
- 5. Job objects can specify restrictions on which group or groups the threads within the processes part of a job can run on. Therefore, PspInsertProcess must make sure the group affinity associated with the process would not violate the group affinity associated with the job. An interesting secondary issue to consider is if the job's permissions grant access to modify the process's affinity permissions, because a lesser-privileged job object might interfere with the affinity requirements of a more privileged process.
- 6. Finally, PspInsertProcess creates a handle for the new process by calling ObOpenObject-ByPointer, and then returns this handle to the caller. Note that no process-creation callback is sent until the first thread within the process is created, and the code always sends process callbacks before sending object managed-based callbacks.

## Stage 4: Creating the initial thread and its stack and context

At this point, the Windows executive process object is completely set up. It still has no thread, however, so it can't do anything yet. It's now time to start that work. Normally, the PspCreateThread routine is responsible for all aspects of thread creation and is called by NtCreateThread when a new thread is being created. However, because the initial thread is created internally by the kernel without user-mode input, the two helper routines that PspCreateThread relies on are used instead: PspAllocate-Thread and PspInsertThread. PspAllocateThread handles the actual creation and initialization of the executive thread object itself, while PspInsertThread to turn the executive object into a schedulable thread on the system. However, the thread won't do anything yet. It is created in a suspended state and isn't resumed until the process is completely initialized (as described in stage 5).

**Note** The thread parameter (which can't be specified in CreateProcess but can be specified in CreateThread) is the address of the PEB. This parameter will be used by the initialization code that runs in the context of this new thread (as described in stage 6).

PspAllocateThread performs the following steps:

- 1. It prevents user-mode scheduling (UMS) threads from being created in Wow64 processes, as well as preventing user-mode callers from creating threads in the system process.
- 2. An executive thread object is created and initialized.
- **3.** If energy estimation is enabled for the system (always disabled for XBOX), then it allocates and initializes a THREAD\_ENERGY\_VALUES structure pointed to by the ETHREAD object.
- 4. The various lists used by LPC, I/O Management, and the Executive are initialized.
- 5. The thread's creation time is set, and its thread ID (TID) is created.
- 6. Before the thread can execute, it needs a stack and a context in which to run, so these are set up. The stack size for the initial thread is taken from the image; there's no way to specify another size. If this is a Wow64 process, the Wow64 thread context will also be initialized.
- 7. The thread environment block (TEB) is allocated for the new thread.
- 8. The user-mode thread start address is stored in the ETHREAD (in the StartAddress field). This is the system-supplied thread startup function in Ntdll.dll (RtlUserThreadStart). The user's specified Windows start address is stored in the ETHREAD in a different location (the Win32StartAddress field) so that debugging tools such as Process Explorer can display the information.
- 9. KeInitThread is called to set up the KTHREAD structure. The thread's initial and current base priorities are set to the process's base priority, and its affinity and quantum are set to that of the process. KeInitThread next allocates a kernel stack for the thread and initializes the machine-dependent hardware context for the thread, including the context, trap, and exception frames.

The thread's context is set up so that the thread will start in kernel mode in KiThreadStartup. Finally, KeInitThread sets the thread's state to Initialized and returns to PspAllocateThread.

**10.** If this is a UMS thread, PspUmsInitThread is called to initialize the UMS state.

Once that work is finished, NtCreateUserProcess calls PspInsertThread to perform the following steps:

- 1. The thread ideal processor is initialized if it was specified using an attribute.
- 2. The thread group affinity is initialized if it was specified using an attribute.
- **3.** If the process is part of a job, a check is made to ensure that the thread's group affinity does not violate job limitations (described earlier).
- 4. Checks are made to ensure that the process hasn't already been terminated, that the thread hasn't already been terminated, or that the thread hasn't even been able to start running. If any of these are true, thread creation will fail.
- 5. If the thread is part of a secure process (IUM), then the secure thread object is created and initialized.
- 6. The KTHREAD part of the thread object is initialized by calling KeStartThread. This involves inheriting scheduler settings from the owner process, setting the ideal node and processor, updating the group affinity, setting the base and dynamic priorities (by copying from the process), setting the thread quantum, and inserting the thread in the process list maintained by KPROCESS (a separate list from the one in EPROCESS).
- **7.** If the process is in a deep freeze (meaning no threads are allowed to run, including new threads), then this thread is frozen as well.
- 8. On non-x86 systems, if the thread is the first in the process (and the process is not the idle process), then the process is inserted into another system-wide list of processes maintained by the global variable KiProcessListHead.
- **9.** The thread count in the process object is incremented, and the owner process's I/O priority and page priority are inherited. If this is the highest number of threads the process has ever had, the thread count high watermark is updated as well. If this was the second thread in the process, the primary token is frozen (that is, it can no longer be changed).
- **10.** The thread is inserted in the process's thread list, and the thread is suspended if the creating process requested it.
- **11.** The thread object is inserted into the process handle table.
- 12. If it's the first thread created in the process (that is, the operation happened as part of a Create-Process\* call), any registered callbacks for process creation are called. Then any registered thread callbacks are called. If any callback vetoes the creation, it will fail and return an appropriate status to the caller.

- **13.** If a job list was supplied (using an attribute) and this is the first thread in the process, then the process is assigned to all of the jobs in the job list.
- **14.** The thread is readied for execution by calling KeReadyThread. It enters the deferred ready state. (See Chapter 4 for more information on thread states.)

## Stage 5: Performing Windows subsystem–specific initialization

Once NtCreateUserProcess returns with a success code, the necessary executive process and thread objects have been created. CreateProcessInternalW then performs various operations related to Windows subsystem—specific operations to finish initializing the process.

- Various checks are made for whether Windows should allow the executable to run. These checks include validating the image version in the header and checking whether Windows application certification has blocked the process (through a group policy). On specialized editions of Windows Server 2012 R2, such as Windows Storage Server 2012 R2, additional checks are made to see whether the application imports any disallowed APIs.
- 2. If software restriction policies dictate, a restricted token is created for the new process. Afterward, the application-compatibility database is queried to see whether an entry exists in either the registry or system application database for the process. Compatibility shims will not be applied at this point; the information will be stored in the PEB once the initial thread starts executing (stage 6).
- 3. CreateProcessInternalW calls some internal functions (for non-protected processes) to get SxS information (see the section "DLL name resolution and redirection" later in this chapter for more information on side-by-side) such as manifest files and DLL redirection paths, as well as other information such as whether the media on which the EXE resides is removable and installer detection flags. For immersive processes, it also returns version information and target platform from the package manifest.
- **4.** A message to the Windows subsystem is constructed based on the information collected to be sent to Csrss. The message includes the following information:
  - Path name and SxS path name
  - Process and thread handles
  - Section handle
  - The access token handle
  - Media information
  - AppCompat and shim data
  - Immersive process information
  - The PEB address
  - Various flags such as whether it's a protected process or whether it is required to run elevated

- A flag indicating whether the process belongs to a Windows application (so that Csrss can determine whether to show the startup cursor)
- UI language information
- DLL redirection and .local flags (discussed in the "Image loader" section later in this chapter)
- Manifest file information

When it receives this message, the Windows subsystem performs the following steps:

- 1. CsrCreateProcess duplicates a handle for the process and thread. In this step, the usage count of the process and the thread is incremented from 1 (which was set at creation time) to 2.
- 2. The Csrss process structure (CSR\_PROCESS) is allocated.
- **3.** The new process's exception port is set to be the general function port for the Windows subsystem so that the Windows subsystem will receive a message when a second-chance exception occurs in the process. (For further information on exception handling, see Chapter 8 in Part 2.)
- 4. If a new process group is to be created with the new process serving as the root (CREATE\_NEW\_ PROCESS\_GROUP flag in CreateProcess), then it's set in CSR\_PROCESS. A process group is useful for sending a control event to a set of processes sharing a console. See the Windows SDK documentation for CreateProcess and GenerateConsoleCtrlEvent for more information.
- 5. The Csrss thread structure (CSR\_THREAD) is allocated and initialized.
- 6. CsrCreateThread inserts the thread in the list of threads for the process.
- 7. The count of processes in this session is incremented.
- 8. The process shutdown level is set to 0x280, the default process shutdown level. (See SetProcess-ShutdownParameters in the Windows SDK documentation for more information.)
- 9. The new Csrss process structure is inserted into the list of Windows subsystem-wide processes.

After Csrss has performed these steps, CreateProcessInternalW checks whether the process was run elevated (which means it was executed through ShellExecute and elevated by the AppInfo service after the consent dialog box was shown to the user). This includes checking whether the process was a setup program. If it was, the process's token is opened, and the virtualization flag is turned on so that the application is virtualized. (See the information on UAC and virtualization in Chapter 7.) If the application contained elevation shims or had a requested elevation level in its manifest, the process is destroyed and an elevation request is sent to the AppInfo service.

Note that most of these checks are not performed for protected processes. Because these processes must have been designed for Windows Vista or later, there's no reason they should require elevation, virtualization, or application-compatibility checks and processing. Additionally, allowing mechanisms such as the shim engine to use its usual hooking and memory-patching techniques on a protected process would result in a security hole if someone could figure how to insert arbitrary shims that modify the behavior of the protected process. Additionally, because the shim engine is installed by the parent process, which might not have access to its child protected process, even legitimate shimming cannot work.

# Stage 6: Starting execution of the initial thread

At this point, the process environment has been determined, resources for its threads to use have been allocated, the process has a thread, and the Windows subsystem knows about the new process. Unless the caller specified the CREATE\_SUSPENDED flag, the initial thread is now resumed so that it can start running and perform the remainder of the process-initialization work that occurs in the context of the new process (stage 7).

# Stage 7: Performing process initialization in the context of the new process

The new thread begins life running the kernel-mode thread startup routine KiStartUserThread. KiStartUserThread lowers the thread's IRQL level from deferred procedure call (DPC) level to APC level and then calls the system initial thread routine, PspUserThreadStartup. The user-specified thread start address is passed as a parameter to this routine. PspUserThreadStartup performs the following actions:

- **1.** It installs an exception chain on x86 architecture. (Other architectures work differently in this regard, see Chapter 8 in Part 2.)
- 2. It lowers IRQL to PASSIVE\_LEVEL (0, which is the only IRQL user code is allowed to run at).
- 3. It disables the ability to swap the primary process token at runtime.
- **4.** If the thread was killed on startup (for whatever reason), it's terminated and no further action is taken.
- **5.** It sets the locale ID and the ideal processor in the TEB, based on the information present in kernel-mode data structures, and then it checks whether thread creation actually failed.
- 6. It calls DbgkCreateThread, which checks whether image notifications were sent for the new process. If they weren't, and notifications are enabled, an image notification is sent first for the process and then for the image load of Ntdll.dll.

-	_	_	-	
-	_	_	=	
-			=	
-	_	_	=	

**Note** This is done in this stage rather than when the images were first mapped because the process ID (which is required for the kernel callouts) is not yet allocated at that time.

7. Once those checks are completed, another check is performed to see whether the process is a debuggee. If it is and if debugger notifications have not been sent yet, then a create process message is sent through the debug object (if one is present) so that the process startup debug event (CREATE\_PROCESS\_DEBUG\_INFO) can be sent to the appropriate debugger process. This is followed by a similar thread startup debug event and by another debug event for the image load of Ntdll.dll. DbgkCreateThread then waits for a reply from the debugger (via the Continue-DebugEvent function).

- 8. It checks whether application prefetching is enabled on the system and, if so, calls the prefetcher (and Superfetch) to process the prefetch instruction file (if it exists) and prefetch pages referenced during the first 10 seconds the last time the process ran. (For details on the prefetcher and Superfetch, see Chapter 5.)
- **9.** It checks whether the system-wide cookie in the SharedUserData structure has been set up. If it hasn't, it generates it based on a hash of system information such as the number of interrupts processed, DPC deliveries, page faults, interrupt time, and a random number. This system-wide cookie is used in the internal decoding and encoding of pointers, such as in the heap manager to protect against certain classes of exploitation. (For more information on the heap manager security, see Chapter 5.)
- **10.** If the process is secure (IUM process), then a call is made to HvlStartSecureThread that transfers control to the secure kernel to start thread execution. This function only returns when the thread exits.
- 11. It sets up the initial thunk context to run the image-loader initialization routine (LdrInitialize-Thunk in Ntdll.dll), as well as the system-wide thread startup stub (RtlUserThreadStart in Ntdll.dll). These steps are done by editing the context of the thread in place and then issuing an exit from system service operation, which loads the specially crafted user context. The LdrInitializeThunk routine initializes the loader, the heap manager, NLS tables, thread-local storage (TLS) and fiber-local storage (FLS) arrays, and critical section structures. It then loads any required DLLs and calls the DLL entry points with the DLL\_PROCESS\_ATTACH function code.

Once the function returns, NtContinue restores the new user context and returns to user mode. Thread execution now truly starts.

RtlUserThreadStart uses the address of the actual image entry point and the start parameter and calls the application's entry point. These two parameters have also already been pushed onto the stack by the kernel. This complicated series of events has two purposes:

- It allows the image loader inside Ntdll.dll to set up the process internally and behind the scenes so that other user-mode code can run properly. (Otherwise, it would have no heap, no threadlocal storage, and so on.)
- Having all threads begin in a common routine allows them to be wrapped in exception handling so that if they crash, Ntdll.dll is aware of that and can call the unhandled exception filter inside Kernel32.dll. It is also able to coordinate thread exit on return from the thread's start routine and to perform various cleanup work. Application developers can also call SetUnhandled-ExceptionFilter to add their own unhandled exception-handling code.

#### **EXPERIMENT:** Tracing process startup

Now that we've looked in detail at how a process starts up and the different operations required to begin executing an application, we're going to use Process Monitor to look at some of the file I/O and registry keys that are accessed during this process.

Although this experiment will not provide a complete picture of all the internal steps we've described, you'll be able to see several parts of the system in action, notably prefetch and Superfetch, image-file execution options and other compatibility checks, and the image loader's DLL mapping.

We'll look at a very simple executable—Notepad.exe—and launch it from a Command Prompt window (Cmd.exe). It's important that we look both at the operations inside Cmd.exe and those inside Notepad.exe. Recall that a lot of the user-mode work is performed by CreateProcessIn-ternalW, which is called by the parent process before the kernel has created a new process object.

To set things up correctly, follow these steps:

1. Add two filters to Process Monitor: one for Cmd.exe and one for Notepad.exe. These are the only two processes you should include. Be sure you don't have any currently running instances of these two processes so that you know you're looking at the right events. The filter window should look like this:

apiey enuies mater	ing these cond	litions:				
Process Name	∼ is	~	notepad.exe	~	then [	Include
Reset				Add		Remove
Column	Relation	-	Value	Action		,
Process N	is		cmd.exe	Include		
Process N	is		notepad.exe	Include		
Process N	is		Procexp.exe	Exclude		
	10		Autoruns.exe	Exclude		
Process N	14					
Process N			Procmon64.exe	Exclude		

- Make sure event logging is currently disabled (open the File and deselect Capture Events) and then start the command prompt.
- Enable event logging (open the File menu and choose Event Logging, press Ctrl+E, or click the magnifying glass icon on the toolbar) and then type Notepad.exe and press Enter. On a typical Windows system, you should see anywhere between 500 and 3,500 events appear.
- **4.** Stop capture and hide the Sequence and Time of Day columns so that you can focus your attention on the columns of interest. Your window should look similar to the one shown in the following screenshot.

As described in stage 1 of the CreateProcess flow, one of the first things to notice is that just before the process is started and the first thread is created, Cmd.exe does a registry read at HKLM\SOFTWARE\Microsoft\Windows NT\CurrentVersion\Image File Execution Options\ Notepad.exe. Because there were no image-execution options associated with Notepad.exe, the process was created as is.

File Edit Event Filt	er Tools Options Help	
📽 🖬   🕺 🖗 🛙	5   🗢 🛕 🚱   🗉   🗛 🖐	± B A 3
Process Name	PID Operation	Path
cmd.exe	14524 CreateFile	C:\Users\pavely
cmd.exe	14524 QueryDirectory	C:\Users\pavely\notepad.*
cmd.exe	14524 CreateFile	C:\Program Files\Common Files\microsoft shared\Microsoft Online Servic
cmd.exe	14524 QueryDirectory	C:\Program Files\Common Files\microsoft shared\Microsoft Online Servic
cmd.exe	14524 CreateFile	C:\Program Files (x86)\Common Files\Microsoft Shared\Microsoft Online
cmd.exe	14524 QueryDirectory	C:\Program Files (x86)\Common Files\Microsoft Shared\Microsoft Online
cmd.exe	14524 CreateFile	C:\Windows\System32
cmd.exe	14524 AueryDirectory	C:\Windows\System32\notepad.*
cmd.exe	14524 CreateFile	C:\Windows\System32
cmd.exe	14524 QueryDirectory	C:\Windows\System32\notepad.COM
cmd.exe	14524 CreateFile	C:\Windows\System32
cmd.exe	14524 QueryDirectory	C:\Windows\System32\notepad.EXE
and exe	14524 CreateFile	C:\Llsers\pavely
cmd.exe	14524 CreateFile	C:\Windows\System32\notepad.exe
an cmd.exe	14524 KegOpenKey	HKLM\SOFTWARE\MICROSOFT\WINDOWS NT\CURRENTVERSION
cmd.exe	14524 QueryNameInformationFile	C:\Windows\System32\notepad.exe
cmd.exe	14524 RegOpenKey	HKLM\SOFTWARE\Microsoft\UEV\Agent\Processes\notepad.exe
m.cmd.exe	14524 Recess Create	C:\WINDOWS\system32\notepad.exe
notepad.exe	12276 Trocess Start	~
<		>

As with this and any other event in Process Monitor's log, you can see whether each part of the process-creation flow was performed in user mode or kernel mode, and by which routines, by looking at the stack of the event. To do this, double-click the RegOpenKey event and switch to the **Stack** tab. The following screenshot shows the standard stack on a 64-bit Windows 10 machine:

vent	Process Stack				
Frame	Module	Location	Address	Path	
KO	ntoskml.exe	CmpCallCallBacks + 0x3b0	0xffff803f048f640	C:\WINDOWS\system32\m	toskml
K 1	ntoskml.exe	CmpParseKey + 0x24e	0xffff803f048283e	C:\WINDOWS\system32\m	toskml
K 2	ntoskml.exe	ObpLookupObjectName + 0x776	0xffff803f048c916	C:\WINDOWS\system32\m	toskml
K 3	ntoskml.exe	ObOpenObjectByNameEx + 0x1ec	0xffff803f048b31c	C:\WINDOWS\system32\m	toskml
K4	ntoskml.exe	CmOpenKey + 0x2a6	0xffff803f04796e6	C:\WINDOWS\system32\m	toskml
K 5	ntoskml.exe	NtOpenKey + 0x12	0xffff803f04789d2	C:\WINDOWS\system32\m	toskml
K 6	ntoskml.exe	KiSystemServiceCopyEnd + 0x13	0xffff803f01ccfa3	C:\WINDOWS\system32\m	toskml
K 7	ntoskml.exe	KiServiceLinkage	0xffff803f01c5650	C:\WINDOWS\system32\m	toskml
K 8	ntoskml.exe	RtlpOpenImageFileOptionsKey + 0xb0	0xffff803f04fa9fc	C:\WINDOWS\system32\m	toskml
K 9	ntoskml.exe	PspAllocateProcess + 0x4e1	0xffff803f04c8481	C:\WINDOWS\system32\m	toskml
K 10	ntoskml.exe	NtCreateUserProcess + 0x620	0xffff803f04ae18c	C:\WINDOWS\system32\m	toskml
K 11	ntoskml.exe	KiSystemServiceCopyEnd + 0x13	0xffff803f01ccfa3	C:\WINDOWS\system32\m	toskml
U 12	ntdll.dll	NtCreate UserProcess + 0x14	0x7#a252c6824	C:\WINDOWS\SYSTEM32	Antdl.
U 13	KERNELBASE.dl	CreateProcessInternalW + 0x14e1	0x7ffa21f7e541	C:\WINDOWS\system32\K	ERNE
U 14	KERNELBASE dl	CreateProcessW + 0x66	0x7ffa21f7c9e6	C:\WINDOWS\system32\K	ERNE
U 15	KERNEL32.DLL	CreateProcessWStub + 0x53	0x7#a236a3b53	C:\WINDOWS\system32\K	ERNE
U 16	cmd.exe	ExecPgm + 0x228	0x7#633b4e2d8	C:\WINDOWS\system32\c	md.exe
U 17	cmd.exe	ECWork + 0xa3	0x7#633b50a4b	C:\WINDOWS\system32\c	md.exe
U 18	cmd.exe	FindFixAndRun + 0x36d	0x7#633b4b7cd	C:\WINDOWS\system32\c	md.exx
U 19	cmd.exe	Dispatch + 0xa5	0x7#633b4af45	C:\WINDOWS\system32\c	md.exe
U 20	cmd.exe	CmpType + 0x21a1	0x7#633b58191	C:\WINDOWS\system32\c	md.exe
U 21	cmd.exe	_delayLoadHelper2 + 0x2dc	0x7#633b5536c	C:\WINDOWS\system32\c	md.exx
U 22	KERNEL32.DLL	BaseThreadInitThunk + 0x22	0x7#a23698102	C:\WINDOWS\system32\K	ERNE
U 23	ntdll.dll	RtIUserThreadStart + 0x34	0x7#a2527c5b4	C:\WINDOWS\SYSTEM32	Pontdli.c
<					>
		Propert	ies Search	Source Save	

This stack shows that you already reached the part of process creation performed in kernel mode (through NtCreateUserProcess) and that the helper routine PspAllocateProcess is responsible for this check.

Going down the list of events after the thread and process have been created, you will notice three groups of events:

- A simple check for application-compatibility flags, which will let the user-mode processcreation code know if checks inside the application-compatibility database are required through the shim engine.
- Multiple reads to SxS (search for Side-By-Side), Manifest, and MUI/Language keys, which are part of the assembly framework mentioned earlier.
- File I/O to one or more .sdb files, which are the application-compatibility databases on the system. This I/O is where additional checks are done to see if the shim engine needs to be invoked for this application. Because Notepad is a well-behaved Microsoft program, it doesn't require any shims.

The following screenshot shows the next series of events, which happen inside the Notepad process itself. These are actions initiated by the user-mode thread startup wrapper in kernel mode, which performs the actions described earlier. The first two are the Notepad.exe and Ntdll. dll image load debug notification messages, which can be generated only now that code is running inside Notepad's process context and not inside the context for the command prompt.

File Edit Event	Filter Tools Options Help				
😂 🖬 🕴 🕅	🖡 🖾   🗢 🗛 🚱   🗉	🗛 📕 🛛 🎎 🗟 🛝 🖓 🛄			
Process Name	PID Operation	Path	Result	Detail	
mcmd.exe 1	7548 RegCloseKey	HKLM\SOFTWARE\Microsoft\Window	SUCCESS		
mcmd.exe 1	7548 CloseFile	C:\Windows\Svstem32\notepad.exe	SUCCESS		
notepad.exe 1	6128 CLoad Image	C:\Windows\System32\notepad.exe	SUCCESS	Image Base: 0x7ff7	
notepad.exe 1	6128 ar Load Image		SUCCESS	Image Base: 0x7ffb	
notepad.exe 1	6128 RegOpenKey	HKLM\SYSTEM\CurrentControlSet\Con	REPARSE	Desired Access: Q	
notepad.exe 1	6128 RegOpenKey	HKLM\System\CurrentControlSet\Contr	NAME NOT FOUND	Desired Access: Q	
notepad.exe 1	6128 CreateFile	C:\Users\pavely	SUCCESS	Desired Access: E	
notepad.exe 1	6128 QuerySecurityFile	C:\Users\pavely	SUCCESS	Information: Attribute	
notepad.exe 1	6128 Rt Load Image	C:\Windows\System32\kemel32.dll	SUCCESS	Image Base: 0x7ffb	
notepad.exe 1	6128 At Load Image	C:\Windows\System32\KemelBase.dll	SUCCESS	Image Base: 0x7ffb	
notepad.exe 1	6128 RegQueryValue	HKLM\System\CurrentControlSet\Contr	NAME NOT FOUND	Length: 524	
notepad.exe 1	6128 RegOpenKey	HKLM\System\CurrentControlSet\Contr	REPARSE	Desired Access: Q	
notepad.exe 1	6128 RegOpenKey	HKLM\System\CurrentControlSet\Contr	NAME NOT FOUND	Desired Access: Q	
notepad.exe 1	6128 RegOpenKey	HKLM\System\CurrentControlSet\Contr	REPARSE	Desired Access: R	
notepad.exe 1	6128 RegOpenKey	HKLM\System\CurrentControlSet\Contr	NAME NOT FOUND	Desired Access: R	
notepad.exe 1	6128 RegOpenKey	HKLM\Software\Policies\Microsoft\Win		Desired Access: Q	
notepad.exe 1	6128 RegQueryValue	HKLM\SOFTWARE\Policies\Microsoft\	NAME NOT FOUND	Length: 80	
notepad.exe 1	6128 RegCloseKey	HKLM\SOFTWARE\Policies\Microsoft\	SUCCESS		
notepad.exe 1	6128 RegOpenKey	HKCU\Software\Policies\Microsoft\Win	NAME NOT FOUND	Desired Access: Q	
notepad.exe 1	6128 CreateFile	C:\Program Files\Microsoft User Experie	SUCCESS	Desired Access: R	
notepad.exe 1	6128 RueryBasicInformationFile	C:\Program Files\Microsoft User Experie	SUCCESS	Creation Time: 25-J	
notepad.exe 1	6128 CloseFile	C:\Program Files\Microsoft User Experie	SUCCESS		

Next, the prefetcher kicks in, looking for a prefetch database file that has already been generated for Notepad. (For more information on the prefetcher, see Chapter 5.) On a system where Notepad has already been run at least once, this database will exist, and the prefetcher will begin executing the commands specified inside it. If this is the case, scrolling down, you will see multiple DLLs being read and queried. Unlike typical DLL loading, which is done by the usermode image loader by looking at the import tables or when an application manually loads a DLL, these events are being generated by the prefetcher, which is already aware of the libraries that Notepad will require. Typical image loading of the DLLs required happens next, and you will see events similar to the ones shown here:

File Edit Event Filter	Tools Options Help	
🛎 🖬   🔌 📴 🖾	🗢 🛆 🛞   🗉   🗛 📕	■ 🗱 🛃 📾 🔳
Process Name	PID Operation	Path
Sond exe Sond exe Sond exe Sond exe Sond exe Sond exe Sond exe notepad exe notepad exe notepad exe notepad exe notepad exe notepad exe	14524 at RegDueryValue 14524 rt RegDueryValue 14524 rt RegDueryValue 14524 at RegDueryValue 14524 at RegDueryValue 14524 at RegDueryValue 12276 at RegDueryValue 12276 at Load Image 12276 at Load Image 12276 at Load Image 12276 at RegDenKey	HKCU/SOFTWARE/Microsoft/Windows/Qurrent/Version/Explorer/Shell Folders/Cache HKCU/SOFTWARE/Microsoft/Windows NT/Current/Version/AppCompatRags/Layers HKCU/SOFTWARE/Microsoft/Windows NT/Current/Version/AppCompatRags/Layers/C/WINDOWS/syr C/Windows/VepPatch/appatch64/sysmain.adb HKLM/Software/Microsoft Windows/Current/Version/SideBySide HKLM/Software/Microsoft Windows/Current/Version/SideBySide HKLM/Software/Microsoft Windows/Current/Version/SideBySide HKLM/Software/Microsoft Windows/Current/Version/SideBySide HKLM/Software/Microsoft Windows/Current/Version/SideBySide HKLM/Software/Microsoft Windows/Current/Version/SideBySide HKLM/Software/System22/nctabad.exe C/Windows/System2
notepad.exe	12276 CreateFile	C:\Users\pavely
notepad exe	12276 Coad Image	C.\Windows\System32'kernel32.dll
Indepad exe notepad exe	12276 all Load Image 12276 all RegDuen Value 12276 all RegDuen Key 12276 all Load Image 12276 all RegDuen Key 12276 all RegDuen Key	C: Windows Vsystem 32: ViennellBase dll HKLM-System \CurrentCorttolSet\Control\VMINSecurity\D9/95efe-7775-49c7-a994-60a55cc09571 HKLM-System\CurrentCorttolSet\Control\SafeBoot\Option HKLM-System\CurrentCorttolSet\Control\SyStePDLL HKLM-System\CurrentCorttolSet\Control\SyStePDLL HKLM-System\CurrentCorttolSet\Control\SyStePDLL HKLM-System\CurrentCorttolSet\Control\SyStePDLL HKLM-System\CurrentCorttolSet\Control\SyStePDLL HKLM-System\CurrentCorttolSet\Control\SystePDLL CurrentCorttolSet\Control\SystemSafer\Codeldentifiers HKLM-System\CurrentCorttolSet\Control\SystemSafer\Codeldentifiers CrPtogram Files\Microsoft Uler Experience Virtualization\Agent\Set\Microsoft. Uev AppAgent dll C:\Program Files\Microsoft Uler Experience Virtualization\Agent\Set\Microsoft. Ulev AppAgent dll C:\Windows\System32:user32.dl HKLM\System\CurrentCortrolSet\Cortrol\Session Manager HKLM\System\CurrentCortrolSet\Cortrol\SetSSION MANAGER\SetEDISearchMode
notepad.exe	12276 Ar Load Image	C:\Windows\System32\gdi32.dll
notenad exe	1777h an Inread Lineate	)

These events are now being generated from code running inside user mode, which was called once the kernel-mode wrapper function finished its work. Therefore, these are the first events coming from LdrpInitializeProcess, which is called by LdrInitializeThunk for the first thread in the process. You can confirm this on your own by looking at the stack of these events—for example, the kernel32.dll image load event, which is shown in the following screenshot.

Further events are generated by this routine and its associated helper functions until you finally reach events generated by the WinMain function inside Notepad, which is where code under the developer's control is now being executed. Describing in detail all the events and usermode components that come into play during process execution would fill up this entire chapter, so exploration of any further events is left as an exercise for the reader.

nt Pr	ocess Stack			
Frame	Module	Location	Address	Path
KO	ntoskml.exe	PsCallImageNotifyRoutines + 0x123	0x1111803f049e1e3	C:\WINDOWS\system32\
K 1	ntoskml.exe	MiMapViewOfImageSection + 0x6fc	0xffff803f04a140c	C:\WINDOWS\system32\
K 2	ntoskmi.exe	MMapViewOfSection + 0x336	0xffff803f045cd66	C:\WINDOWS\system32\
< 3	ntoskml.exe	NtMapViewOfSection + 0x2d5	0x11111803f04e9605	C:\WINDOWS\system32\
54	ntoskml.exe	KiSystemServiceCopyEnd + 0x13	0xffff803f01ccfa3	C:\WINDOWS\system32\
U 5	ntdii.dii	NtMapViewOfSection + 0x14	0x7ffa252c55d4	C:\Windows\System32\nt
U 6	ntdil.di	LdrpMapViewOfSection + Dxbe	0x7ffa2522eaee	C:\Windows\System32\nt
U 7	ntdli.dli	LdrpMapImage + 0x72	0x7#a2522e77e	C:\Windows\System32\nt
U 8	ntdli.dli	LdrpMapDIIWithSectionHandle + 0		C:\Windows\System32\nt
6 U	ntdil.dl	LdrpLoadKnownDII + 0d3	0x7#a252306b3	C:\Windows\System32\nt
U 10	ntdli.dli	LdrpFindOrPrepareLoadingModule		C:\Windows\System32\nt
U 11	ntdl.dl	LdrpLoadDIIInternal + 0x12f	0x7#a25231e5b	C:\Windows\System32\nt
U 12	ntdli.dli	LdrpLoadDll + 0d2	0x7#a252319fe	C:\Windows\System32\nt
U 13	ntdi.di	LdrLoadDll + 0x114	0x7#a25230c44	C:\Windows\System32\nt
U 14	ntdli.dli	LdrpInitializeProcess + 0x187b	0x7ffa252afdaf	C:\Windows\System32\nt
U 15	ntdi.di	_Ldm/nitialize + 0x4a8b9	0x7ffa252e166d	C:\Windows\System32\nt
U 16	ntdli.dli	LdrinitializeThunk + Dxe	0x7ffa25296d5e	C:\Windows\System32\nt
¢				•
		Properties	Search S	ource Save

## **Terminating a process**

A process is a container and a boundary. This means resources used by one process are not automatically visible in other processes, so some inter-process communication mechanism needs to be used to pass information between processes. Therefore, a process cannot accidentally write arbitrary bytes on another process's memory. That would require explicit call to a function such as WriteProcessMemory. However, to get that to work, a handle with the proper access mask (PROCESS\_VM\_WRITE) must be opened explicitly, which may or may not be granted. This natural isolation between processes also means that if some exception happens in one process, it will have no effect on other processes. The worst that can happen is that same process would crash, but the rest of the system stays intact.

A process can exit gracefully by calling the ExitProcess function. For many processes—depending on linker settings—the process startup code for the first thread calls ExitProcess on the process's behalf when the thread returns from its main function. The term *gracefully* means that DLLs loaded into the process get a chance to do some work by getting notified of the process exit using a call to their D11Main function with DLL\_PROCESS\_DETACH.

ExitProcess can be called only by the process itself asking to exit. An ungraceful termination of a process is possible using the TerminateProcess function, which can be called from outside the process. (For example, Process Explorer and Task Manager use it when so requested.) TerminateProcess requires a handle to the process that is opened with the PROCESS\_TERMINATE access mask, which may or may not be granted. This is why it's not easy (or it's impossible) to terminate some processes (for example, Csrss)—the handle with the required access mask cannot be obtained by the requesting user.

The meaning of *ungraceful* here is that DLLs don't get a chance to execute code (DLL\_PROCESS\_DETACH is not sent) and all threads are terminated abruptly. This can lead to data loss in some cases—for example, if a file cache has no chance to flush its data to the target file.

In whatever way a process ceases to exist, there can never be any leaks. That is, all process's private memory is freed automatically by the kernel, the address space is destroyed, all handles to kernel objects are closed, etc. If open handles to the process still exist (the EPROCESS structure still exists), then other processes can still gain access to some process-management information, such as the process exit code (GetExitCodeProcess). Once these handles are closed, the EPROCESS is properly destroyed, and there's truly nothing left of the process.

That being said, if third party drivers make allocations in kernel memory on behalf of a process say, due to an IOCTL or merely due to a process notification—it is their responsibility to free any such pool memory on their own. Windows does not track or clean-up process-owned kernel memory (except for memory occupied by objects due to handles that the process created). This would typically be done through the IRP\_MJ\_CLOSE or IRP\_MJ\_CLEANUP notification to tell the driver that the handle to the device object has been closed, or through a process termination notification. (see Chapter 6, "I/O system," for more on IOCTLs.)

## **Image loader**

As we've just seen, when a process is started on the system, the kernel creates a process object to represent it and performs various kernel-related initialization tasks. However, these tasks do not result in the execution of the application, merely in the preparation of its context and environment. In fact, unlike drivers, which are kernel-mode code, applications execute in user mode. So most of the actual initialization work is done outside the kernel. This work is performed by the *image loader*, also internally referred to as Ldr.

The image loader lives in the user-mode system DLL *Ntdll.dll* and not in the kernel library. Therefore, it behaves just like standard code that is part of a DLL, and it is subject to the same restrictions in terms of memory access and security rights. What makes this code special is the guarantee that it will always be present in the running process (Ntdll.dll is always loaded) and that it is the first piece of code to run in user mode as part of a new process.

Because the loader runs before the actual application code, it is usually invisible to users and developers. Additionally, although the loader's initialization tasks are hidden, a program typically does interact with its interfaces during the run time of a program—for example, whenever loading or unloading a DLL or querying the base address of one. Some of the main tasks the loader is responsible for include:

- Initializing the user-mode state for the application, such as creating the initial heap and setting up the thread-local storage (TLS) and fiber-local storage (FLS) slots.
- Parsing the import table (IAT) of the application to look for all DLLs that it requires (and then recursively parsing the IAT of each DLL), followed by parsing the export table of the DLLs to make sure the function is actually present. (Special *forwarder entries* can also redirect an export to yet another DLL.)

- Loading and unloading DLLs at run time, as well as on demand, and maintaining a list of all loaded modules (the module database).
- Handling manifest files, needed for Windows Side-by-Side (SxS) support, as well as Multiple Language User Interface (MUI) files and resources.
- Reading the application compatibility database for any shims, and loading the shim engine DLL if required.
- Enabling support for API Sets and API redirection, a core part of the One Core functionality that allows creating Universal Windows Platform (UWP) applications.
- Enabling dynamic runtime compatibility mitigations through the *SwitchBack* mechanism as well as interfacing with the shim engine and Application Verifier mechanisms.

As you can see, most of these tasks are critical to enabling an application to actually run its code. Without them, everything from calling external functions to using the heap would immediately fail. After the process has been created, the loader calls the NtContinue special native API to continue execution based on an exception frame located on the stack, just as an exception handler would. This exception frame, built by the kernel as we saw in an earlier section, contains the actual entry point of the application. Therefore, because the loader doesn't use a standard call or jump into the running application, you'll never see the loader initialization functions as part of the call tree in a stack trace for a thread.

### **EXPERIMENT:** Watching the image loader

In this experiment, you'll use global flags to enable a debugging feature called *loader snaps*. This allows you to see debug output from the image loader while debugging application startup.

- **1.** From the directory where you've installed WinDbg, launch the Gflags.exe application, and then click the **Image File** tab.
- 2. In the Image field, type **Notepad.exe**, and then press the **Tab** key. This should enable the various options. Select the **Show Loader Snaps** option and then click **OK** or **Apply**.
- 3. Now launch WinDbg, open the File menu, choose Open Executable, and navigate to c:\windows\system32\notepad.exe to launch it. You should see a couple of screens of debug information similar to that shown here:

```
0f64:2090 @ 02405218 - LdrpInitializeProcess - INFO: Beginning execution of
notepad.exe (C:\WINDOWS\notepad.exe)
Current directory: C:\Program Files (x86)\Windows Kits\10\Debuggers\
Package directories: (null)
0f64:2090 @ 02405218 - LdrLoadDll - ENTER: DLL name: KERNEL32.DLL
0f64:2090 @ 02405218 - LdrpLoadDllInternal - ENTER: DLL name: KERNEL32.DLL
0f64:2090 @ 02405218 - LdrpFindKnownDll - ENTER: DLL name: KERNEL32.DLL
0f64:2090 @ 02405218 - LdrpFindKnownDll - ENTER: DLL name: KERNEL32.DLL
```

```
Of64:2090 @ 02405218 - LdrpMinimalMapModule - ENTER: DLL name: C:\WINDOWS\
System32\KERNEL32.DLL
ModLoad: 00007fff'5b4b0000 00007fff'5b55d000 C:\WINDOWS\System32\KERNEL32.DLL
0f64:2090 @ 02405218 - LdrpMinimalMapModule - RETURN: Status: 0x00000000
0f64:2090 @ 02405218 - LdrpPreprocessDllName - INFO: DLL api-ms-win-core-
rtlsupport-l1-2-0.dll was redirected to C:\WINDOWS\SYSTEM32\ntdll.dll by API set
0f64:2090 @ 02405218 - LdrpFindKnownDll - ENTER: DLL name: KERNELBASE.dll
0f64:2090 @ 02405218 - LdrpFindKnownDll - RETURN: Status: 0x00000000
Of64:2090 @ 02405218 - LdrpMinimalMapModule - ENTER: DLL name: C:\WINDOWS\
System32\KERNELBASE.dll
ModLoad: 00007fff'58b90000 00007fff'58dc6000 C:\WINDOWS\System32\KERNELBASE.d11
0f64:2090 @ 02405218 - LdrpMinimalMapModule - RETURN: Status: 0x00000000
Of64:2090 @ 02405218 - LdrpPreprocessDllName - INFO: DLL api-ms-win-
eventing-provider-l1-1-0.dll was redirected to C:\WINDOWS\SYSTEM32\
kernelbase.dll by API set
0f64:2090 @ 02405218 - LdrpPreprocessDllName - INFO: DLL api-ms-win-core-
apiquery-l1-1-0.dll was redirected to C:\WINDOWS\SYSTEM32\ntdll.dll by API set
```

- 4. Eventually, the debugger breaks somewhere inside the loader code, at a location where the image loader checks whether a debugger is attached and fires a breakpoint. If you press the g key to continue execution, you will see more messages from the loader, and Notepad will appear.
- 5. Try interacting with Notepad and see how certain operations invoke the loader. A good experiment is to open the Save/Open dialog box. That demonstrates that the loader not only runs at startup, but continuously responds to thread requests that can cause *delayed loads* of other modules (which can then be unloaded after use).

## Early process initialization

Because the loader is present in Ntdll.dll, which is a native DLL that's not associated with any particular subsystem, all processes are subject to the same loader behavior (with some minor differences). Earlier, we took a detailed look at the steps that lead to the creation of a process in kernel mode, as well as some of the work performed by the Windows function CreateProcess. Here, we'll cover all the *other* work that takes place in user mode, independent of any subsystem, as soon as the first user-mode instruction starts execution.

When a process starts, the loader performs the following steps:

- It checks if LdrpProcessInitialized is already set to 1 or if the SkipLoaderInit flag is set in the TEB. In this case, skip all initialization and wait three seconds for someone to call LdrpProcess-InitializationComplete. This is used in cases where process reflection is used by Windows Error Reporting, or other process fork attempts where loader initialization is not needed.
- 2. It sets the LdrInitState to 0, meaning that the loader is uninitialized. Also set the PEB's ProcessInitializing flag to 1 and the TEB's RanProcessInit to 1.

- 3. It initializes the loader lock in the PEB.
- 4. It initializes the dynamic function table, used for unwind/exception support in JIT code.
- It initializes the Mutable Read Only Heap Section (MRDATA), which is used to store securityrelevant global variables that should not be modified by exploits (see Chapter 7 for more information).
- 6. It initializes the loader database in the PEB.
- 7. It initializes the National Language Support (NLS, for internationalization) tables for the process.
- 8. It builds the image path name for the application.
- **9.** It captures the SEH exception handlers from the .pdata section and builds the internal exception tables.
- **10.** It captures the system call thunks for the five critical loader functions: NtCreateSection, NtOpenFile, NtQueryAttributesFile, NtOpenSection, and NtMapViewOfSection.
- **11.** It reads the mitigation options for the application (which are passed in by the kernel through the LdrSystemDllInitBlock exported variable). These are described in more detail in Chapter 7.
- 12. It queries the Image File Execution Options (IFEO) registry key for the application. This will include options such as the global flags (stored in GlobalFlags), as well as heap-debugging options (DisableHeapLookaside, ShutdownFlags, and FrontEndHeapDebugOptions), loader settings (UnloadEventTraceDepth, MaxLoaderThreads, UseImpersonatedDeviceMap), ETW settings (TracingFlags). Other options include MinimumStackCommitInBytes and MaxDead-ActivationContexts. As part of this work, the Application Verifier package and related Verifier DLLs will be initialized and Control Flow Guard (CFG) options will be read from CFGOptions.
- **13.** It looks inside the executable's header to see whether it is a .NET application (specified by the presence of a .NET-specific image directory) and if it's a 32-bit image. It also queries the kernel to verify if this is a Wow64 process. If needed, it handles a 32-bit IL-only image, which does not require Wow64.
- **14.** It loads any configuration options specified in the executable's Image Load Configuration Directory. These options, which a developer can define when compiling the application, and which the compiler and linker also use to implement certain security and mitigation features such as CFG, control the behavior of the executable.
- **15.** It minimally initializes FLS and TLS.
- **16.** It sets up debugging options for critical sections, creates the user-mode stack trace database if the appropriate global flag was enabled, and queries StrackTraceDatabaseSizeInMb from the Image File Execution Options.
- **17.** It initializes the heap manager for the process and creates the first process heap. This will use various load configuration, image file execution, global flags, and executable header options to set up the required parameters.

- **18.** It enables the Terminate process on heap corruption mitigation if it's turned on.
- **19.** It initializes the exception dispatch log if the appropriate global flag has enabled this.
- **20.** It initializes the thread pool package, which supports the Thread Pool API. This queries and takes into account NUMA information.
- **21.** It initializes and converts the environment block and parameter block, especially as needed to support WoW64 processes.
- **22.** It opens the \KnownDlls object directory and builds the known DLL path. For a Wow64 process, \KnownDlls32 is used instead.
- **23.** For store applications, it reads the Application Model Policy options, which are encoded in the WIN://PKG and WP://SKUID claims of the token (see the "AppContainers" section in Chapter 7 for more information).
- 24. It determines the process's current directory, system path, and default load path (used when loading images and opening files), as well as the rules around default DLL search order. This includes reading the current policy settings for Universal (UWP) versus Desktop Bridge (Centennial) versus Silverlight (Windows Phone 8) packaged applications (or services).
- 25. It builds the first loader data table entry for Ntdll.dll and inserts it into the module database.
- 26. It builds the unwind history table.
- **27.** It initializes the parallel loader, which is used to load all the dependencies (which don't have cross-dependencies) using the thread pool and concurrent threads.
- **28.** It builds the next loader data table entry for the main executable and inserts it into the module database.
- 29. If needed, it relocates the main executable image.
- 30. If enabled, it initializes Application Verifier.
- **31.** It initializes the Wow64 engine if this is a Wow64 process. In this case, the 64-bit loader will finish its initialization, and the 32-bit loader will take control and re-start most of the operations we've just described up until this point.
- **32.** If this is a .NET image, it validates it, loads Mscoree.dll (.NET runtime shim), and retrieves the main executable entry point (\_CorExeMain), overwriting the exception record to set this as the entry point instead of the regular main function.
- **33.** It initializes the TLS slots of the process.
- 34. For Windows subsystem applications, it manually loads Kernel32.dll and Kernelbase.dll, regard-less of actual imports of the process. As needed, it uses these libraries to initialize the SRP/Safer (Software Restriction Policies) mechanisms, as well as capture the Windows subsystem thread initialization thunk function. Finally, it resolves any API Set dependencies that exist specifically between these two libraries.

- 35. It initializes the shim engine and parses the shim database.
- **36.** It enables the parallel image loader, as long as the core loader functions scanned earlier do not have any system call hooks or "detours" attached to them, and based on the number of loader threads that have been configured through policy and image file execution options.
- 37. It sets the LdrInitState variable to 1, meaning "import loading in progress."

At this point, the image loader is ready to start parsing the import table of the executable belonging to the application and start loading any DLLs that were dynamically linked during the compilation of the application. This will happen both for .NET images, which will have their imports processed by calling into the .NET runtime, as well as for regular images. Because each imported DLL can also have its own import table, this operation, in the past, continued recursively until all DLLs had been satisfied and all functions to be imported have been found. As each DLL was loaded, the loader kept state information for it and built the module database.

In newer versions of Windows, the loader instead builds a dependency map ahead of time, with specific nodes that describe a single DLL and its dependency graph, building out separate nodes that can be loaded in parallel. At various points when serialization is needed, the thread pool worker queue is "drained," which services as a synchronization point. One such point is before calling all the DLL initialization routines of all the static imports, which is one of the last stages of the loader. Once this is done, all the static TLS initializers are called. Finally, for Windows applications, in between these two steps, the Kernel32 thread initialization thunk function (BaseThreadInitThunk) is called at the beginning, and the Kernel32 post-process initialization routine is called at the end.

## DLL name resolution and redirection

Name resolution is the process by which the system converts the name of a PE-format binary to a physical file in situations where the caller has not specified or cannot specify a unique file identity. Because the locations of various directories (the application directory, the system directory, and so on) cannot be hardcoded at link time, this includes the resolution of all binary dependencies as well as LoadLibrary operations in which the caller does not specify a full path.

When resolving binary dependencies, the basic Windows application model locates files in a search path—a list of locations that is searched sequentially for a file with a matching base name—although various system components override the search path mechanism in order to extend the default application model. The notion of a search path is a holdover from the era of the command line, when an application's current directory was a meaningful notion; this is somewhat anachronistic for modern GUI applications.

However, the placement of the current directory in this ordering allowed load operations on system binaries to be overridden by placing malicious binaries with the same base name in the application's current directory, a technique often known as *binary planting*. To prevent security risks associated with this behavior, a feature known as *safe DLL search mode* was added to the path search computation and is enabled by default for all processes. Under safe search mode, the current directory is moved behind the three system directories, resulting in the following path ordering:

- 1. The directory from which the application was launched
- 2. The native Windows system directory (for example, C:\Windows\System32)
- 3. The 16-bit Windows system directory (for example, C:\Windows\System)
- 4. The Windows directory (for example, C:\Windows)
- 5. The current directory at application launch time
- 6. Any directories specified by the %PATH% environment variable

The DLL search path is recomputed for each subsequent DLL load operation. The algorithm used to compute the search path is the same as the one used to compute the default search path, but the application can change specific path elements by editing the %PATH% variable using the SetEnviron-mentVariable API, changing the current directory using the SetCurrentDirectory API, or using the SetD11Directory API to specify a DLL directory for the process. When a DLL directory is specified, the directory replaces the current directory in the search path and the loader ignores the safe DLL search mode setting for the process.

Callers can also modify the DLL search path for specific load operations by supplying the LOAD\_ WITH\_ALTERED\_SEARCH\_PATH flag to the LoadLibraryEx API. When this flag is supplied and the DLL name supplied to the API specifies a full path string, the path containing the DLL file is used in place of the application directory when computing the search path for the operation. Note that if the path is a relative path, this behavior is undefined and potentially dangerous. When Desktop Bridge (Centennial) applications load, this flag is ignored.

Other flags that applications can specify to LoadLibraryEx include LOAD\_LIBRARY\_SEARCH\_DLL\_ LOAD\_DIR, LOAD\_LIBRARY\_SEARCH\_APPLICATION\_DIR, LOAD\_LIBRARY\_SEARCH\_SYSTEM32, and LOAD\_ LIBRARY\_SEARCH\_USER\_DIRS, in place of the LOAD\_WITH\_ALTERED\_SEARCH\_PATH flag. Each of these modifies the search order to only search the specific directory (or directories) that the flag references, or the flags can be combined as desired to search multiple locations. For example, combining the application, system32, and user directories results in LOAD\_LIBRARY\_SEARCH\_DEFAULT\_DIRS. Furthermore, these flags can be globally set using the SetDefaultD11Directories API, which will affect all library loads from that point on.

Another way search-path ordering can be affected is if the application is a packaged application or if it is not a packaged service or legacy Silverlight 8.0 Windows Phone application. In these conditions, the DLL search order will not use the traditional mechanism and APIs, but will rather be restricted to the package-based graph search. This is also the case when the LoadPackagedLibrary API is used instead of the regular LoadLibraryEx function. The package-based graph is computed based on the <Pack-ageDependency> entries in the UWP application's manifest file's <Dependencies> section, and guarantees that no arbitrary DLLs can accidentally load in the package.

Additionally, when a packaged application is loaded, as long as it is not a Desktop Bridge application, all application-configurable DLL search path ordering APIs, such as the ones we saw earlier, will be disabled, and only the default system behavior will be used (in combination with only looking through package dependencies for most UWP applications as per the above). Unfortunately, even with safe search mode and the default path searching algorithms for legacy applications, which always include the application directory first, a binary might still be copied from its usual location to a user-accessible location (for example, from c:\windows\system32\notepad.exe into c:\temp\notepad.exe, an operation that does not require administrative rights). In this situation, an attacker can place a specifically crafted DLL in the same directory as the application, and due to the ordering above, it will take precedence over the system DLL. This can then be used for persistence or otherwise affecting the application, which might be privileged (especially if the user, unaware of the change, is elevating it through UAC). To defend against this, processes and/or administrators can use a process-mitigation policy (see Chapter 7 for more information on these) called Prefer System32 Images, which inverts the order above between points 1 and 2, as the name suggests.

#### **DLL** name redirection

Before attempting to resolve a DLL name string to a file, the loader attempts to apply DLL name redirection rules. These redirection rules are used to extend or override portions of the DLL namespace which normally corresponds to the Win32 file system namespace—to extend the Windows application model. In order of application, these are:

- MinWin API Set redirection The API set mechanism is designed to allow different versions or editions of Windows to change the binary that exports a given system API in a manner that is transparent to applications, by introducing the concept of contracts. This mechanism was briefly touched upon in Chapter 2, and will be further explained in a later section.
- LOCAL redirection The .LOCAL redirection mechanism allows applications to redirect all loads of a specific DLL base name, regardless of whether a full path is specified, to a local copy of the DLL in the application directory—either by creating a copy of the DLL with the same base name followed by .local (for example, MyLibrary.dll.local) or by creating a file folder with the name .local under the application directory and placing a copy of the local DLL in the folder (for example, C:\MyApp\.LOCAL\MyLibrary.dll). DLLs redirected by the .LOCAL mechanism are handled identically to those redirected by SxS. (See the next bullet point.) The loader honors .LOCAL redirection of DLLs only when the executable does not have an associated manifest, either embedded or external. It's not enabled by default. To enable it globally, add the DWORD value DevOverrideEnable in the base IFEO key (HKLM\Software\Microsoft\WindowsNT\CurrentVersion\Image File Execution Options) and set it to 1.
- Fusion (SxS) redirection Fusion (also referred to as *side-by-side*, or SxS) is an extension to the Windows application model that allows components to express more detailed binary dependency information (usually versioning information) by embedding binary resources known as *manifests*. The Fusion mechanism was first used so that applications could load the correct version of the Windows common controls package (comctl32.dll) after that binary was split into different versions that could be installed alongside one another; other binaries have since been versioned in the same fashion. As of Visual Studio 2005, applications built with the Microsoft linker use Fusion to locate the appropriate version of the C runtime libraries, while Visual Studio 2015 and later use API Set redirection to implement the idea of the universal CRT.

The Fusion runtime tool reads embedded dependency information from a binary's resource section using the Windows resource loader, and it packages the dependency information into lookup structures known as *activation contexts*. The system creates default activation contexts at the system and process level at boot and process startup time, respectively; in addition, each thread has an associated activation context stack, with the activation context structure at the top of the stack considered active. The per-thread activation context stack is managed both explicitly, via the ActivateActCtx and DeactivateActCtx APIs, and implicitly by the system at certain points, such as when the DLL main routine of a binary with embedded dependency information is called. When a Fusion DLL name redirection lookup occurs, the system searches for redirection information in the activation context at the head of the thread's activation context stack, followed by the process and system activation contexts; if redirection information is present, the file identity specified by the activation context is used for the load operation.

Known DLL redirection Known DLLs is a mechanism that maps specific DLL base names to files in the system directory, preventing the DLL from being replaced with an alternate version in a different location.

One edge case in the DLL path search algorithm is the DLL versioning check performed on 64bit and WoW64 applications. If a DLL with a matching base name is located but is subsequently determined to have been compiled for the wrong machine architecture—for example, a 64bit image in a 32-bit application—the loader ignores the error and resumes the path search operation, starting with the path element after the one used to locate the incorrect file. This behavior is designed to allow applications to specify both 64-bit and 32-bit entries in the global %PATH% environment variable.

### **EXPERIMENT: Observing DLL load search order**

You can use Sysinternals Process Monitor tool to watch how the loader searches for DLLs. When the loader attempts to resolve a DLL dependency, you will see it perform CreateFile calls to probe each location in the search sequence until either it finds the specified DLL or the load fails.

Here's the capture of the loader's search for the OneDrive.exe executable. To re-create the experiment, do the following:

- 1. If the OneDrive is running, close it from its tray icon. Make sure to close all Explorer windows that are looking at OneDrive content.
- 2. Open Process Monitor and add filters to show just the process OneDrive.exe. Optionally, show only the operation for CreateFile.
- Go to %LocalAppData%\Microsoft\OneDrive and launch OneDrive.exe or OneDrive Personal.cmd (which launches OneDrive.exe as "personal" rather than "business"). You should see something like the following (note that OneDrive is a 32 bit process, here running on a 64 bit system):

Image: Control of the second state of the s	ile i	Edit	Event	Filter	Tool	: 0	otions	Help								
137035765/ml         Complexe xm         508         28772         CheckeFile         C/Windows         C/Windows         State         Desired A           1337035765/ml         Complexe xm         508         28772         A.CheareFile         C/Windows         NAME NOT FOUND Desired A           133703577577         Complexe xm         5208         28772         A.CheareFile         C/Windows         SUCCESS         Desired A           13370357757         Complexe xm         5208         28772         A.CheareFile         C/Windows         SUCCESS         Desired A           133703587747         Complexe xm         5208         28772         A.CheareFile         C/Windows', SyWWWF4/ums2,dl         SUCCESS         Desired A           133703587746         Complexe xm         5208         28772         A.CheareFile         C/Windows', SyWWWF4/ums2,dl         SUCCESS         Desired A           133703587746         Complexe xm         5208         28772         A.CheareFile         C/Windows', SyWWWF4/ums2,dl         SUCCESS         Desired A           133703587576         Complexe xm         5208         28772         A.CheareFile         C/Windows', SyWWWF4/uss2,dl         SUCCESS         Desired A           133703587576         ComareFile         C/Windows', SyWWWF4/uss2,d	21								1	M 15		*	14	a 🖪		
13/20/20/27/20         Constrile         C:Windowi System32:work46g/gil         NAME NOT FOUND Desired A           13/20/20/27/20         Constrile         C:Windowi System32:work46g/gil         Name Found System32:work46g/gil           13/20/20/27/21         Constrile         C:Windowi System32:work46g/gil         SUCCESS         Desired A           13/20/20/20/20         Constrile         C:Windowi System32:work46g/gil         SUCCESS         Desired A           13/20/20/20/27         Constrile         C:Windowi System32:work46ez32:dl         SUCCESS         Desired A           13/20/20/20/27         Constrile         C:Windowi System32:work46ez32:dl         SUCCESS         Desired A           13/20/20/20/27         Constrile         C:Windowi System32:work46ez32:dl         SUCCESS         Desired A           13/20/20/20/27         Constrile         C:Windowi SyW		Tim	e of Day	Proc	ess Nam	е	PID		TID	Operat	lon		Path	h Result	Detail	
132703         Strömbre ave 32702         Schederfie 2002         C/Windows 2002         Success 2002         Success 2002         Success 2002         Berrier A Success 2002         Success 2002	13:3	7 03 5	5726726	770	ne@rive.e	DIB.	6208					1			Deared A	Acces
13.370.3585964         Charatelie         C:\Laer:\Local\Monexthink_DepUtat.Local\MonexthineDrue         SUCCESS         Desired A           13.370.3587576         MoneDrue exe         528         28772         J.CreateFile         C:\Windows\SyNWOW4Furm32.dl         SUCCESS         Desired A           13.370.3587765         MoneDrue exe         528         28772         J.CreateFile         C:\Windows\SyNWOW4Furm32.dl         SUCCESS         Desired A           13.370.3587746         MoneDrue exe         528         28772         J.CreateFile         C:\Windows\SyNWOW4Furm32.dl         SUCCESS         Desired A           13.370.3587746         MoneDrue exe         528         28772         J.CreateFile         C:\Windows\SyNWOW4Furm32.dl         SUCCESS         Desired A           13.370.3587777         MonetPreue         528         28772         J.CreateFile         C:\Windows\SyNWOW4Fuebal2.2dl         SUCCESS         Desired A           13.370.3587577         MonetPreue         528         28772         J.CreateFile         C:\Windows\SyNWOW4Fuebal2.2dl         SUCCESS         Desired A           13.370.3587575         MoneDrue exe         528         28772         J.CreateFile         C:\WeneYADMINkpopDtat Local\Wincreath'OneDrue'NT3.5743.1212.LoggingPlatform.dl         SUCCESS         Desired A           13.37	13:3	7:03.5	5745968	- Or	e Drive a	DIE							C:\W			
13/37/03/23114         Combare served         S202         27/27         Constantine         C:Windows (SyNUOWE4/wm32 di         SUCCESS         Desired A           13/37/03/237/26         Constantine         C:Windows (SyNUOWE4/wm32 di         SUCCESS         Desired A           13/37/03/237/26         Constantine         C:Windows (SyNUOWE4/wm32 di         SUCCESS         Desired A           13/37/03/237/26         Constantine         C:Windows (SyNUOWE4/wm32 di         SUCCESS         Desired A           13/37/03/237/27         Constantine         C:Windows (SyNUOWE4/selesd 2 di         SUCCESS         Desired A           13/37/03/237/27         Constantine         C:Windows (SyNUOWE4/selesd 2 di         SUCCESS         Desired A           13/37/03/237/26         Constantine         C:Windows (SyNUOWE4/selesd 2 di         SUCCESS         Desired A           13/37/03/237/26         Constantine         C:Windows (SyNUOWE4/selesd 2 di         SUCCESS         Desired A           13/37/03/237/26         Constantine         C:Windows (SyNUOWE4/selesd 2 di         NAME NOT FOUND         Desired A           13/37/03/237/26         Constantine         C:Windows (SyNUOWE4/selesd 2 di         NAME NOT FOUND         Desired A           13/37/03/37/26         Constantine         C:Windows (SyNUOWE4/selesd 2 di         NAME NOT FOUND																
13:70:3527309         Constraine         5208         2772         Constraine         C/Window/SynWOWE4/wm32.dl         SUCCESS         Desired A           13:70:3527366         whorehove sss         6208         2772         Constrike         C/Window/SynWOWE4/wm32.dl         SUCCESS         Desired A           13:70:3527366         whorehove sss         6208         2772         Constrike         C/Window/SynWOWE4/wm32.dl         SUCCESS         Desired A           13:70:3527366         whorehove sss         6208         2772         Constrike         C/Window/SynWOWE4/west2.dl         SUCCESS         Desired A           13:70:3527366         whorehove sss         6208         2772         Constrike         C/Window/SynWOWE4/west2.dl         SUCCESS         Desired A           13:70:355756         whorehove sss         6208         2772         Constrike         C/Window/SynWOWE4/west2.dl         SUCCESS         Desired A           13:70:355756         whorehove sss         6208         2772         Constrike         C/Window/SynWOWE4/west2.dl         SUCCESS         Desired A           13:70:3507567         whorehove sss         6208         2776         Constrike         C/Window/SynWOWE4/west2.dl         NAME NOT FOUND Desired A           13:70:3707627         whorehove sss	13:3	7:03.5	5809647	- Or	eDrive a	000	6208						C:\U	Isers\ADMIN\AppData\Local\Microsoft\OneDrive SUCCESS	Desired A	Acces
13.703.8257126         44.On-Dhive see         528         2772         3.Onestefile         C.Window SynWOW44/um32.dl         SUCCESS         Desired A           13.370.8257126         44.OneDhive see         528         23772         3.Onestefile         C.Window SynWOW44/um32.dl         SUCCESS         Desired A           13.370.8257146         44.OneDhive see         528         23772         3.Onestefile         C.Window SynWOW44/uess12.dl         SUCCESS         Desired A           13.370.8257127         4.Onebhive see         528         23772         3.Onestefile         C.Window SynWOW44/uess12.dl         SUCCESS         Desired A           13.370.825757         4.Onebhive see         528         23772         3.Onestefile         C.Users VJDINI AppData Local Microset/OneDrev VI3.5743.1212 Logging/Reform.dl         SUCCESS         Desired A           13.370.855575         4.Onebhive see         628         2175         3.Onestefile         C.Users VJDINI VappData Local Microset/OneDrev VI3.5743.1212 Logging/Reform.dl         NAME NOT FOUND         Desired A           13.370.85575         4.Onebhive see         628         2776         3.Onestefile         C.Users VJDINIV VappData Local Microset/OneDrev VI3.5743.1212 Logging/Reform.dl         NAME NOT FOUND         Desired A           13.370.857256         4.Onestefile         C.Users VJDINIV VappData	13:3	7:03.6	5215721	ALC:	Drive e	000	6208	28					C:\W	Vindows\SysWOW64\mm32.dll SUCCESS	Desired /	Acces
13/30/18/27440         Components         S202         22772         Constellie         C. Windown SystWOWK4 kemn32 dl         SUCCESS         Desired A           13/30/18/27440         Chondbrie sam         6208         28772         S. CreateFile         C. Windown SystWOWK4 keeda 22 dl         SUCCESS         Desired A           13/30/18/18/46         Chondbrie sam         6208         28772         S. CreateFile         C. Windown SystWOWK4 keeda 22 dl         SUCCESS         Desired A           13/30/18/57/27         All-CreateFile         C. Ulaeri ADMINI AppData Local Microadh Une Drive \17.3.6743.1212 LoggingPlatform.dl         SUCCESS         Desired A           13/30/18/57/27         All-CreateFile         C. Ulaeri ADMINI AppData Local Microadh Une Drive \17.3.6743.1212 LoggingPlatform.dl         SUCCESS         Desired A           13/30/18/57/27         All-CreateFile         C. Ulaeri ADMINI AppData Local Microadh Une Drive \17.3.6743.1212 LoggingPlatform.dl         SUCCESS         Desired A           13/30/18/57/27         All-CreateFile         C. Ulaeri ADMINI AppData Local Microadh Une Drive \17.3.6743.1212 LoggingPlatform.dl         SUCCESS         Desired A           13/30/18/57/27         All-CreateFile         C. Ulaeri ADMINI AppData Local Microadh Une Drive \17.3.6743.1212 MissOCK32 dl         NAME NOT FOUND         Desired A           13/30/18/30/274         MonDrive sam         62	13:3	7:03.6	5227305	-0r	Drive	900							C:\W		Desired A	Acces
13:70:35811644         44.On-Dhrve area         5202         2772         3.OncetaFile         C.Window SyrWOWE4 desu2.2.dl         SUCCESS         Desired A           13:70:13:511645         44.On-Dhrve area         5208         2772         3.OncetaFile         C.Window SyrWOWE4 desu2.2.dl         SUCCESS         Desired A           13:70:13:511645         40.On-Dhrve area         5208         2772         3.OncetaFile         C.Ulaers/VOMIN/AppDtat Local/Microsoft/OneDrev/17.3.5743.1212.LogsinpPlatform.dl         SUCCESS         Desired A           13:70:13:515575         40.On-Dhrve area         5208         2772         3.OncetaFile         C.Ulaers/VOMIN/AppDtat Local/Microsoft/OneDrev/17.3.5743.1212.LogsinpPlatform.dl         SUCCESS         Desired A           13:70:13:51575         40.On-Dhrve area         5208         2776         3.OncetaFile         C.Ulaers/VOMIN/AppDtat Local/Microsoft/OneDrev/MS/CPI2.0.dl         NAME NOT FOUND         Desired A           13:70:10:703576         40.OncetaFile         C.Ulaers/VOMIN/AppDtat Local/Microsoft/OneDrev/MS/CPI2.0.dl         NAME NOT FOUND         Desired A           13:70:10:703576         40.OncetaFile         C.Ulaers/VOMIN/AppDtat Local/Microsoft/OneDrev/17.3.5743.1212 micror120.dl         SUCCESS         Desired A           13:70:10:703776         40.OncetaFile         C.Ulaers/VOMIN/AppDtat Local/Microsoft/OneDrev/17.3.5743.1212 micror120.dl	13.3	7:03.6	5257126	-	Drive e	sxe.	6208						C:\W		Desired A	Acces
13:70:35841086         40:no Dive em         520         2772         30:notatile         C:Window SynVOW64/eds2.dll         SUCCESS         Deserd A           13:70:3587504         40:no Dive em         5208         28772         30:cetatile         C:Window SynVOW64/eds2.dll         SUCCESS         Deserd A           13:70:35857504         40:no Dive em         5208         28772         30:cetatile         C:Window SynVOW64/eds2.dll         NAHE NOT FOUND         Deserd A           13:70:35857504         40:one Dive em         5208         28772         30:cetatile         C:Window YonVApo Data Local Microsoft/One Dive/\17.3.5743.1212.LoggingPlatform.dll         NAHE NOT FOUND         Deserd A           13:70:30:30210150         40:one Dive em         5208         20775         30:creatile         C:Window YonVApo Data Local Microsoft/One Dive/\17.3.5743.1212.WSOCK32.dl         NAHE NOT FOUND         Deserd A           13:70:370:370244         40:one Dive em         5208         20775         30:creatile         C:Window YonVVVVAVapo Data Local Microsoft/One Dive/\17.3.5743.1212.WSOCK32.dl         NAHE NOT FOUND         Deserd A           13:70:370:370244         40:one Dive em         5208         20776         30:creatile         C:Window YonVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVVV	13:3	7:03.6	5273460	ALC:	Drive.e	me	6208	28	772	Crea	teFile	2	C:\W	Vindows\SysWOW64\imm32.dl SUCCESS	Desired A	Acces
13:703 555527         Chondhrve ava         5208         25772         Schedelike         C:\Users \u00001 \u0000 \u00000 \u0000 \u0000 \	13:3	7:03.6	6816494	-COr	Drive e	908	6208	28	772	Crea	teFile	2	C:\W	Vindows\SysWOW64\oleaut32.dl SUCCESS	Desired A	Acces
1373035857534         440-nohwe awa         528         23772         337043172         33704         3724         1272 Logging/Reform         UNIX           133703         33703         528         23772         33704         2172 August         32703         33704         3724         1272 Logging/Reform         UNIX         NAME NOT FOUND Desired A           133703         33703         7001592         440/neb/ne awa         528         2775         30 CreateFile         C:\Usen' ADMINI AppData' Local Microach/One-Drive/MSVCR120 dl         NAME NOT FOUND Desired A           133703         7001592         440/neb/ne awa         528         2775         30 CreateFile         C:\Usen' ADMINI AppData' Local Microach/One/Nev/MSVCR120 dl         NAME NOT FOUND Desired A           133703         70015924         440/neb/ne awa         528         2775         30 CreateFile         C:\Usen' ADMINI AppData' Local Microach/One/Nev/17.3 5743 1212 WSOCK32 dl         NAME NOT FOUND Desired A           133703         70015924         440/neb/ne awa         528         2776         30 CreateFile         C:\Usen' ADMINI AppData' Local Microach/One/Nev 17.3 5743 1212 WSOCK32 dl         SUCCESS         Desired A           133703         70015924         40/neb/ne awa         6208         2776         30 CreateFile         C:\Usen' ADMINI AppData' Local Microach/One	13.3	7:03.6	5841086	ALOr	eDrive.e	soe.	6208	28	772	Crea	deFile	2	C:\W	Vindows\SysWOW64\ole32.dl SUCCESS	Desired A	Acces
13:37:03:3999755         40-DnDrve am         5208         115:21         Chutteri VDMIN-AppLitat Local-Microsoft One Drive VMSVCP120.dl         NAME NOT FOUND         Desired A           13:37:03:7001590         40-DnDrve am         5208         2776         30-CreateFile         C-Ulaeri VDMIN-AppLitat Local-Microsoft One Drive VMSVCP120.dl         NAME NOT FOUND         Desired A           13:37:03:7001590         40-DnDrve am         5208         2776         30-CreateFile         C-Ulaeri VDMIN-AppLitat Local-Microsoft One Drive VMSVCP120.dl         NAME NOT FOUND Desired A           13:37:03:7001590         40-One Drive am         5208         2776         30-CreateFile         C-Ulaeri VDMIN-AppLitat Local-Microsoft One Drive V17.3 5743 1212 (micro120.dl         SUCCESS         Desired A           13:37:03:701250         40-CreateFile         C-Ulaeri VDMIN/AppLitat Local-Microsoft One Drive V17.3 5743 1212 (micro120.dl         SUCCESS         Desired A           13:37:03:701250         40-CreateFile         C-Ulaeri VDMIN/AppLitat Local-Microsoft One Drive V17.3 5743 1212 (micro120.dl         SUCCESS         Desired A           13:37:03:701254         40-CreateFile         C-Ulaeri VDMIN/AppLitat Local-Microsoft One Drive V17.3 5743 1212 (micro120.dl)         SUCCESS         Desired A           13:37:03:71873         40-CreateFile         C-Ulaeri VDMIN/AppLitat Local-Microsoft One Drive V17.3 5743 1212 (micro120.dl)         SUCCESS	13.3	7:03.6	5955727	-COr	eDrive.e	808	6208	28	772	Crea	teFile	2	C:\U	Isers\ADMIN\AppData\Local\Microsoft\OneDrive\17.3.6743.1212\LoggingPlatform.dl SUCCESS	Desired A	Acces
13:730.700122         4Condbree and Gondbree and 33:700.700150         4Condbree and Gondbree and 4Condbree and 33:700.700150         4Condbree and Gondbree and 4Condbree and 33:700.700150         4Condbree and 4Condbree an	13.3	7:03.6	5967504	1 AD	eDrive.e	908	6208	28	772	Crea	teFile	9	C:\U	sers\ADMIN\AppData\Local\Microsoft\OneDrive\17.3.6743.1212\LoggingPlatform.dl SUCCESS	Desired A	Acces
13:373:3701150         40:netDive are available         528         2077         30:netaFile         C:\User:\Uper\Uper\Uper\Uper\Uper\Uper\Uper\Uper	13:3	7:03.6	5996755	Or	eDrive e	exe	6208	11	532	Crea	teFile		C:\U	kers\ADMIN\AppData\Local\Microsoft\OneDrive\MSVCR120.dl NAME.NOT.FOUND	Desired A	Acces
1373233208826         40-mb/we aw         528         20776         30-createFile         C:\Leer\XDMIN\AppDitat.Local\MicrosoftOneDire\17.35743.1212\wworl20.dl         NUME NOT FOUND Desired A           13370337023726         40-mb/we aw         5208         21776         30-createFile         C:\Leer\XDMIN\AppDitat.Local\MicrosoftOneDire\17.35743.1212\wworl20.dl         SUCCESS         Desired A           1337037022542         40-mb/we aw         5208         21776         30-createFile         C:\Leer\XDMIN\AppDitat.Local\MicrosoftOneDire\17.35743.1212\wworl20.dl         SUCCESS         Desired A           1337037022542         40-mb/we aw         5208         20776         30-createFile         C:\Weer\XDMIN\AppDitat.Local\MicrosoftOneDire\17.36743.1212\wworl20.dl         SUCCESS         Desired A           1337037023787         40-mb/we aw         5208         20776         30-createFile         C:\Weer\XDMIN\AppDitat.Local\MicrosoftOneDire\17.36743.1212\wworl20.dl         SUCCESS         Desired A           1337037037887         40-mb/we aw         6208         2772         30-createFile         C:\Weer\XDMIN\AppDitat.Local\MicrosoftOneDire\17.36743.1212\wworl20.dl         NUME NOT FOUND         SUCCESS         Desired A           13370377873786         40-mb/we aw         6208         2772         30-createFile         C:\Weer\XDMIN\AppDitat.Local\MicrosoftOneDire\17.36743.1212\woworl20.dl         NUME NO	13:3	7:03.7	7001021	-0r	e Drive e	908	6208	27	400	Crea	teFile	3	C:\U	Isers\ADMIN\AppData\Local\Microsoft\OneDrive\MSVCP120.dl NAME NOT FOUND	Desired A	Acces
13.3703.3705234         4.6.OneDive errs         528         153.2         Densitie         C:\Users\dDMI\AppCtat.Local\MicrosoftOneDive\17.3.5743.1212/micros12.01         SUCCESS         Deared A           13.3703.3703244         46.OneDive errs         528         2776         3.CreateFile         C.\Users\dDMI\AppCtat.Local\MicrosoftOneDive\17.3.5743.1212/micros12.01         SUCCESS         Deared A           13.3703.3723424         46.OneDive errs         528         2776         3.CreateFile         C.\Users\dDMI\AppCtat.Local\MicrosoftOneDive\17.3.5743.1212/micros12.01         SUCCESS         Deared A           13.3703.37334         46.OneDive errs         528         2776         3.CreateFile         C.\Users\dDMI\AppCtat.Local\Microsoft\OneDive\17.3.5743.1212/micros12.01         SUCCESS         Deared A           13.3703.73734         46.OneDive errs         528         2776         3.CreateFile         C.\Users\dDMI\AppCtat.Local\Microsoft\OneDive\17.3.5743.1212/micros12.01         SUCCESS         Deared A           13.3703.715336         46.OneDive errs         528         2772         3.CreateFile         C.\Users\dDMI\AppCtat.Local\Microsoft\OneDive\17.3.5743.1212/micros12.01         NAME NOT FOUND         Deared A           13.3703.715336         46.OneDive errs         528         2772         3.CreateFile         C.\Users\dDMI\AppDtat.Local\Microsoft\OneDive\17.3.5743.1212/CRYPTSP.dI         NAME	13:3	7:03.7	7001950	-	eDrive e	800	6208	20	776	Crea	teFile	3	C:\U	Isers\ADMIN\AppData\Local\Microsoft\OneDrive\WSOCK32.dl NAME NOT FOUND	Desired /	Acces
13:70:37017220         4:GoneDrive exe         5208         27400         3:CreateFile         C:\User\VDMI\AppClat.\Local\MicroadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVOneDrive\\7.3.6743.1212\microadVONED\\00000\\00000\\00000\\00000\\00000\\0000	13:3	7:03.7	7008826	- CO	eDrive e	boe	6208	20	776	Crea	teFile		C:\U	Isers\ADMIN\AppData\Local\Microsoft\OneDrive\17.3.6743.1212\WSOCK32.dl NAME.NOT.FOUND	Desired /	Acces
13.370.3702242         46-Dealbye area         528         277Fe         3.CreateFile         C.Window SysWOWE4-wasck22d         SUCCESS         Deared A           13.370.3703397         46-Dealbye area         5208         277Fe         3.CreateFile         C.Window SysWOWE4-wasck22d         SUCCESS         Deared A           13.370.3703397         46-Dealbye area         5208         277Fe         3.CreateFile         C.Window SysWOWE4-wasck22d         SUCCESS         Deared A           13.370.3703397         46-Dealbye area         5208         277Fe         3.CreateFile         C.Window SysWOWE4-wasck22d         SUCCESS         Deared A           13.370.3716520         46.DreB/bye area         5208         2772         3.CreateFile         C.Window SysWOWE4-wasch22d         Note Hill Not Deared A         SUCCESS         Deared A           13.370.3716520         46.DreB/bye area         5208         2772         3.CreateFile         C.Window SysWOWE4-wasptb d         NAME NOT FOUND Deared A           13.370.3716530         46.DreB/bye area         5208         2772         3.CreateFile         C.Window SysWOWE4-wasptb d         SUCCESS         Deared A           13.370.3716304         46.DreB/bye area         5208         2772         3.CreateFile         C.Window SysWOWE4-wasptb d         SUCCESS         Deared	13.3	7:03.3	7009294	-	eDrive e	200	6208	11	532	ACrea	deFile		C-VU	Isers\ADMIN\AppData\Local\Microsoft\OneDrive\17.3.6743.1212\msvcr120.dl SUCCESS	Desired A	Acces
13.730.703316         40.0mb/me ass         5208         1152         Densite file         C:\Users\UDMIN\App.Dist.Local\Microsoft\One_Dire\17.3.6743.1212/mevc120.dl         SUCCESS         Densite A           13.370.7033734         40.0mb/me ass         5208         20776         B.CreateFile         C:\Users\UDMIN\App.Dist.Local\Microsoft\One_Dire\17.3.6743.1212/mevcp120.dl         SUCCESS         Densite A           13.370.7033734         40.0mb/me ass         5208         20776         B.CreateFile         C:\Users\UDMIN\App.Dist.Local\Microsoft\One_Dire\17.3.6743.1212/mevcp120.dl         SUCCESS         Densite A           13.370.7187202         40.0mb/me ass         5208         2772         S.CreateFile         C:\Users\UDMIN\App.Dist.Local\Microsoft\One_Dire\17.3.6743.1212/mevcp120.dl         SUCCESS         Densite A           13.370.718702         40.0mb/me ass         5208         2772         S.CreateFile         C:\Users\UDMIN\App.Dist.Local\Microsoft\One_Dire\17.3.6743.1212/mevcp120.dl         NAME NOT FOUND         Densite A           13.370.7184700         40.0mb/me ass         5208         2772         S.CreateFile         C:\Windown\SysWOWS4/reproto.dl         SUCCESS         Densite A           13.370.375184700         40.0mb/me ass         5208         2772         S.CreateFile         C:\Windown\SysWOWS4/reprot.dl         SUCCESS         Densite A <td< td=""><td>13.3</td><td>7:03.</td><td>7017280</td><td>-Or</td><td>Drive e</td><td>008</td><td>6208</td><td>27</td><td>400</td><td>ACrea</td><td>teFile</td><td></td><td>C.\U</td><td>sers\ADMIN\AppData\Local\Microsoft\OneDrive\17.3.6743.1212\msvcp120.dl SUCCESS</td><td>Desired A</td><td>Acces</td></td<>	13.3	7:03.	7017280	-Or	Drive e	008	6208	27	400	ACrea	teFile		C.\U	sers\ADMIN\AppData\Local\Microsoft\OneDrive\17.3.6743.1212\msvcp120.dl SUCCESS	Desired A	Acces
13.17.03.37.03392         Componence         S208         20776         S. CreateFile         C. Windows / SyM/OWE4 weexk3.201         SUCCESS         Desired A           13.37.03.370.370.0392         4G/netDive.see         5208         220776         3.CreateFile         C. Users / ADMIN / AppLata Local Microsoft / OneDive / CRYPTSP.dl         NAME NOT FOUND Desired A           13.37.03.370.6720         4G/netDive.see         5208         26772         3.CreateFile         C. Users / ADMIN / AppLata Local Microsoft / OneDive / CRYPTSP.dl         NAME NOT FOUND Desired A           13.37.03.370.6720         4G/netDive.see         5208         26772         3.CreateFile         C. Users / ADMIN / AppLata Local Microsoft / OneDive / CRYPTSP.dl         NAME NOT FOUND Desired A           13.37.03.370.56024         4G/netDive.see         5208         2772         3.CreateFile         C. Windows / SyM/OW 544 / corptst.dl         SUCCESS         Desired A           13.37.03.3725564         4G/netDive.see         5208         2772         3.CreateFile         C. Windows / SyM/OW 544 / corptst.dl         SUCCESS         Desired A           13.37.03.3725564         4G/netDive.see         5208         2772         3.CreateFile         C. Windows / SyM/OW 544 / corptst.dl         SUCCESS         Desired A           13.37.03.37325594         4G/netDive.see         5208         2772	13.3	7:03.7	7022642	-0r	Drive e	DOC	6208	20	776	ACres	deFile		C:\W	Vindows\SysWOW64\wsock32.dl SUCCESS	Desired A	Acces
13.3703.3703387         Componence         6208         27776         Schematelie         C:Windowi-(5):wV/0W44/wasch2.2dl         SUCCESS         Desired A           13.3703.3703387         40:OneDrive exec         6208         27776         Schematelie         C:Users/VOINtA/opDataLocal/Microsoft/OneDrive/CR/PTSP.dl         NAME NOT FOUND         Desired A           13.3703.37163720         40:OneDrive exec         6208         28772         Schematelie         C:Users/VOINtA/opDataLocal/Microsoft/OneDrive/CR/PTSP.dl         NAME NOT FOUND         Desired A           13.3703.7184720         40:OneDrive exec         6208         28772         Schematelie         C:Users/VOINtA/opDataLocal/Microsoft/OneDrive/CR/PTSP.dl         NAME NOT FOUND         Desired A           13.3703.7184700         40:OneDrive exec         6208         28772         Schematelie         C:Windown:SynVOWS4-rupsta; dl         SUCCESS         Desired A           13.3703.7184700         40:OneDrive exec         6208         28772         Scheatelie         C:Windown:SynVOWS4-rupsta; dl         SUCCESS         Desired A           13.3703.733282         40:OneDrive exec         6208         28772         Scheatelie         C:Windown:SynVOWS4-rupsta; dl         SUCCESS         Desired A           13.3703.733282         40:OneDrive exec         6208         28772         Sc	13.3	7:03.7	7033116	-0r	Drive e	sxe.	6208	11	532	ACres	deFile		C-\U	sers\ADMIN\AppData\Loca\\Microsoft\OneDrive\17.3.6743.1212\msvcr120.dl SUCCESS	Desired A	Acces
13.37.01.7163720         44.OneDirve.exe         6208         22772         Cheater Model         ADMINAppOlata Local/Microsoft/OneDirve/CRYPTSP.dl         NAME NOT FOUND Desired A           13.37.03.7163720         44.OneDirve.exe         6208         22772         OceaterFile         C/Literer V/DMIN/AppOlata Local/Microsoft/OneDirve/CRYPTSP.dl         NAME NOT FOUND Desired A           13.3703.718/700         44.OneDirve.exe         6208         22772         OceaterFile         C/Literer V/DMIN/AppOlata Local/Microsoft/OneDirve/CRYPTSP.dl         NAME NOT FOUND Desired A           13.3703.718/700         44.OneDirve.exe         6208         28772         OceaterFile         C/Windows/SyN/00/W64/kopstpp.dl         SUCCESS         Desired A           13.3703.7285564         44.OneDirve.exe         6208         28772         OceaterFile         C/Windows/SyN/00/W64/kopstpp.dl         SUCCESS         Desired A           13.3703.733288         44.OneDirve.exe         6208         28772         OceaterFile         C/Windows/SyN/00/W64/kopstp.dl         SUCCESS         Desired A           13.3703.733288         44.OneDirve.exe         6208         28772         OceaterFile         C/Window/SyN/00/W64/kasenh.dl         SUCCESS         Desired A           13.3703.7376186         44.OneDirve.exe         6208         24700         OceaterFile         C/Window/SyN/00/	13:3	7:03.7	7033897	ALOr	eDrive e	soe	6208	20	776	ACres	deFile				Desired A	Acces
13.370.37168720         4Condbre are         528         28772         Cheaterile         C:\Laesr\JOMIN\AppClat.Local\Microsoft\OneDrevCRYPTSP.dl         NAME NOT FOUND Desired A           13.370.37168720         4Condbre are         528         28772         Cheaterile         C:\Laesr\JOMIN\AppClat.Local\Microsoft\OneDrevCRYPTSP.dl         NAME NOT FOUND Desired A           13.370.37184700         4Condbre are         528         28772         Cheaterile         C:\Windows\SyNWOW64\crystp.dl         SUCCESs         Desired A           13.370.37184700         4Condbre are         528         28772         Cheaterile         C:\Windows\SyNWOW64\crystp.dl         SUCCESs         Desired A           13.370.3738289         4Condbre are         528         28772         Cheaterile         C:\Windows\SyNWOW64\crystp.dl         SUCCESs         Desired A           13.370.3738289         4Condbre are         528         28772         Cheaterile         C:\Windows\SyNWOW64\crystp.dl         SUCCESs         Desired A           13.370.3738289         4Condbre are         528         28772         Cheaterile         C:\Windows\SyNWOW64\crystp.dl         SUCCESs         Desired A           13.370.3738289         4Condbre are         528         28772         Cheaterile         C:\Windows\SyNWOW64\crystp.dl         SUCCESs         Desired A							6208								Desired A	Acces
133703.776356         40-neDive.exe         528         2872         3-CreateFile         C:\Userv\DMIN\AppData.Local\Microsoft\OneDive\\17.3.6743.1212\CRYPTSP.dl         NAME NOT FOUND Desired A           133703.776356         40-neDive.exe         528         2872         3-CreateFile         C:\Windows\SyNVOW64\cryptsp.dl         SUCCESS         Desired A           133703.776356         46-OneDive.exe         528         28772         3-CreateFile         C:\Windows\SyNVOW64\cryptsp.dl         SUCCESS         Desired A           133703.7764576         46-OneDive.exe         528         28772         3-CreateFile         C:\Windows\SyNVOW64\cryptsp.dl         SUCCESS         Desired A           133703.7764576         46-OneDive.exe         528         28772         3-CreateFile         C:\Windows\SyNVOW64\createrHa         SUCCESS         Desired A           133703.776551         46-OneDive.exe         528         28772         3-CreateFile         C:\Windows\SyNVOW64\createrHa         SUCCESS         Desired A           133703.776551         46-OneDive.exe         528         24700         3-CreateFile         C:\Windows\SyNVOW64\createrHa         SUCCESS         Desired A           133703.776565         46-OneDive.exe         528         24400         3-CreateFile         C:\Windows\SyNVOW64\createrHa         NAME NOT FOUND Desir	13.3	7.03.	7168720	-0r	eDrive e	xe	6208									
13/37/03/71847/0         4C) nearbine area         6208         28772         CheateFile         C:Windown:\9y/WOW64/usynte.dll         SUCCESS         Deared A           13/37/03/71847/0         4C) nearbine area         6208         28772         CheateFile         C:Windown:\SyWOW64/usynte.dll         SUCCESS         Deared A           13/37/03/72814/4         4C) nearbine area         6208         28772         CheateFile         C:Windown:\SyWOW64/uspat.dll         SUCCESS         Deared A           13/37/03/73144/2         4C) nearbine area         6208         28772         CheateFile         C:Windown:\SyWOW64/usenh.dl         SUCCESS         Deared A           13/37/03/7383289         4C) nearbine area         6208         28772         CheateFile         C:Windown:\SyWOW64/usenh.dl         SUCCESS         Deared A           13/37/03/7383289         4C) nearbine         C:Windown:\SyWOW64/usenh.dl         SUCCESS         Deared A           13/37/03/7376186	13.3	7.03.	7176336	-	eDrive e	see	6208	28	772	Crea	teFile				Desired A	Acces
13.3703.7205504         4%OneDrive awa         6208         28772         CreateFile         C:Windows/SyWW0%64 crystsp.dll         SUCCESS         Desired A           13.3703.7214342         4%OneDrive awa         6208         28772         CreateFile         C:Windows/SyWW0%64 crystsp.dll         SUCCESS         Desired A           13.3703.7214342         4%OneDrive awa         6208         28772         CreateFile         C:Windows/SyWW0%64 repsth and I         SUCCESS         Desired A           13.3703.73265513         4%OneDrive awa         6208         27400         CreateFile         C:Windows/SyWW0%64 repsth and I         SUCCESS         Desired A           13.3703.73265513         4%OneDrive awa         6208         27400         A/CreateFile         C:Windows/SyWW0%64 repsth Allocal/Microadth/OneDrive/bcrypt.dl         NAME NOT FOUND Desired A           13.3703.7376166         4%OneDrive awa         6208         27400         A/CreateFile         C:Windows/SyWW0%64 repsth Allocal/Microadth/OneDrive/tors/17.3.6743.1212/bcrypt.dl         NAME NOT FOUND Desired A           13.3703.7376166         4%OneDrive awa         6208         27400         A/CreateFile         C:Windows/SyWW0%64 repsth Allocal/Microadth/OneDrive/tors/17.3.6743.1212/bcrypt.dl         NAME NOT FOUND Desired A           13.3703.7376166         4%OneDrive awa         6208         27400 <t< td=""><td>13.3</td><td>7:03.7</td><td>7184700</td><td>-</td><td>eDrive a</td><td>exe</td><td>6208</td><td>28</td><td>772</td><td>Crea</td><td>teFile</td><td></td><td></td><td></td><td>Desired A</td><td>Acces</td></t<>	13.3	7:03.7	7184700	-	eDrive a	exe	6208	28	772	Crea	teFile				Desired A	Acces
13:37:03:7314342         4CheDhive awa         528         28772         CreateFile         C:Windowi-SysWOW64/vasenh dl         SUCCESS         Deared A           13:37:03:7314342         4CheDhive awa         5208         28772         CreateFile         C:Windowi-SysWOW64/vasenh dl         SUCCESS         Deared A           13:37:03:735513         4CheDhive awa         5208         28772         CreateFile         C:Windowi-SysWOW64/vasenh dl         SUCCESS         Deared A           13:37:03:735515         4CheDhive awa         5208         27400         CreateFile         C:Windowi-SysWOW64/vasenh dl         NAME NOT FOUND Deared A           13:37:03:73576156         4CheDhive awa         5208         27400         CreateFile         C:Windowi-SysWOW64/vasenh dl         NAME NOT FOUND Deared A           13:37:03:73576156         4CheDhive awa         5208         27400         CreateFile         C:Windowi-SysWOW64/vasenh Unacl/NoreDive \tracking Local/Microadh/UneDive\tracking Local/Mic	13:3	7:03.7	7205504	-	eDrive e	ne	6208	28	772	Crea	teFile				Desired A	Acces
13.3703.733289         Anne Drive ava         6208         28772         Anne Drive ava         6208         27400         Create File         C: Windows\SystWOW64/vsaenh dI         SUCCESS         Desired A           13.3703.7365513         4Anne Drive ava         6208         27400         Anne Create File         C: Users \ADMIN\App Data Local\Anne on the Drive borpt dI         NAME NOT FOUND Desired A           13.3703.73655         4Anne Drive ava         6208         27400         Anne on the Create File         C: \Users \ADMIN\App Data Local\Anne on the Drive borpt dI         NAME NOT FOUND Desired A           13.3703.736756         4Anne Drive ava         6208         27400         Anne the C: \Users \ADMIN\App Data Local\Anne on the Drive borpt dI         NAME NOT FOUND Desired A           13.3703.7380756         4Anne Drive ava         6208         27400         Anne the C: \Users \ADMIN\App Data Local\Anne on the Drive borpt dI         NAME NOT FOUND Desired A           13.3703.7380756         4Anne Drive ava         6208         27400         Anne the C: \Users \ADMIN\App Data Local\Anne on the Drive borpt dI         NAME NOT FOUND Desired A	13:3	7:03.7	7314342	60	e Drive e	008	6208								Desired A	Acces
1337037365513 Constitution of the same 5208 27400 CreateFile C-\Ulsers \ADMIN\AppData Loca\Microsoft\OneDive \borypt.dl NAME NOT FOUND Desired A 1337037276156 Control Control on the same same same same same same same sam	13:3	7:03.7	7333289	60r	e Drive e	DOB	6208	28	772	A Crea	teFile				Desired /	Acces
13:37:03.7376186 Concentre exe 5208 27400 Constelle C-Luees ADMIN AppBata Local Microsoft One Drive 17:3:5743.1212 borpt dl NAME NOT FOUND Deared A 13:37:03.7380785 Concentre exe 5208 27400 Constelle C-Lillero ADMIN AppBata Local Microsoft One Drive 17:3:5743.1212 borpt dl SUCCESS Deared A SUCCESS Deared A																
13:37:03.7380785 ConeDrive.exe 5208 27400 CreateFile C:\Windows\SysWOW64\bcrypt.dl SUCCESS Desired A																
							6208								Desired /	
13-37-03 7645028 CheeDrive even 5208 28772 Carrier File C:\Windows\Ginbaltzation\Sotton\Sotton\Sotton																

Here are some of the calls shown as they relate to the search order described previously:

- KnownDlls DLLs load from the system location (ole32.dll in the screenshot).
- LoggingPlatform.Dll is loaded from a version subdirectory, probably because OneDrive calls SetDllDirectory to redirect searches to the latest version (17.3.6743.1212 in the screenshot).
- The MSVCR120.dll (MSVC run time version 12) is searched for in the executable's directory, and is not found. Then it's searched in the version subdirectory, where it's located.
- The Wsock32.Dll (WinSock) is searched in the executable's path, then in the version subdirectory, and finally located in the system directory (SysWow64). Note that this DLL is not a KnownDll.

## Loaded module database

The loader maintains a list of all modules (DLLs as well as the primary executable) that have been loaded by a process. This information is stored in the PEB—namely, in a substructure identified by *Ldr* and called PEB\_LDR\_DATA. In the structure, the loader maintains three doubly linked lists, all containing the same information but ordered differently (either by load order, memory location, or initialization order). These lists contain structures called *loader data table entries* (LDR\_DATA\_TABLE\_ENTRY) that store information about each module.

Additionally, because lookups in linked lists are algorithmically expensive (being done in linear time), the loader also maintains two red-black trees, which are efficient binary lookup trees. The first is sorted by base address, while the second is sorted by the hash of the module's name. With these trees, the searching algorithm can run in logarithmic time, which is significantly more efficient and greatly speeds up process-creation performance in Windows 8 and later. Additionally, as a security precaution, the root of these two trees, unlike the linked lists, is not accessible in the PEB. This makes them harder to locate by shell code, which is operating in an environment where address space layout randomization (ASLR) is enabled. (See Chapter 5 for more on ASLR.)

Table 3-9 lists the various pieces of information the loader maintains in an entry.

Field	Meaning						
BaseAddressIndexNode	Links this entry as a node in the Red-Black Tree sorted by base address.						
BaseDllName/ BaseNameHashValue	The name of the module itself, without the full path. The second field stores its hash using RtlHashUnicodeString.						
DdagNode/NodeModuleLink	A pointer to the data structure tracking the distributed dependency graph (DDAG), which parallelizes dependency loading through the worker thread pool. The second field links the structure with the LDR_DATA_TABLE_ENTRYs associated with it (part of the same graph).						
DllBase	Holds the base address at which the module was loaded.						
EntryPoint	Contains the initial routine of the module (such as DllMain).						
EntryPointActivationContext	Contains the SxS/Fusion activation context when calling initializers.						
Flags	Loader state flags for this module (see Table 3-10 for a description of the flags).						
ForwarderLinks	A linked list of modules that were loaded as a result of export table forwarders from the module.						
FullDllName	The fully qualified path name of the module.						
HashLinks	A linked list used during process startup and shutdown for quicker lookups.						
ImplicitPathOptions	Used to store path lookup flags that can be set with the LdrSetImplicitPathOptions API or that are inherited based on the DLL path.						
List Entry Links	Links this entry into each of the three ordered lists part of the loader database.						
LoadContext	Pointer to the current load information for the DLL. Typically NULL unless activel being loaded.						
ObsoleteLoadCount	A reference count for the module (that is, how many times it has been loaded). This is no longer accurate and has been moved to the DDAG node structure instead.						
LoadReason	Contains an enumeration value that explains why this DLL was loaded (dynami- cally, statically, as a forwarder, as a delay-load dependency, etc.).						
LoadTime	Stores the system time value when this module was being loaded.						
MappingInfoIndexNode	Links this entry as a node in the red-black tree sorted by the hash of the name.						
OriginalBase	Stores the original base address (set by the linker) of this module, before ASLR or relocations, enabling faster processing of relocated import entries.						

TABLE 3-9 Fields in a loader data table entr	·у
--	----

Continues...

TABLE 3-9 Fields in a loader data table entry (continued)

Field	Meaning
ParentDllBase	In case of static (or forwarder, or delay-load) dependencies, stores the address of the DLL that has a dependency on this one.
SigningLevel	Stores the signature level of this image (see Chapter 8, Part 2, for more informa- tion on the Code Integrity infrastructure).
SizeOfImage	The size of the module in memory.
SwitchBackContext	Used by SwitchBack (described later) to store the current Windows context GUID associated with this module, and other data.
TimeDateStamp	A time stamp written by the linker when the module was linked, which the loader obtains from the module's image PE header.
TlsIndex	The thread local storage slot associated with this module.

One way to look at a process's loader database is to use WinDbg and its formatted output of the PEB. The next experiment shows you how to do this and how to look at the LDR\_DATA\_TABLE\_ENTRY structures on your own.

#### **EXPERIMENT:** Dumping the loaded modules database

Before starting the experiment, perform the same steps as in the previous two experiments to launch Notepad.exe with WinDbg as the debugger. When you get to the initial breakpoint (where you've been instructed to type **g** until now), follow these instructions:

1. You can look at the PEB of the current process with the !peb command. For now, you're interested only in the Ldr data that will be displayed.

```
0:000> !peb
PEB at 000000dd4c901000
   InheritedAddressSpace:
                             No
   ReadImageFileExecOptions: No
   BeingDebugged:
                      Yes
   ImageBaseAddress: 00007ff720b60000
                             00007ffe855d23a0
   Ldr
   Ldr.Initialized:
                           Yes
   Ldr.InInitializationOrderModuleList: 0000022815d23d30 . 0000022815d24430
   Ldr.InLoadOrderModuleList: 0000022815d23ee0 . 0000022815d31240
   Ldr.InMemoryOrderModuleList: 0000022815d23ef0 . 0000022815d31250
Base TimeStamp Module
           7ff720b60000 5789986a Jul 16 05:14:02 2016 C:\Windows\System32\
notepad.exe
           7ffe85480000 5825887f Nov 11 10:59:43 2016 C:\WINDOWS\SYSTEM32\
ntdll.dll
           7ffe84bd0000 57899a29 Jul 16 05:21:29 2016 C:\WINDOWS\System32\
KERNEL32.DLL
           7ffe823c0000 582588e6 Nov 11 11:01:26 2016 C:\WINDOWS\System32\
KERNELBASE.d11
. . .
```

- 2. The address shown on the Ldr line is a pointer to the PEB\_LDR\_DATA structure described earlier. Notice that WinDbg shows you the address of the three lists, and dumps the initialization order list for you, displaying the full path, time stamp, and base address of each module.
- 3. You can also analyze each module entry on its own by going through the module list and then dumping the data at each address, formatted as a LDR\_DATA\_TABLE\_ENTRY structure. Instead of doing this for each entry, however, WinDbg can do most of the work by using the !list extension and the following syntax:

```
!list -x "dt ntdll!_LDR_DATA_TABLE_ENTRY" @@C++(&@$peb->Ldr-
>InLoadOrderModuleList)
```

4. You should then see the entries for each module:

```
+0x000 InLoadOrderLinks : _LIST_ENTRY [ 0x00000228'15d23d10 -

0x00007ffe'855d23b0 ]

+0x010 InMemoryOrderLinks : _LIST_ENTRY [ 0x00000228'15d23d20 -

0x00007ffe'855d23c0 ]

+0x020 InInitializationOrderLinks : _LIST_ENTRY [ 0x0000000'0000000 -

0x000000'0000000 ]

+0x030 D11Base : 0x00007ff7'20b60000 Void

+0x038 EntryPoint : 0x00007ff7'20b787d0 Void

+0x040 SizeOfImage : 0x41000

+0x048 FullD11Name : _UNICODE_STRING "C:\Windows\System32\notepad.

exe"

+0x058 BaseD11Name : _UNICODE_STRING "notepad.exe"

+0x068 FlagGroup : [4] "???"

+0x068 Flags : 0xa2cc
```

Although this section covers the user-mode loader in Ntdll.dll, note that the kernel also employs its own loader for drivers and dependent DLLs, with a similar loader entry structure called KLDR\_DATA\_ TABLE\_ENTRY instead. Likewise, the kernel-mode loader has its own database of such entries, which is directly accessible through the PsLoadedModuleList global data variable. To dump the kernel's loaded module database, you can use a similar !list command as shown in the preceding experiment by replacing the pointer at the end of the command with nt! PsLoadedModuleList and using the new structure/ module name: !list -x "dt nt!\_kldr\_data\_table\_entry" nt!PsLoadedModuleList

Looking at the list in this raw format gives you some extra insight into the loader's *internals*, such as the Flags field, which contains state information that ! peb on its own would not show you. See Table 3-10 for their meaning. Because both the kernel and user-mode loaders use this structure, the meaning of the flags is not always the same. In this table, we explicitly cover the user-mode flags only (some of which may exist in the kernel structure as well).

#### TABLE 3-10 Loader data table entry flags

Flag	Meaning
Packaged Binary (0x1)	This module is part of a packaged application (it can only be set on the main module of an AppX package).
Marked for Removal (0x2)	This module will be unloaded as soon as all references (such as from an executing worker thread) are dropped.
Image DLL (0x4)	This module is an image DLL (and not a data DLL or executable).
Load Notifications Sent (0x8)	Registered DLL notification callouts were notified of this image already.
Telemetry Entry Processed (0x10)	Telemetry data has already been processed for this image.
Process Static Import (0x20)	This module is a static import of the main application binary.
In Legacy Lists (0x40)	This image entry is in the loader's doubly linked lists.
In Indexes (0x80)	This image entry is in the loader's red-black trees.
Shim DLL (0x100)	This image entry represents a DLL part of the shim engine/application compatibility database.
In Exception Table (0x200)	This module's .pdata exception handlers have been captured in the loader's inverted function table.
Load In Progress (0x800)	This module is currently being loaded.
Load Config Processed (0x1000)	This module's image load configuration directory has been found and processed.
Entry Processed (0x2000)	The loader has fully finished processing this module.
Protect Delay Load (0x4000)	Control Flow Guard features for this binary have requested the protec- tion of the delay-load IAT. See chapter 7 for more information.
Process Attach Called (0x20000)	The DLL_PROCESS_ATTACH notification has already been sent to the DLL.
Process Attach Failed (0x40000)	The DIIMain routine of the DLL has failed the DLL_PROCESS_ATTACH notification.
Don't Call for Threads (0x80000)	Do not send DLL_THREAD_ATTACH/DETACH notifications to this DLL. Can be set with DisableThreadLibraryCalls.
COR Deferred Validate (0x100000)	The Common Object Runtime (COR) will validate this .NET image at a later time.
COR Image (0x200000)	This module is a .NET application.
Don't Relocate (0x400000)	This image should not be relocated or randomized.
COR IL Only (0x800000)	This is a .NET intermediate-language (IL)-only library, which does not contain native assembly code.
Compat Database Processed (0x4000000)	The shim engine has processed this DLL.

## Import parsing

Now that we've explained the way the loader keeps track of all the modules loaded for a process, you can continue analyzing the startup initialization tasks performed by the loader. During this step, the loader will do the following:

- 1. Load each DLL referenced in the import table of the process's executable image.
- **2.** Check whether the DLL has already been loaded by checking the module database. If it doesn't find it in the list, the loader opens the DLL and maps it into memory.
- 3. During the mapping operation, the loader first looks at the various paths where it should attempt to find this DLL, as well as whether this DLL is a *known DLL*, meaning that the system has already loaded it at startup and provided a global memory mapped file for accessing it. Certain deviations from the standard lookup algorithm can also occur, either through the use of a .local file (which forces the loader to use DLLs in the local path) or through a manifest file, which can specify a redirected DLL to use to guarantee a specific version.
- 4. After the DLL has been found on disk and mapped, the loader checks whether the kernel has loaded it somewhere else—this is called *relocation*. If the loader detects relocation, it parses the relocation information in the DLL and performs the operations required. If no relocation information is present, DLL loading fails.
- 5. The loader then creates a loader data table entry for this DLL and inserts it into the database.
- **6.** After a DLL has been mapped, the process is repeated for this DLL to parse its import table and all its dependencies.
- 7. After each DLL is loaded, the loader parses the IAT to look for specific functions that are being imported. Usually this is done by name, but it can also be done by ordinal (an index number). For each name, the loader parses the export table of the imported DLL and tries to locate a match. If no match is found, the operation is aborted.
- 8. The import table of an image can also be bound. This means that at link time, the developers already assigned static addresses pointing to imported functions in external DLLs. This removes the need to do the lookup for each name, but it assumes that the DLLs the application will use will always be located at the same address. Because Windows uses address space randomization (see Chapter 5 for more information on ASLR), this is usually not the case for system applications and libraries.
- **9.** The export table of an imported DLL can use a forwarder entry, meaning that the actual function is implemented in another DLL. This must essentially be treated like an import or dependency, so after parsing the export table, each DLL referenced by a forwarder is also loaded and the loader goes back to step 1.

After all imported DLLs (and their own dependencies, or imports) have been loaded, all the required imported functions have been looked up and found, and all forwarders also have been loaded and processed, the step is complete: All dependencies that were defined at compile time by the application and its various DLLs have now been fulfilled. During execution, delayed dependencies (called *delay load*), as well as run-time operations (such as calling LoadLibrary) can call into the loader and essentially repeat the same tasks. Note, however, that a failure in these steps will result in an error launching the application if they are done during process startup. For example, attempting to run an application that requires a function that isn't present in the current version of the operating system can result in a message similar to the one in Figure 3-12.




FIGURE 3-12 The dialog box shown when a required (imported) function is not present in a DLL.

## Post-import process initialization

After the required dependencies have been loaded, several initialization tasks must be performed to fully finalize launching the application. In this phase, the loader will do the following:

- 1. These steps begin with the LdrInitState variable set to 2, which means imports have loaded.
- 2. The initial debugger breakpoint will be hit when using a debugger such as WinDbg. This is where you had to type **g** to continue execution in earlier experiments.
- 3. Check if this is a Windows subsystem application, in which case the BaseThreadInitThunk function should've been captured in the early process initialization steps. At this point, it is called and checked for success. Similarly, the TermsrvGetWindowsDirectoryW function, which should have been captured earlier (if on a system which supports terminal services), is now called, which resets the System and Windows directories path.
- 4. Using the distributed graph, recurse through all dependencies and run the initializers for all of the images' static imports. This is the step that calls the D11Main routine for each DLL (allowing each DLL to perform its own initialization work, which might even include loading new DLLs at run time) as well as processes the TLS initializers of each DLL. This is one of the last steps in which loading an application can fail. If all the loaded DLLs do not return a successful return code after finishing their D11Main routines, the loader aborts starting the application.
- 5. If the image uses any TLS slots, call its TLS initializer.
- **6.** Run the post-initialization shim engine callback if the module is being shimmed for application compatibility.
- **7.** Run the associated subsystem DLL post-process initialization routine registered in the PEB. For Windows applications, this does Terminal Services–specific checks, for example.
- 8. At this point, write an ETW event indicating that the process has loaded successfully.
- **9.** If there is a minimum stack commit, touch the thread stack to force an in-page of the committed pages.
- **10.** Set LdrInitState to 3, which means initialization done. Set the PEB's ProcessInitializing field back to 0. Then, update the LdrpProcessInitialized variable.

## SwitchBack

As each new version of Windows fixes bugs such as race conditions and incorrect parameter validation checks in existing API functions, an application-compatibility risk is created for each change, no matter how minor. Windows makes use of a technology called *SwitchBack*, implemented in the loader, which enables software developers to embed a GUID specific to the Windows version they are targeting in their executable's associated manifest.

For example, if a developer wants to take advantage of improvements added in Windows 10 to a given API, she would include the Windows 10 GUID in her manifest, while if a developer has a legacy application that depends on Windows 7–specific behavior, she would put the Windows 7 GUID in the manifest instead.

SwitchBack parses this information and correlates it with embedded information in SwitchBackcompatible DLLs (in the .sb\_data image section) to decide which version of an affected API should be called by the module. Because SwitchBack works at the loaded-module level, it enables a process to have both legacy and current DLLs concurrently calling the same API, yet observing different results.

## SwitchBack GUIDs

Windows currently defines GUIDs that represent compatibility settings for every version from Windows Vista:

- e2011457-1546-43c5-a5fe-008deee3d3f0} for Windows Vista
- {35138b9a-5d96-4fbd-8e2d-a2440225f93a} for Windows 7
- {4a2f28e3-53b9-4441-ba9c-d69d4a4a6e38} for Windows 8
- {1f676c76-80e1-4239-95bb-83d0f6d0da78} for Windows 8.1
- {8e0f7a12-bfb3-4fe8-b9a5-48fd50a15a9a} for Windows 10

These GUIDs must be present in the application's manifest file under the <SupportedOS> element in the ID attribute in a compatibility attribute entry. (If the application manifest does not contain a GUID, Windows Vista is chosen as the default compatibility mode.) Using Task Manager, you can enable an Operating System Context column in the Details tab, which will show if any applications are running with a specific OS context (an empty value usually means they are operating in Windows 10 mode). Figure 3-13 shows an example of a few such applications, which are operating in Windows Vista and Windows 7 modes, even on a Windows 10 system.

Here is an example of a manifest entry that sets compatibility for Windows 10:

```
<compatibility xmlns="urn:schemas-microsoft-com:compatibility.v1">
    <application>
    <!-- Windows 10 -->
    <supportedOS Id="{&e0f7a12-bfb3-4fe8-b9a5-4&fd50a15a9a}" />
    </application>
</compatibility>
```

File Options View Processes Performance	App hist	ory Startup	Users Details Se	rvices				
Name	PID	Status	Operating syst	User na	Description	CPU	Memory (p	
sychost.exe	2788	Running		SYSTEM	Host Process for Windows Services	00	8.936 K	
sychost.exe	2836	Running		LOCAL	Host Process for Windows Services	00	3.172 K	
svchost.exe	2848	Running		SYSTEM	Host Process for Windows Services	00	1,036 K	
II svchost.exe	4084	Running		aione	Host Process for Windows Services	00	10,384 K	
SystemSettings.exe	10528	Suspended		aione	Settings	00	5.148 K	
SystemSettingsBroke	15948	Running		aione	System Settings Broker	00	1,852 K	
taskhostw.exe	4128	Running		aione	Host Process for Windows Tasks	01	9,644 K	
Taskmgr.exe	13032	Running		aione	Task Manager	00	14,880 K	
@ TSVNCache.exe	5740	Running		aione	TortoiseSVN status cache	00	8,000 K	
Twitter.Windows.exe	7028	Suspended		aione	Twitter.Windows	00	320 K	
windbg.exe	14888	Running		aione	Windows GUI symbolic debugger	00	139, 192 K	
windbg.exe	12924	Running		aione	Windows GUI symbolic debugger	00	128,656 K	
WINWORD.EXE	11576	Running		aione	Microsoft Word	00	146,108 K	
Ivnchtmlconv.exe	14464	Running	Windows 7	aione	Microsoft Lync	00	12,936 K	
S UcMapi.exe	9440	Running	Windows 7	aione	Skype for Business	00	28,988 K	
idaq64.exe	18964	Running	Windows Vista	aione	The Interactive Disassembler	00	119,844 K	
IpOverUsbSvc.exe	2552	Running	Windows Vista	SYSTEM	Windows IP Over USB PC Service	00	2,136 K	
Evcpkgsrv.exe	4876	Running	Windows Vista	aione	Microsoft (R) Visual C++ Package Server	00	7,200 K	
vcpkgsrv.exe	16240	Running	Windows Vista	aione	Microsoft (R) Visual C++ Package Server	00	3,068 K	
vcpkgsrv.exe	17004	Running	Windows Vista	aione	Microsoft (R) Visual C++ Package Server	00	2,588 K	
Coom.exe	4012	Running	Windows Vista	aione	Zoom Meetings	00	15,352 K	
Coom.exe	15832	Running	Windows Vista	aione	Zoom Meetings	00	96,092 K	
conhost.exe	7652	Running		aione	Console Window Host	00	4,552 K	
conhost.exe	11940	Running		aione	Console Window Host	00	5,140 K	
conhost.exe	11184	Running		aione	Console Window Host	00	5,128 K	
conhost.exe	2204	Running		aione	Console Window Host	00	5,104 K	
conhost.exe	11696	Running		aione	Console Window Host	00	5,148 K	
conhost.exe	5224	Running		aione	Console Window Host	00	5,128 K	
	11011	n .		14	~ 1 M 1 11 1		CARD IF	

FIGURE 3-13 Some processes that run with compatibility modes.

#### SwitchBack compatibility modes

As a few examples of what SwitchBack can do, here's what running under the Windows 7 context affects:

- RPC components use the Windows thread pool instead of a private implementation.
- DirectDraw Lock cannot be acquired on the primary buffer.
- Blitting on the desktop is not allowed without a clipping window.
- A race condition in GetOverlappedResult is fixed.
- Calls to CreateFile are allowed to pass a "downgrade" flag to receive exclusive open to a file even when the caller does not have write privilege, which causes NtCreateFile not to receive the FILE\_DISALLOW\_EXCLUSIVE flag.

Running in Windows 10 mode, on the other hand, subtly affects how the Low Fragmentation Heap (LFH) behaves, by forcing LFH sub-segments to be fully committed and padding all allocations with a header block unless the Windows 10 GUID is present. Additionally, in Windows 10, using the Raise Exception on Invalid Handle Close mitigation (see Chapter 7 for more information) will result in CloseHandle and RegCloseKey respecting the behavior. On the other hand, on previous operating systems, if the debugger is not attached, this behavior will be disabled before calling NtClose, and then re-enabled after the call.

As another example, the Spell Checking Facility will return NULL for languages which don't have a spell checker, while it returns an "empty" spell checker on Windows 8.1. Similarly, the implementation of the function IShellLink::Resolve will return E\_INVALIDARG when operating in Windows 8 compatibility mode when given a relative path, but will not contain this check in Windows 7 mode.

Furthermore, calls to GetVersionEx or the equivalent functions in NtDll such as RtlVerifyVersion-Info will return the maximum version number that corresponds to the SwitchBack Context GUID that was specified.

**Note** These APIs have been deprecated, and calls to GetVersionEx will return 6.2 on all versions of Windows 8 and later if a higher SwitchBack GUID is not provided.

#### SwitchBack behavior

Whenever a Windows API is affected by changes that might break compatibility, the function's entry code calls the SbSwitchProcedure to invoke the SwitchBack logic. It passes along a pointer to the SwitchBack *module table*, which contains information about the SwitchBack mechanisms employed in the module. The table also contains a pointer to an array of entries for each SwitchBack point. This table contains a description of each branch-point that identifies it with a symbolic name and a comprehensive description, along with an associated mitigation tag. Typically, there will be several branch-points in a module, one for Windows Vista behavior, one for Windows 7 behavior, etc.

For each branch-point, the required SwitchBack context is given—it is this context that determines which of the two (or more) branches is taken at runtime. Finally, each of these descriptors contains a function pointer to the actual code that each branch should execute. If the application is running with the Windows 10 GUID, this will be part of its SwitchBack context, and the SbSelectProcedure API, upon parsing the module table, will perform a match operation. It finds the module entry descriptor for the context and proceeds to call the function pointer included in the descriptor.

SwitchBack uses ETW to trace the selection of given SwitchBack contexts and branch-points and feeds the data into the Windows AIT (Application Impact Telemetry) logger. This data can be periodically collected by Microsoft to determine the extent to which each compatibility entry is being used, identify the applications using it (a full stack trace is provided in the log), and notify third-party vendors.

As mentioned, the compatibility level of the application is stored in its manifest. At load time, the loader parses the manifest file, creates a context data structure, and caches it in the pShimData member of the PEB. This context data contains the associated compatibility GUIDs that this process is executing under and determines which version of the branch-points in the called APIs that employ SwitchBack will be executed.

## **API Sets**

While SwitchBack uses API redirection for specific application-compatibility scenarios, there is a much more pervasive redirection mechanism used in Windows for all applications, called *API Sets*. Its purpose

is to enable fine-grained categorization of Windows APIs into sub-DLLs instead of having large multipurpose DLLs that span nearly thousands of APIs that might not be needed on all types of Windows systems today and in the future. This technology, developed mainly to support the refactoring of the bottom-most layers of the Windows architecture to separate it from higher layers, goes hand in hand with the breakdown of Kernel32.dll and Advapi32.dll (among others) into multiple, virtual DLL files.

For example, Figure 3-14 shows a screenshot of Dependency Walker where Kernel32.dll, which is a core Windows library, imports from many other DLLs, beginning with API-MS-WIN. Each of these DLLs contains a small subset of the APIs that Kernel32 normally provides, but together they make up the entire API surface exposed by Kernel32.dll. The CORE-STRING library, for instance, provides only the Windows base string functions.




FIGURE 3-14 API sets for kernel32.dll.

In splitting functions across discrete files, two objectives are achieved. First, doing this allows future applications to link only with the API libraries that provide the functionality that they need. Second, if Microsoft were to create a version of Windows that did not support, for example, localization (say, a non-user-facing, English-only embedded system), it would be possible to simply remove the sub-DLL and modify the API Set schema. This would result in a smaller Kernel32 binary, and any applications that ran without requiring localization would still run.

With this technology, a "base" Windows system called *MinWin* is defined (and, at the source level, built), with a minimum set of services that includes the kernel, core drivers (including file systems, basic system processes such as CSRSS and the Service Control Manager, and a handful of Windows services). Windows Embedded, with its Platform Builder, provides what might seem to be a similar technology, as system builders are able to remove select "Windows components," such as the shell, or the network stack. However, removing components from Windows leaves *dangling dependencies*—code paths that, if exercised, would fail because they depend on the removed components. MinWin's dependencies, on the other hand, are entirely self-contained.

When the process manager initializes, it calls the PspInitializeApiSetMap function, which is responsible for creating a section object of the API Set redirection table, which is stored in %System-Root%\System32\ApiSetSchema.dll. The DLL contains no executable code, but it has a section called .api set that contains API Set mapping data that maps virtual API Set DLLs to logical DLLs that implement the APIs. Whenever a new process starts, the process manager maps the section object into the process's address space and sets the ApiSetMap field in the process's PEB to point to the base address where the section object was mapped.

In turn, the loader's LdrpApp1yFileNameRedirection function, which is normally responsible for the .local and SxS/Fusion manifest redirection that was mentioned earlier, also checks for API Set redirection data whenever a new import library that has a name starting with *API*- loads (either dynamically or statically). The API Set table is organized by library with each entry describing in which logical DLL the function can be found, and that DLL is what gets loaded. Although the schema data is a binary format, you can dump its strings with the Sysinternals Strings tool to see which DLLs are currently defined:

```
C:\Windows\System32>strings apisetschema.dll
```

```
. . .
api-ms-onecoreuap-print-render-11-1-0
printrenderapihost.dllapi-ms-onecoreuap-settingsync-status-ll-1-0
settingsynccore.dll
api-ms-win-appmodel-identity-l1-2-0
kernel.appcore.dllapi-ms-win-appmodel-runtime-internal-l1-1-3
api-ms-win-appmodel-runtime-l1-1-2
api-ms-win-appmodel-state-l1-1-2
api-ms-win-appmodel-state-11-2-0
api-ms-win-appmodel-unlock-l1-1-0
api-ms-win-base-bootconfig-11-1-0
advapi32.dllapi-ms-win-base-util-l1-1-0
api-ms-win-composition-redirection-l1-1-0
. . .
api-ms-win-core-com-midlproxystub-l1-1-0
api-ms-win-core-com-private-l1-1-1
api-ms-win-core-comm-l1-1-0
api-ms-win-core-console-ansi-12-1-0
api-ms-win-core-console-l1-1-0
api-ms-win-core-console-12-1-0
api-ms-win-core-crt-l1-1-0
api-ms-win-core-crt-12-1-0
api-ms-win-core-datetime-l1-1-2
api-ms-win-core-debug-l1-1-2
api-ms-win-core-debug-minidump-l1-1-0
```

```
api-ms-win-core-firmware-l1-1-0
api-ms-win-core-guard-l1-1-0
api-ms-win-core-handle-l1-1-0
api-ms-win-core-heap-l1-1-0
api-ms-win-core-heap-l1-2-0
api-ms-win-core-heap-l2-1-0
api-ms-win-core-heap-obsolete-l1-1-0
api-ms-win-core-interlocked-l1-1-1
api-ms-win-core-interlocked-l1-2-0
api-ms-win-core-job-l1-1-1
```

## Jobs

A *job* is a nameable, securable, shareable kernel object that allows control of one or more processes as a group. A job object's basic function is to allow groups of processes to be managed and manipulated as a unit. A process can be a member of any number of jobs, although the typical case is just one. A process's association with a job object can't be broken, and all processes created by the process and its descendants are associated with the same job object (unless child processes are created with the CREATE\_BREAKAWAY\_FROM\_JOB flag and the job itself has not restricted it). The job object also records basic accounting information for all processes associated with the job and for all processes that were associated with the job but have since terminated.

Jobs can also be associated with an I/O completion port object, which other threads might be waiting for, with the Windows GetQueuedCompletionStatus function or by using the Thread Pool API (the native function TpAllocJobNotification). This allows interested parties (typically the job creator) to monitor for limit violations and events that could affect the job's security, such as a new process being created or a process abnormally exiting.

Jobs play a significant role in a number of system mechanisms, enumerated here:

- They manage modern apps (UWP processes), as discussed in more detail in Chapter 9 in Part 2. In fact, every modern app is running under a job. You can verify this with Process Explorer, as described in the "Viewing the job object" experiment later in this chapter.
- They are used to implement Windows Container support, through a mechanism called *server silo*, covered later in this section.
- They are the primary way through which the Desktop Activity Moderator (DAM) manages throttling, timer virtualization, timer freezing, and other idle-inducing behaviors for Win32 applications and services. The DAM is described in Chapter 8 in Part 2.
- They allow the definition and management of scheduling groups for dynamic fair-share scheduling (DFSS), which is described in Chapter 4.

- They allow for the specification of a custom memory partition, which enables usage of the Memory Partitioning API described in Chapter 5.
- They serve as a key enabler for features such as Run As (Secondary Logon), Application Boxing, and Program Compatibility Assistant.
- They provide part of the security sandbox for applications such as Google Chrome and Microsoft Office Document Converter, as well as mitigation from denial-of-service (DoS) attacks through Windows Management Instrumentation (WMI) requests.

# Job limits

The following are some of the CPU-, memory-, and I/O-related limits you can specify for a job:

- Maximum number of active processes This limits the number of concurrently existing processes in the job. If this limit is reached, new processes that should be assigned to the job are blocked from creation.
- Job-wide user-mode CPU time limit This limits the maximum amount of user-mode CPU time that the processes in the job can consume (including processes that have run and exited). Once this limit is reached, by default all the processes in the job are terminated with an error code and no new processes can be created in the job (unless the limit is reset). The job object is signaled, so any threads waiting for the job will be released. You can change this default behavior with a call to SetInformationJobObject to set the EndOfJobTimeAction member of the JOBOBJECT\_END\_OF\_JOB\_TIME\_INFORMATION structure passed with the JobObjectEnd-OfJobTimeInformation information class and request a notification to be sent through the job's completion port instead.
- Per-process user-mode CPU time limit This allows each process in the job to accumulate only a fixed maximum amount of user-mode CPU time. When the maximum is reached, the process terminates (with no chance to clean up).
- Job processor affinity This sets the processor affinity mask for each process in the job. (Individual threads can alter their affinity to any subset of the job affinity, but processes can't alter their process affinity setting.)
- Job group affinity This sets a list of groups to which the processes in the job can be assigned. Any affinity changes are then subject to the group selection imposed by the limit. This is treated as a group-aware version of the job processor affinity limit (legacy), and prevents that limit from being used.
- Job process priority class This sets the priority class for each process in the job. Threads can't increase their priority relative to the class (as they normally can). Attempts to increase thread priority are ignored. (No error is returned on calls to SetThreadPriority, but the increase doesn't occur.)

- Default working set minimum and maximum This defines the specified working set minimum and maximum for each process in the job. (This setting isn't job-wide. Each process has its own working set with the same minimum and maximum values.)
- Process and job committed virtual memory limit This defines the maximum amount of virtual address space that can be committed by either a single process or the entire job.
- **CPU rate control** This defines the maximum amount of CPU time that the job is allowed to use before it will experience forced throttling. This is used as part of the scheduling group support described in Chapter 4.
- Network bandwidth rate control This defines the maximum outgoing bandwidth for the entire job before throttling takes effect. It also enables setting a differentiated services code point (DSCP) tag for QoS purposes for each network packet sent by the job. This can only be set for one job in a hierarchy, and affects the job and any child jobs.
- Disk I/O bandwidth rate control This is the same as network bandwidth rate control, but is applied to disk I/O instead, and can control either bandwidth itself or the number of I/O operations per second (IOPS). It can be set either for a particular volume or for all volumes on the system.

For many of these limits, the job owner can set specific thresholds, at which point a notification will be sent (or, if no notification is registered, the job will simply be killed). Additionally, rate controls allow for tolerance ranges and tolerance intervals—for example, allowing a process to go beyond 20 percent of its network bandwidth limit for up to 10 seconds every 5 minutes. These notifications are done by queuing an appropriate message to the I/O completion port for the job. (See the Windows SDK documentation for the details.)

Finally, you can place user-interface limits on processes in a job. Such limits include restricting processes from opening handles to windows owned by threads outside the job, reading and/or writing to the clipboard, and changing the many user-interface system parameters via the Windows System-ParametersInfo function. These user-interface limits are managed by the Windows subsystem GDI/USER driver, Win32k.sys, and are enforced through one of the special callouts that it registers with the process manager, the job callout. You can grant access for all processes in a job to specific user handles (for example, window handle) by calling the UserHandleGrantAccess function; this can only be called by a process that is not part of the job in question (naturally).

## Working with a job

A job object is created using the CreateJobObject API. The job is initially created empty of any process. To add a process to a job, call the AssignProcessToJobObject, which can be called multiple times to add processes to the job or even to add the same process to multiple jobs. This last option creates a nested job, described in the next section. Another way to add a process to a job is to manually specify a handle to the job object by using the PS\_CP\_JOB\_LIST process-creation attribute described earlier in this chapter. One or more handles to job objects can be specified, which will all be joined.

The most interesting API for jobs is SetInformationJobObject, which allows the setting of the various limits and settings mentioned in the previous section, and contains internal information classes used by mechanisms such as Containers (Silo), the DAM, or Windows UWP applications. These values can be read back with QueryInformationJobObject, which can provide interested parties with the limits set on a job. It's also necessary to call in case limit notifications have been set (as described in the previous section) in order for the caller to know precisely which limits were violated. Another sometimes-useful function is TerminateJobObject, which terminates all processes in the job (as if TerminateProcess were called on each process).

# Nested jobs

Until Windows 7 and Windows Server 2008 R2, a process could only be associated with a single job, which made jobs less useful than they could be, as in some cases an application could not know in advance whether a process it needed to manage happened to be in a job or not. Starting with Windows 8 and Windows Server 2012, a process can be associated with multiple jobs, effectively creating a job hierarchy.

A child job holds a subset of processes of its parent job. Once a process is added to more than one job, the system tries to form a hierarchy, if possible. A current restriction is that jobs cannot form a hierarchy if any of them sets any UI limits (SetInformationJobObject with JobObjectBasicUIRestrictions argument).

Job limits for a child job cannot be more permissive than its parent, but they can be more restrictive. For example, if a parent job sets a memory limit of 100 MB for the job, any child job cannot set a higher memory limit (such requests simply fail). A child job can, however, set a more restrictive limit for its processes (and any child jobs it has), such as 80 MB. Any notifications that target the I/O completion port of a job will be sent to the job and all its ancestors. (The job itself does not have to have an I/O completion port for the notification to be sent to ancestor jobs.)

Resource accounting for a parent job includes the aggregated resources used by its direct managed processes and all processes in child jobs. When a job is terminated (TerminateJobObject), all processes in the job and in child jobs are terminated, starting with the child jobs at the bottom of the hierarchy. Figure 3-15 shows four processes managed by a job hierarchy.




FIGURE 3-15 A job hierarchy.

To create this hierarchy, processes should be added to jobs from the root job. Here are a set of steps to create this hierarchy:


- 1. Add process P1 to job 1.
- 2. Add process P1 to job 2. This creates the first nesting.
- 3. Add process P2 to job 1.
- 4. Add process P2 to job 3. This creates the second nesting.
- **5.** Add process P3 to job 2.
- 6. Add process P4 to job 1.

#### **EXPERIMENT:** Viewing the job object

You can view named job objects with the Performance Monitor tool. (Look for the Job Object and Job Object Details categories.) You can view unnamed jobs with the kernel debugger ! job or dt nt!\_ejob commands.

To see whether a process is associated with a job, you can use the kernel debugger !process command or Process Explorer. Follow these steps to create and view an unnamed job object:

- 1. From the command prompt, use the runas command to create a process running the command prompt (Cmd.exe). For example, type **runas /user:<domain>\< username> cmd**.
- 2. You'll be prompted for your password. Enter your password, and a Command Prompt window will appear. The Windows service that executes runas commands creates an unnamed job to contain all processes (so that it can terminate these processes at logoff time).
- 3. Run Process Explorer, open the **Options** menu, choose **Configure Colors**, and check the **Jobs** entry. Notice that the Cmd.exe process and its child ConHost.exe process are highlighted as part of a job, as shown here:



**4.** Double click the **Cmd.exe** or **ConHost.Exe** process to open its properties dialog box. Then click the **Job** tab to see information about the job this process is part of:

Image	Perform	ance	Performan	ce Graph	Disk and	Network
GPU Graph	Threads	TCP/IP	Security	Environment	Job	String
Job Name:						
<unnamed .<="" td=""><td>lob&gt;</td><td></td><td></td><td></td><td></td><td></td></unnamed>	lob>					
Processes in	Job:					
Process	PID					
cmd.exe	1500					
conhost.exe	16136					
٢						)
Job Limits:						
Limit	Va	lue				

- 5. From the command prompt, run Notepad.exe.
- 6. Open Notepad's process and look at the Job tab. Notepad is running under the same job. This is because cmd.exe does not use the CREATE\_BREAKAWAY\_FROM\_JOB creation flag. In the case of nested jobs, the Job tab shows the processes in the direct job this process belongs to and all processes in child jobs.
- 7. Run the kernel debugger on the live system and type the **!process** command to find the notepad.exe and show its basic info:

```
1kd> !process 0 1 notepad.exe
PROCESS ffffe001eacf2080
SessionId: 1 Cid: 3078 Peb: 7f4113b000 ParentCid: 05dc
DirBase: 4878b3000 ObjectTable: ffffc0015b89fd80 HandleCount: 188.
Image: notepad.exe
...
BasePriority
8
CommitCharge
671
Job
ffffe00189aec460
```

Note the Job pointer, which is non-zero. To get a summary of the job, type the **!job** debugger command:

```
lkd> !job ffffe00189aec460
Job at ffffe00189aec460
 Basic Accounting Information
   TotalUserTime:
                           0x0
   TotalKernelTime:
                           0x0
   TotalCycleTime:
                           0x0
   ThisPeriodTotalUserTime: 0x0
   ThisPeriodTotalKernelTime: 0x0
   TotalPageFaultCount: 0x0
   TotalProcesses:
                           0x3
   ActiveProcesses:
                           0x3
```

FreezeCount:0BackgroundCount:0TotalTerminatedProcesses:0x0PeakJobMemoryUsed:0x10dbPeakProcessMemoryUsed:0xa56Job FlagsLimit Information (LimitFlags: 0x0)Limit Information (EffectiveLimitFlags: 0x0)

9. Notice the ActiveProcesses member set to 3 (cmd.exe, conhost.exe, and notepad.exe). You can use flag 2 after the ! job command to see a list of the processes that are part of the job:

```
1kd> !job ffffe00189aec460 2
Processes assigned to this job:
    PROCESS ffff8188d84dd780
       SessionId: 1 Cid: 5720 Peb: 43bedb6000 ParentCid: 13cc
       DirBase: 707466000 ObjectTable: ffffbe0dc4e3a040 HandleCount:
<Data Not Accessible>
       Image: cmd.exe
    PROCESS ffff8188ea077540
       SessionId: 1 Cid: 30ec Peb: dd7f17c000 ParentCid: 5720
       DirBase: 75a183000 ObjectTable: ffffbe0dafb79040 HandleCount:
<Data Not Accessible>
       Image: conhost.exe
   PROCESS ffffe001eacf2080
       SessionId: 1 Cid: 3078 Peb: 7f4113b000 ParentCid: 05dc
   DirBase: 4878b3000 ObjectTable: ffffc0015b89fd80 HandleCount: 188.
   Image: notepad.exe
```

10. You can also use the dt command to display the job object and see the additional fields shown about the job, such as its member level and its relations to other jobs in case of nesting (parent job, siblings, and root job):

```
lkd> dt nt!_ejob ffffe00189aec460
  +0x000 Event
                  : _KEVENT
: _LIST_ENTRY [ 0xffffe001'8d93e548 -
  +0x018 JobLinks
0xffffe001'df30f8d8 ]
  +0x028 ProcessListHead : _LIST_ENTRY [ 0xffffe001'8c4924f0 -
0xffffe001'eacf24f0 ]
                        : _ERESOURCE
  +0x038 JobLock
  +0x0a0 TotalUserTime : _LARGE_INTEGER 0x0
  +0x0a8 TotalKernelTime : _LARGE_INTEGER 0x2625a
  +0x0b0 TotalCycleTime : _LARGE_INTEGER 0xc9e03d
   . . .
  +0x0d4 TotalProcesses : 4
  +0x0d8 ActiveProcesses : 3
  +0x0dc TotalTerminatedProcesses : 0
```

```
+0x428 ParentJob : (null)
+0x430 RootJob : 0xffffe001'89aec460 _EJOB
...
+0x518 EnergyValues : 0xffffe001'89aec988 _PROCESS_ENERGY_VALUES
+0x520 SharedCommitCharge : 0x5e8
```

## Windows containers (server silos)

The rise of cheap, ubiquitous cloud computing has led to another major Internet revolution, in which building online services and/or back-end servers for mobile applications is as easy as clicking a button on one of the many cloud providers. But as competition among cloud providers has increased, and as the need to migrate from one to another, or even from a cloud provider to a datacenter, or from a datacenter to a high-end personal server, has grown, it has become increasingly important to have portable back ends, which can be deployed and moved around as needed without the costs associated with running them in a virtual machine.

It is to satisfy this need that technologies such as Docker were created. These technologies essentially allow the deployment of an "application in a box" from one Linux distribution to another without worrying about the complicated deployment of a local installation or the resource consumption of a virtual machine. Originally a Linux-only technology, Microsoft has helped bring Docker to Windows 10 as part of the Anniversary Update. It can work in two modes:

- By deploying an application in a heavyweight, but fully isolated, Hyper-V container, which is supported on both client and server scenarios
- By deploying an application in a lightweight, OS-isolated, server silo container, which is currently supported only in server scenarios due to licensing reasons

This latter technology, which we will investigate in this section, has resulted in deep changes in the operating system to support this capability. Note that, as mentioned, the ability for client systems to create server silo containers exists, but is currently disabled. Unlike a Hyper-V container, which leverages a true virtualized environment, a server silo container provides a second "instance" of all user-mode components while running on top of the same kernel and drivers. At the cost of some security, this provides a much more lightweight container environment.

#### Job objects and silos

The ability to create a silo is associated with a number of undocumented subclasses as part of the SetJobObjectInformation API. In other words, a silo is essentially a super-job, with additional rules and capabilities beyond those we've seen so far. In fact, a job object can be used for the isolation and resource management capabilities we've looked at as well as used to create a silo. Such jobs are called *hybrid jobs* by the system.

In practice, job objects can actually host two types of silos: application silos (which are currently used to implement the Desktop Bridge are not covered in this section, and are left for Chapter 9 in Part 2) and server silos, which are the ones used for Docker container support.

#### Silo isolation

The first element that defines a server silo is the existence of a custom object manager root directory object (\). (The object manager is discussed in Chapter 8 in Part 2.) Even though we have not yet learned about this mechanism, suffice it to say that all application-visible named objects (such as files, registry keys, events, mutexes, RPC ports, and more) are hosted in a root namespace, which allows applications to create, locate, and share these objects among themselves.

The ability for a server silo to have its own root means that all access to any named object can be controlled. This is done in one of three ways:

- By creating a new copy of an existing object to provide an alternate access to it from within the silo
- By creating a symbolic link to an existing object to provide direct access to it
- By creating a brand-new object that only exists within the silo, such as the ones a containerized application would use

This initial ability is then combined with the Virtual Machine Compute (Vmcompute) service (used by Docker), which interacts with additional components to provide a full isolation layer:

- A base Windows image (WIM) file called base OS This provides a separate copy of the operating system. At this time, Microsoft provides a Server Core image as well as a Nano Server image.
- The Ntdll.dll library of the host OS This overrides the one in the base OS image. This is due to the fact that, as mentioned, server silos leverage the same host kernel and drivers, and because Ntdll.dll handles system calls, it is the one user-mode component that must be reused from the host OS.
- A sandbox virtual file system provided by the Wcifs.sys filter driver This allows temporary changes to be made to the file system by the container without affecting the underlying NTFS drive, and which can be wiped once the container is shut down.
- A sandbox virtual registry provided by the VReg kernel component This allows for the provision of a temporary set of registry hives (as well as another layer of namespace isolation, as the object manager root namespace only isolates the root of the registry, not the registry hives themselves).
- The Session Manager (Smss.exe) This is now used to create additional service sessions or console sessions, which is a new capability required by the container support. This extends Smss to handle not only additional user sessions, but also sessions needed for each container launched.




FIGURE 3-16 Containers architecture.

#### Silo isolation boundaries

The aforementioned components provide the user-mode isolation environment. However, as the host Ntdll.dll component is used, which talks to the host kernel and drivers, it is important to create additional isolation boundaries, which the kernel provides to differentiate one silo from another. As such, each server silo will contain its own isolated:

- Micro shared user data (SILO\_USER\_SHARED\_DATA in the symbols) This contains the custom system path, session ID, foreground PID, and product type/suite. These are elements of the original KUSER\_SHARED\_DATA that cannot come from the host, as they reference information relevant to the host OS image instead of the base OS image, which must be used instead. Various components and APIs were modified to read the silo shared data instead of the user shared data when they look up such data. Note that the original KUSER\_SHARED\_DATA remains at its usual address with its original view of the host details, so this is one way that host state "leaks" inside container state.
- Object directory root namespace This has its own \SystemRoot symlink, \Device directory (which is how all user-mode components access device drivers indirectly), device map and DOS device mappings (which is how user-mode applications access network mapped drivers, for example), \Sessions directory, and more.
- API Set mapping This is based on the API Set schema of the base OS WIM, and not the one stored on the host OS file system. As you've seen, the loader uses API Set mappings to determine which DLL, if any, implements a certain function. This can be different from one SKU to another, and applications must see the base OS SKU, not the host's.

- Logon session This is associated with the SYSTEM and Anonymous local unique ID (LUID), plus the LUID of a virtual service account describing the user in the silo. This essentially represents the token of the services and application that will be running inside the container service session created by Smss. For more information on LUIDs and logon sessions, see Chapter 7.
- ETW tracing and logger contexts These are for isolating ETW operations to the silo and not exposing or leaking states between the containers and/or the host OS itself. (See Chapter 9 in Part 2 for more on ETW.)

#### Silo contexts

While these are the isolation boundaries provided by the core host OS kernel itself, other components inside the kernel, as well as drivers (including third party), can add contextual data to silos by using the PsCreateSiloContext API to set custom data associated with a silo or by associating an existing object with a silo. Each such silo context will utilize a silo slot index that will be inserted in all running, and future, server silos, storing a pointer to the context. The system provides 32 built-in system-wide storage slot indexes, plus 256 expansion slots, providing lots of extensibility options.

As each server silo is created, it receives its own silo-local storage (SLS) array, much like a thread has thread-local storage (TLS). Within this array, the different entries will correspond to slot indices that have been allocated to store silo contexts. Each silo will have a different pointer at the same slot index, but will always store the same context at that index. (For example, driver "Foo" will own index 5 in all silos, and can use it to store a different pointer/context in each silo.) In some cases, built-in kernel components, such as the object manager, security reference monitor (SRM), and Configuration Manager use some of these slots, while other slots are used by inbox drivers (such as the Ancillary Function Driver for Winsock, Afd.sys).

Just like when dealing with the server silo shared user data, various components and APIs have been updated to access data by getting it from the relevant silo context instead of what used to be a global kernel variable. As an example, because each container will now host its own Lsass.exe process, and since the kernel's SRM needs to own a handle to the Lsass.exe process (see Chapter 7 for more information on Lsass and the SRM), this can no longer be a singleton stored in a global variable. As such, the handle is now accessed by the SRM through querying the silo context of the active server silo, and getting the variable from the data structure that is returned.

This leads to an interesting question: What happens with the Lsass.exe that is running on the host OS itself? How will the SRM access the handle, as there's no server silo for this set of processes and session (that is, session 0 itself)? To solve this conundrum, the kernel now implements a root host silo. In other words, the host itself is presumed to be part of a silo as well! This isn't a silo in the true sense of the word, but rather a clever trick to make querying silo contexts for the current silo work, even when there is no current silo. This is implemented by storing a global kernel variable called PspHostSilo-Globals, which has its own Slot Local Storage Array, as well as other silo contexts used by built-in kernel components. When various silo APIs are called with a NULL pointer, this "NULL" is instead treated as "no silo—i.e., use the host silo."

### EXPERIMENT: Dumping SRM silo context for the host silo

As shown, even though your Windows 10 system may not be hosting any server silos, especially if it is a client system, a host silo still exists, which contains the silo-aware isolated contexts used by the kernel. The Windows Debugger has an extension, !silo, which can be used with the -g Host parameters as follows: !silo -g Host. You should see output similar to the one below:

In your output, the pointer to the silo globals should be hyperlinked, and clicking it will result in the following command execution and output:

```
lkd> dx -r1 (*((nt!_ESERVERSILO_GLOBALS *)0xffff801b73bc580))
(*((nt!_ESERVERSILO_GLOBALS *)0xffff801b73bc580)) [Type: _
ESERVERSILO_GLOBALS]
[+0x000] ObSiloState [Type: _OBP_SILODRIVERSTATE]
[+0x2e0] SeSiloState [Type: _SEP_SILOSTATE]
[+0x310] SeRmSiloState [Type: _SEP_RM_LSA_CONNECTION_STATE]
[+0x360] CmSiloState : 0xffffc308870931b0 [Type: _CMP_SILO_CONTEXT *]
[+0x368] EtwSiloState : 0xffffb30f236c4000 [Type: _ETW_SILODRIVERSTATE *]
```

. . .

Now click the SeRmSiloState field, which will expand to show you, among other things, a pointer to the Lsass.exe process:

```
lkd> dx -r1 ((ntkrnlmp!_SEP_RM_LSA_CONNECTION_STATE *)0xfffff801b73bc890)
((ntkrnlmp!_SEP_RM_LSA_CONNECTION_STATE *)0xfffff801b73bc890) :
0xfffff801b73bc890 [Type: _SEP_RM_LSA_CONNECTION_STATE *]
    [+0x000] LsaProcessHandle : 0xfffffff80000870 [Type: void *]
    [+0x008] LsaCommandPortHandle : 0xfffffff8000087c [Type: void *]
    [+0x010] SepRmThreadHandle : 0x0 [Type: void *]
    [+0x018] RmCommandPortHandle : 0xfffffff80000874 [Type: void *]
```

#### Silo monitors

If kernel drivers have the capability to add their own silo contexts, how do they first know what silos are executing, and what new silos are created as containers are launched? The answer lies in the silo monitor facility, which provides a set of APIs to receive notifications whenever a server silo is created and/ or terminated (PsRegisterSiloMonitor, PsStartSiloMonitor, PsUnregisterSiloMonitor), as well as notifications for any already-existing silos. Then, each silo monitor can retrieve its own slot index by calling PsGetSiloMonitorContextSlot, which it can then use with the PsInsertSiloContext, PsReplaceSiloContext, and PsRemoveSiloContext functions as needed. Additional slots can be allocated with PsAllocSiloContextSlot, but this would be needed only if a component would wish to store two contexts for some reason. Additionally, drivers can also use the PsInsertPermanentSiloContext or

PsMakeSiloContextPermanent APIs to use "permanent" silo contexts, which are not reference counted and are not tied to the lifetime of the server silo or the number of silo context getters. Once inserted, such silo contexts can be retrieved with PsGetSiloContext and/or PsGetPermanentSiloContext.

#### **EXPERIMENT: Silo monitors and contexts**

To understand how silo monitors are used, and how they store silo contexts, let's take a look at the Ancillary Function Driver for Winsock (Afd.sys) and its monitor. First, let's dump the data structure that represents the monitor. Unfortunately, it is not in the symbol files, so we must do this as raw data.

```
lkd> dps poi(afd!AfdPodMonitor)
ffffe387'a79fc120 ffffe387'a7d760c0
ffffe387'a79fc128 ffffe387'a7b54b60
ffffe387'a79fc130 0000009'00000101
ffffe387'a79fc138 fffff807'be4b5b10 afd!AfdPodSiloCreateCallback
ffffe387'a79fc140 fffff807'be4bee40 afd!AfdPodSiloTerminateCallback
```

Now get the slot (9 in this example) from the host silo. Silos store their SLS in a field called Storage, which contains an array of data structures (slot entries), each storing a pointer, and some flags. We are multiplying the index by 2 to get the offset of the right slot entry, then accessing the second field (+1) to get the pointer to the context pointer:

```
lkd> r? @$t0 = (nt!_ESERVERSILO_GLOBALS*)@@masm(nt!PspHostSiloGlobals)
lkd> ?? ((void***)@$t0->Storage)[9 * 2 + 1]
void ** 0xffff988f'ab815941
```

Note that the permanent flag (0x2) is ORed into the pointer, mask it out, and then use the !object extension to confirm that this is truly a silo context.

lkd> !object (0xffff988f'ab815941 & -2)
Object: ffff988fab815940 Type: (ffff988faaac9f20) PsSiloContextNonPaged

#### Creation of a server silo

When a server silo is created, a job object is first used, because as mentioned, silos are a feature of job objects. This is done through the standard CreateJobObject API, which was modified as part of the Anniversary Update to now have an associated job ID, or JID. The JID comes from the same pool of numbers as the process and thread ID (PID and TID), which is the client ID (CID) table. As such, a JID is unique among not only other jobs, but also other processes and threads. Additionally, a container GUID is automatically created.

Next, the SetInformationJobObject API is used, with the create silo information class. This results in the Silo flag being set inside of the EJOB executive object that represents the job, as well as the allocation of the SLS slot array we saw earlier in the Storage member of EJOB. At this point, we have an *application silo*. After this, the root object directory namespace is created with another information class and call to SetInformationJobObject. This new class requires the trusted computing base (TCB) privilege. As silos are normally created only by the Vmcompute service, this is to ensure that virtual object namespaces are not used maliciously to confuse applications and potentially break them. When this namespace is created, the object manager creates or opens a new Silos directory under the real host root (\) and appends the JID to create a new virtual root (e.g., \Silos\148\). It then creates the Kernel-Objects, ObjectTypes, GLOBALROOT, and DosDevices objects. The root is then stored as a silo context with whatever slot index is in PsObjectDirectorySiloContextSlot, which was allocated by the object manager at boot.

The next step is to convert this silo into a server silo, which is done with yet another call to Set-InformationJobObject and another information class. The PspConvertSiloToServerSilo function in the kernel now runs, which initializes the ESERVERSILO\_GLOBALS structure we saw earlier as part of the experiment dumping the PspHostSiloGlobals with the !silo command. This initializes the silo shared user data, API Set mapping, SystemRoot, and the various silo contexts, such as the one used by the SRM to identify the Lsass.exe process. While conversion is in progress, silo monitors that have registered and started their callbacks will now receive a notification, such that they can add their own silo context data.

The final step, then, is to "boot up" the server silo by initializing a new service session for it. You can think of this as session 0, but for the server silo. This is done through an ALPC message sent to Smss SmApiPort, which contains a handle to the job object created by Vmcompute, which has now become a server silo job object. Just like when creating a real user session, Smss will clone a copy of itself, except this time, the clone will be associated with the job object at creation time. This will attach this new Smss copy to all the containerized elements of the server silo. Smss will believe this is session 0, and will perform its usual duties, such as launching Csrss.exe, Wininit.exe, Lsass.exe, etc. The "boot-up" process will continue as normal, with Wininit.exe then launching the Service Control Manager (Services.exe), which will then launch all the automatic start services, and so on. New applications can now execute in the server silo, which will run with a logon session associated with a virtual service account LUID, as described earlier.

#### Ancillary functionality

You may have noticed that the short description we've seen so far would obviously not result in this "boot" process actually succeeding. For example, as part of its initialization, it will want to create a named pipe called ntsvcs, which will require communicating with \Device\NamedPipe, or as Services. exe sees it, \Silos\JID\Device\NamedPipe. But no such device object exists!

As such, in order for device driver access to function, drivers must be enlightened and register their own silo monitors, which will then use the notifications to create their own per-silo device objects. The kernel provides an API, PsAttachSiloToCurrentThread (and matching PsDetachSiloFromCurrent-Thread), which temporarily sets the Silo field of the ETHREAD object to the passed-in job object. This will cause all access, such as that to the object manager, to be treated as if it were coming from the silo. The named pipe driver, for example, can use this functionality to then create a NamedPipe object under the \Device namespace, which will now be part of \Silos\JID\.

Another question is this: If applications launch in essentially a "service" session, how can they be interactive and process input and output? First, it is important to note that there is no GUI possible or permitted when launching under a Windows container, and attempting to use Remote Desktop (RDP) to access a container will also be impossible. As such, only command-line applications can execute. But even such applications normally need an "interactive" session. So how can *those* function? The secret lies in a special host process, CExecSvc.exe, which implements the container execution service. This service uses a named pipe to communicate with the Docker and Vmcompute services on the host, and is used to launch the actual containerized applications in the session. It is also used to emulate the console functionality that is normally provided by Conhost.exe, piping the input and output through the named pipe to the actual command prompt (or PowerShell) window that was used in the first place to execute the docker command on the host. This service is also used when using commands such as docker cp to transfer files from or to the container.

#### **Container template**

Even if we take into account all the device objects that can be created by drivers as silos are created, there are still countless *other* objects, created by the kernel as well as other components, with which services running in session 0 are expected to communicate, and vice-versa. In user mode, there is no silo monitor system that would somehow allow components to support this need, and forcing every driver to always create a specialized device object to represent each silo wouldn't make sense.

If a silo wants to play music on the sound card, it shouldn't have to use a separate device object to represent the exact same sound card as every other silo would access, as well as the host itself. This would only be needed if, say, per-silo object sound isolation was required. Another example is AFD. Although it does use a silo monitor, this is to identify which user-mode service hosts the DNS client that it needs to talk to service kernel-mode DNS requests, which will be per-silo, and not to create separate \Silos\JID\Device\Afd objects, as there is a single network/Winsock stack in the system.

Beyond drivers and objects, the registry also contains various pieces of global information that must be visible and exist across all silos, which the VReg component can then provide sandboxing around.

To support all these needs, the silo namespace, registry, and file system are defined by a specialized container template file, which is located in %SystemRoot%\System32\Containers\wsc.def by default, once the Windows Containers feature is enabled in the Add/Remove Windows Features dialog box. This file describes the object manager and registry namespace and rules surrounding it, allowing the definition of symbolic links as needed to the true objects on the host. It also describes which job object, volume mount points, and network isolation policies should be used. In theory, future uses of silo objects in the Windows operating system could allow different template files to be used to provide other kinds of containerized environments. The following is an excerpt from wsc.def on a system for which containers are enabled:

```
<!-- This is a silo definition file for cmdserver.exe -->
<container>
    <namespace>
        <ob shadow="false">
            <symlink name="FileSystem" path="\FileSystem" scope="Global" />
            <symlink name="PdcPort" path="\PdcPort" scope="Global" />
            <symlink name="SeRmCommandPort" path="\SeRmCommandPort" scope="Global" />
            <symlink name="Registry" path="\Registry" scope="Global" />
            <symlink name="Driver" path="\Driver" scope="Global" />
            <objdir name="BaseNamedObjects" clonesd="\BaseNamedObjects" shadow="false"/>
            <objdir name="GLOBAL??" clonesd="\GLOBAL??" shadow="false">
                <!-- Needed to map directories from the host -->
                <symlink name="ContainerMappedDirectories" path="\
ContainerMappedDirectories" scope="Local" />
                <!-- Valid links to \Device -->
                <symlink name="WMIDataDevice" path="\Device\WMIDataDevice" scope="Local"
/>
                <symlink name="UNC" path="\Device\Mup" scope="Local" />
. . .
            </objdir>
            <objdir name="Device" clonesd="\Device" shadow="false">
                <symlink name="Afd" path="\Device\Afd" scope="Global" />
                <symlink name="ahcache" path="\Device\ahcache" scope="Global" />
                <symlink name="CNG" path="\Device\CNG" scope="Global" />
                <symlink name="ConDrv" path="\Device\ConDrv" scope="Global" />
. . .
        <registry>
            <load
                key="$SiloHivesRoot$\Silo$TopLayerName$Software_Base"
                path="$TopLayerPath$\Hives\Software_Base"
                ReadOnly="true"
                />
. . .
                <mkkey
                    name="ControlSet001"
                    clonesd="\REGISTRY\Machine\SYSTEM\ControlSet001"
                    />
                <mkkey
                    name="ControlSet001\Control"
                    clonesd="\REGISTRY\Machine\SYSTEM\ControlSet001\Control"
                    />
```

## Conclusion

This chapter examined the structure of processes, including the way processes are created and destroyed. We've seen how jobs can be used to manage a group of processes as a unit and how server silos can be used to usher in a new era of container support to Windows Server versions. The next chapter delves into threads—their structure and operation, how they're scheduled for execution, and the various ways they can be manipulated and used. This page intentionally left blank

#### CHAPTER 4

# Threads

This chapter explains the data structures and algorithms that deal with threads and thread scheduling in Windows. The first section shows how to create threads. Then the internals of threads and thread scheduling are described. The chapter concludes with a discussion of thread pools.

## **Creating threads**

Before discussing the internal structures used to manage threads, let's take a look at creating threads from an API perspective to give a sense of the steps and arguments involved.

The simplest creation function in user mode is CreateThread. This function creates a thread in the current process, accepting the following arguments:

- An optional security attributes structure This specifies the security descriptor to attach to the newly created thread. It also specifies whether the thread handle is to be created as inheritable. (Handle inheritance is discussed in Chapter 8, "System mechanisms," in Windows Internals Part 2.)
- An optional stack size If zero is specified, a default is taken from the executable's header. This always applies to the first thread in a user-mode process. (Thread's stack is discussed further in Chapter 5, "Memory management.")
- **A function pointer** This serves as the entry point for the new thread's execution.
- **An optional argument** This is to pass to the thread's function.
- Optional flags One controls whether the thread starts suspended (CREATE\_SUSPENDED). The
  other controls the interpretation of the stack size argument (initial committed size or maximum
  reserved size).

On successful completion, a non-zero handle is returned for the new thread and, if requested by the caller, the unique thread ID.

An extended thread creation function is CreateRemoteThread. This function accepts an extra argument (the first), which is a handle to a target process where the thread is to be created. You can use this function to inject a thread into another process. One common use of this technique is for a debugger to force a break in a debugged process. The debugger injects the thread, which immediately causes a breakpoint by calling the DebugBreak function. Another common use of this technique is for one process to obtain internal information about another process, which is easier when running within the target process context (for example, the entire address space is visible). This could be done for legitimate or malicious purposes.

To make CreateRemoteThread work, the process handle must have been obtained with enough access rights to allow such operation. As an extreme example, protected processes cannot be injected in this way because handles to such processes can be obtained with very limited rights only.

The final function worth mentioning here is CreateRemoteThreadEx, which is a superset of Create-Thread and CreateRemoteThread. In fact, the implementation of CreateThread and CreateRemote-Thread simply calls CreateRemoteThreadEx with the appropriate defaults. CreateRemoteThreadEx adds the ability to provide an attribute list (similar to the STARTUPINFOEX structure's role with an additional member over STARTUPINFO when creating processes). Examples of attributes include setting the ideal processor and group affinity (both discussed later in this chapter).

If all goes well, CreateRemoteThreadEx eventually calls NtCreateThreadEx in Ntdll.dll. This makes the usual transition to kernel mode, where execution continues in the executive function NtCreate-ThreadEx. There, the kernel mode part of thread creation occurs (described later in this chapter, in the "Birth of a thread" section).

Creating a thread in kernel mode is achieved with the PsCreateSystemThread function (documented in the WDK). This is useful for drivers that need independent work to be processes within the system process (meaning it's not associated with any particular process). Technically, the function can be used to create a thread under any process, which is less useful for drivers.

Exiting a kernel thread's function does not automatically destroy the thread object. Instead, drivers must call PsTerminateSystemThread from within the thread function to properly terminate the thread. Consequently, this function never returns.

## **Thread internals**

This section discusses the internal structures used within the kernel (and some in user mode) to manage a thread. Unless explicitly stated otherwise, you can assume that anything in this section applies to both user-mode threads and kernel-mode system threads.

## Data structures

At the operating-system (OS) level, a Windows thread is represented by an executive thread object. The executive thread object encapsulates an ETHREAD structure, which in turn contains a KTHREAD structure as its first member. These are illustrated in Figure 4-1 (ETHREAD) and Figure 4-2 (KTHREAD). The ETHREAD structure and the other structures it points to exist in the system address space. The only exception is the thread environment block (TEB), which exists in the process address space (similar to a PEB, because user-mode components need to access it).




FIGURE 4-1 Important fields of the executive thread structure (ETHREAD).




FIGURE 4-2 Important fields of the kernel thread structure (KTHREAD).

The Windows subsystem process (Csrss) maintains a parallel structure for each thread created in a Windows subsystem application, called the CSR\_THREAD. For threads that have called a Windows subsystem USER or GDI function, the kernel-mode portion of the Windows subsystem (Win32k.sys) maintains a per-thread data structure (W32THREAD) that the KTHREAD structure points to.

**Note** The fact that the executive, high-level, graphics-related, Win32k thread structure is pointed to by KTHREAD instead of the ETHREAD appears to be a layer violation or oversight in the standard kernel's abstraction architecture. The scheduler and other low-level components do not use this field.

Most of the fields illustrated in Figure 4-1 are self-explanatory. The first member of the ETHREAD is called Tcb. This is short for *thread control block*, which is a structure of type KTHREAD. Following that are the thread identification information, the process identification information (including a pointer to the owning process so that its environment information can be accessed), security information in the form of a pointer to the access token and impersonation information, fields relating to Asynchronous Local Procedure Call (ALPC) messages, pending I/O requests (IRPs) and Windows 10–specific fields related to power management (described in Chapter 6 , "I/O system") and CPU Sets (described later in this chapter). Some of these key fields are covered in more detail elsewhere in this book. For more details on the internal structure of an ETHREAD structure, you can use the kernel debugger dt command to display its format.

Let's take a closer look at two of the key thread data structures referred to in the preceding text: ETHREAD and KTHREAD. The KTHREAD structure (which is the Tcb member of the ETHREAD) contains information that the Windows kernel needs to perform thread scheduling, synchronization, and timekeeping functions.

#### **EXPERIMENT: Displaying ETHREAD and KTHREAD structures**

You can display the ETHREAD and KTHREAD structures with the dt command in the kernel debugger. The following output shows the format of an ETHREAD on a 64-bit Windows 10 system:

```
1kd> dt nt!_ethread
+0x000 Tcb : _KTHREAD
+0x5d8 CreateTime : _LARGE_INTEGER
+0x5e0 ExitTime : _LARGE_INTEGER
...
+0x7a0 EnergyValues : Ptr64 _THREAD_ENERGY_VALUES
+0x7a8 CmCellReferences : Uint4B
+0x7b0 SelectedCpuSets : Uint8B
+0x7b0 SelectedCpuSetsIndirect : Ptr64 Uint8B
+0x7b8 Silo : Ptr64 _EJ0B
```

You can display the KTHREAD with a similar command or by typing **dt nt!\_ETHREAD Tcb**, as shown in the experiment "Displaying the format of an EPROCESS structure" in Chapter 3, "Processes and jobs."

```
1kd> dt nt!_kthread
+0x000 Header : _DISPATCHER_HEADER
+0x018 SListFaultAddress : Ptr64 Void
+0x020 QuantumTarget : Uint8B
+0x028 InitialStack : Ptr64 Void
+0x030 StackLimit : Ptr64 Void
+0x038 StackBase : Ptr64 Void
```

```
+0x040 ThreadLock : Uint8B
+0x048 CycleTime : Uint8B
+0x050 CurrentRunTime : Uint4B
....
+0x5a0 ReadOperationCount : Int8B
+0x5a8 WriteOperationCount : Int8B
+0x5b0 OtherOperationCount : Int8B
+0x5b8 ReadTransferCount : Int8B
+0x5c0 WriteTransferCount : Int8B
+0x5c8 OtherTransferCount : Int8B
+0x5c0 QueuedScb : Ptr64 _KSCB
```

#### EXPERIMENT: Using the kernel debugger !thread command

The kernel debugger ! thread command dumps a subset of the information in the thread data structures. Some key elements of the information the kernel debugger displays can't be displayed by any utility, including the following information:

- Internal structure addresses
- Priority details
- Stack information
- The pending I/O request list

Image: explorer.exe

For threads in a wait state, the list of objects the thread is waiting for

To display thread information, use either the !process command (which displays all the threads of a process after displaying the process information) or the !thread command with the address of a thread object to display a specific thread.

Let's find all instances of explorer.exe:

```
1kd> !process 0 0 explorer.exe
PROCESS ffffe00017f3e7c0
SessionId: 1 Cid: 0b7c Peb: 00291000 ParentCid: 0c34
DirBase: 19b264000 ObjectTable: ffffc00007268cc0 HandleCount: 2248.
Image: explorer.exe
PROCESS ffffe00018c817c0
SessionId: 1 Cid: 23b0 Peb: 00256000 ParentCid: 03f0
DirBase: 2d4010000 ObjectTable: ffffc0001aef0480 HandleCount: 2208.
Image: explorer.exe
We'll select one of the instances and show its threads:
1kd> !process ffffe00018c817c0 2
PROCESS ffffe00018c817c0 2
PROCESS ffffe00018c817c0
SessionId: 1 Cid: 23b0 Peb: 00256000 ParentCid: 03f0
DirBase: 2d4010000 ObjectTable: ffffc0001 ParentCid: 03f0
DirBase: 2d4010000 ParentCid: 03f0
```

THREAD ffffe0001ac3c080 Cid 23b0.2b88 Teb: 000000000257000 Win32Thread: ffffe0001570ca20 WAIT: (UserRequest) UserMode Non-Alertable ffffe0001b6eb470 SynchronizationEvent

THREAD ffffe0001af10800 Cid 23b0.2f40 Teb: 000000000265000 Win32Thread: ffffe000156688a0 WAIT: (UserRequest) UserMode Non-Alertable ffffe000172ad4f0 SynchronizationEvent ffffe0001ac26420 SynchronizationEvent

THREAD ffffe0001b69a080 Cid 23b0.2f4c Teb: 000000000267000 Win32Thread: ffffe000192c5350 WAIT: (UserRequest) UserMode Non-Alertable ffffe00018d83c00 SynchronizationEvent ffffe0001552ff40 SynchronizationEvent

. . .

THREAD ffffe00023422080 Cid 23b0.3d8c Teb: 0000000003cf000 Win32Thread: ffffe0001eccd790 WAIT: (WrQueue) UserMode Alertable ffffe0001aec9080 QueueObject

THREAD ffffe00023f23080 Cid 23b0.3af8 Teb: 0000000003d1000 Win32Thread: 00000000000000 WAIT: (WrQueue) UserMode Alertable ffffe0001aec9080 QueueObject

THREAD ffffe000230bf800 Cid 23b0.2d6c Teb: 0000000003d3000 Win32Thread: 00000000000000 WAIT: (WrQueue) UserMode Alertable ffffe0001aec9080 QueueObject

THREAD ffffe0001f0b5800 Cid 23b0.3398 Teb: 0000000003e3000 Win32Thread: 0000000000000 WAIT: (UserRequest) UserMode Alertable ffffe0001d19d790 SynchronizationEvent ffffe00022b42660 SynchronizationTimer

The list of threads is truncated for the sake of space. Each thread shows its address (ETHREAD), which can be passed to the !thread command; its client ID (Cid)–process ID and thread ID (the process ID for all the preceding threads is the same, as they are part of the same explorer.exe process); the Thread Environment Block (TEB, discussed momentarily); and the thread state (most should be in the Wait state, with the reason for the wait in parentheses). The next line may show a list of synchronization objects the threads is waiting on.

To get more information on a specific thread, pass its address to the !thread command:

```
1kd> !thread ffffe0001d45d800
THREAD ffffe0001d45d800 Cid 23b0.452c Teb: 00000000026d000 Win32Thread:
ffffe0001aace630 WAIT: (UserRequest) UserMode Non-Alertable
    ffffe00023678350 NotificationEvent
    ffffe00022aeb370 Semaphore Limit 0xffff
    ffffe000225645b0 SynchronizationEvent
Not impersonating
DeviceMap ffffc00004f7ddb0
Owning Process ffffe00018c817c0 Image: explorer.exe
```

Attached Process N/A N/A Image: Wait Start TickCount Ticks: 270 (0:00:00:04.218) 7233205 Context Switch Count IdealProcessor: 7 6570 UserTime 00:00:00.078 KernelTime 00:00:00.046 Win32 Start Address Oc Stack Init ffffd000271d4c90 Current ffffd000271d3f80 Base ffffd000271d5000 Limit ffffd000271cf000 Call 00000000000000 Priority 9 BasePriority 8 PriorityDecrement 0 IoPriority 2 PagePriority 5 GetContextState failed, 0x80004001 Unable to get current machine context, HRESULT 0x80004001 : Args to Child Child-SP RetAddr : Call Site ffffd000'271d3fc0 fffff803'bef086ca : 00000000'00000000 00000000'00000001 00000000'0000000 0000000'00000000 : nt!KiSwapContext+0x76 ffffd000'271d4100 fffff803'bef08159 : ffffe000'1d45d800 fffff803'00000000 ffffe000'1aec9080 00000000'0000000f : nt!KiSwapThread+0x15a ffffd000'271d41b0 fffff803'bef09cfe : 00000000'00000000 00000000'00000000 ffffe000'000000f 00000000'00000003 : nt!KiCommitThreadWait+0x149 ffffd000'271d4240 fffff803'bf2a445d : ffffd000'00000003 ffffd000'271d43c0 00000000'0000000 fffff960'00000006 : nt!KeWaitForMultipleObjects+0x24e ffffd000'271d4300 fffff803'bf2fa246 : fffff803'bf1a6b40 ffffd000'271d4810 ffffd000'271d4858 ffffe000'20aeca60 : nt!ObWaitForMultipleObjects+0x2bd ffffd000'271d4810 fffff803'befdefa3 : 0000000'00000fa0 fffff803'bef02aad ffffe000'1d45d800 00000000'1e22f198 : nt!NtWaitForMultipleObjects+0xf6 ffffd000'271d4a90 00007ffe'f42b5c24 : 0000000'00000000 0000000'0000000 00000000'0000000 00000000'00000000 : nt!KiSystemServiceCopyEnd+0x13 (TrapFrame @ ffffd000'271d4b00) 00000000'1e22f178 0000000'00000000 : 0000000'00000000 0000000'0000000 0000000'0000000 0000000'00000000 : 0x00007ffe'f42b5c24

There is a lot of information about the thread, such as its priority, stack details, user and kernel times, and much more. You'll look at many of these details throughout this chapter and in Chapter 5, "Memory management," and Chapter 6, "I/O system."

#### **EXPERIMENT:** Viewing thread information with tlist

The following output is the detailed display of a process produced by using tlist in the Debugging Tools for Windows. (Make sure you run tlist from the same "bitness" as the target process.) Notice that the thread list shows Win32StartAddr. This is the address passed to the CreateThread function by the application. All the other utilities (except Process Explorer) that show the thread start address show the actual start address (a function in Ntdll.dll), not the application-specified start address.

The following output is from running tlist on Word 2016 (truncated):

```
C:\Dbg\x86>tlist winword
120 WINWORD.EXE Chapter04.docm - Word
CWD: C:\Users\pavely\Documents\
```

```
CmdLine: "C:\Program Files (x86)\Microsoft Office\Root\Office16\WINWORD.EXE" /n
"D:\OneDrive\WindowsInternalsBook\7thEdition\Chapter04\Chapter04.docm
  VirtualSize: 778012 KB PeakVirtualSize:
                                                832680 KB
  WorkingSetSize:185336 KB PeakWorkingSetSize:227144 KB
  NumberOfThreads: 45
  12132 Win32StartAddr:0x00921000 LastErr:0x00000000 State:Waiting
  15540 Win32StartAddr:0x6cc2fdd8 LastErr:0x00000000 State:Waiting
  7096 Win32StartAddr:0x6cc3c6b2 LastErr:0x0000006 State:Waiting
  17696 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  17492 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  4052 Win32StartAddr:0x70aa5cf7 LastErr:0x00000000 State:Waiting
  14096 Win32StartAddr:0x70aa41d4 LastErr:0x00000000 State:Waiting
  6220 Win32StartAddr:0x70aa41d4 LastErr:0x0000000 State:Waiting
  7204 Win32StartAddr:0x77c1c6d0 LastErr:0x0000000 State:Waiting
  1196 Win32StartAddr:0x6ea016c0 LastErr:0x00000057 State:Waiting
  8848 Win32StartAddr:0x70aa41d4 LastErr:0x0000000 State:Waiting
  3352 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  11612 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  17420 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  13612 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  15052 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
   12080 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  9456 Win32StartAddr:0x77c1c6d0 LastErr:0x00002f94 State:Waiting
  9808 Win32StartAddr:0x77c1c6d0 LastErr:0x0000000 State:Waiting
  16208 Win32StartAddr:0x77c1c6d0 LastErr:0x00000000 State:Waiting
  9396 Win32StartAddr:0x77c1c6d0 LastErr:0x0000000 State:Waiting
  2688 Win32StartAddr:0x70aa41d4 LastErr:0x0000000 State:Waiting
  9100 Win32StartAddr:0x70aa41d4 LastErr:0x00000000 State:Waiting
  18364 Win32StartAddr:0x70aa41d4 LastErr:0x00000000 State:Waiting
  11180 Win32StartAddr:0x70aa41d4 LastErr:0x00000000 State:Waiting
16.0.6741.2037 shp 0x00920000 C:\Program Files (x86)\Microsoft Office\Root\
Office16\WINWORD.EXE
10.0.10586.122 shp 0x77BF0000 C:\windows\SYSTEM32\ntd]].d]]
  10.0.10586.0 shp 0x75540000 C:\windows\SYSTEM32\KERNEL32.DLL
10.0.10586.162 shp 0x77850000 C:\windows\SYSTEM32\KERNELBASE.d]]
 10.0.10586.63 shp 0x75AF0000 C:\windows\SYSTEM32\ADVAPI32.dll
  10.0.10586.0 shp 0x68540000 C:\Windows\SYSTEM32\VssTrace.DLL
  10.0.10586.0 shp 0x5C390000 C:\Windows\SYSTEM32\adsldpc.dll
10.0.10586.122 shp 0x5DE60000 C:\Windows\SYSTEM32\taskschd.dll
  10.0.10586.0 shp 0x5E3F0000 C:\Windows\SYSTEM32\srmstormod.dll
  10.0.10586.0 shp 0x5DCA0000 C:\Windows\SYSTEM32\srmscan.dll
  10.0.10586.0 shp 0x5D2E0000 C:\Windows\SYSTEM32\msdrm.d]]
  10.0.10586.0 shp 0x711E0000 C:\Windows\SYSTEM32\srm_ps.dll
  10.0.10586.0 shp 0x56680000 C:\windows\System32\OpcServices.dll
                    0x5D240000 C:\Program Files (x86)\Common Files\Microsoft
Shared\Office16\WXPNSE.DLL
 16.0.6701.1023 shp 0x77E80000 C:\Program Files (x86)\Microsoft Office\Root\
Office16\GROOVEEX.DLL
  10.0.10586.0 shp 0x693F0000 C:\windows\system32\dataexchange.dll
```

The TEB, illustrated in Figure 4-3, is one of the data structures explained in this section that exists in the process address space (as opposed to the system space). Internally, it is made up of a header called the *Thread Information Block (TIB)*, which mainly existed for compatibility with OS/2 and Win9x applications. It also allows exception and stack information to be kept into a smaller structure when creating new threads by using an initial TIB.




FIGURE 4-3 Important fields of the thread environment block.

The TEB stores context information for the image loader and various Windows DLLs. Because these components run in user mode, they need a data structure writable from user mode. That's why this structure exists in the process address space instead of in the system space, where it would be writable only from kernel mode. You can find the address of the TEB with the kernel debugger ! thread command.

#### **EXPERIMENT: Examining the TEB**

You can dump the TEB structure with the !teb command in the kernel or user-mode debugger. The command can be used on its own to dump the TEB for the current thread of the debugger or with a TEB address to get it for an arbitrary thread. In case of a kernel debugger, the current process must be set before issuing the command on a TEB address so that the correct process context is used.

To view the TEB with a user-mode debugger, follow these steps. (You'll learn how to view the TEB using a kernel debugger in the next experiment.)

- 1. Open WinDbg.
- 2. Open the File menu and choose Run Executable.
- 3. Navigate to c:\windows\system32\Notepad.exe. The debugger should break at the initial breakpoint.
- **4.** Issue the **!teb** command to view the TEB of the only thread existing at the moment (the example is from 64 bit Windows):

0:000> !teb		
TEB at 000000ef125c1000		
ExceptionList:	000000000000000	
StackBase:	000000ef12290000	
StackLimit:	000000ef1227f000	
SubSystemTib:	000000000000000	
FiberData:	000000000001e00	
ArbitraryUserPointer:	000000000000000	
Self:	000000ef125c1000	
EnvironmentPointer:	000000000000000	
ClientId:	0000000000021bc . 00	0000000001b74
RpcHandle:	000000000000000	
Tls Storage:	00000266e572b600	
PEB Address:	000000ef125c0000	
LastErrorValue:	0	
LastStatusValue:	0	
Count Owned Locks:	0	
HardErrorMode:	0	

- 5. Enter the g command or press F5 to proceed with running Notepad.
- 6. In Notepad, open the **File** menu and choose **Open**. Then click **Cancel** to dismiss the Open File dialog box.
- 7. Press **Ctrl+Break** or open the **Debug** menu and choose **Break** to forcibly break into the process.
- Enter the ~ (tilde) command to show all threads in the process. You should see something like this:

```
0:005> ~

0 Id: 21bc.1b74 Suspend: 1 Teb: 000000ef'125c1000 Unfrozen

1 Id: 21bc.640 Suspend: 1 Teb: 000000ef'125e3000 Unfrozen

2 Id: 21bc.1a98 Suspend: 1 Teb: 000000ef'125e7000 Unfrozen

3 Id: 21bc.860 Suspend: 1 Teb: 000000ef'125c7000 Unfrozen

4 Id: 21bc.28e0 Suspend: 1 Teb: 000000ef'125c9000 Unfrozen

5 Id: 21bc.23e0 Suspend: 1 Teb: 000000ef'125e0000 Unfrozen

6 Id: 21bc.244c Suspend: 1 Teb: 000000ef'125eb000 Unfrozen

7 Id: 21bc.168c Suspend: 1 Teb: 000000ef'125ed000 Unfrozen
```

8 Id: 21bc.1c90 Suspend: 1 Teb: 000000ef'125ef000 Unfrozen
9 Id: 21bc.1558 Suspend: 1 Teb: 000000ef'125f1000 Unfrozen
10 Id: 21bc.a64 Suspend: 1 Teb: 000000ef'125f3000 Unfrozen
11 Id: 21bc.20c4 Suspend: 1 Teb: 000000ef'125f5000 Unfrozen
12 Id: 21bc.1524 Suspend: 1 Teb: 000000ef'125f7000 Unfrozen
13 Id: 21bc.1738 Suspend: 1 Teb: 000000ef'125f9000 Unfrozen
14 Id: 21bc.f48 Suspend: 1 Teb: 000000ef'125fb000 Unfrozen

- 15 Id: 21bc.17bc Suspend: 1 Teb: 000000ef'125fd000 Unfrozen
- 9. Each thread shows its TEB address. You can examine a specific thread by specifying its TEB address to the !teb command. Here's an example for thread 9 from the preceding output:

0:005> !teb 000000ef'125f1 TEB at 000000ef125f1000 ExceptionList: StackBase: StackLimit: SubSystemTib: FiberData: ArbitraryUserPointer: Self: EnvironmentPointer: ClientId: RpcHandle: Tls Storage:	0000000000000000 000000ef13400000 00000000000000000 0000000000000	. 000000000001558
RpcHandle:	000000000000000000000000000000000000000	. 000000000001558

**10.** Of course, it's possible to view the actual structure with the TEB address (truncated to conserve space):

```
0:005> dt ntdll!_teb 000000ef'125f1000

+0x000 NtTib : _NT_TIB

+0x038 EnvironmentPointer : (null)

+0x040 ClientId : _CLIENT_ID

+0x050 ActiveRpcHandle : (null)

+0x058 ThreadLocalStoragePointer : 0x00000266'ea1af280 Void

+0x060 ProcessEnvironmentBlock : 0x000000ef'125c0000 _PEB

+0x068 LastErrorValue : 0

+0x06c CountOfOwnedCriticalSections : 0

...

+0x1808 LockCount : 0

+0x180c WowTebOffset : 0n0

+0x1810 ResourceRetValue : 0x00000266'ea2a5e50 Void

+0x1818 ReservedForWdf : (null)

+0x1820 ReservedForCrt : 0

+0x1828 EffectiveContainerId : _GUID {0000000-0000-0000-00000000000}
```

#### EXPERIMENT: Examining the TEB with a kernel debugger

Follow these steps to view the TEB with a kernel debugger:

 Find the process for which a thread's TEB is of interest. For example, the following looks for explorer.exe processes and lists its threads with basic information (truncated):

```
lkd> !process 0 2 explorer.exe
PROCESS ffffe0012bea7840
    SessionId: 2 Cid: 10d8    Peb: 00251000 ParentCid: 10bc
    DirBase: 76e12000 ObjectTable: ffffc000e1ca0c80 HandleCount: <Data Not
Accessible>
    Image: explorer.exe
```

THREAD **ffffe0012bf53080** Cid 10d8.10dc Teb: **000000000252000** Win32Thread: ffffe0012c1532f0 WAIT: (WrUserRequest) UserMode Non-Alertable ffffe0012c257fe0 SynchronizationEvent

THREAD ffffe0012a30f080 Cid 10d8.114c Teb: 000000000266000 Win32Thread: ffffe0012c2e9a20 WAIT: (UserRequest) UserMode Alertable ffffe0012bab85d0 SynchronizationEvent

THREAD ffffe0012c8bd080 Cid 10d8.1178 Teb: 00000000026c000 Win32Thread: ffffe0012a801310 WAIT: (UserRequest) UserMode Alertable ffffe0012bfd9250 NotificationEvent ffffe0012c9512f0 NotificationEvent ffffe0012c876b80 NotificationEvent ffffe0012c010fe0 NotificationEvent ffffe0012d0ba7e0 NotificationEvent ffffe0012cf9d1e0 NotificationEvent

. . .

. . .

THREAD ffffe0012c8be080 Cid 10d8.1180 Teb: 000000000270000 Win32Thread: 0000000000000 WAIT: (UserRequest) UserMode Alertable ffff80156946440 NotificationEvent

THREAD ffffe0012afd4040 Cid 10d8.1184 Teb: 000000000272000 Win32Thread: ffffe0012c7c53a0 WAIT: (UserRequest) UserMode Non-Alertable ffffe0012a3dafe0 NotificationEvent ffffe0012c21ee70 Semaphore Limit 0xffff ffffe0012c8db6f0 SynchronizationEvent

THREAD ffffe0012c88a080 Cid 10d8.1188 Teb: 000000000274000 Win32Thread: 0000000000000 WAIT: (UserRequest) UserMode Alertable ffffe0012afd4920 NotificationEvent ffffe0012c87b480 SynchronizationEvent ffffe0012c87b400 SynchronizationEvent

2. If more than one explorer.exe process exists, select one arbitrarily for the following steps.

3. Each thread shows the address of its TEB. Because the TEB is in user space, the address has meaning only in the context of the relevant process. You need to switch to the process/thread as seen by the debugger. Select the first thread of explorer because its kernel stack is probably resident in physical memory. Otherwise, you'll get an error.

lkd> .thread /p ffffe0012bf53080
Implicit thread is now ffffe001'2bf53080
Implicit process is now ffffe001'2bea7840

**4.** This switches the context to the specified thread (and by extension, the process). Now you can use the ! teb command with the TEB address listed for that thread:

1kd>	> !teb 000000000252000	)	
TEB	at 000000000252000		
	ExceptionList:	000000000000000000000000000000000000000	
	StackBase:	000000000000000000	
	StackLimit:	0000000000c2000	
	SubSystemTib:	000000000000000000000000000000000000000	
	FiberData:	000000000001e00	
	ArbitraryUserPointer:	000000000000000000000000000000000000000	
	Self:	000000000252000	
	EnvironmentPointer:	000000000000000000000000000000000000000	
	ClientId:	0000000000010d8	. 0000000000010dc
	RpcHandle:	000000000000000000000000000000000000000	
	Tls Storage:	000000009f73f30	
	PEB Address:	000000000251000	
	LastErrorValue:	0	
	LastStatusValue:	c0150008	
	Count Owned Locks:	0	
	HardErrorMode:	0	

The CSR\_THREAD, illustrated in Figure 4-4 is analogous to the data structure of CSR\_PROCESS, but it's applied to threads. As you might recall, this is maintained by each Csrss process within a session and identifies the Windows subsystem threads running within it. CSR\_THREAD stores a handle that Csrss keeps for the thread, various flags, the client ID (thread ID and process ID), and a copy of the thread's creation time. Note that threads are registered with Csrss when they send their first message to Csrss, typically due to some API that requires notifying Csrss of some operation or condition.




FIGURE 4-4 Fields of the CSR thread.

#### **EXPERIMENT: Examining the CSR\_THREAD**

You can dump the CSR\_THREAD structure with the dt command in the kernel-mode debugger while the debugger context is set to a Csrss process. Follow the instructions in the experiment "Examining the CSR\_PROCESS" in Chapter 3 to perform this operation. Here is an example output from Windows 10 x64 system:

<pre>lkd&gt; dt csrss!_csr_thread</pre>		
+0x000 CreateTime	:	_LARGE_INTEGER
+0x008 Link	:	_LIST_ENTRY
+0x018 HashLinks	:	_LIST_ENTRY
+0x028 ClientId	:	_CLIENT_ID
+0x038 Process	:	Ptr64 _CSR_PROCESS
+0x040 ThreadHandle	:	Ptr64 Void
+0x048 Flags	:	Uint4B
+0x04c ReferenceCount	:	Int4B
+0x050 ImpersonateCount	:	Uint4B

Finally, the W32THREAD structure, illustrated in Figure 4-5, is analogous to the data structure of W32PROCESS, but it's applied to threads This structure mainly contains information useful for the GDI subsystem (brushes and Device Context attributes) and DirectX, as well as for the User Mode Print Driver (UMPD) framework that vendors use to write user-mode printer drivers. Finally, it contains a rendering state useful for desktop compositing and anti-aliasing.




FIGURE 4-5 Fields of the Win32k thread.

## Birth of a thread

A thread's life cycle starts when a process (in the context of some thread, such as the thread running the main function) creates a new thread. The request filters down to the Windows executive, where the process manager allocates space for a thread object and calls the kernel to initialize the thread control block (KTHREAD). As mentioned, the various thread-creation functions eventually end up at CreateRemote-ThreadEx. The following steps are taken inside this function in Kernel32.dll to create a Windows thread:

- 1. The function converts the Windows API parameters to native flags and builds a native structure describing object parameters (OBJECT\_ATTRIBUTES, described in Chapter 8 in Part 2).
- 2. It builds an attribute list with two entries: client ID and TEB address. (For more information on attribute lists, see the section "Flow of CreateProcess" in Chapter 3.)
- 3. It determines whether the thread is created in the calling process or another process indicated by the handle passed in. If the handle is equal to the pseudo handle returned from GetCurrent-Process (with a value of -1), then it's the same process. If the process handle is different, it could still be a valid handle to the same process, so a call is made to NtQueryInformation-Process (in Ntdll) to find out whether that is indeed the case.
- **4.** It calls NtCreateThreadEx (in Ntdll) to make the transition to the executive in kernel mode and continues inside a function with the same name and arguments.
- 5. NtCreateThreadEx (inside the executive) creates and initializes the user-mode thread context (its structure is architecture-specific) and then calls PspCreateThread to create a suspended executive thread object. (For a description of the steps performed by this function, see the descriptions of stage 3 and stage 5 in Chapter 3 in the section "Flow of CreateProcess.") Then the function returns, eventually ending back in user mode at CreateRemoteThreadEx.
- **6.** CreateRemoteThreadEx allocates an activation context for the thread used by side-by-side assembly support. It then queries the activation stack to see if it requires activation and activates it if needed. The activation stack pointer is saved in the new thread's TEB.
- 7. Unless the caller created the thread with the CREATE\_SUSPENDED flag set, the thread is now resumed so that it can be scheduled for execution. When the thread starts running, it executes the steps described in Chapter 3 in the section "Stage 7: performing process initialization in the context of the new process" before calling the actual user's specified start address.
- 8. The thread handle and the thread ID are returned to the caller.

# **Examining thread activity**

Examining thread activity is especially important if you are trying to determine why a process that is hosting multiple services is running (such as Svchost.exe, Dllhost.exe, or Lsass.exe) or why a process has stopped responding.

There are several tools that expose various elements of the state of Windows threads: WinDbg (in user-process attach and kernel-debugging mode), Performance Monitor, and Process Explorer. (The tools that show thread-scheduling information are listed in the section "Thread scheduling.")

To view the threads in a process with Process Explorer, select a process and double-click it to open its Properties dialog box. Alternatively, right-click the process and select the **Properties** menu item.

Then click the **Threads** tab. This tab shows a list of the threads in the process and four columns of information for each thread: its ID, the percentage of CPU consumed (based on the refresh interval configured), the number of cycles charged to the thread, and the thread start address. You can sort by any of these four columns.

New threads that are created are highlighted in green, and threads that exit are highlighted in red. (To configure the highlight duration, open the **Options** menu and choose **Difference Highlight Dura-tion**.) This might be helpful to discover unnecessary thread creation occurring in a process. (In general, threads should be created at process startup, not every time a request is processed inside a process.)

As you select each thread in the list, Process Explorer displays the thread ID, start time, state, CPU time counters, number of cycles charged, number of context switches, the ideal processor and its group, and the I/O priority, memory priority, and base and current (dynamic) priority. There is a Kill button, which terminates an individual thread, but this should be used with extreme care. Another option is the Suspend button, which prevents the thread from forward execution and thus prevents a runaway thread from consuming CPU time. However, this can also lead to deadlocks and should be used with the same care as the Kill button. Finally, the Permissions button allows you to view the security descriptor of the thread. (See Chapter 7, "Security," for more information on security descriptors.)

Unlike Task Manager and all other process/processor monitoring tools, Process Explorer uses the clock cycle counter designed for thread run-time accounting (described later in this chapter) instead of the clock interval timer, so you will see a significantly different view of CPU consumption using Process Explorer. This is because many threads run for such a short time that they are seldom (if ever) the currently running thread when the clock interval timer interrupt occurs. As a result, they are not charged for much of their CPU time, leading clock-based tools to perceive a CPU usage of 0 percent. On the other hand, the total number of clock cycles represents the actual number of processor cycles that each thread in the process accrued. It is independent of the clock interval timer's resolution because the count is maintained internally by the processor at each cycle and updated by Windows at each interrupt entry. (A final accumulation is done before a context switch.)

The thread start address is displayed in the form *module! function*, where *module* is the name of the .EXE or .DLL. The function name relies on access to symbol files for the module (see the section "Experiment: Viewing process details with Process Explorer" in Chapter 1, "Concepts and tools"). If you are unsure what the module is, click the **Module** button to open an Explorer file Properties dialog box for the module containing the thread's start address (for example, the .EXE or .DLL).

**Note** For threads created by the Windows CreateThread function, Process Explorer displays the function passed to CreateThread, not the actual thread start function. This is because all Windows threads start at a common thread startup wrapper function (Rt1UserThreadStart in Ntdll.dll). If Process Explorer showed the actual start address, most threads in processes would appear to have started at the same address, which would not be helpful in trying to understand what code the thread was executing. However, if Process Explorer can't query the user-defined startup address (such as in the case of a protected process), it will show the wrapper function, so you will see all threads starting at Rt1UserThreadStart.

The thread start address displayed might not be enough information to pinpoint what the thread is doing and which component within the process is responsible for the CPU consumed by the thread. This is especially true if the thread start address is a generic startup function—for example, if the function name does not indicate what the thread is actually doing. In this case, examining the thread stack might answer the question. To view the stack for a thread, double-click the thread of interest (or select it and click the **Stack** button). Process Explorer displays the thread's stack (both user and kernel, if the thread was in kernel mode).

**Note** While the user-mode debuggers (WinDbg, Ntsd, and Cdb) permit you to attach to a process and display the user stack for a thread, Process Explorer shows both the user and kernel stack in one easy click of a button. You can also examine user and kernel thread stacks using WinDbg in local kernel debugging mode, as the next two experiments demonstrate.

When looking at 32-bit processes running on 64-bit systems as a Wow64 process (see Chapter 8 in Part 2 for more information on Wow64), Process Explorer shows both the 32-bit and 64-bit stack for threads. Because at the time of the real (64 bit) system call, the thread has been switched to a 64-bit stack and context, simply looking at the thread's 64-bit stack would reveal only half the story—the 64-bit part of the thread, with Wow64's thunking code. So, when examining Wow64 processes, be sure to take into account both the 32-bit and 64-bit stacks.

#### EXPERIMENT: Viewing a thread stack with a user-mode debugger

Follow these steps to attach WinDbg to a process and view thread information and its stack:

1. Run notepad.exe and WinDbg.exe.

- 2. In WinDbg, open the File menu and select Attach to Process.
- Find the notepad.exe instance and click OK to attach. The debugger should break into Notepad.
- 4. List the existing threads in the process with the ~ command. Each thread shows its debugger ID, the client ID (*ProcessID. ThreadID*), its suspend count (this should be 1 most of the time, as it is suspended because of the breakpoint), the TEB address, and whether it has been frozen using a debugger command.

```
0:005> ~

0 Id: 612c.5f68 Suspend: 1 Teb: 00000022'41da2000 Unfrozen

1 Id: 612c.5564 Suspend: 1 Teb: 00000022'41da4000 Unfrozen

2 Id: 612c.4f88 Suspend: 1 Teb: 00000022'41da8000 Unfrozen

3 Id: 612c.cf4 Suspend: 1 Teb: 00000022'41da8000 Unfrozen

4 Id: 612c.cf4 Suspend: 1 Teb: 00000022'41da8000 Unfrozen

5 Id: 612c.9f8 Suspend: 1 Teb: 00000022'41db0000 Unfrozen
```

 Notice the dot preceding thread 5 in the output. This is the current debugger thread. Issue the k command to view the call stack:

```
0:005> k

# Child-SP RetAddr Call Site

00 0000022'421ff7e8 00007ff8'504d9031 ntdll!DbgBreakPoint

01 0000022'421ff7f0 00007ff8'501b8102 ntdll!DbgUiRemoteBreakin+0x51

02 00000022'421ff820 00007ff8'5046c5b4 KERNEL32!BaseThreadInitThunk+0x22

03 00000022'421ff850 00000000 ntdll!RtllserThreadStart+0x34
```

6. The debugger injected a thread into Notepad's process that issues a breakpoint instruction (DbgBreakPoint). To view the call stack of another thread, use the ~nk command, where n is the thread number as seen by WinDbg. (This does not change the current debugger thread.) Here's an example for thread 2:

```
0:005> ~2k

# Child-SP RetAddr Call Site

00 00000022'41f7f9e8 00007ff8'5043b5e8 ntdll!ZwWaitForWorkViaWorkerFactory+0x14

01 00000022'41f7f9f0 00007ff8'501b8102 ntdll!TppWorkerThread+0x298

02 00000022'41f7fe00 00007ff8'5046c5b4 KERNEL32!BaseThreadInitThunk+0x22

03 00000022'41f7fe30 0000000'0000000 ntdll!RtlUserThreadStart+0x34
```

**7.** To switch the debugger to another thread, use the ~*ns* command (again, *n* is the thread number). Let's switch to thread 0 and show its stack:

```
0:005> ~0s
USER32!ZwUserGetMessage+0x14:
00007ff8'502e21d4 c3 ret
0:000> k
# Child-SP RetAddr Call Site
00 0000022'41e7f048 00007ff8'502d3075 USER32!ZwUserGetMessage+0x14
01 00000022'41e7f050 00007ff6'88273bb3 USER32!GetMessage+0x25
02 0000022'41e7f080 00007ff6'882890b5 notepad!WinMain+0x27b
03 0000022'41e7f180 00007ff8'341229b8 notepad!WinMain+0x27b
03 0000022'41e7f9f0 00007ff8'5046c5b4 KERNEL32!BaseThreadInitThunk+0x22
05 0000022'41e7fa20 0000000'0000000 ntdll!RtlUserThreadStart+0x34
```

 Note that even though a thread might be in kernel mode at the time, a user-mode debugger shows its last function that's still in user mode (ZwUserGetMessage in the preceding output).

#### EXPERIMENT: Viewing a thread stack with a local kernel-mode debugger

In this experiment, you'll use a local kernel debugger to view a thread's stack (both user mode and kernel mode). The experiment uses one of Explorer's threads, but you can try it with other processes or threads.

1. Show all the processes running the image explorer.exe. (Note that you may see more than one instance of Explorer if the Launch Folder Windows in a Separate Process

option in Explorer options is selected. One process manages the desktop and taskbar, while the other manages Explorer windows.)

```
lkd> !process 0 0 explorer.exe
   PROCESS ffffe00197398080
        SessionId: 1 Cid: 18a0 Peb: 00320000 ParentCid: 1840
       DirBase: 17c028000 ObjectTable: ffffc000bd4aa880 HandleCount: <Data
   Not Accessible>
       Image: explorer.exe
    PROCESS ffffe00196039080
        SessionId: 1 Cid: 1f30 Peb: 00290000 ParentCid: 0238
       DirBase: 24cc7b000 ObjectTable: ffffc000bbbef740 HandleCount: <Data
   Not Accessible>
       Image: explorer.exe
2. Select one instance and show its thread summary:
   1kd> !process ffffe00196039080 2
    PROCESS ffffe00196039080
        SessionId: 1 Cid: 1f30 Peb: 00290000 ParentCid: 0238
       DirBase: 24cc7b000 ObjectTable: ffffc000bbbef740 HandleCount: <Data
   Not Accessible>
       Image: explorer.exe
            THREAD ffffe0019758f080 Cid 1f30.0718 Teb: 000000000291000
   Win32Thread: ffffe001972e3220 WAIT: (UserRequest) UserMode Non-Alertable
                ffffe00192c08150 SynchronizationEvent
           THREAD ffffe00198911080 Cid 1f30.1aac Teb: 0000000002a1000
   Win32Thread: ffffe001926147e0 WAIT: (UserRequest) UserMode Non-Alertable
               ffffe00197d6e150 SynchronizationEvent
                ffffe001987bf9e0 SvnchronizationEvent
           THREAD ffffe00199553080 Cid 1f30.1ad4 Teb: 0000000002b1000
   Win32Thread: ffffe0019263c740 WAIT: (UserRequest) UserMode Non-Alertable
               ffffe0019ac6b150 NotificationEvent
                ffffe0019a7da5e0 SynchronizationEvent
           THREAD ffffe0019b6b2800 Cid 1f30.1758 Teb: 0000000002bd000
   Win32Thread: 00000000000000 WAIT: (Suspended) KernelMode Non-Alertable
    SuspendCount 1
               ffffe0019b6b2ae0 NotificationEvent
3. Switch to the context of the first thread in the process (you can select other threads):
   lkd> .thread /p /r ffffe0019758f080
   Implicit thread is now ffffe001'9758f080
   Implicit process is now ffffe001'96039080
```

Loading User Symbols

**4.** Now look at the thread to show its details and its call stack (addresses are truncated in the shown output):

```
lkd> !thread ffffe0019758f080
THREAD ffffe0019758f080 Cid 1f30.0718 Teb: 000000000291000 Win32Thread :
ffffe001972e3220 WAIT : (UserRequest)UserMode Non - Alertable
ffffe00192c08150 SynchronizationEvent
Not impersonating
Not ImpersonatingDeviceMapffffc000b77f1f30Owning Processffffc00196039080Attached ProcessN / AWait Start TickCount17415276Context Switch Count2788UserTime00 : 00 : 00 : 00.031
                          00 : 00 : 00.000
KernelTime
*** WARNING : Unable to verify checksum for C : \windows\explorer.exe
Win32 Start Address explorer!wWinMainCRTStartup(0x00007ff7b80de4a0)
Stack Init ffffd0002727cc90 Current ffffd0002727bf80
Base ffffd0002727d000 Limit ffffd00027277000 Call 00000000000000
Priority 8 BasePriority 8 PriorityDecrement 0 IoPriority 2 PagePriority 5
... Call Site
... nt!KiSwapContext + 0x76
... nt!KiSwapThread + 0x15a
... nt!KiCommitThreadWait + 0x149
... nt!KeWaitForSingleObject + 0x375
... nt!ObWaitForMultipleObjects + 0x2bd
... nt!NtWaitForMultipleObjects + 0xf6
... nt!KiSystemServiceCopyEnd + 0x13 (TrapFrame @ ffffd000'2727cb00)
... ntdll!ZwWaitForMultipleObjects + 0x14
... KERNELBASE!WaitForMultipleObjectsEx + 0xef
... USER32!RealMsgWaitForMultipleObjectsEx + 0xdb
... USER32!MsgWaitForMultipleObjectsEx + 0x152
... explorerframe!SHProcessMessagesUntilEventsEx + 0x8a
... explorerframe!SHProcessMessagesUntilEventEx + 0x22
... explorerframe!CExplorerHostCreator::RunHost + 0x6d
... explorer!wWinMain + 0xa04fd
... explorer!__wmainCRTStartup + 0x1d6
```

## Limitations on protected process threads

As discussed in Chapter 3, protected processes (classic protected or PPL) have several limitations in terms of which access rights will be granted, even to the users with the highest privileges on the system. These limitations also apply to threads inside such a process. This ensures that the actual code running inside the protected process cannot be hijacked or otherwise affected through standard Windows functions, which require access rights that are not granted for protected process threads. In fact, the only permissions granted are THREAD\_SUSPEND\_RESUME and THREAD\_SET/QUERY\_LIMITED\_INFORMATION.

# **EXPERIMENT:** Viewing protected process thread information with Process Explorer

In this experiment, you'll view protected process thread information. Follow these steps:

- 1. Find any protected or PPL process, such as the Audiodg.exe or Csrss.exe process inside the process list.
- 2. Open the process's Properties dialog box and click the **Threads** tab.

Image	Perfor	mance	Pe	erforman	ce Grap	h	Disk an	d Network
GPU Graph	Threa	ads	TCP/IP	Sec	urity	Enviro	onment	String
Count: 10								
TID	CPU	CSw	itch D	Start A	ddress			
876	< 0.01		2	RtIUse	Thread	Start		
708	< 0.01		1					
864				<b>IRtIUse</b>				
1364 3324				<b>IRtIUse</b>				_
880				IRtIUse				
792				Rtillse	Thread	Start		
792 796				IRtIUse 0x0	Thread	Start		
					Thread	Start		
796 800				0x0 !RtlUse	Thread	Start		2
796 800 952		3324		0x0 !RtlUse	Thread	Start		Module
796 800 952		1000	:32 16-	0x0 !RtiUse !RtiUse	Thread	IStart IStart		-
796 800 952		17:08		0x0 !RtiUse !RtiUse May-16	r Thread	IStart IStart	13	Module
796 800 952		17:08 Wait:	:32 16-	0x0 !RtiUse !RtiUse May-16	Thread Thread	IStart IStart Stack	13	Module
796 800 952		17:08 Wait: 0:00:0	:32 16- WrLpcRe	0x0 !Rt/Use !Rt/Use May-16 ceive	Thread Thread	Start Start Stack	13	Module
796 800 952 Chread ID: Start Time: State: Kernel Time:		17:08 Wait: 0:00:0	:32 16- WrLpcRe 00.609 00.187	0x0 !Rt/Use !Rt/Use May-16 ceive	Base F Dynan I/O Pr	Start Start Stack	13 ty: 14 n/	Module B H a
796 800 952 Chread ID: Start Time: State: Kernel Time: User Time:		17:08 Wait: 0:00:0	:32 16- WrLpcRe 00.609 00.187	0x0 !Rt/Use !Rt/Use May-16 ceive	Base F Dynan I/O Pr Memoi	IStart IStart Stack Priority: nic Priorit Iority:	15 ty: 14 n/ ty: n/	Module B H a

- 3. Process Explorer doesn't show the Win32 thread start address. Instead, it displays the standard thread start wrapper inside Ntdll.dll. If you click the **Stack** button, you'll get an error, because Process Explorer needs to read the virtual memory inside the protected process, which it can't do.
- 4. Note that although the base and dynamic priorities are shown, the I/O and memory priorities are not (nor is Cycles), which is another example of the limited access right THREAD\_QUERY\_LIMITED\_INFORMATION versus full query information access right (THREAD\_QUERY\_INFORMATION).
- **5.** Try to kill a thread inside a protected process. When you do, notice yet another accessdenied error: recall the lack of THREAD\_TERMINATE access.

# Thread scheduling

This section describes the Windows scheduling policies and algorithms. The first subsection provides a condensed description of how scheduling works on Windows and a definition of key terms. Then Windows priority levels are described from both the Windows API and the Windows kernel points of view. After a review of the relevant Windows utilities and tools that relate to scheduling, the detailed data structures and algorithms that make up the Windows scheduling system are presented, including a description of common scheduling scenarios and how thread selection, as well as processor selection, occurs.

## **Overview of Windows scheduling**

Windows implements a priority-driven, preemptive scheduling system. At least one of the highestpriority runnable (ready) threads always runs, with the caveat that certain high-priority threads ready to run might be limited by the processors on which they might be allowed or preferred to run on phenomenon called *processor affinity*. Processor affinity is defined based on a given processor group, which collects up to 64 processors. By default, threads can run only on available processors within the processor group associated with the process. (This is to maintain compatibility with older versions of Windows, which supported only 64 processors). Developers can alter processor affinity by using the appropriate APIs or by setting an affinity mask in the image header, and users can use tools to change affinity at run time or at process creation. However, although multiple threads in a process can be associated with different groups, a thread on its own can run only on the processors available within its assigned group. Additionally, developers can choose to create group-aware applications, which use extended scheduling APIs to associate logical processors on different groups with the affinity of their threads. Doing so converts the process into a multigroup process that can theoretically run its threads on any available processor within the machine.

After a thread is selected to run, it runs for an amount of time called a *quantum*. A quantum is the length of time a thread is allowed to run before another thread at the same priority level is given a turn to run. Quantum values can vary from system to system and process to process for any of three reasons:

- System configuration settings (long or short quantums, variable or fixed quantums, and priority separation)
- Foreground or background status of the process
- Use of the job object to alter the quantum

These details are explained in the "Quantum" section later in this chapter.

A thread might not get to complete its quantum, however, because Windows implements a preemptive scheduler. That is, if another thread with a higher priority becomes ready to run, the currently running thread might be preempted before finishing its time slice. In fact, a thread can be selected to run next and be preempted before even beginning its quantum!

The Windows scheduling code is implemented in the kernel. There's no single "scheduler" module or routine, however. The code is spread throughout the kernel in which scheduling-related events occur.

The routines that perform these duties are collectively called the kernel's *dispatcher*. The following events might require thread dispatching:

- A thread becomes ready to execute—for example, a thread has been newly created or has just been released from the wait state.
- A thread leaves the running state because its time quantum ends, it terminates, it yields execution, or it enters a wait state.
- A thread's priority changes, either because of a system service call or because Windows itself changes the priority value.
- A thread's processor affinity changes so that it will no longer run on the processor on which it was running.


At each of these junctions, Windows must determine which thread should run next on the logical processor that was running the thread, if applicable, or on which logical processor the thread should now run. After a logical processor has selected a new thread to run, it eventually performs a context switch to it. A *context switch* is the procedure of saving the volatile processor state associated with a running thread, loading another thread's volatile state, and starting the new thread's execution.

As noted, Windows schedules at the thread granularity level. This approach makes sense when you consider that processes don't run; rather, they only provide resources and a context in which their threads run. Because scheduling decisions are made strictly on a thread basis, no consideration is given to what process the thread belongs to. For example, if process A has 10 runnable threads, process B has 2 runnable threads, and all 12 threads are at the same priority, each thread would theoretically receive one-twelfth of the CPU time. That is, Windows wouldn't give 50 percent of the CPU to process A and 50 percent to process B.

# **Priority levels**

To understand the thread-scheduling algorithms, one must first understand the priority levels that Windows uses. As illustrated in Figure 4-6, Windows uses 32 priority levels internally, ranging from 0 to 31 (31 is the highest). These values divide up as follows:

- Sixteen real-time levels (16 through 31)
- Sixteen variable levels (0 through 15), out of which level 0 is reserved for the zero page thread (described in Chapter 5).





Thread priority levels are assigned from two different perspectives: those of the Windows API and those of the Windows kernel. The Windows API first organizes processes by the priority class to which they are assigned at creation (the numbers in parentheses represent the internal PROCESS\_PRIORITY\_ CLASS index recognized by the kernel):

- Real-Time (4)
- High (3)
- Above Normal (6)
- Normal (2)
- Below Normal (5)
- Idle (1)

The Windows API SetPriorityClass allows changing a process's priority class to one of these levels.

It then assigns a relative priority of the individual threads within those processes. Here, the numbers represent a priority delta that is applied to the process base priority:

- Time-Critical (15)
- Highest (2)
- Above-Normal (1)
- Normal (0)
- Below-Normal (–1)
- Lowest (-2)
- Idle (–15)

Time-Critical and Idle levels (+15 and –15) are called *saturation values* and represent specific levels that are applied rather than true offsets. These values can be passed to the SetThreadPriority Windows API to change a thread's relative priority.

Therefore, in the Windows API, each thread has a base priority that is a function of its process priority class and its relative thread priority. In the kernel, the process priority class is converted to a base priority by using the PspPriorityTable global array and the PROCESS\_PRIORITY\_CLASS indices shown earlier, which sets priorities of 4, 8, 13, 24, 6, and 10, respectively. (This is a fixed mapping that cannot be changed.) The relative thread priority is then applied as a differential to this base priority. For example, a Highest thread will receive a thread base priority of two levels higher than the base priority of its process.

This mapping from Windows priority to internal Windows numeric priority is shown graphically in Figure 4-7 and textually in Table 4-1.




FIGURE 4-7 A graphic view of available thread priorities from a Windows API perspective.

Priority Class Relative Priority	Real-Time	High	Above-Normal	Normal	Below-Normal	Idle
Time Critical (+Saturation)	31	15	15	15	15	15
Highest (+2)	26	15	12	10	8	6
Above Normal (+1)	25	14	11	9	7	5
Normal (0)	24	13	10	8	6	4
Below Normal (-1)	23	12	9	7	5	3
Lowest (-2)	22	11	8	6	4	2
Idle (–Saturation)	16	1	1	1	1	1

TABLE 4-1 Mapping Windows kernel priorities to the Windows API

You'll note that the Time-Critical and Idle relative thread priorities maintain their respective values regardless of the process priority class (unless it is Real-Time). This is because the Windows API requests saturation of the priority from the kernel, by passing in +16 or –16 as the requested relative priority. The formula used to get these values is as follows (HIGH\_PRIORITY equals 31):

```
If Time-Critical: ((HIGH_PRIORITY+1) / 2
```

```
If Idle: -((HIGH_PRIORITY+1) / 2
```

These values are then recognized by the kernel as a request for saturation, and the Saturation field in KTHREAD is set. For positive saturation, this causes the thread to receive the highest possible priority within its priority class (dynamic or real-time); for negative saturation, it's the lowest possible one. Additionally, future requests to change the base priority of the process will no longer affect the base priority of these threads because saturated threads are skipped in the processing code. As shown in Table 4-1, threads have seven levels of possible priorities to set as viewed from the Windows API (six levels for the High priority class). The Real-Time priority class actually allows setting all priority levels between 16 and 31 (as shown in Figure 4-7). The values not covered by the standard constants shown in the table can be specified with the values -7, -6, -5, -4, -3, 3, 4, 5, and 6 as an argument to SetThreadPriority. (See the upcoming section "Real-Time priorities" for more information.)

Regardless of how the thread's priority came to be by using the Windows API (a combination of process priority class and a relative thread priority), from the point of view of the scheduler, only the final result matters. For example, priority level 10 can be obtained in two ways: a Normal priority class process (8) with a thread relative priority of Highest (+2), or an Above-Normal priority class process (10) and a Normal thread relative priority (0). From the scheduler's perspectives, these settings lead to the same value (10), so these threads are identical in terms of their priority.

Whereas a process has only a single base priority value, each thread has two priority values: current (dynamic) and base. Scheduling decisions are made based on the current priority. As explained in the upcoming section called "Priority boosts," under certain circumstances, the system increases the priority of threads in the dynamic range (1 through 15) for brief periods. Windows never adjusts the priority of threads in the Real-Time range (16 through 31), so they always have the same base and current priority.

A thread's initial base priority is inherited from the process base priority. A process, by default, inherits its base priority from the process that created it. You can override this behavior on the Create-Process function or by using the command-line start command. You can also change a process priority after it is created by using the SetPriorityClass function or by using various tools that expose that function, such as Task Manager or Process Explorer. (Right-click on the process and choose a new priority class.) For example, you can lower the priority of a CPU-intensive process so that it does not interfere with normal system activities. Changing the priority of a process changes the thread priorities up or down, but their relative settings remain the same.

Normally, user applications and services start with a normal base priority, so their initial thread typically executes at priority level 8. However, some Windows system processes (such as the Session manager, Service Control Manager, and local security authentication process) have a base process priority slightly higher than the default for the Normal class (8). This higher default value ensures that the threads in these processes will all start at a higher priority than the default value of 8.

#### **Real-Time priorities**

You can raise or lower thread priorities within the dynamic range in any application. However, you must have the increase scheduling priority privilege (SeIncreaseBasePriorityPrivilege) to enter the Real-Time range. Be aware that many important Windows kernel-mode system threads run in the Real-Time priority range, so if threads spend excessive time running in this range, they might block critical system functions (such as in the memory manager, cache manager, or some device drivers).

Using the standard Windows APIs, once a process has entered the Real-Time range, all its threads (even Idle ones) must run at one of the Real-Time priority levels. It is thus impossible to mix real-time and dynamic threads within the same process through standard interfaces. This is because the SetThread-Priority API calls the native NtSetInformationThread API with the ThreadBasePriority information

class, which allows priorities to remain only in the same range. Furthermore, this information class allows priority changes only in the recognized Windows API deltas of -2 to 2 (or Time-Critical/Idle) unless the request comes from CSRSS or another real-time process. In other words, this means that a real-time process can pick thread priorities anywhere between 16 and 31, even though the standard Windows API relative thread priorities would seem to limit its choices based on the table that was shown earlier.

As mentioned, calling SetThreadPriority with one of a set of special values causes a call to NtSetInformationThread with the ThreadActualBasePriority information class, the kernel base priority for the thread can be directly set, including in the dynamic range for a real-time process.

**Note** The name *real-time* does not imply that Windows is a real-time OS in the common definition of the term. This is because Windows doesn't provide true, real-time OS facilities, such as guaranteed interrupt latency or a way for threads to obtain a guaranteed execution time. The term *real-time* really just means "higher than all the others."

#### Using tools to interact with priority

You can change (and view) the base-process priority with Task Manager and Process Explorer. You can kill individual threads in a process with Process Explorer (which should be done, of course, with extreme care).

You can view individual thread priorities with Performance Monitor, Process Explorer, or WinDbg. Although it might be useful to increase or decrease the priority of a process, it typically does not make sense to adjust individual thread priorities within a process because only a person who thoroughly understands the program (in other words, the developer) would understand the relative importance of the threads within the process.

The only way to specify a starting priority class for a process is with the start command in the Windows command prompt. If you want to have a program start every time with a specific priority, you can define a shortcut to use the start command by beginning the command with cmd /c. This runs the command prompt, executes the command on the command line, and terminates the command prompt. For example, to run Notepad in the Idle-process priority, the command is cmd /c start/low Notepad.exe.

#### EXPERIMENT: Examining and specifying process and thread priorities

To examine and specify process and thread priorities, follow these steps:

- 1. Run notepad.exe normally—for example, by typing Notepad in a command window.
- 2. Open Task Manager and click to the **Details** tab.
- 3. Add a column named **Base Priority**. This is the name Task Manager uses for priority class.

4. Find Notepad in the list. You should see something like the following:

MSOIDSVCM.EXE         4144         Running         SYSTEM         00         716 K         Normal         M           Imspaint.exe         14596         Running         pavely         00         42,712 K         Normal         P           IN Norve         5248         Running         pavely         00         5,096 K         Above nor         N           IN Norve         5040         Running         pavely         00         5,096 K         Above nor         N           Inotepad.exe         5348         Running         pavely         00         1,992 K         Normal         N           OfficeClickToRun.exe         3480         Running         SYSTEM         00         28,804 K         Normal         N           OneDrive.exe         8912         Running         pavely         00         7,108 K         Normal         M           OneDrive.exe         8912         Running         pavely         00         168,552 K         Normal         M           OUTLOOK.EXE         10380         Running         pavely         00         17,716 K         Normal         M           POWERNT.EXE         1124         Running         pavely         00         7,800 K	File Options View							
Name         PID         Status         User name         CPU         Memory (p         Base priority         D           MSOIDSVCM.EXE         4144         Running         SYSTEM         00         716 K         Normal         M           Imspaint.exe         14596         Running         pavely         00         42,712 K         Normal         M           INstorkUXBroker.exe         5248         Running         pavely         00         5,096 K         Above nor         N           INsSrv.exe         5040         Running         pavely         00         7,768 K         Normal         M           OfficeClickToRun.exe         5348         Running         pavely         00         28,804 K         Normal         M           OfficeClickToRun.exe         8912         Running         pavely         00         7,108 K         Normal         M           ODDTive.exe         8952         Running         pavely         00         168,552 K         Normal         M           OUTLOOK.EXE         10380         Running         pavely         00         17,716 K         Normal         M           POWERNT.EXE         1124         Running         pavely         00	Processes Performance	App hist	ory Startup	Users Details	Service	es .		
Imspaint.exe         14596         Running         pavely         00         42,712 K         Normal         P.           INtetworkUXBroker.exe         5248         Running         pavely         00         5,096 K         Above nor         N           INtsrv.exe         5040         Running         pavely         00         7,768 K         Normal         N           Inotepad.exe         5348         Running         pavely         00         1,992 K         Normal         N           OfficeClickToRun.exe         4840         Running         SYSTEM         00         28,804 K         Normal         N           OneDrive.exe         8912         Running         pavely         00         7,108 K         Normal         N           OneDrive.exe         8912         Running         pavely         00         168,552 K         Normal         N           OUTLOOK.EXE         10380         Running         pavely         00         168,552 K         Normal         N           POWERNT.EXE         1124         Running         pavely         00         78,000 K         Normal         N           POwtershell.exe         12936         Running         pavely         00         <		PID	Status	User name	CPU	Memory (p	Base priority	De 1
INetworkUXBroker.exe         5248         Running         pavely         00         5,096 K         Above nor         N           INis5rv.exe         5040         Running         LOCAL SERV         00         7,768 K         Normal         N           Integad.exe         5348         Running         pavely         00         1,992 K         Normal         N           OfficeClickToRun.exe         3480         Running         SYSTEM         00         28,804 4 K         Normal         N           © OfficeClickToRun.exe         8912         Running         pavely         00         7,108 K         Normal         M           © OneDrive.exe         8912         Running         pavely         00         168,552 K         Normal         M           © OUTLOOK.EXE         10380         Running         pavely         00         117,716 K         Normal         M           © POWERNT.EXE         1124         Running         pavely         00         49,972 K         Normal         M           © powershell.exe         12936         Running         pavely         00         49,972 K         Normal         M	MSOIDSVCM.EXE	4144	Running	SYSTEM	00	716 K	Normal	Mi
INisSrv.exe         5040         Running         LOCAL SERV         00         7,768 K         Normal         M           Inotepad.exe         5348         Running         pavely         00         1,992 K         Normal         N           I OfficeClickToRun.exe         3480         Running         SYSTEM         00         28,804 K         Normal         N           I OfficeClickToRun.exe         8912         Running         pavely         00         7,108 K         Normal         N           I OneDrive.exe         8912         Running         pavely         00         168,552 K         Normal         N           I OUTLOOK.EXE         10380         Running         pavely         00         117,716 K         Normal         N           I POWERPNT.EXE         1124         Running         pavely         00         78,000 K         Normal         N           I POWERPNT.EXE         1248         Running         pavely         00         49,972 K         Normal         N	🗐 mspaint.exe	14596	Running	pavely	00	42,712 K	Normal	Pa
Inotepad.exe         5348         Running         pavely         00         1,992 K         Normal N           OfficeClickToRun.exe         3480         Running         SYSTEM         00         28,804 K         Normal N           OneDrive.exe         8912         Running         pavely         00         7,108 K         Normal N           OneDrive.exe         8952         Running         pavely         00         168,552 K         Normal N           OUTLOOK.EXE         10380         Running         pavely         00         117,716 K         Normal N           DPOWERNT.EXE         1124         Running         pavely         00         78,000 K         Normal N           Powershell.exe         12936         Running         pavely         00         49,972 K         Normal N	NetworkUXBroker.exe	5248	Running	pavely	00	5,096 K	Above nor	Ne
OfficeClickToRun.exe         3480         Running         SYSTEM         00         28,804 K         Normal         M           CheDrive.exe         8912         Running         pavely         00         7,108 K         Normal         M           CheDrive.exe         8912         Running         pavely         00         7,108 K         Normal         M           Dialogue         00         168,552 K         Normal         M         D         D         D         D         D         Normal         N         D	NisSrv.exe	5040	Running	LOCAL SERV	00	7,768 K	Normal	Mi
OneDrive.exe         8912         Running         pavely         00         7,108 K         Normal M           CheDrive.exe         8952         Running         pavely         00         168,552 K         Normal M           DOUTLOOK.EXE         10380         Running         pavely         00         117,716 K         Normal M           D/POWERNT.EXE         1124         Running         pavely         00         78,000 K         Normal M           Powershell.exe         12936         Running         pavely         00         49,972 K         Normal M	notepad.exe	5348	Running	pavely	00	1,992 K	Normal	Nc
OneDrive.exe         8952         Running         pavely         00         168,552 K         Normal         M           OUTLOOK.EXE         10380         Running         pavely         00         117,716 K         Normal         M           POWERPNT.EXE         1124         Running         pavely         00         78,000 K         Normal         M           Powershell.exe         12936         Running         pavely         00         49,972 K         Normal         W	OfficeClickToRun.exe	3480	Running	SYSTEM	00	28,804 K	Normal	Mi
OUTLOOK.EXE         10380         Running         pavely         00         117,716 K         Normal         N           POWERPNT.EXE         1124         Running         pavely         00         78,000 K         Normal         N           Powershell.exe         12936         Running         pavely         00         49,972 K         Normal         N	ConeDrive.exe	8912	Running	pavely	00	7,108 K	Normal	Mi
POWERPNT.EXE 1124 Running pavely 00 78,000 K Normal M Powershell.exe 12936 Running pavely 00 49,972 K Normal W	ConeDrive.exe	8952	Running	pavely	00	168,552 K	Normal	Mi
🗷 powershell.exe 12936 Running pavely 00 49,972 K Normal W	OUTLOOK.EXE	10380	Running	pavely	00	117,716 K	Normal	Mi
	P POWERPNT.EXE	1124	Running	pavely	00	78,000 K	Normal	Mi
	🗵 powershell.exe	12936	Running	pavely	00	49,972 K	Normal	Wi
	■ DescentationEontCar ≪	6056	Dunning	LOCAL SERV	m	A 356 V	Normal	>

- **5.** Notice the Notepad process running with the Normal priority class (8) and that Task Manager shows the Idle priority class as Low.
- 6. Open Process Explorer.
- 7. Double-click the **Notepad** process to show its Properties dialog box and click the **Threads** tab.
- 8. Select the first thread (if there's more than one). You should see something like this:

Image	Performance	Performance Gra	ph Disk	and Network
GPU Graph	Threads TCP	/IP Security	Environmen	nt Strings
Count: 4				
TID ČP	U Cycles Delta	Start Address		
11940		notepad.exe/WinMa		
10108		MICROS~2.DLLI_th ntdll.dll!TppWorkerT		
16492		ntdl.dllTppWorkerT		
<				>
< Thread ID:	11940		Stack	> Module
Thread ID: Start Time:	09:14:52 27-		-	
Thread ID: Start Time: State:	09:14:52 27-0 Wait:WrUserRe	equest Base Priorit	y: 8	
Thread ID: Start Time: State: Kernel Time:	09:14:52 274 Wait:WrUserRe 0:00:00.312	equest Base Priorit Dynamic Pri	y: 8 ority: 10	Module
Thread ID: Start Time: State: Kernel Time: User Time:	09:14:52 274 Wait:WrUserRe 0:00:00.312 0:00:00.125	equest Base Priorit Dynamic Pri I/O Priority	y: 8 ority: 10 : Normal	Module
Thread ID: Start Time: State: Kernel Time: User Time: Context Switches:	09:14:52 27-4 Wait:WrUserRe 0:00:00.312 0:00:00.125 10,020	equest Base Priorit Dynamic Pri I/O Priority: Memory Prio	y: 8 ority: 10 : Normal ority: 5	Module
Thread ID: Start Time: State: Kernel Time: User Time: Context Switches:	09:14:52 274 Wait:WrUserRe 0:00:00.312 0:00:00.125	equest Base Priorit Dynamic Pri I/O Priority: Memory Prio	y: 8 ority: 10 : Normal ority: 5	Module
Thread ID: Start Time: State: Kernel Time: User Time:	09:14:52 27-4 Wait:WrUserRe 0:00:00.312 0:00:00.125 10,020	equest Base Priorit Dynamic Pri I/O Priority: Memory Prio	y: 8 ority: 10 : Normal ority: 5	Module

- **9.** Notice the thread's priorities. Its base priority is 8 but its current (dynamic) priority is 10. (The reason for this priority boost is discussed in the upcoming "Priority boosts" section).
- **10.** If you want, you can suspend and kill the thread. (Both operations must be used with caution, of course.)
- **11.** In Task Manager, right-click the **Notepad** process, select **Set Priority**, and set the value to **High**, as shown here:

	ADIOKELEKE	J240	Numm		μανειγ	vv	
NisSrv.exe	e	5040	Runni	ng	LOCAL SERV	00	
notepad.e	exe	5348	Runni	ng	pavely	00	
1 Office	End task			9	SYSTEM	00	
🝊 OneD	End proces	s tree		g	pavely	00	
ConeD	Set priority		>		Realtime	~~	
	Set affinity				High		
·	Analyze wa	it chain			Above normal		-
🔿 Fev	Debug			٠	Normal		
	UAC virtua	lization			Below normal		
	Create dun				Low		
	0 01				- Zerist i S		

**12.** Accept the confirmation dialog box change and go back to Process Explorer. Notice that the thread's priority has jumped to the new base for High (13). The dynamic priority has made the same relative jump:

Image	Performance	Pe	rformance Grap	h	Disk an	d Network	¢
GPU Graph	Threads	TCP/IP	Security	Env	vironment	Strin	gs
Count: 4							
TID ČF	U Cycles	Delta Start	Address				
11940 < 0.0	)1 384	,216 noter	ad.exe!WinMair	nCRTS	tartup		
15632 16492			III!TppWorkerTh III!TppWorkerTh				
٢							>
< Thread ID:	11940			Sta	ck	Module	>
-		2 27-May-1	6	Sta	dk 🗌		>
Thread ID:	09:14:52	1.1	6 t Base Priority	_	dk 13		>
Thread ID: Start Time:	09:14:52	UserReques		:			>
Thread ID: Start Time: State:	09:14:52 Wait:Wrl	UserReques 312	t Base Priority	: rity:	13		>
Thread ID: Start Time: State: Kernel Time:	09:14:52 Wait:Wrl 0:00:00. 0:00:00.	UserReques 312	t Base Priority Dynamic Prio	: rity:	13 15		>
Thread ID: Start Time: State: Kernel Time: User Time:	09:14:52 Wait:Wrl 0:00:00. 0:00:00.	UserReques 312 125	<ul> <li>Base Priority</li> <li>Dynamic Prio</li> <li>I/O Priority:</li> </ul>	: rity: rity:	13 15 Normal		>

**13.** In Task Manager, change the priority class to **Realtime**. (You must be an administrator on the machine for this to succeed. Note that you can also make this change in Process Explorer.)

**14.** In Process Manager, notice that the base and dynamic priorities of the thread are now 24. Recall that the kernel never applies priority boosts for threads in the Real-Time priority range.

Image Pe	erformance	Performance (	Graph D	isk and Network
GPU Graph T	hreads TCP	/IP Securit	y Environm	nent String
Count: 4				
TID ČPL		Start Address		
11940 < 0.01		notepad exelWin		
10108		MICROS~2.DLLI ntdll.dll!TppWork		
16492		ntdl.dllTppWork		
K				
< Thread ID:	11940		Stack	Module
and the second	11940 09:14:52 27+	tay-16	Stack	-
Thread ID: Start Time: State:	09:14:52 27-1	fay-16 quest Base Pric		-
Thread ID: Start Time: State:	09:14:52 27-1	quest Base Pric		-
Thread ID: Start Time: State: Kernel Time: User Time:	09:14:52 27-4 Wait:WrUserRe 0:00:00.312 0:00:00.125	quest Base Prio Dynamic I/O Prior	prity: 24 Priority: 24 Ity: Norm	Module
Thread ID: Start Time:	09:14:52 27-4 Wait:WrUserRe 0:00:00.312 0:00:00.125	quest Base Prio Dynamic I/O Prior	prity: 24 Priority: 24	Module
Thread ID: Start Time: State: Kernel Time: User Time:	09:14:52 27-4 Wait:WrUserRe 0:00:00.312 0:00:00.125	quest Base Prio Dynamic I/O Prior Memory	prity: 24 Priority: 24 Ity: Norm	Module

#### Windows System Resource Manager

Windows Server 2012 R2 Standard Edition and higher SKUs include an optionally installable component called *Windows System Resource Manager (WSRM)*. It permits the administrator to configure policies that specify CPU utilization, affinity settings, and memory limits (both physical and virtual) for processes. In addition, WSRM can generate resource-utilization reports that can be used for accounting and verification of service-level agreements with users.

Policies can be applied for specific applications (by matching the name of the image with or without specific command-line arguments), users, or groups. The policies can be scheduled to take effect at certain periods or can be enabled all the time.

After you set a resource-allocation policy to manage specific processes, the WSRM service monitors CPU consumption of managed processes and adjusts process base priorities when those processes do not meet their target CPU allocations.

The physical memory limitation uses the function SetProcessWorkingSetSizeEx to set a hard-working set maximum. The virtual memory limit is implemented by the service checking the private virtual memory consumed by the processes. (See Chapter 5 for an explanation of these memory limits.) If this limit is exceeded, WSRM can be configured to either kill the processes or write an entry to the event log. This behavior can be used to detect a process with a memory

leak before it consumes all the available committed memory on the system. Note that WSRM memory limits do not apply to Address Windowing Extensions (AWE) memory, large page memory, or kernel memory (non-paged or paged pool). (See Chapter 5 for more information on these terms.)

# **Thread states**

Before looking at the thread-scheduling algorithms, you must understand the various execution states that a thread can be in. The thread states are as follows:

- Ready A thread in the ready state is waiting to execute or to be in-swapped after completing a wait. When looking for a thread to execute, the dispatcher considers only the threads in the ready state.
- Deferred ready This state is used for threads that have been selected to run on a specific processor but have not actually started running there. This state exists so that the kernel can minimize the amount of time the per-processor lock on the scheduling database is held.
- **Standby** A thread in this state has been selected to run next on a particular processor. When the correct conditions exist, the dispatcher performs a context switch to this thread. Only one thread can be in the standby state for each processor on the system. Note that a thread can be preempted out of the standby state before it ever executes (if, for example, a higher-priority thread becomes runnable before the standby thread begins execution).
- Running After the dispatcher performs a context switch to a thread, the thread enters the running state and executes. The thread's execution continues until its quantum ends (and another thread at the same priority is ready to run), it is preempted by a higher-priority thread, it terminates, it yields execution, or it voluntarily enters the waiting state.
- Waiting A thread can enter the waiting state in several ways: A thread can voluntarily wait for an object to synchronize its execution, the OS can wait on the thread's behalf (such as to resolve a paging I/O), or an environment subsystem can direct the thread to suspend itself. When the thread's wait ends, depending on its priority, the thread either begins running immediately or is moved back to the ready state.
- Transition A thread enters the transition state if it is ready for execution but its kernel stack is paged out of memory. After its kernel stack is brought back into memory, the thread enters the ready state. (Thread stacks are discussed in Chapter 5.)
- Terminated When a thread finishes executing, it enters this state. After the thread is terminated, the executive thread object (the data structure in system memory that describes the thread) might or might not be deallocated. The object manager sets the policy regarding when to delete the object. For example, the object remains if there are any open handles to the thread. A thread can also enter the terminated state from other states if it's killed explicitly by some other thread—for example, by calling the TerminateThread Windows API.
- Initialized This state is used internally while a thread is being created.

Figure 4-8 shows the main state transitions for threads. The numeric values shown represent the internal values of each state and can be viewed with a tool such as Performance Monitor. The ready and deferred ready states are represented as one. This reflects the fact that the deferred ready state acts as a temporary placeholder for the scheduling routines. This is true for the standby state as well. These states are almost always very short-lived. Threads in these states always transition quickly to ready, running, or waiting.




FIGURE 4-8 Thread states and transitions.

#### **EXPERIMENT:** Thread-scheduling state changes

You can watch thread-scheduling state changes with the Performance Monitor tool in Windows. This utility can be useful when you're debugging a multithreaded application and you're unsure about the state of the threads running in the process. To watch thread-scheduling state changes by using the Performance Monitor tool, follow these steps:


- 1. Download the CPU Stress tool from the book's downloadable resources.
- 2. Run CPUSTRES.exe. Thread 1 should be active.
- Activate thread 2 by selecting it in the list and clicking the Activate button or by rightclicking it and selecting Activate from the context menu. The tool should look something like this:

	Process T	्रि	Proc	ess Affinity: 111111 ess Priority Class: No		
#	ID	Active?	Activity	Priority	Ideal CPU	Affinity
1	2708	Yes	Low	Normal	3	11111111
2	14852	Yes	Low	Normal	5	11111111
3	16848		Low	Normal	7	11111111
4	14084		Low	Normal	0	11111111


- 4. Click the Start button and type perfmon to start the Performance Monitor tool.
- 5. If necessary, select the chart view. Then remove the existing CPU counter.
- 6. Right-click the graph and choose Properties.
- Click the Graph tab and change the chart vertical scale maximum to 7. (As you saw in Figure 4-8, the various states are associated with numbers 0 through 7.) Then click OK.
- 8. Click the Add button on the toolbar to open the Add Counters dialog box.
- 9. Select the Thread performance object and then select the Thread State counter.
- **10.** Select the **Show Description** check box to see the definition of the values:

Show description	ОК	Cancel	
Description:			
Thread State is the current state of the thread. It is 0 for Initialized, 1 for Ready, 2 for Running, 3 for Stan Wait, 6 for Transition, 7 for Unknown. A Running thread is using a processor; a Standby thread is about to wants to use a processor, but is waiting for a processor because none are free. A thread in Transition is wa to execute, such as waiting for its execution stack to be paged in from disk. A Waiting thread has no use for	use one. A Read iting for a resourc	y thread ce in order	

- 11. In the Instances box, select <**All instances**>. Then type **cpustres** and click **Search**.
- 12. Select the first three threads of cpustres (cpustres/0, cpustres/1, and cpustres/2) and click the Add >> button. Then click OK. Thread 0 should be in state 5 (waiting), because that's the GUI thread and it's waiting for user input. Threads 1 and 2 should be alternating between states 2 and 5 (running and waiting). (Thread 1 may be hiding thread 2 as they're running with the same activity level and the same priority.)




**13.** Go back to CPU Stress, right-click thread 2, and choose **Busy** from the activity context menu. You should see thread 2 in state 2 (running) more often than thread 1:



**14.** Right-click thread 1 and choose an activity level of **Maximum**. Then repeat this step for thread 2. Both threads now should be constantly in state 2 because they're running essentially an infinite loop:

Eile Action	View Win	dow <u>H</u> elp									- 0
		2 m									- 6
the second second		And a second sec									
Performance	國會國	-   🔶 🗙			. ⊳i						
Perfori	2000000		0.000000000								
📑 Data Colle				(							
Reports	6.0-										
											_
	4.0-										
	4.0										
	2.0-										
	2.0-	10 50.01	10.50	15 10.55.45	10.56.55 10.1	57.05 10.57	15 10.57	35	10.57.25	,	10.57.57
	2.0-	10:58:0	5 10:58:	15 10:56:45	10:56:55 10:5	57:05 10:57	:15 10:57	:25	10:57:35	-	10:57:52
	2.0-	10:58:0 Last		15 10:56:45 5.000 Average		57:05 10:57		:25	10:57:35 Maximum		
	2.0-										10:57:52 5.00 1:4
	2.0-				5.000				Maximum		5.00
	2.0- 0.0 10:57:53	Last	Scale	5.000 Average	5.000	Minimum tance Par	ent (	5.000 Dbject	Maximum Duration Compo	uter V-LAP	5.00 1:4 4
	2.0- 0.0 10:57:53	Last	Scale	5.000 Average	5.000 Inst	Minimum tance Par CPI	ent ( JSTRES T JSTRES T	5.000 Dbject	Maximum Duration Comp	uter V-LAP LY-LAP	5.00 1:4 4


If you're trying this on a single processor system, you'll see something different. Because there is only one processor, only one thread can execute at a time, so you'll see the two threads alternating between states 1 (ready) and 2 (running):



15. If you're on a multiprocessor system (very likely), you can get the same effect by going to Task Manager, right-clicking the CPUSTRES process, selecting Set Affinity, and then select just one processor—it doesn't matter which one—as shown here. (You can also do it from CPU Stress by opening the Process menu and selecting Affinity.)

<all pro<="" th=""><th>cessors &gt;</th><th></th><th></th></all>	cessors >		
CPU 0			
CPU 1			
CPU 2			
CPU 3			
CPU 4			
CPU 5			
CPU 6			
CPU 7			


16. There's one more thing you can try. With this setting in place, go back to CPU Stress, right-click thread 1, and choose a priority of **Above Normal**. You'll see that thread 1 is running continuously (state 2) and thread 2 is always in the ready state (state 1). This is because there's only one processor, so in general, the higher priority thread wins out. From time to time, however, you'll see a change in thread 1's state to ready. This is because every 4 seconds or so, the starved thread gets a boost that enables it to run for a little while. (Often, this state change is not reflected by the graph because the granularity of Performance Monitor is limited to 1 second, which is too coarse.) This is described in more detail later in this chapter in the section "Priority boosts."



## **Dispatcher database**

To make thread-scheduling decisions, the kernel maintains a set of data structures known collectively as the *dispatcher database*. The dispatcher database keeps track of which threads are waiting to execute and which processors are executing which threads.

To improve scalability, including thread-dispatching concurrency, Windows multiprocessor systems have per-processor dispatcher ready queues and shared processor group queues, as illustrated in Figure 4-9. In this way, each CPU can check its own shared ready queue for the next thread to run without having to lock the system-wide ready queues.



**FIGURE 4-9** Windows multiprocessor dispatcher database. (This example shows six processors. *P* represents processes; *T* represents threads.)

Windows versions prior to Windows 8 and Windows Server 2012 used per-processor ready queues and a per-processor ready summary, which were stored as part of processor control block (PRCB) structure. (To see the fields in the PRCB, type **dt nt!\_kprcb** in the kernel debugger.) Starting with Windows 8 and Windows Server 2012, a shared ready queue and ready summary are used for a group of processors. This enables the system to make better decisions about which processor to use next for that group of processors. (The per-CPU ready queues are still there and used for threads with affinity constraints.)

**Note** Because the shared data structure must be protected (by a spinlock), the group should not be too large. That way, contention on the queues is insignificant. In the current implementation, the maximum group size is four logical processors. If the number of logical processors is greater than four, then more than one group would be created, and the available processors spread evenly. For example, on a six-processor system, two groups of three processors each would be created.

The ready queues, ready summary (described next), and some other information is stored in a kernel structure named KSHARED\_READY\_QUEUE that is stored in the PRCB. Although it exists for every processor, it's used only on the first processor of each processor group, sharing it with the rest of the processors in that group.

The dispatcher ready queues (ReadListHead in KSHARED\_READY\_QUEUE) contain the threads that are in the ready state, waiting to be scheduled for execution. There is one queue for each of the 32 priority levels. To speed up the selection of which thread to run or preempt, Windows maintains a 32-bit bitmask called the *ready summary* (ReadySummary). Each bit set indicates one or more threads in the ready queue for that priority level (bit 0 represents priority 0, bit 1 priority 1, and so on).

Instead of scanning each ready list to see whether it is empty or not (which would make scheduling decisions dependent on the number of different priority threads), a single bit scan is performed as a native processor command to find the highest bit set. Regardless of the number of threads in the ready queue, this operation takes a constant amount of time.

The dispatcher database is synchronized by raising IRQL to DISPATCH\_LEVEL (2). (For an explanation of interrupt priority levels, or IRQLs, see Chapter 6.) Raising IRQL in this way prevents other threads from interrupting thread dispatching on the processor because threads normally run at IRQL 0 or 1. However, more is required than just raising IRQL, because other processors can simultaneously raise to the same IRQL and attempt to operate on their dispatcher database. How Windows synchronizes access to the dispatcher database is explained later in this chapter in the section "Multiprocessor systems."

#### **EXPERIMENT:** Viewing ready threads

You can view the list of ready threads with the kernel-debugger ! ready command. This command displays the thread or list of threads that are ready to run at each priority level. Here is an example generated on a 32-bit machine with four logical processors:

```
0: kd> !ready
KSHARED_READY_QUEUE 8147e800: (00) ****------
SharedReadyQueue 8147e800: Ready Threads at priority 8
   THREAD 80af8bc0 Cid 1300.15c4 Teb: 7ffdb000 Win32Thread: 00000000 READY on
processor 8000002
   THREAD 80b58bc0 Cid 0454.0fc0 Teb: 7f82e000 Win32Thread: 00000000 READY on
processor 8000003
SharedReadyQueue 8147e800: Ready Threads at priority 7
   THREAD a24b4700 Cid 0004.11dc Teb: 00000000 Win32Thread: 00000000 READY on
processor 8000001
   THREAD a1bad040 Cid 0004.096c Teb: 00000000 Win32Thread: 00000000 READY on
processor 8000001
SharedReadyQueue 8147e800: Ready Threads at priority 6
   THREAD a1bad4c0 Cid 0004.0950 Teb: 00000000 Win32Thread: 00000000 READY on
processor 8000002
   THREAD 80b5e040 Cid 0574.12a4 Teb: 7fc33000 Win32Thread: 00000000 READY on
processor 8000000
SharedReadyQueue 8147e800: Ready Threads at priority 4
   THREAD 80b09bc0 Cid 0004.12dc Teb: 00000000 Win32Thread: 00000000 READY on
processor 8000003
SharedReadyQueue 8147e800: Ready Threads at priority 0
   THREAD 82889bc0 Cid 0004.0008 Teb: 00000000 Win32Thread: 00000000 READY on
processor 8000000
Processor 0: No threads in READY state
Processor 1: No threads in READY state
Processor 2: No threads in READY state
Processor 3: No threads in READY state
```

The processor numbers have a 0x8000000 added to them, but the actual processor numbers are easy to see. The first line shows the address of the KSHARED\_READY\_QUEUE with the group number in parentheses (00 in the output) and then a graphic representation of the processors in this particular group (the four asterisks).

The last four lines seem odd, as they appear to indicate no ready threads, contradicting the preceding output. These lines indicate ready threads from the older DispatcherReadyListHead member of the PRCB because the per-processor ready queues are used for threads that have restrictive affinity (set to run on a subset of processors inside that processor group).

You can also dump the KSHARED\_READY\_QUEUE with the address given by the ! ready command:

0: kd> dt nt!\_KSHARED\_READY\_QUEUE 8147e800

+0x000	Lock	з.	0
+0x004	ReadySummary	:	0x1d1
+0x008	ReadyListHead	:	[32] _LIST_ENTRY [ 0x82889c5c - 0x82889c5c ]
+0x108	RunningSummary	:	[32] "???"
+0x128	Span	:	4
+0x12c	LowProcIndex	:	0
+0x130	QueueIndex	:	1
+0x134	ProcCount	:	4
+0x138	Affinity	:	0xf

The ProcCount member shows the processor count in the shared group (4 in this example). Also note the ReadySummary value, 0x1d1. This translates to 111010001 in binary. Reading the binary one bits from right to left, this indicates that threads exist in priorities 0, 4, 6, 7, 8, which match the preceding output.

# Quantum

As mentioned earlier in the chapter, a *quantum* is the amount of time a thread is permitted to run before Windows checks to see whether another thread at the same priority is waiting to run. If a thread completes its quantum and there are no other threads at its priority, Windows permits the thread to run for another quantum.

On client versions of Windows, threads run for two clock intervals by default. On server systems, threads runs for 12 clock intervals by default. (We'll explain how to change these values in the "Controlling the quantum" section.) The rationale for the longer default value on server systems is to minimize context switching. By having a longer quantum, server applications that wake up because of a client request have a better chance of completing the request and going back into a wait state before their quantum ends.

The length of the clock interval varies according to the hardware platform. The frequency of the clock interrupts is up to the HAL, not the kernel. For example, the clock interval for most x86 uniprocessors is about 10 milliseconds (note that these machines are no longer supported by Windows and are used here only for example purposes), and for most x86 and x64 multiprocessors it is about 15 milliseconds. This clock interval is stored in the kernel variable KeMaximumIncrement as hundreds of nanoseconds.

Although threads run in units of clock intervals, the system does not use the count of clock ticks as the gauge for how long a thread has run and whether its quantum has expired. This is because thread run-time accounting is based on processor cycles. When the system starts up, it multiplies the processor speed (CPU clock cycles per second) in hertz (Hz) by the number of seconds it takes for one clock tick to fire (based on the KeMaximumIncrement value described earlier) to calculate the number of clock cycles to which each quantum is equivalent. This value is stored in the kernel variable KiCyclesPerClock-Quantum.

The result of this accounting method is that threads do not actually run for a quantum number based on clock ticks. Instead, they run for a quantum target, which represents an estimate of what the number of CPU clock cycles the thread has consumed should be when its turn would be given up. This target should be equal to an equivalent number of clock interval timer ticks. This is because, as you just saw, the calculation of clock cycles per quantum is based on the clock interval timer frequency, which you can check using the following experiment. Note, however, that because interrupt cycles are not charged to the thread, the actual clock time might be longer.

#### **EXPERIMENT:** Determining the clock interval frequency

The Windows GetSystemTimeAdjustment function returns the clock interval. To determine the clock interval, run the clockres tool from Sysinternals. Here's the output from a quad-core 64-bit Windows 10 system:

C:\>clockres

```
ClockRes v2.0 - View the system clock resolution
Copyright (C) 2009 Mark Russinovich
SysInternals - www.sysinternals.com
Maximum timer interval: 15.600 ms
Minimum timer interval: 0.500 ms
```

Current timer interval: 1.000 ms

The current interval may be lower than the maximum (default) clock interval because of multimedia timers. Multimedia timers are used with functions such as timeBeginPeriod and timeSetEvent that are used to receive callbacks with intervals of 1 millisecond (ms) at best. This causes a global reprogramming of the kernel interval timer, meaning the scheduler wakes up in more frequent intervals, which can degrade system performance. In any case, this does not affect quantum lengths, as described in the next section.

It's also possible to read the value using the kernel global variable KeMaximumIncrement as shown here (not the same system as the previous example):

```
0: kd> dd nt!KeMaximumIncrement L1
814973b4 0002625a
0: kd> ? 0002625a
Evaluate expression: 156250 = 0002625a
This corresponds to the default of 15.6 ms.
```

#### Quantum accounting

Each process has a quantum reset value in the process control block (KPROCESS). This value is used when creating new threads inside the process and is duplicated in the thread control block (KTHREAD), which is then used when giving a thread a new quantum target. The quantum reset value is stored in terms of actual quantum units (we'll discuss what these mean soon), which are then multiplied by the number of clock cycles per quantum, resulting in the quantum target.

As a thread runs, CPU clock cycles are charged at different events, such as context switches, interrupts, and certain scheduling decisions. If, at a clock interval timer interrupt, the number of CPU clock cycles charged has reached (or passed) the quantum target, quantum end processing is triggered. If there is another thread at the same priority waiting to run, a context switch occurs to the next thread in the ready queue.

Internally, a quantum unit is represented as one-third of a clock tick. That is, one clock tick equals three quantums. This means that on client Windows systems, threads have a quantum reset value of 6 (2 \* 3) and that server systems have a quantum reset value of 36 (12 \* 3) by default. For this reason, the KiCyclesPerClockQuantum value is divided by 3 at the end of the calculation previously described, because the original value describes only CPU clock cycles per clock interval timer tick.

The reason a quantum was stored internally as a fraction of a clock tick rather than as an entire tick was to allow for partial quantum decay-on-wait completion on versions of Windows prior to Windows Vista. Prior versions used the clock interval timer for quantum expiration. If this adjustment had not been made, it would have been possible for threads to never have their quantums reduced. For example, if a thread ran, entered a wait state, ran again, and entered another wait state but was never the currently running thread when the clock interval timer fired, it would never have its quantum charged for the time it was running. Because threads now have CPU clock cycles charged instead of quantums, and because this no longer depends on the clock interval timer, these adjustments are not required.

#### EXPERIMENT: Determining the clock cycles per quantum

Windows doesn't expose the number of clock cycles per quantum through any function. However, with the calculation and description we've given, you should be able to determine this on your own using the following steps and a kernel debugger such as WinDbg in local debugging mode:

 Obtain your processor frequency as Windows has detected it. You can use the value stored in the PRCB's MHz field, which you can display with the !cpuinfo command. Here is a sample output of a four-processor system running at 2794 megahertz (MHz):

lkd> !cpuinfo

СР	F/M/S Manufacturer	MHz PRCB Signature	MSR 8B Signature Features
0	6,60,3 GenuineIntel	2794 fffffff0000000	>fffffff0000000 <a3cd3fff< td=""></a3cd3fff<>
1	6,60,3 GenuineIntel	2794 fffffff0000000	a3cd3fff
2	6,60,3 GenuineIntel	2794 fffffff0000000	a3cd3fff
3	6,60,3 GenuineIntel	2794 fffffff0000000	a3cd3fff

- **2.** Convert the number to hertz (Hz). This is the number of CPU clock cycles that occur each second on your system—in this case, 2,794,000,000 cycles per second.
- Obtain the clock interval on your system by using clockres. This measures how long it takes before the clock fires. On the sample system used here, this interval was 15.625 msec.
- **4.** Convert this number to the number of times the clock interval timer fires each second. One second equals 1,000 ms, so divide the number derived in step 3 by 1,000. In this case, the timer fires every 0.015625 seconds.
- **5.** Multiply this count by the number of cycles each second that you obtained in step 2. In this case, 43,656,250 cycles have elapsed after each clock interval.
- **6.** Remember that each quantum unit is one-third of a clock interval, so divide the number of cycles by 3. This gives you 14,528,083, or 0xDE0C13 in hexadecimal. This is the number of clock cycles each quantum unit should take on a system running at 2,794 MHz with a clock interval of around 15.6 ms.
- 7. To verify your calculation, dump the value of KiCyclesPerClockQuantum on your system. It should match (or be close enough because of rounding errors).

lkd> dd nt!KiCyclesPerClockQuantum L1
8149755c 00de0c10

#### Controlling the quantum

You can change the thread quantum for all processes, but you can choose only one of two settings: short (two clock ticks, which is the default for client machines) or long (12 clock ticks, which is the default for server systems).

**Note** By using the job object on a system running with long quantums, you can select other quantum values for the processes in the job.

To change this setting, right-click the **This PC** icon on the desktop. Alternatively, in Windows Explorer, choose **Properties**, click the **Advanced System Settings** label, click the **Advanced** tab, click the **Settings** button in the **Performance** section, and click yet another **Advanced** tab. Figure 4-10 shows the resulting dialog box.



FIGURE 4-10 Quantum configuration in the Performance Options dialog box.

This dialog box contains two key options:

- Programs This setting designates the use of short, variable quantums, which is the default for client versions of Windows (and other client-like versions, such as mobile, XBOX, HoloLens, and so on). If you install Terminal Services on a server system and configure the server as an application server, this setting is selected so that the users on the terminal server have the same quantum settings that would normally be set on a desktop or client system. You might also select this manually if you were running Windows Server as your desktop OS.
- Background Services This setting designates the use of long, fixed quantums—the default for server systems. The only reason you might select this option on a workstation system is if you were using the workstation as a server system. However, because changes in this option take effect immediately, it might make sense to use it if the machine is about to run a back-ground or server-style workload. For example, if a long-running computation, encoding, or modeling simulation needs to run overnight, you could select the Background Services option at night and return the system to Programs mode in the morning.

#### Variable quantums

When variable quantums are enabled, the variable quantum table (PspVariableQuantums), which holds an array of six quantum numbers, is loaded into the PspForegroundQuantum table (a three-element array) that is used by the PspComputeQuantum function. Its algorithm will pick the appropriate quantum index based on whether the process is a foreground process—that is, whether it contains the thread that owns the foreground window on the desktop. If this is not the case, an index of 0 is chosen, which corresponds to the default thread quantum described earlier. If it is a foreground process, the quantum index corresponds to the priority separation. This priority separation value determines the priority boost (described in the upcoming section "Priority boosts") that the scheduler will apply to foreground threads, and it is thus paired with an appropriate extension of the quantum. For each extra priority level (up to 2), another quantum is given to the thread. For example, if the thread receives a boost of one priority level, it receives an extra quantum as well. By default, Windows sets the maximum possible priority boost to foreground threads, meaning that the priority separation will be 2, which means quantum index 2 is selected in the variable quantum table. This leads to the thread receiving two extra quantums, for a total of three quantums.

Table 4-2 describes the exact quantum value (recall that this is stored in a unit representing one-third of a clock tick) that will be selected based on the quantum index and which quantum configuration is in use.

Short Quantum Index			Long Quantum Index			
Variable	6	12	18	12	24	36
Fixed	18	18	18	36	36	36

TABLE 4-2 Quantum values

Thus, when a window is brought into the foreground on a client system, all the threads in the process containing the thread that owns the foreground window have their quantums tripled. Threads in the foreground process run with a quantum of six clock ticks, whereas threads in other processes have the default client quantum of two clock ticks. In this way, when you switch away from a CPU-intensive process, the new foreground process will get proportionally more of the CPU. This is because when its threads run, they will have a longer turn than background threads (again, assuming the thread priorities are the same in both the foreground and background processes).

### Quantum settings registry value

The user interface that controls quantum settings described earlier modifies the registry value Win32-PrioritySeparation in the key HKLM\SYSTEM\CurrentControlSet\Control\PriorityControl. In addition to specifying the relative length of thread quantums (short or long), this registry value also defines whether variable quantums should be used, as well as the priority separation (which, as you've seen, will determine the quantum index used when variable quantums are enabled). This value consists of 6 bits divided into the three 2-bit fields shown in Figure 4-11.

4	2	0
Short vs.	Variable	Priority
Long	vs. Fixed	Separation

FIGURE 4-11 Fields of the Win32PrioritySeparation registry value.

The fields shown in Figure 4-11 can be defined as follows:

Short vs. Long A value of 1 specifies long quantums, and a value of 2 specifies short ones. A setting of 0 or 3 indicates that the default appropriate for the system will be used (short for client systems, long for server systems).

- Variable vs. Fixed A value of 1 means to enable the variable quantum table based on the algorithm shown in the "Variable quantums" section. A setting of 0 or 3 means that the default appropriate for the system will be used (variable for client systems, fixed for server systems).
- Priority Separation This field (stored in the kernel variable PsPrioritySeparation) defines the priority separation (up to 2), as explained in the "Variable quantums" section.

When you use the Performance Options dialog box (refer to Figure 4-10), you can choose from only two combinations: short quantums with foreground quantums tripled, or long quantums with no quantum changes for foreground threads. However, you can select other combinations by modifying the Win32PrioritySeparation registry value directly.

Threads that are part of a process running in the idle process priority class always receive a single thread quantum, ignoring any sort of quantum configuration settings, whether set by default or set through the registry.

On Windows Server systems configured as application servers, the initial value of the Win32PrioritySeparation registry value will be hex 26, which is identical to the value set by the Optimize Performance for Programs option in the Performance Options dialog box. This selects quantum and priorityboost behavior like that on Windows client systems, which is appropriate for a server used primarily to host users' applications.

On Windows client systems and on servers not configured as application servers, the initial value of the Win32PrioritySeparation registry setting will be 2. This provides values of 0 for the Short vs. Long and Variable vs. Fixed Bit fields, relying on the default behavior of the system (depending on whether it is a client system or a server system) for these options. However, it provides a value of 2 for the Priority Separation field. After the registry value has been changed via the Performance Options dialog box, it cannot be restored to this original value other than by modifying the registry directly.

### **EXPERIMENT: Effects of changing the quantum configuration**

Using a local kernel debugger, you can see how the two quantum configuration settings, Programs and Background Services, affect the PsPrioritySeparation and PspForegroundQuantum tables, as well as modify the QuantumReset value of threads on the system. Take the following steps:

- 1. Open the **System** utility in Control Panel or right-click the **This PC** icon on the desktop and choose **Properties**.
- 2. Click the **Advanced System Settings** label, click the **Advanced** tab, click the **Settings** button in the Performance section, and click the second **Advanced** tab.
- **3.** Select the **Programs** option and click **Apply**. Keep this dialog box open for the duration of the experiment.
- 4. Dump the values of PsPrioritySeparation and PspForegroundQuantum, as shown here. The values shown are what you should see on a Windows system after making the change in steps 1–3. Notice how the variable short quantum table is being used and that a priority boost of 2 will apply to foreground applications:

```
lkd> dd nt!PsPrioritySeparation L1
fffff803'75e0e388 00000002
lkd> db nt!PspForegroundQuantum L3
```

```
fffff803'76189d28 06 0c 12
```

5. Look at the QuantumReset value of any process on the system. As noted, this is the default full quantum of each thread on the system when it is replenished. This value is cached into each thread of the process, but the KPROCESS structure is easier to look at. Notice in this case it is 6, because WinDbg, like most other applications, gets the quantum set in the first entry of the PspForegroundQuantum table:

```
lkd> .process
Implicit process is now ffffe001'4f51f080
lkd> dt nt!_KPROCESS ffffe001'4f51f080 QuantumReset
+0x1bd QuantumReset : 6 ''
```

- 6. Change the Performance option to **Background Services** in the dialog box you opened in steps 1 and 2.
- **7.** Repeat the commands shown in steps 4 and 5. You should see the values change in a manner consistent with our discussion in this section:

```
lkd> dd nt!PsPrioritySeparation L1
fffff803'75e0e388 0000000
lkd> db nt!PspForegroundQuantum L3
fffff803'76189d28 24 24 24
lkd> dt nt!_KPROCESS ffffe001'4f51f080 QuantumReset
  +0x1bd QuantumReset : 36 '$'
```

# **Priority boosts**

The Windows scheduler periodically adjusts the current (dynamic) priority of threads through an internal priority-boosting mechanism. In many cases, it does so to decrease various latencies (that is, to make threads respond faster to the events they are waiting on) and increase responsiveness. In others, it applies these boosts to prevent inversion and starvation scenarios. Here are some of the boost scenarios that will be described in this section (and their purpose):

- Boosts due to scheduler/dispatcher events (latency reduction)
- Boosts due to I/O completion (latency reduction)
- Boosts due to user interface (UI) input (latency reduction/responsiveness)
- Boosts due to a thread waiting on an executive resource (ERESOURCE) for too long (starvation avoidance)
- Boosts when a thread that's ready to run hasn't been running for some time (starvation and priority-inversion avoidance)

Like any scheduling algorithms, however, these adjustments aren't perfect, and they might not benefit all applications.

**Note** Windows never boosts the priority of threads in the real-time range (16 through 31). Therefore, scheduling is always predictable with respect to other threads in this range. Windows assumes that if you're using the real-time thread priorities, you know what you're doing.

Client versions of Windows also include a pseudo-boosting mechanism that occurs during multimedia playback. Unlike the other priority boosts, multimedia-playback boosts are managed by a kernel-mode driver called the Multimedia Class Scheduler Service (mmcss.sys). They are not really boosts, however. The driver merely sets new priorities for the threads as needed. Therefore, none of the rules regarding boosts apply. We'll first cover the typical kernel-managed priority boosts and then talk about MMCSS and the kind of "boosting" it performs.

### Boosts due to scheduler/dispatcher events

Whenever a dispatch event occurs, the KiExitDispatcher routine is called. Its job is to process the deferred ready list by calling KiProcessThreadWaitList and then call KzCheckForThreadDispatch to check whether any threads on the current processor should not be scheduled. Whenever such an event occurs, the caller can also specify which type of boost should be applied to the thread, as well as what priority increment the boost should be associated with. The following scenarios are considered as AdjustUnwait dispatch events because they deal with a dispatcher (synchronization) object entering a signaled state, which might cause one or more threads to wake up:

- An asynchronous procedure call (APC; described in Chapter 6 and in more detail in Chapter 8 in Part 2) is queued to a thread.
- An event is set or pulsed.
- A timer was set, or the system time was changed, and timers had to be reset.
- A mutex was released or abandoned.
- A process exited.
- An entry was inserted in a queue (KQUEUE), or the queue was flushed.
- A semaphore was released.
- A thread was alerted, suspended, resumed, frozen, or thawed.
- A primary UMS thread is waiting to switch to a scheduled UMS thread.

For scheduling events associated with a public API (such as SetEvent), the boost increment applied is specified by the caller. Windows recommends certain values to be used by developers, which will be described later. For alerts, a boost of 2 is applied (unless the thread is put in an alert wait by calling KeAlertThreadByThreadId, in which case the applied boost is 1), because the alert API does not have a parameter allowing a caller to set a custom increment.

The scheduler also has two special AdjustBoost dispatch events, which are part of the lock-ownership priority mechanism. These boosts attempt to fix situations in which a caller that owns the lock at priority x ends up releasing the lock to a waiting thread at priority < = x. In this situation, the new owner thread must wait for its turn (if running at priority x), or worse, it might not even get to run at all if its priority is lower than x. This means the releasing thread continues its execution, even though it should have caused the new owner thread to wake up and take control of the processor. The following two dispatcher events cause an AdjustBoost dispatcher exit:

- An event is set through the KeSetEventBoostPriority interface, which is used by the ERESOURCE reader-writer kernel lock.
- A gate is set through the KeSignalGate interface, which is used by various internal mechanisms when releasing a gate lock.

#### **Unwait boosts**

Unwait boosts attempt to decrease the latency between a thread waking up due to an object being signaled (thus entering the ready state) and the thread actually beginning its execution to process the unwait (thus entering the running state). Generally speaking, it is desirable that a thread that wakes up from a waiting state would be able to run as soon as possible.

The various Windows header files specify recommended values that kernel-mode callers of APIs such as KeReleaseMutex, KeSetEvent and KeReleaseSemaphore should use, which correspond to definitions such as MUTANT\_INCREMENT, SEMAPHORE\_INCREMENT, and EVENT\_INCREMENT. These three definitions have always been set to 1 in the headers, so it is safe to assume that most unwaits on these objects result in a boost of 1. In the user-mode API, an increment cannot be specified, nor do the native system calls such as NtSetEvent have parameters to specify such a boost. Instead, when these APIs call the underlying Ke interface, they automatically use the default \_INCREMENT definition. This is also the case when mutexes are abandoned or timers are reset due to a system time change: The system uses the default boost that normally would have been applied when the mutex would have been released. Finally, the APC boost is completely up to the caller. Soon, you'll see a specific usage of the APC boost related to I/O completion.

**Note** Some dispatcher objects don't have boosts associated with them. For example, when a timer is set or expires, or when a process is signaled, no boost is applied.

All these boosts of 1 attempt to solve the initial problem by assuming that both the releasing and waiting threads are running at the same priority. By boosting the waiting thread by one priority level, the waiting thread should preempt the releasing thread as soon as the operation completes. Unfortunately, on uniprocessor systems, if this assumption does not hold, the boost might not do much. For example, if the waiting thread is at priority 4 and the releasing thread is at priority 8, waiting at priority 5 won't do much to reduce latency and force preemption. On multiprocessor systems, however, due to the stealing and balancing algorithms, this higher-priority thread may have a better chance of getting picked up by another logical processor. This is due to a design choice made in the initial NT architecture,

which is to not track lock ownership (except a few locks). This means the scheduler can't be sure who really owns an event and if it's really being used as a lock. Even with lock-ownership tracking, ownership is not usually passed (to avoid convoy issues) other than in the executive resource case, explained in an upcoming section.

For certain kinds of lock objects that use events or gates as their underlying synchronization object, the lock-ownership boost resolves the dilemma. Also, on a multiprocessor machine, the ready thread might get picked up on another processor (due to the processor-distribution and load-balancing schemes you'll see later), and its high priority might increase the chances of it running on that second-ary processor instead.

### Lock-ownership boosts

Because the executive-resource (ERESOURCE) and critical-section locks use underlying dispatcher objects, releasing these locks results in an unwait boost as described earlier. On the other hand, because the high-level implementation of these objects tracks the owner of the lock, the kernel can make a more informed decision as to what kind of boost should be applied by using the AdjustBoost reason. In these kinds of boosts, AdjustIncrement is set to the current priority of the releasing (or setting) thread, minus any graphical user interface (GUI) foreground separation boost. In addition, before the KiExitDispatcher function is called, KiRemoveBoostThread is called by the event and gate code to return the releasing thread back to its regular priority. This step is needed to avoid a lock-convoy situation, in which two threads repeatedly passing the lock between one another get ever-increasing boosts.

**Note** Pushlocks, which are unfair locks because ownership of the lock in a contended acquisition path is not predictable (rather, it's random, like a spinlock), do not apply priority boosts due to lock ownership. This is because doing so only contributes to preemption and priority proliferation, which isn't required because the lock becomes immediately free as soon as it is released (bypassing the normal wait/unwait path).

Other differences between the lock-ownership boost and unwait boost will be exposed in the way the scheduler actually applies boosting, which is the subject of the next section.

### Priority boosting after I/O completion

Windows gives temporary priority boosts upon completion of certain I/O operations so that threads that were waiting for an I/O have more of a chance to run right away and process whatever was being waited for. Although you'll find recommended boost values in the Windows Driver Kit (WDK) header files (by searching for *#define IO\_* in Wdm.h or Ntddk.h), the actual value for the boost is up to the device driver. (These values are listed in Table 4-3.) It is the device driver that specifies the boost when it completes an I/O request on its call to the kernel function, IoCompleteRequest. In Table 4-3, notice that I/O requests to devices that warrant better responsiveness have higher boost values.

#### TABLE 4-3 Recommended boost values

Device	Boost
Disk, CD-ROM, parallel, video	1
Network, mailslot, named pipe, serial	2
Keyboard, mouse	6
Sound	8

**Note** You might intuitively expect better responsiveness from your video card or disk than a boost of 1. However, the kernel is in fact trying to optimize for *latency*, to which some devices (as well as human sensory inputs) are more sensitive than others. To give you an idea, a sound card expects data around every 1 ms to play back music without perceptible glitches, while a video card needs to output at only 24 frames per second, or about once every 40 ms, before the human eye can notice glitches.

As hinted earlier, these I/O completion boosts rely on the unwait boosts seen in the previous section. Chapter 6 shows the mechanism of I/O completion in depth. For now, the important detail is that the kernel implements the signaling code in the IoCompleteRequest API through the use of either an APC (for asynchronous I/O) or through an event (for synchronous I/O). When a driver passes in—for example, IO\_DISK\_INCREMENT to IoCompleteRequest for an asynchronous disk read—the kernel calls KeInsertQueueApc with the boost parameter set to IO\_DISK\_INCREMENT. In turn, when the thread's wait is broken due to the APC, it receives a boost of 1.

Be aware that the boost values given in Table 4-3 are merely recommendations by Microsoft. Driver developers are free to ignore them, and certain specialized drivers can use their own values. For example, a driver handling ultrasound data from a medical device, which must notify a user-mode visualization application of new data, would probably use a boost value of 8 as well, to satisfy the same latency as a sound card. In most cases, however, due to the way Windows driver stacks are built (again, see Chapter 6 for more information), driver developers often write *minidrivers*, which call into a Microsoft-owned driver that supplies its own boost to IoCompleteRequest. For example, RAID or SATA controller card developers typically call StorPortCompleteRequest to complete processing their requests. This call does not have any parameter for a boost value, because the Storport.sys driver fills in the right value when calling the kernel. Additionally, whenever any file system driver (identified by setting its device type to FILE\_ DEVICE\_DISK\_FILE\_SYSTEM or FILE\_DEVICE\_NETWORK\_FILE\_SYSTEM) completes its request, a boost of IO\_DISK\_INCREMENT is always applied if the driver passed in IO\_NO\_INCREMENT (0) instead. So this boost value has become less of a recommendation and more of a requirement enforced by the kernel.

### Boosts during waiting on executive resources

When a thread attempts to acquire an executive resource (ERESOURCE; see Chapter 8 in Part 2 for more information on kernel-synchronization objects) that is already owned exclusively by another thread, it must enter a wait state until the other thread has released the resource. To limit the risk of deadlocks, the executive performs this wait in intervals of 500 ms instead of doing an infinite wait on the resource.

At the end of these 500 ms, if the resource is still owned, the executive attempts to prevent CPU starvation by acquiring the dispatcher lock, boosting the owning thread or threads to 15 (if the original owner priority is less than the waiter's and not already 15), resetting their quantums, and performing another wait.

Because executive resources can be either shared or exclusive, the kernel first boosts the exclusive owner and then checks for shared owners and boosts all of them. When the waiting thread enters the wait state again, the hope is that the scheduler will schedule one of the owner threads, which will have enough time to complete its work and release the resource. Note that this boosting mechanism is used only if the resource doesn't have the Disable Boost flag set, which developers can choose to set if the priority-inversion mechanism described here works well with their usage of the resource.

Additionally, this mechanism isn't perfect. For example, if the resource has multiple shared owners, the executive boosts all those threads to priority 15. This results in a sudden surge of high-priority threads on the system, all with full quantums. Although the initial owner thread will run first (because it was the first to be boosted and therefore is first on the ready list), the other shared owners will run next because the waiting thread's priority was not boosted. Only after all the shared owners have had a chance to run and their priority has been decreased below the waiting thread will the waiting thread finally get its chance to acquire the resource. Because shared owners can promote or convert their ownership from shared to exclusive as soon as the exclusive owner releases the resource, it's possible for this mechanism not to work as intended.

### Priority boosts for foreground threads after waits

As will be described shortly, whenever a thread in the foreground process completes a wait operation on a kernel object, the kernel boosts its current (not base) priority by the current value of PsPrioritySeparation. (The windowing system is responsible for determining which process is considered to be in the foreground.) As described earlier in this chapter in the section "Controlling the quantum," PsPrioritySeparation reflects the quantum-table index used to select quantums for the threads of foreground applications. However, in this case, it is being used as a priority boost value.

The reason for this boost is to improve the responsiveness of interactive applications. By giving the foreground application a small boost when it completes a wait, it has a better chance of running right away, especially when other processes at the same base priority might be running in the background.

### **EXPERIMENT:** Watching foreground priority boosts and decays


Using the CPU Stress tool, you can watch priority boosts in action. Take the following steps:

- Open the System utility in Control Panel or right-click the **This Computer** icon on the desktop and choose **Properties**.
- 2. Click the Advanced System Settings label, click the Advanced tab, click the Settings button in the Performance section, and click the Advanced tab.
- 3. Select the **Programs** option. This gives PsPrioritySeparation a value of 2.

- 4. Run CPU Stress, right-click thread 1, and choose Busy from the context menu.
- 5. Start the Performance Monitor tool.
- Click the Add Counter toolbar button or press Ctrl+l to open the Add Counters dialog box.
- 7. Select the Thread object and then select the Priority Current counter.
- 8. In the Instances box, select <**All Instances**> and click **Search**.
- **9.** Scroll down to the CPUSTRES process, select the second thread (thread 1; the first thread is the GUI thread) and click the **Add** button. You should see something like this:

vailable counters		Added counters				
Select counters from computer:		Counter	Parent	Inst	Computer	
<local computer=""></local>	Browse	Thread	1 contained			-
re provieges reve % Processor Time % User Time Context Switches/sec Elapsed Time ID Process ID Thread Priority Base Priority Current	*	Priority Current	CPU	1		
Start Address Instances of selected object:	×					
conhost/3 conhost/3#1 conhost/3#2 CPUSTRES/0 CPUSTRES/1	^					
CPUSTRES/2 CPUSTRES/3 CPLISTRES/4	*					
<all instances=""> v</all>	Search					
L	Add >>	Remove <<				

- 10. Click OK.
- 11. Right-click the counter and select **Properties**.
- 12. Click the Graph tab and change the maximum vertical scale to 16. Then click OK.
- 13. Bring the CPUSTRES process to the foreground. You should see the priority of the CPUSTRES thread being boosted by 2 and then decaying back to the base priority. CPUSTRES periodically receives a boost of 2 because the thread you're monitoring is sleeping about 25 percent of the time and then waking up. (This is the Busy activity level.) The boost is applied when the thread wakes up. If you set the activity level to Maximum, you won't see any boosts because Maximum in CPUSTRES puts the thread into an infinite loop. Therefore, the thread doesn't invoke any wait functions and therefore doesn't receive any boosts.



14. When you've finished, exit Performance Monitor and CPU Stress.

### Priority boosts after GUI threads wake up

Threads that own windows receive an additional boost of 2 when they wake up because of windowing activity such as the arrival of window messages. The windowing system (Win32k.sys) applies this boost when it calls KeSetEvent to set an event used to wake up a GUI thread. The reason for this boost is similar to the previous one: to favor interactive applications.

### **EXPERIMENT:** Watching priority boosts on GUI threads

You can see the windowing system apply its boost of 2 for GUI threads that wake up to process window messages by monitoring the current priority of a GUI application and moving the mouse across the window. Just follow these steps:

- 1. Open the System utility in Control Panel.
- 2. Click the Advanced System Settings label, click the Advanced tab, click the Settings button in the Performance section, and click the Advanced tab.
- 3. Select the **Programs** option. This gives PsPrioritySeparation a value of 2.
- 4. Run Notepad.

- 5. Start the Performance Monitor tool.
- Click the Add Counter toolbar button or press Ctrl+I to open the Add Counters dialog box.
- 7. Select the Thread object and then select the Priority Current counter.
- 8. In the Instances box, type Notepad. Then click Search.
- 9. Scroll down to the Notepad/0 entry, click it, click the Add button, and then click OK.
- **10.** As in the previous experiment, change the maximum vertical scale to 16. You should see the priority of thread 0 in Notepad at 8 or 10. (Because Notepad entered a wait state shortly after it received the boost of 2 that threads in the foreground process receive, it might not yet have decayed from 10 to 8.)
- **11.** With Performance Monitor in the foreground, move the mouse across the Notepad window. (Make both windows visible on the desktop.) Notice that the priority sometimes remains at 10 and sometimes at 9, for the reasons just explained.

**Note** You won't likely catch Notepad at 8. This is because it runs so little after receiving the GUI thread boost of 2 that it never experiences more than one priority level of decay before waking up again. (This is due to additional windowing activity and the fact that it receives the boost of 2 again.)

- **12.** Bring Notepad to the foreground. You should see the priority rise to 12 and remain there. This is because the thread is receiving two boosts: the boost of 2 applied to GUI threads when they wake up to process windowing input and an additional boost of 2 because Notepad is in the foreground. (Or, you may see it drop to 11 if it experiences the normal priority decay that occurs for boosted threads on the quantum end.)
- **13.** Move the mouse over Notepad while it's still in the foreground. You might see the priority drop to 11 (or maybe even 10) as it experiences the priority decay that normally occurs on boosted threads as they complete their turn. However, the boost of 2 that is applied because it's the foreground process remains as long as Notepad remains in the foreground.
- 14. Exit Performance Monitor and Notepad.

#### Priority boosts for CPU starvation

Imagine the following situation: A priority 7 thread is running, preventing a priority 4 thread from ever receiving CPU time. However, a priority 11 thread is waiting for some resource that the priority 4 thread has locked. But because the priority 7 thread in the middle is eating up all the CPU time, the priority 4 thread will never run long enough to finish whatever it's doing and release the resource blocking the priority 11 thread. This scenario is known as *priority inversion*.

What does Windows do to address this situation? An ideal solution (at least in theory) would be to track locks and owners and boost the appropriate threads so that forward progress can be made. This idea is implemented with a feature called *Autoboost*, described later in this chapter in the section "Autoboost." However, for general starvation scenarios, the following mitigation is used.

You saw how the code responsible for executive resources manages this scenario by boosting the owner threads so that they can have a chance to run and release the resource. However, executive resources are only one of the many synchronization constructs available to developers, and the boosting technique will not apply to any other primitive. Therefore, Windows also includes a generic CPU starvation-relief mechanism as part of a thread called the *balance-set manager*. (This is a system thread that exists primarily to perform memory-management functions and is described in more detail in Chapter 5.) Once per second, this thread scans the ready queues for any threads that have been in the ready state (that is, haven't run) for approximately 4 seconds. If it finds such a thread, the balance-set manager boosts the thread's priority to 15 and sets the quantum target to an equivalent CPU clock cycle count of 3 quantum units. After the quantum expires, the thread's priority thread is ready to run, the decayed thread returns to the ready queue, where it again becomes eligible for another boost if it remains there for another 4 seconds.

The balance-set manager doesn't actually scan all the ready threads every time it runs. To minimize the CPU time it uses, it scans only 16 ready threads, If there are more threads at that priority level, it remembers where it left off and picks up again on the next pass. Also, it boosts only 10 threads per pass. If it finds more than 10 threads meriting this particular boost (which indicates an unusually busy system), it stops the scan and picks up again on the next pass.

**Note** As mentioned, scheduling decisions in Windows are not affected by the number of threads and are made in constant time. Because the balance-set manager must scan ready queues manually, this operation depends on the number of threads on the system; more threads require more scanning time. However, the balance-set manager is not considered part of the scheduler or its algorithms and is simply an extended mechanism to increase reliability. Additionally, because of the cap on threads and queues to scan, the performance impact is minimized and predictable in a worst-case scenario.

### **EXPERIMENT:** Watching priority boosts for CPU starvation

Using the CPU Stress tool, you can watch priority boosts in action. In this experiment, you'll see CPU usage change when a thread's priority is boosted. Take the following steps:

1. Run CPUSTRES.exe.

- 2. The activity level of thread 1 is Low. Change it to Maximum.
- 3. The thread priority of thread 1 is Normal. Change it to Lowest.

- 4. Click thread 2. Its activity level is Low. Change it to Maximum.
- 5. Change the process affinity mask to a single logical processor. To do so, open the Process menu and choose Affinity. (It doesn't matter which processor.) Alternatively, use Task Manager to make the change. The screen should look something like this:

File	Process T	hread Optic	ns Help			
-	- 10	<ul><li>3</li></ul>		s Affinity: 100000 s Priority Class: No		
	ID	Active?	Activity	Priority	Ideal CPU	Affinity
#	10					
1	11724	Yes	Maximum	Lowest	6	11111111
1 2		Yes Yes	Maximum Maximum	Lowest Normal	6 4	11111111 11111111
# 1 2 3	11724				6 4 6	

- 6. Start the Performance Monitor tool.
- 7. Click the Add Counter toolbar button or press Ctrl+I to open the Add Counters dialog box.
- 8. Select the Thread object and then select the Priority Current counter.
- 9. In the Instances box, type **CPUSTRES** and click **Search**.
- 10. Select threads 1 and 2 (thread 0 is the GUI thread), click the Add button, and click OK.
- **11.** Change the vertical scale maximum to 16 for both counters.
- 12. Because Performance Monitor refreshes once per second, you may miss the priority boosts. To help with that, press Ctrl+F to freeze the display. Then force updates to occur more frequently by pressing and holding down Ctrl+U. With some luck, you may see a priority boost for the lower-priority thread to level 15 like so:

Serformance Monitor							
File Action View Window	Help						- 0
🗭 🐟 🙇 📰 🖾 🗰 📓 📷							
Bentationg Tools     Minimum Performance Monitor     Jong Data Collector Sets     Reports	16 14- 12- 10- 8 6 4- 2- 0 21:28:38		Average Counter Priority Current	21:28:	40 21:28 Minimum Instance 1	40 21/28-41 00 Masimum Duration Object Thread	21:28:38 8:00 1:4

13. Exit Performance Monitor and CPU Stress.

### Applying boosts

Back in KiExitDispatcher, you saw that KiProcessThreadWaitList is called to process any threads in the deferred ready list. It is here that the boost information passed by the caller is processed. This is done by looping through each DeferredReady thread, unlinking its wait blocks (only Active and Bypassed blocks are unlinked), and setting two key values in the kernel's thread control block: Adjust-Reason and AdjustIncrement. The reason is one of the two Adjust possibilities seen earlier, and the increment corresponds to the boost value. KiDeferredReadyThread is then called. This makes the thread ready for execution by running two algorithms: the quantum and priority selection algorithm (which you are about to see in two parts) and the processor selection algorithm (which is shown in the "Processor selection" section later in this chapter).

Let's first look at when the algorithm applies boosts, which happens only in cases when a thread is not in the real-time priority range. For an AdjustUnwait boost, it will be applied only if the thread is not already experiencing an unusual boost and only if the thread has not disabled boosting by calling SetThreadPriorityBoost, which sets the DisableBoost flag in the KTHREAD. Another situation that can disable boosting in this case is if the kernel has realized that the thread has actually exhausted its quantum (but the clock interrupt did not fire to consume it) and it has come out of a wait that lasted less than two clock ticks.

If these situations are not currently true, the new priority of the thread will be computed by adding the AdjustIncrement to the thread's current base priority. Additionally, if the thread is known to be part of a foreground process (meaning that the memory priority is set to MEMORY\_PRIORITY\_FOREGROUND, which is configured by Win32k.sys when focus changes), this is where the priority-separation boost (PsPrioritySeparation) is applied by adding its value on top of the new priority. This is also known as the *foreground priority boost*, which was explained earlier.

Finally, the kernel checks whether this newly computed priority is higher than the current priority of the thread, and it limits this value to an upper bound of 15 to avoid crossing into the real-time range. It then sets this value as the thread's new current priority. If any foreground separation boost was applied, it sets this value in the ForegroundBoost field of the KTHREAD, which results in a PriorityDecrement equal to the separation boost.

For AdjustBoost boosts, the kernel checks whether the thread's current priority is lower than the AdjustIncrement (recall this is the priority of the setting thread) and whether the thread's current priority is below 13. If so, and priority boosts have not been disabled for the thread, the AdjustIncrement priority is used as the new current priority, limited to a maximum of 13. Meanwhile, the UnusualBoost field of the KTHREAD contains the boost value, which results in a PriorityDecrement equal to the lock-ownership boost.

In all cases where a PriorityDecrement is present, the quantum of the thread is also recomputed to be the equivalent of only one clock tick, based on the value of KiLockQuantumTarget. This ensures that foreground and unusual boosts will be lost after one clock tick instead of the usual two (or other configured value), as will be shown in the next section. This also happens when an AdjustBoost is requested but the thread is running at priority 13 or 14 or with boosts disabled.

After this work is complete, AdjustReason is now set to AdjustNone.

### **Removing boosts**

Removing boosts is done in KiDeferredReadyThread as boosts and quantum recomputations are being applied (as shown in the previous section). The algorithm first begins by checking the type of adjustment being done.

For an AdjustNone scenario, which means the thread became ready perhaps due to a preemption, the thread's quantum will be recomputed if it already hit its target but the clock interrupt has not yet noticed, as long as the thread was running at a dynamic priority level. Additionally, the thread's priority will be recomputed. For an AdjustUnwait or AdjustBoost scenario on a non-real-time thread, the kernel checks whether the thread silently exhausted its quantum (as in the prior section). If so, or if the thread was running with a base priority of 14 or higher, or if no PriorityDecrement is present and the thread has completed a wait that lasted longer than two clock ticks, the quantum of the thread is recomputed, as is its priority.

Priority recomputation happens on non-real-time threads. It's done by taking the thread's current priority, subtracting its foreground boost, subtracting its unusual boost (the combination of these last two items is the PriorityDecrement), and finally subtracting 1. This new priority is bounded with the base priority as the lowest bound and any existing priority decrement is zeroed out (clearing unusual and foreground boosts). This means that in the case of a lock-ownership boost or any of the other unusual boosts explained, the entire boost value is now lost. On the other hand, for a regular AdjustUnwait boost, the priority naturally trickles down by 1 due to the subtraction by 1. This lowering eventually stops when the base priority is hit due to the lower bound check.

There is another instance where boosts must be removed, which goes through the KiRemoveBoost-Thread function. This is a special-case boost removal that occurs due to the lock-ownership boost rule, which specifies that the setting thread must lose its boost when donating its current priority to the waking thread (to avoid a lock convoy). It is also used to undo the boost due to targeted deferred procedure calls (DPCs) as well as the boost against ERESOURCE lock-starvation boost. The only special detail about this routine is that when computing the new priority, it takes special care to separate the ForegroundBoost and UnusualBoost components of the PriorityDecrement to maintain any GUI foreground-separation boost that the thread accumulated. This behavior, which appeared starting with Windows 7, ensures that threads relying on the lock-ownership boost do not behave erratically when running in the foreground, or vice-versa.

Figure 4-12 displays an example of how normal boosts are removed from a thread as it experiences quantum end.




FIGURE 4-12 Priority boosting and decay.

### Priority boosts for multimedia applications and games

Although Windows' CPU-starvation priority boosts might be enough to get a thread out of an abnormally long wait state or potential deadlock, they simply cannot deal with the resource requirements imposed by a CPU-intensive application such as Windows Media Player or a 3D computer game.

Skipping and other audio glitches have long been a common source of irritation among Windows users. The Windows user-mode audio stack exacerbates this situation because it offers even more chances for preemption. To address this, client versions of Windows use the MMCSS driver (described earlier in this chapter), implemented in %SystemRoot%\System32\Drivers\MMCSS.sys. Its purpose is to ensure glitch-free multimedia playback for applications that register with it.

**Note** Windows 7 implements MMCSS as a service (rather than a driver). This posed a potential risk, however. If the MMCSS managing thread blocked for any reason, the threads managed by it would retain their real-time priorities, potentially causing system-wide starvation. The solution was to move the code to the kernel where the managing thread (and other resources used by MMCSS) could not be touched. There are other benefits to being a kernel driver, such as holding a direct pointer to process and thread objects rather than IDs or handles. This bypasses searches based on IDs or handles and allows faster communication with the scheduler and Power Manager.

Client applications can register with MMCSS by calling AvSetMmThreadCharacteristics with a task name that must match one of the subkeys under HKLM\SOFTWARE\Microsoft\Windows NT\ CurrentVersion\Multimedia\SystemProfile\Tasks. (The list can be modified by OEMs to include other specific tasks as appropriate.) Out of the box, the following tasks exist:

- Audio
- Capture
- Distribution
- Games
- Low Latency
- Playback
- Pro Audio
- Window Manager

Each of these tasks includes information about the various properties that differentiate them. The most important one for scheduling is called the *Scheduling Category*, which is the primary factor determining the priority of threads registered with MMCSS. Table 4-4 shows the various scheduling categories.

Category	Priority	Description
High	23–26	Pro Audio threads running at a higher priority than any other thread on the system except for critical system threads
Medium	16–22	The threads part of a foreground application such as Windows Media Player
Low	8–15	All other threads that are not part of the previous categories
Exhausted	4-6	Threads that have exhausted their share of the CPU and will continue running only if no other higher-priority threads are ready to run

#### **TABLE 4-4** Scheduling categories

The main mechanism behind MMCSS boosts the priority of threads inside a registered process to the priority level matching their scheduling category and relative priority within this category for a guaranteed period. It then lowers those threads to the exhausted category so that other, non-multimedia threads on the system can also get a chance to execute.

By default, multimedia threads get 80 percent of the CPU time available, while other threads receive 20 percent. (Based on a sample of 10 ms, that would be 8 ms and 2 ms, respectively.) You can change this percentage by modifying the SystemResponsiveness registry value under the HKLM\SOFTWARE\ Microsoft\Windows NT\CurrentVersion\Multimedia\SystemProfile key. The value can range from 10 to 100 percent (20 is the default; setting a value lower than 10 evaluates to 10), which indicates the CPU percentage guaranteed to the system (not the registered audio apps). MMCSS scheduling thread runs at priority 27 because they need to preempt any Pro Audio threads to lower their priority to the exhausted category.


As discussed, changing the relative thread priorities within a process does not usually make sense, and no tool allows this because only developers understand the importance of the various threads in their programs. On the other hand, because applications must manually register with MMCSS and provide it with information about what kind of thread this is, MMCSS does have the necessary data to change these relative thread priorities—and developers are well aware that this will happen.

#### **EXPERIMENT: MMCSS priority boosting**

In this experiment, you'll see the effects of MMCSS priority boosting.

- 1. Run Windows Media Player (wmplayer.exe). (Other playback programs might not take advantage of the API calls required to register with MMCSS.)
- 2. Play some audio content.
- **3.** Using Task Manager or Process Explorer, set the affinity of the Wmplayer.exe process so that it runs on only one CPU.
- **4.** Start the Performance Monitor tool.
- **5.** Using Task Manager, change Performance Monitor's priority class to **Realtime** so it will have a better chance of recording activity.

- 6. Click the Add Counter toolbar button or press Ctrl+I to open the Add Counters dialog box.
- 7. Select the Thread object and then select the Priority Current.
- 8. In the Instances box, type Wmplayer, click Search, and then select all its threads.
- 9. Click the Add button and click OK.
- 10. Open the Action menu and choose Properties.
- **11.** On the Graph tab, change the maximum vertical scale to 32. You should see one or more priority-16 threads inside Wmplayer, which will be constantly running unless there is a higher-priority thread requiring the CPU after they are dropped to the exhausted category.
- 12. Run CPU Stress.
- 13. Set the activity level of thread 1 to Maximum.
- 14. The priority of thread 1 is Normal. Change it to Time Critical.
- 15. Change the CPUSTRES priority class to High.
- **16.** Change the CPUSTRES affinity to use the same CPU used for Wmplayer. The system should slow down considerably, but the music playback should continue. Every so often, you'll be able to get back some responsiveness from the rest of the system.
- **17.** In Performance Monitor, notice that the WmPlayer priority 16 threads drop from time to time as shown here:



MMCSS' functionality does not stop at simple priority boosting, however. Because of the nature of network drivers on Windows and the NDIS stack, DPCs are quite common mechanisms for delaying work after an interrupt has been received from the network card. Because DPCs run at an IRQL level higher than user-mode code (see Chapter 6 for more information on DPCs and IRQLs), long-running network card driver code can still interrupt media playback—for example, during network transfers or when playing a game.

MMCSS sends a special command to the network stack, telling it to throttle network packets during the duration of the media playback. This throttling is designed to maximize playback performance—at the cost of some small loss in network throughput (which would not be noticeable for network operations usually performed during playback, such as playing an online game). The exact mechanisms behind it do not belong to any area of the scheduler, so we'll leave them out of this description.

MMCSS also supports a feature called *deadline scheduling*. The idea is that an audio-playing program does not always need the highest priority level in its category. If such a program uses buffering (obtaining audio data from disk or network) and then plays the buffer while building the next buffer, deadline scheduling allows a client thread to indicate a time when it must get the high priority level to avoid glitches, but live with a slightly lower priority (within its category) in the meantime. A thread can use the AvTaskIndexYield function to indicate the next time it must be allowed to run, specifying the time it needs to get the highest priority within its category. Until that time arrives, it gets the lowest priority within its category, potentially freeing more CPU time to the system.

#### Autoboost

*Autoboost* is a framework targeted at the priority-inversion problem described in the previous section. The idea is to track lock owners and lock waiters in such a way that would allow boosting the appropriate threads' priorities (I/O priority as well if needed) to allow threads to make forward progress. The lock information is stored in a static array of KLOCK\_ENTRY objects inside the KTHREAD structure. The current implementation uses a maximum of six entries. Each KLOCK\_ENTRY maintains two binary trees: one for locks owned by the thread and the other for locks waited on by the thread. These trees are keyed by priority so that constant time is required to determine the highest priority to which boosting should be applied. If boost is required, the owner's priority is set to the waiter's priority. It may also boost I/O priority if these were issued with low priority. (See Chapter 6 for more on I/O priority.) As with all priority boosts, the maximum priority achievable by Autoboost is 15. (The priority of real-time threads is never boosted.)

Current implementation uses the Autoboost framework for pushlocks and guarded mutexes synchronization primitives, which are exposed to kernel code only. (See Chapter 8 in Part 2 for more on these objects.) The framework is also used by some executive components for specialized cases. Future versions of Windows may implement Autoboost for user-mode accessible objects that have an ownership concept, such as critical sections.

# **Context switching**


A thread's context and the procedure for context switching vary depending on the processor's architecture. A typical context switch requires saving and reloading the following data:

- Instruction pointer
- Kernel stack pointer
- A pointer to the address space in which the thread runs (the process's page table directory)

The kernel saves this information from the old thread by pushing it onto the current (old thread's) kernel-mode stack, updating the stack pointer, and saving the stack pointer in the old thread's KTHREAD structure. The kernel stack pointer is then set to the new thread's kernel stack, and the new thread's context is loaded. If the new thread is in a different process, it loads the address of its page table directory into a special processor register so that its address space is available. (See the description of address translation in Chapter 5.) If a kernel APC that needs to be delivered is pending, an interrupt at IRQL 1 is requested. (For more information on APCs, see Chapter 8 in Part 2.) Otherwise, control passes to the new thread's restored instruction pointer and the new thread resumes execution.

### **Direct Switch**

Windows 8 and Server 2012 introduced an optimization called Direct Switch, that allows a thread to donate its quantum and boost to another thread, which is then immediately scheduled on the same processor. In synchronous client/server scenarios, this can produce significant throughput improvements because the client/server threads are not migrated to other processors that may be idle or parked. Another way to think about this is that at any given time, only the client or the server thread is running, so the thread scheduler should treat them as a single logical thread. Figure 4-13 shows the effect of using Direct Switch.



The scheduler has no way of knowing that the first thread (T1 in Figure 4-13) is about to enter a wait state after signaling some synchronization object that the second thread (T2) is waiting on. Therefore, a special function must be called to let the scheduler know that this is the case (atomic signal and wait).

If possible, the KiDi rectSwitchThread function performs the actual switch. It's called by KiExit-Dispatcher if passed a flag indicating to use Direct Switch if possible. Priority donation, in which the first thread's priority is "donated" to the second thread (if the latter's priority is lower than the former), is applied if specified by yet another bit flag to KiExitDispatcher. In the current implementation, these two flags are always specified together (or none at all), meaning in any Direct Switch attempt, priority donation is attempted as well. Direct Switch can fail—for example, if the target thread's affinity precludes it from running on the current processor. However, if it succeeds, the quantum of the first thread is transferred to the target thread and the first thread loses its remaining quantum.

Direct Switch is currently used in the following scenarios:

- If a thread calls the SignalObjectAndWait Windows API (or its kernel equivalent NtSignalAndWaitForSingleObject)
- ALPC (described in Chapter 8 in Part 2)
- Synchronous remote procedure call (RPC) calls
- COM remote calls (currently MTA [multithreaded apartment] to MTA only)

# **Scheduling scenarios**

Windows answers the question of "Who gets the CPU?" based on thread priority, but how does this approach work in practice? The following sections illustrate just how priority-driven preemptive multi-tasking works on the thread level.

### Voluntary switch

A thread might voluntarily relinquish use of the processor by entering a wait state on some object (such as an event, a mutex, a semaphore, an I/O completion port, a process, a thread, and so on) by calling one of the Windows wait functions such as WaitForSingleObject or WaitForMultipleObjects. (Waiting for objects is described in more detail in Chapter 8 in Part 2.)

Figure 4-14 illustrates a thread entering a wait state and Windows selecting a new thread to run. In Figure 4-14, the top block (thread) is voluntarily relinquishing the processor so that the next thread in the ready queue can run. (This is represented by the halo it has when in the Running column.) Although it might appear from this figure that the relinquishing thread's priority is being reduced, it's not. It's just being moved to the wait queue of the objects the thread is waiting for.




FIGURE 4-14 Voluntary switching.

### Preemption

In this scheduling scenario, a lower-priority thread is preempted when a higher-priority thread becomes ready to run. This situation might occur for a couple of reasons:

- A higher-priority thread's wait completes (the event that the other thread was waiting for has occurred).
- A thread priority is increased or decreased.

In either of these cases, Windows must determine whether the currently running thread should continue to run or be preempted to allow a higher-priority thread to run.

**Note** Threads running in user mode can preempt threads running in kernel mode. The mode in which the thread is running doesn't matter; the thread priority is the determining factor.

When a thread is preempted, it is put at the head of the ready queue for the priority it was running at (see Figure 4-15).





FIGURE 4-15 Preemptive thread scheduling.

In Figure 4-15, a thread with priority 18 emerges from a wait state and repossesses the CPU, causing the thread that had been running (at priority 16) to be bumped to the head of the ready queue. Notice that the bumped thread doesn't go to the end of the queue. Rather, it goes to the beginning. When the preempting thread has finished running, the bumped thread can complete its quantum.

### Quantum end

When the running thread exhausts its CPU quantum, Windows must determine whether the thread's priority should be decremented and then whether another thread should be scheduled on the processor.

If the thread priority is reduced (for example, because of some boost it received before), Windows looks for a more appropriate thread to schedule, such as one in a ready queue with a higher priority than the new priority for the currently running thread. If the thread priority isn't reduced and there are other threads in the ready queue at the same priority level, Windows selects the next thread in the ready queue at that same priority level. It then moves the previously running thread to the tail of that queue, giving it a new quantum value and changing its state from running to ready. This is illustrated in Figure 4-16. If no other thread of the same priority is ready to run, the thread gets to run for another quantum.





As you saw, instead of simply relying on a clock interval timer–based quantum to schedule threads, Windows uses an accurate CPU clock cycle count to maintain quantum targets. Windows also uses this count to determine whether quantum end is currently appropriate for the thread—something that might have happened previously and is important to discuss.

Using a scheduling model that relies only on the clock interval timer, the following situation can occur:

- Threads A and B become ready to run during the middle of an interval. (Scheduling code runs not just at each clock interval, so this is often the case.)
- Thread A starts running but is interrupted for a while. The time spent handling the interrupt is charged to the thread.
- Interrupt processing finishes and thread A starts running again, but it quickly hits the next clock interval. The scheduler can assume only that thread A had been running all this time and now switches to thread B.

 Thread B starts running and has a chance to run for a full clock interval (barring preemption or interrupt handling).

In this scenario, thread A was unfairly penalized in two different ways. First, the time it spent handling a device interrupt was counted against its own CPU time, even though the thread probably had nothing to do with the interrupt. (Interrupts are handled in the context of whichever thread was running at the time, as discussed in Chapter 6.) It was also unfairly penalized for the time the system was idling inside that clock interval before it was scheduled. Figure 4-17 illustrates this scenario.




FIGURE 4-17 Unfair time slicing in pre-Vista versions of Windows.

Windows keeps an accurate count of the exact number of CPU clock cycles spent doing work that the thread was scheduled to do (which means excluding interrupts). It also keeps a quantum target of clock cycles that should have been spent by the thread at the end of its quantum. Therefore, both of the unfair decisions that would have been made against thread A as described in the preceding paragraph will not happen in Windows. Instead, the following situation occurs:

- Threads A and B become ready to run during the middle of an interval.
- Thread A starts running but is interrupted for a while. The CPU clock cycles spent handling the interrupt are not charged to the thread.
- Interrupt processing finishes and thread A starts running again, but it quickly hits the next clock interval. The scheduler looks at the number of CPU clock cycles charged to the thread and compares them to the expected CPU clock cycles that should have been charged at quantum end.
- Because the former number is much smaller than it should be, the scheduler assumes that thread A started running in the middle of a clock interval and might have been additionally interrupted.
- Thread A gets its quantum increased by another clock interval, and the quantum target is recalculated. Thread A now has its chance to run for a full clock interval.
- At the next clock interval, thread A has finished its quantum, and thread B now gets a chance to run.

Figure 4-18 illustrates this scenario.




FIGURE 4-18 Fair time slicing in current versions of Windows.

### Termination

When a thread finishes running (either because it returned from its main routine, called ExitThread, or was killed with TerminateThread), it moves from the running state to the terminated state. If there are no handles open on the thread object, the thread is removed from the process thread list and the associated data structures are deallocated and released.

## Idle threads

When no runnable thread exists on a CPU, Windows dispatches that CPU's idle thread. Each CPU has its own dedicated idle thread. This is because on a multiprocessor system, one CPU can be executing a thread while other CPUs might have no threads to execute. Each CPU's idle thread is found via a pointer in that CPU's PRCB.

All the idle threads belong to the idle process. The idle process and idle threads are special cases in many ways. They are, of course, represented by EPROCESS/KPROCESS and ETHREAD/KTHREAD structures, but they are not executive manager processes and thread objects. Nor is the idle process on the system process list. (This is why it does not appear in the output of the kernel debugger's !process 0 0 command.) However, the idle thread or threads and their process can be found in other ways.

### EXPERIMENT: Displaying the structures of the idle threads and idle process

You can find the idle thread and process structures in the kernel debugger via the !pcr command. (*PCR* is short for *processor control region*.) This command displays a subset of information from the PCR and from the associated PRCB. !pcr takes a single numeric argument, which is the number of the CPU whose PCR is to be displayed. The boot processor is processor 0. It is always present, so !pcr 0 should always work. The following output shows the results of this command from a local kernel debugging session for a 64-bit, eight-processor system:

```
1kd> !pcr
KPCR for Processor 0 at fffff80174bd0000:
Major 1 Minor 1
NtTib.ExceptionList: fffff80176b4a000
NtTib.StackBase: fffff80176b4b070
NtTib.StackLimit: 00000000108e3f8
NtTib.SubSystemTib: fffff80174bd0000
NtTib.Version: 000000074bd0180
NtTib.UserPointer: fffff80174bd07f0
```

#### NtTib.SelfTib: 00000098af072000

00000000000000000
fffff80174bd0180
000000000000000000000000000000000000000
000000000000000000000000000000000000000
000000000000000000000000000000000000000
000000000000000000000000000000000000000
000000000000000000000000000000000000000
000000000000000000000000000000000000000
000000000000000000000000000000000000000
ffffb882fa27c080
000000000000000000000000000000000000000
fffff80174c4c940

DpcQueue:

This output shows that CPU 0 was executing a thread other than its idle thread at the time the memory dump was obtained because the CurrentThread and IdleThread pointers are different. (On a multi-CPU system you can try !pcr 1, !pcr 2, and so on, until you run out. Observe that each IdleThread pointer is different.)

Now use the !thread command on the indicated idle thread address:

```
lkd> !thread fffff80174c4c940
THREAD fffff80174c4c940 Cid 0000.0000 Teb: 0000000000000 Win32Thread:
00000000000000 RUNNING on processor 0
Not impersonating
DeviceMap
                           ffff800a52e17ce0
Owning Processfffff80174c4b940Image:IdleAttached Processffffb882e7ec7640Image:SystWait Start TickCount1637993Ticks:30 (0:00:00:00.468)
                                                                    Idle
                                                                    System
                          25908837 IdealProcessor: 0
Context Switch Count
UserTime
                           00:00:00.000
KernelTime
                           05:51:23.796
Win32 Start Address nt!KiIdleLoop (0xffff801749e0770)
Stack Init fffff80176b52c90 Current fffff80176b52c20
Base fffff80176b53000 Limit fffff80176b4d000 Call 00000000000000
Priority 0 BasePriority 0 PriorityDecrement 0 IoPriority 0 PagePriority 5
```

Finally, use the !process command on the owning process shown in the preceding output. For brevity, we'll add a second parameter value of 3, which causes !process to emit only minimal information for each thread:

```
lkd> !process fffff80174c4b940 3
PROCESS fffff80174c4b940
SessionId: none Cid: 0000 Peb: 00000000 ParentCid: 0000
DirBase: 001aa000 ObjectTable: ffff800a52e14040 HandleCount: 2011.
Image: Idle
VadRoot ffffb882e7e1ae70 Vads 1 Clone 0 Private 7. Modified 1627. Locked 0.
DeviceMap 0000000000000
```

Token	ffff800a52e17040
ElapsedTime	07:07:04.015
UserTime	00:00:00.000
KernelTime	00:00:00.000
QuotaPoolUsage[PagedPool]	0
QuotaPoolUsage[NonPagedPool]	0
Working Set Sizes (now,min,max)	(7, 50, 450) (28KB, 200KB, 1800KB)
PeakWorkingSetSize	1
VirtualSize	0 Mb
PeakVirtualSize	0 Mb
PageFaultCount	2
MemoryPriority	BACKGROUND
BasePriority	0
CommitCharge	0

THREAD fffff80174c4c940 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 0 THREAD ffff9d81e230ccc0 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 1 THREAD ffff9d81e1bd9cc0 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 2 THREAD ffff9d81e2062cc0 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 3 THREAD ffff9d81e21a7cc0 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 4 THREAD ffff9d81e22ebcc0 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 5 THREAD ffff9d81e2428cc0 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 6 THREAD ffff9d81e256bcc0 Cid 0000.0000 Teb: 00000000000000 Win32Thread: 00000000000000 RUNNING on processor 7

These process and thread addresses can also be used with dt nt!\_EPROCESS, dt nt!\_ KTHREAD, and other such commands.

The preceding experiment shows some of the anomalies associated with the idle process and its threads. The debugger indicates an Image name of Idle (which comes from the EPROCESS structure's ImageFileName member), but various Windows utilities report the idle process using different names. Task Manager and Process Explorer call it *System Idle Process*, while tlist calls it *System Process*. The process ID and thread IDs (the client IDs, or Cid in the debugger's output) are 0, as are the PEB and TEB pointers and potentially many other fields in the idle process or its threads. Because the idle process has no user-mode address space and its threads execute no user-mode code, they have no need of the various data required to manage a user-mode environment. Also, the idle process is not an object-manager process object, and its idle threads are not object-manager thread objects. Instead, the initial idle thread and idle process structures are statically allocated and used to bootstrap the system before the process manager and the object manager are initialized. Subsequent idle thread structures are allocated dynamically (as simple allocations from a non-paged pool, bypassing the object manager) as additional process to refer to the idle process.

Perhaps the most interesting anomaly regarding the idle process is that Windows reports the priority of the idle threads as 0. In reality, however, the values of the idle threads' priority members are irrelevant because these threads are selected for dispatching only when there are no other threads to run. Their priority is never compared with that of any other thread. Nor is it used to put an idle thread on a ready queue, as idle threads are never part of any ready queues. (Only one thread per Windows system is actually running at priority 0—the zero page thread, explained in Chapter 5.)

Just as the idle threads are special cases in terms of selection for execution, they are also special cases for preemption. The idle thread's routine, KiIdleLoop, performs a number of operations that preclude its being preempted by another thread in the usual fashion. When no non-idle threads are available to run on a processor, that processor is marked as idle in its PRCB. After that, if a thread is selected for execution on the idle processor, the thread's address is stored in the NextThread pointer of the idle processor's PRCB. The idle thread checks this pointer on each pass through its loop.

Although some details of the flow vary between architectures (this is one of the few routines written in assembly and not in C), the basic sequence of operations of the idle thread is as follows:

- 1. The idle thread briefly enables interrupts, allowing any pending interrupts to be delivered, and then disables them (using the STI and CLI instructions on x86 and x64 processors). This is desirable because significant parts of the idle thread execute with interrupts disabled.
- 2. On the debug build on some architectures, the idle thread checks whether there is a kernel debugger trying to break into the system. If so, it gives it access.
- 3. The idle thread checks whether any DPCs (described in Chapter 6) are pending on the processor. DPCs could be pending if a DPC interrupt was not generated when they were queued. If DPCs are pending, the idle loop calls KiRetireDpcList to deliver them. This will also perform timer expiration, as well as deferred ready processing; the latter is explained in the upcoming "Multiprocessor systems" section. KiRetireDpcList must be entered with interrupts disabled, which is why interrupts are left disabled at the end of step 1. KiRetireDpcList exits with interrupts disabled as well.
- 4. The idle thread checks whether quantum end processing has been requested. If so, KiQuantum-End is called to process the request.
- 5. The idle thread checks whether a thread has been selected to run next on the processor. If so, it dispatches that thread. This could be the case if, for example, a DPC or timer expiration processed in step 3 resolved the wait of a waiting thread, or if another processor selected a thread for this processor to run while it was already in the idle loop.
- If requested, the idle thread checks for threads ready to run on other processors and, if possible, schedules one of them locally. (This operation is explained in the upcoming "Idle scheduler" section).
- 7. The idle thread calls the registered power-management processor idle routine (in case any power-management functions need to be performed), which is either in the processor power driver (such as intelppm.sys) or in the HAL if such a driver is unavailable.

# **Thread suspension**

Threads can be suspended and resumed explicitly with the SuspendThread and ResumeThread API functions, respectively. Every thread has a suspend count, which is incremented by suspension and decremented by resuming. If the count is 0, the thread is free to execute. Otherwise, it will not execute.

Suspension works by queuing a kernel APC to the thread. When the thread is switched in to execute, the APC is executed first. This puts the thread in a wait state on event that is signaled when the thread is finally resumed.

This suspension mechanism has a noticeable drawback if the thread is in a wait state while a suspension request comes in, because it means that the thread needs to wake up just to be suspended. This can result in a kernel stack inswap (if the thread's kernel stack was swapped out). Windows 8.1 and Server 2012 R2 added a mechanism called *Lightweight Suspend* to allow for the suspension of a thread that is in a wait state not by using the APC mechanism, but by directly manipulating the thread's object in memory and marking it as suspended.

# (Deep) freeze

Freezing is a mechanism by which processes enter a suspended state that cannot be changed by calling ResumeThread on threads in the process. This is useful when the system needs to suspend a UWP app. This happens when a Windows app goes to the background—for example, because another app comes to the foreground in Tablet mode or the app is minimized in Desktop mode. In this case, the system gives to the app roughly five seconds to do work, typically to save application state. Saving state is important because Windows apps may be killed without any notice if memory resources become low. If the app is killed, the state can be reloaded on the next launch and the user would have the perception that the app never really went away. Freezing a process means suspending all threads in such a way that ResumeThread is not able to wake. A flag in the KTHREAD structure indicates whether a thread is frozen. For a thread to be able to execute, its suspend count must be 0 and the frozen flag must be clear.

Deep freeze adds another constraint: Newly created threads in the process cannot start as well. For example, if a call to CreateRemoteThreadEx is used to create a new thread in a deep-frozen process, the thread will be frozen before actually starting. This is the typical usage of the freezing capability.

Process- and thread-freezing functionality is not exposed directly to user mode. It is used internally by the Process State Manager (PSM) service that is responsible for issuing the requests to the kernel for deep freezing and thawing (unfreezing).

You can also freeze processes using jobs. The ability to freeze and unfreeze a job is not publicly documented, but it's possible to do using the standard NtSetInformationJobObject system call. This is typically used for Windows apps, as all Windows apps processes are contained in jobs. Such a job may contain a single process (the Windows app itself), but it can also contain background task-hosting processes related to the same Window app so that freezing or thawing (unfreezing) all processes under that job can be done in a single stroke. (See Chapter 8 in Part 2 for more on Windows apps.)

### **EXPERIMENT:** Deep freeze

In this experiment, you'll watch deep freeze happening by debugging a virtual machine.

- 1. Open WinDbg with admin privileges and attach to a virtual machine running Windows 10.
- 2. Press Ctrl+Break to break into the VM.
- **3.** Set a breakpoint when deep freeze begins with a command to show the process that is frozen:

```
bp nt!PsFreezeProcess "!process -1 0; g"
```

- 4. Enter the g (go) command or press F5. You should see many deep freeze occurrences.
- **5.** Start the Cortana UI from the taskbar and then close the UI. After about 5 seconds you should see something like the following:

PROCESS 8f518500 SessionId: 2 Cid: 12c8 Peb: 03945000 ParentCid: 02ac DirBase: 054007e0 ObjectTable: b0a8a040 HandleCount: 988. Image: SearchUI.exe

6. Now break into the debugger and show more info on that process:

```
1: kd> !process 8f518500 1
PROCESS 8f518500 SessionId: 2 Cid: 12c8 Peb: 03945000 ParentCid: 02ac
DeepFreeze
   DirBase: 054007e0 ObjectTable: b0a8a040 HandleCount: 988.
   Image: SearchUI.exe
   VadRoot 95c1ffd8 Vads 405 Clone 0 Private 7682. Modified 201241. Locked 0.
   DeviceMap a12509c0
   Token
                                     b0a65bd0
   ElapsedTime
                                     04:02:33.518
   UserTime
                                     00:00:06.937
   KernelTime
                                    00:00:00.703
   QuotaPoolUsage[PagedPool]
                                    562688
   QuotaPoolUsage[NonPagedPool]
                                     34392
   Working Set Sizes (now,min,max) (20470, 50, 345) (81880KB, 200KB, 1380KB)
    PeakWorkingSetSize
                                     25878
   VirtualSize
                                    367 Mb
    PeakVirtualSize
                                    400 Mb
   PageFaultCount
                                    307764
   MemoryPriority
                                     BACKGROUND
   BasePriority
                                     8
   CommitCharge
                                     8908
    Job
                                     8f575030
```

7. Notice the DeepFreeze attribute written by the debugger. Also notice that the process is part of a job. Use the ! job command to see more details:

```
1: kd> !job 8f575030
Job at 8f575030
Basic Accounting Information
TotalUserTime: 0x0
```

TotalKernelTime: 0x0 TotalCycleTime: 0x0 ThisPeriodTotalUserTime: 0x0 ThisPeriodTotalKernelTime: 0x0 TotalPageFaultCount: 0x0 TotalProcesses: 0x1 ActiveProcesses: 0x1 FreezeCount: 1 BackgroundCount: 0 TotalTerminatedProcesses: 0x0 PeakJobMemoryUsed: 0x38e2 PeakProcessMemoryUsed: 0x38e2 Job Flags [cpu rate control] [frozen] [wake notification allocated] [wake notification enabled] [timers virtualized] [job swapped] Limit Information (LimitFlags: 0x0) Limit Information (EffectiveLimitFlags: 0x3000) CPU Rate Control Rate = 100.00%Scheduling Group: a469f330

**8.** The job is under CPU rate control (see the section "CPU rate limits" later in this chapter for more on CPU rate control) and is frozen. Detach from the VM and close the debugger.

## **Thread selection**

Whenever a logical processor needs to pick the next thread to run, it calls the KiSelectNextThread scheduler function. This can happen in a variety of scenarios:

- A hard affinity change has occurred, making the currently running or standby thread ineligible for execution on its selected logical processor. Therefore, another must be chosen.
- The currently running thread reached its quantum end, and the Symmetric Multithreading (SMT) set it was running on has become busy while other SMT sets within the ideal node are fully idle. (Symmetric Multithreading is the technical name for the hyper-threading technology described in Chapter 2.) The scheduler performs a quantum-end migration of the current thread, so another must be chosen.
- A wait operation has finished, and there were pending scheduling operations in the wait status register (in other words, the priority and/or affinity bits were set).

In these scenarios, the behavior of the scheduler is as follows:

- The scheduler calls KiSelectReadyThreadEx to search for the next ready thread that the processor should run and check whether one was found.
- If a ready thread was not found, the idle scheduler is enabled, and the idle thread is selected for execution. If a ready thread was found, it is put in the ready state in the local or shared ready queue, as appropriate.

The KiSelectNextThread operation is performed only when the logical processor needs to pick but not yet run—the next schedulable thread (which is why the thread will enter the Ready state). Other times, however, the logical processor is interested in immediately running the next ready thread or performing another action if one is not available (instead of going idle), such as when the following occurs:

- A priority change causes the current standby or running thread to no longer be the highest-priority ready thread on its selected logical processor, meaning that a higher priority ready thread must now run.
- The thread has explicitly yielded with YieldProcessor or NtYieldExecution and another thread might be ready for execution.
- The quantum of the current thread has expired, and other threads at the same priority level need their chance to run as well.
- A thread has lost its priority boost, causing a similar priority change to the scenario just described.
- The idle scheduler is running and needs to check whether a ready thread has not appeared in the interval between when the idle scheduling was requested and the idle scheduler ran.

A simple way to remember the difference between which routine runs is to check whether the logical processor *must* run a different thread (in which case KiSelectNextThread is called) or if it *should if possible* run a different thread (in which case KiSelectReadyThreadEx is called). In either case, because each processor belongs to a shared ready queue (pointed to by the KPRCB), KiSelectReady-ThreadEx can simply check the current logical processor's (LP's) queues, removing the first highestpriority thread that it finds unless this priority is lower than the one of the currently running thread (depending on whether the current thread is still allowed to run, which would not be the case in the KiSelectNextThread scenario). If there is no higher-priority thread (or no threads are ready at all), no thread is returned.

### Idle scheduler

Whenever the idle thread runs, it checks whether idle scheduling has been enabled. If so, the idle thread begins scanning other processors' ready queues for threads it can run by calling KiSearch-ForNewThread. The run-time costs associated with this operation are not charged as idle thread time, but are instead charged as interrupt and DPC time (charged to the processor), so idle scheduling time is considered system time. The KiSearchForNewThread algorithm, which is based on the functions described earlier in this section, is explained shortly.

# **Multiprocessor systems**

On a uniprocessor system, scheduling is relatively simple: The highest-priority thread that wants to run is always running. On a multiprocessor system, it is more complex. This is because Windows attempts to schedule threads on the most optimal processor for the thread, taking into account the thread's preferred and previous processors as well as the configuration of the multiprocessor system. Therefore, although Windows attempts to schedule the highest-priority runnable threads on all available CPUs, it guarantees only to be running one of the highest-priority threads somewhere. With shared ready queues (for threads with no affinity restrictions), the guarantee is stronger. Each shared group of processors is running at least one of the highest-priority threads.

Before we describe the specific algorithms used to choose which threads run where and when, let's examine the additional information Windows maintains to track thread and processor state on multiprocessor systems and the three different types of multiprocessor systems supported by Windows (SMT, multicore, and NUMA).

### Package sets and SMT sets

Windows uses five fields in the KPRCB to determine correct scheduling decisions when dealing with logical processor topologies. The first field, CoresPerPhysicalProcessor, determines whether this logical processor is part of a multicore package. It's computed from the CPUID returned by the processor and rounded to a power of 2. The second field, LogicalProcessorsPerCore, determines whether the logical processor is part of an SMT set, such as on an Intel processor with hyper-threading enabled, and is also queried through CPUID and rounded. Multiplying these two numbers yields the number of logical processors per package, or an actual physical processor that fits into a socket. With these numbers, each PRCB can then populate its PackageProcessorSet value. This is the affinity mask describing which other logical processors. Similarly, the CoreProcessorSet value connects other logical processors to the same core, also called an *SMT set*. Finally, the GroupSetMember value defines which bitmask within the current processor group identifies this very logical processor. For example, the logical processor 3 normally has a GroupSetMember value of 8 (which equals 2 to the third power).

### **EXPERIMENT:** Viewing logical processor information

You can examine the information Windows maintains for SMT processors using the ! smt command in the kernel debugger. The following output is from a quad-core Intel Core i7 system with SMT (eight logical processors):

lkd> !smt SMT Summary:	
KeActiveProcessors:	
******	(000000000000ff)
IdleSummary:	
_*****	(00000000000009e)

No	PRCB	SMT Set			APIC Id
0	fffff803d7546180	**		(000000000000003)	0x00000000
1	ffffba01cb31a180	**		(00000000000003)	0x0000001
2	ffffba01cb3dd180	**		(00000000000000c)	0x0000002
3	ffffba01cb122180	**		(00000000000000c)	0x0000003
4	ffffba01cb266180	**		(00000000000030)	0x0000004
5	ffffba01cabd6180	**		(00000000000030)	0x0000005
6	ffffba01cb491180	**		(0000000000000c0)	0x0000006
7	ffffba01cb5d4180	**		(0000000000000c0)	0x0000007
	imum cores per phy	· ·	8		
Max	imum logical proce	essons per core:	2		

#### NUMA systems

Another type of multiprocessor system supported by Windows is one with a non-uniform memory architecture (NUMA). In a NUMA system, processors are grouped together in smaller units called *nodes*. Each node has its own processors and memory and is connected to the larger system through a cache-coherent interconnect bus. These systems are called *non-uniform* because each node has its own local high-speed memory. Although any processor in any node can access all of memory, node-local memory is much faster to access.

The kernel maintains information about each node in a NUMA system in a data structure called KNODE. The kernel variable KeNodeBlock is an array of pointers to the KNODE structures for each node. You can reveal the format of the KNODE structure using the dt command in the kernel debugger, as shown here:


```
lkd> dt nt!_KNODE
```

+0x000	IdleNonParkedCpuS	Get : Uint8B
	IdleSmtSet	
+0x010	IdleCpuSet	: Uint8B
+0x040	DeepIdleSet	: Uint8B
+0x048	IdleConstrainedSe	et : Uint8B
+0x050	NonParkedSet	: Uint8B
+0x058	ParkLock	: Int4B
+0x05c	Seed	: Uint4B
+0x080	SiblingMask	: Uint4B
+0x088	Affinity	: _GROUP_AFFINITY
+0x088	AffinityFill	: [10] UChar
+0x092	NodeNumber	: Uint2B
+0x094	PrimaryNodeNumber	: Uint2B
+0x096	Stride	: UChar
+0x097	Spare0	: UChar
+0x098	SharedReadyQueueL	eaders : Uint8B.
	ProximityId	
+0x0a4	Lowest	: Uint4B
+0x0a8	Highest	: Uint4B
+0x0ac	MaximumProcessors	; : UChar
+0x0ad	Flags	: _flags
	Spare10	
+0x0b0	HeteroSets	: [5] _KHETERO_PROCESSOR_SET

### **EXPERIMENT: Viewing NUMA information**

You can examine the information Windows maintains for each node in a NUMA system using the !numa command in the kernel debugger. To experiment with NUMA systems even when such hardware is not available, it's possible to configure a Hyper-V virtual machine to include more than one NUMA node that the guest VM will use. To configure a Hyper-V VM to use NUMA, do the following. (You will need a host machine with more than four logical processors.)

- 1. Click Start, type hyper, and click the Hyper-V Manager option.
- 2. Make sure the VM is powered off. Otherwise the following changes cannot be made.
- 3. Right-click the VM in Hyper-V Manager and select Settings to open the VM's settings.
- 4. Click the Memory node and make sure Dynamic Memory is unchecked.
- 5. Click the Processor node and enter 4 in the Number of Virtual Processors box:



- 6. Expand the Processor node and select the NUMA sub-node.
- 7. Enter 2 in the Maximum Number of Processors and Maximum NUMA Nodes Allowed on a Socket boxes:

Memory 2048 MB Processor 4 Virtuel processors	Processors: 4 NUMA nodes: 2 Sockets: 1	
Compatibility	NUMA topology	
NUMA	Select the maximum number of processors and memory allowed on a single virtual non-uniform memory architecture (NUMA) node.	
E IDE Controller 0		
Hard Drive Win 10x86VM. vhdx	Maximum number of processors:	2 🖨
E IDE Controller 1	Maximum amount of memory (MB):	30878 🜲
DVD Drive MSITWin 10x86.ISO	Select the maximum number of nodes allowed on a single socket.	
SCSI Controller	Maximum NUMA nodes allowed on a socket:	2 🗘
🗉 📮 Network Adapter		1. 1400

- 8. Click OK to save the settings.
- 9. Power up the VM.
- **10.** Use a kernel debugger to issue the **!numa** command. Here's an example of output for the previously configured VM:

2: kd> !numa NUMA Summary:

```
Number of NUMA nodes : 2
    Number of Processors : 4
unable to get nt!MmAvailablePages
   MmAvailablePages : 0x0000000
   KeActiveProcessors :
    **** (000000f)
    NODE 0 (FFFFFFF820510C0):
   Group : 0 (Assigned, Committed, Assignment Adjustable)
   ProcessorMask : **----- (0000003)
   ProximityId : 0
Capacity : 2
Seed : 0x0

        Seed
        : 0x00000001

        IdleCpuSet
        : 00000003

        IdleSmtSet
        : 00000003

        NonParkedSet
        : 00000003

Unable to get MiNodeInformation
    NODE 1 (FFFFFFF8719E0C0):
   Group : 0 (Assigned, Committed, Assignment Adjustable)
   ProcessorMask : --**----- (0000000c)
   ProximityId : 1
  Capacity : 2
Seed : 0x00000003
IdleCpuSet : 00000008
IdleSmtSet : 00000008
NonParkedSet : 0000000c
Unable to get MiNodeInformation
```

Applications that want to gain the most performance out of NUMA systems can set the affinity mask to restrict a process to the processors in a specific node, although Windows already restricts nearly all threads to a single NUMA node due to its NUMA-aware scheduling algorithms.

How the scheduling algorithms account for NUMA systems is covered later in this chapter in the section "Processor selection." (The optimizations in the memory manager to take advantage of node-local memory are covered in Chapter 5.)

### Processor group assignment

While querying the topology of the system to build the various relationships between logical processors, SMT sets, multicore packages, and physical sockets, Windows assigns processors to an appropriate group that will describe their affinity (through the extended affinity mask seen earlier). This work is done by the KePerformGroupConfiguration routine, which is called during initialization before any other phase 1 work is done. The steps of this process are as follows:

 The function queries all detected nodes (KeNumberNodes) and computes the capacity of each node—that is, how many logical processors can be part of the node. This value is stored in MaximumProcessors in the KeNodeBlock array, which identifies all NUMA nodes on the system. If the system supports NUMA proximity IDs, the proximity ID is queried for each node and saved in the node block.

2. The NUMA distance array is allocated (KeNodeDistance) and the distance between each NUMA node is computed.

The next series of steps deal with specific user-configuration options that override default NUMA assignments. For example, consider a system with Hyper-V installed and with the hyper-visor configured to auto-start. If the CPU does not support the extended hypervisor interface, then only one processor group will be enabled, and all NUMA nodes (that can fit) will be associated with group 0. Therefore, in this case, Hyper-V cannot take advantage of machines with more than 64 processors.

3. The function checks whether any static group assignment data was passed by the loader (and thus configured by the user). This data specifies the proximity information and group assignment for each NUMA node.

**Note** Users dealing with large NUMA servers who might need custom control of proximity information and group assignments for testing or validation purposes can enter this data through the Group Assignment and Node Distance registry values. These are found in the HKLM\SYSTEM\ CurrentControlSet\ControlNUMA registry key. The exact format of this data includes a count followed by an array of proximity IDs and group assignments, which are all 32-bit values.

**4.** Before treating this data as valid, the kernel queries the proximity ID to match the node number and then associates group numbers as requested. It then makes sure that NUMA node 0 is associated with group 0, and that the capacity for all NUMA nodes is consistent with the group size. Finally, the function checks how many groups still have remaining capacity.

Note NUMA node 0 is always assigned to group 0, no matter what.

- 5. The kernel dynamically attempts to assign NUMA nodes to groups while respecting any statically configured nodes if passed in as just described. Normally, the kernel tries to minimize the number of groups created, combining as many NUMA nodes as possible per group. However, if this behavior is not desired, it can be configured differently with the /MAXGROUP loader parameter, configured through the maxgroup BCD option. Turning this value on overrides the default behavior and causes the algorithm to spread as many NUMA nodes as possible into as many groups as possible, while respecting that the currently implemented group limit is 20. If there is only one node, or if all nodes can fit into a single group (and maxgroup is off), the system performs the default setting of assigning all nodes to group 0.
- 6. If there is more than one node, Windows checks the static NUMA node distances (if any). It then sorts all the nodes by their capacity so that the largest nodes come first. In the group-minimization mode, the kernel figures out the maximum processors there can be by adding up

all the capacities. By dividing that by the number of processors per group, the kernel assumes there will be this many total groups on the machine (limited to a maximum of 20). In group-maximization mode, the initial estimate is that there will be as many groups as nodes (limited again to 20).

- 7. The kernel begins the final assignment process. All fixed assignments from earlier are now committed and groups are created for those assignments.
- 8. All the NUMA nodes are reshuffled to minimize the distance between the different nodes within a group. In other words, closer nodes are put in the same group and sorted by distance.
- 9. The same process is performed for any dynamically configured node to group assignments.
- **10.** Any remaining empty nodes are assigned to group 0.

#### Logical processors per group

Generally, Windows assigns 64 processors per group. But you can also customize this configuration by using different load options such as the /GROUPSIZE option, which is configured through the groupsize BCD element. By specifying a number that is a power of 2, you can force groups to contain fewer processors than normal for purposes such as testing group awareness in the system. For example, a system with eight logical processors can be made to appear to have one, two, or four groups. To force the issue, the /FORCEGROUPAWARE option (BCD element groupaware) causes the kernel to avoid group 0 whenever possible, assigning the highest group number available in actions such as thread and DPC affinity selection and process group assignment. You should avoid setting a group size of 1 because this will force almost all applications on the system to behave as if they're running on a uniprocessor machine. This is because the kernel sets the affinity mask of a given process to span only one group until the application requests otherwise (which most applications will not do).

In the edge case where the number of logical processors in a package cannot fit into a single group, Windows adjusts these numbers so that a package can fit into a single group. It does so by shrinking the CoresPerPhysicalProcessor number and, if the SMT cannot fit, the LogicalProcessorsPerCore number. The exception to this rule is if the system actually contains multiple NUMA nodes within a single package (uncommon, but possible). In these multi-chip modules (MCMs), two sets of cores as well as two memory controllers are on the same die/package. If the ACPI Static Resource Affinity Table (SRAT) defines the MCM as having two NUMA nodes, Windows might associate the two nodes with two different groups (depending on group-configuration algorithms). In this scenario, the MCM package would span more than one group.

Other than causing significant driver and application compatibility problems—which they are designed to identify and root out, when used by developers—these options have an even greater impact on the machine: They force NUMA behaviors even on a non-NUMA machine. This is because Windows will never allow a NUMA node to span multiple groups, as was shown in the assignment algorithms. So, if the kernel is creating artificially small groups, those two groups must each have their own NUMA node. For example, on a quad-core processor with a group size of 2, this will create two groups, and thus two NUMA nodes, which will be subnodes of the main node. This will affect scheduling and memorymanagement policies in the same way a true NUMA system would, which can be useful for testing.

### Logical processor state

In addition to the shared and local ready queues and summaries, Windows maintains two bitmasks that track the state of the processors on the system. (How these bitmasks are used is explained in the upcoming "Processor selection" section.) Following are the bitmasks that Windows maintains:

- KeActiveProcessors This is the active processor mask, which has a bit set for each usable processor on the system. These might be fewer than the number of actual processors if the licensing limits of the version of Windows running supports fewer than the number of available physical processors. Use the KeRegisteredProcessors variable to see how many processors are actually licensed on the machine. In this instance, *processors* refers to physical packages.
- KeMaximumProcessors This is the maximum number of logical processors (including all future possible dynamic processor additions) bounded within the licensing limit. It also reveals any platform limitations that are queried by calling the HAL and checking with the ACPI SRAT table, if any.

Part of the node's data (KNODE) is the set of idle CPUs in this node (the IdleCpuSet member), idle CPUs that are not parked (IdleNonParkedCpuSet), and idle SMT sets (IdleSmtSet).

#### Scheduler scalability

On a multiprocessor system, one processor might need to modify another processor's per-CPU scheduling data structures—for example, inserting a thread that would like to run on a certain processor. For this reason, you synchronize these structures by using a per-PRCB queued spinlock, which is held at DISPATCH\_LEVEL. Thus, thread selection can occur while locking only an individual processor's PRCB. If needed, one more processor's PRCB can also be locked, such as in scenarios of thread stealing (described later). Thread context switching is also synchronized by using a finer-grained per-thread spinlock.

There is also a per-CPU list of threads in the deferred ready state (DeferredReadyListHead). These represent threads that are ready to run but have not yet been readied for execution; the actual ready operation has been deferred to a more appropriate time. Because each processor manipulates only its own per-processor deferred ready list, this list is not synchronized by the PRCB spinlock. The deferred ready thread list is processed by KiProcessDeferredReadyList after a function has already done modifications to process or thread affinity, priority (including due to priority boosting), or quantum values.

This function calls KiDeferredReadyThread for each thread on the list, which performs the algorithm shown later in this chapter in the "Processor selection" section. This could cause the thread to run immediately; to be put on the ready list of the processor; or, if the processor is unavailable, to be potentially put on a different processor's deferred ready list, in a standby state or immediately executed. This property is used by the core parking engine when parking a core: All threads are put into the deferred ready list, and it is then processed. Because KiDeferredReadyThread skips parked cores ( as will be shown), it causes all of this processor's threads to wind up on other processors.

## Affinity

Each thread has an affinity mask that specifies the processors on which the thread is allowed to run. The thread affinity mask is inherited from the process affinity mask. By default, all processes (and therefore all threads) begin with an affinity mask that is equal to the set of all active processors on their assigned group. In other words, the system is free to schedule all threads on any available processor within the group associated with the process. However, to optimize throughput, partition workloads to a specific set of processors, or both, applications can choose to change the affinity mask for a thread. This can be done at several levels:

- By calling the SetThreadAffinityMask function to set the affinity for an individual thread.
- By calling the SetProcessAffinityMask function to set the affinity for all the threads in a process.
- Task Manager and Process Explorer provide a GUI to this function. To access it, right-click a process and choose Set Affinity. In addition, the Psexec tool (from Sysinternals) provides a command-line interface to this function. (See the –a switch in its help output.)
- By making a process a member of a job that has a job-wide affinity mask set using the SetInformationJobObject function (described in Chapter 3).
- By specifying an affinity mask in the image header when compiling the application.

**Tip** For a detailed specification of the Windows images format, search for *Portable Executable and Common Object File Format Specification* on *http://msdn.microsoft.com*.

An image can also have the uniprocessor flag set at link time. If this flag is set, the system chooses a single processor at process-creation time (MmRotatingProcessorNumber) and assigns that as the process affinity mask, starting with the first processor and then going round-robin across all the processors within the group. For example, on a dual-processor system, the first time an image marked with the uniprocessor flag is launched, it is assigned to CPU 0; the second time, CPU 1; the third time, CPU 0; the fourth time, CPU 1; and so on. This flag can be useful as a temporary workaround for programs that have multithreaded synchronization bugs that surface on multiprocessor systems due to race conditions but not on uniprocessor systems. If an image exhibits such symptoms and is unsigned, you can add the flag manually editing the image header with a Portable Executable (PE) image-editing tool. A better solution, also compatible with signed executables, is to use the Microsoft Application Compatibility Toolkit and add a shim to force the compatibility database to mark the image as uniprocessor-only at launch time.

#### **EXPERIMENT:** Viewing and changing process affinity

In this experiment, you will modify the affinity settings for a process and see that process affinity is inherited by new processes:

- 1. Run the command prompt (Cmd.exe).
- 2. Run Task Manager or Process Explorer and find the Cmd.exe process in the process list.
- **3.** Right-click the process and select **Set Affinity**. A list of processors should be displayed. For example, on a system with eight logical processes, you will see this:

< <a]< th=""><th>Processors</th><th>s&gt;</th><th></th></a]<>	Processors	s>	
CPL	10		
CPL OPL	11		
CPL			
CPL			
CPL			
CPL CPL			
CPL			
OPL OPL	17		

- **4.** Select a subset of the available processors on the system and click **OK**. The process's threads are now restricted to run on the processors you just selected.
- 5. At the command prompt, type Notepad to run Notepad.exe.
- 6. Go back to Task Manager or Process Explorer and find the new Notepad process.
- 7. Right-click the process and choose **Affinity**. You should see the same list of processors you chose for the command-prompt process. This is because processes inherit their affinity settings from their parent.

Windows won't move a running thread that could run on a different processor from one CPU to a second processor to permit a thread with an affinity for the first processor to run on the first processor. For example, consider this scenario: CPU 0 is running a priority 8 thread that can run on any processor, and CPU 1 is running a priority 4 thread that can run on any processor. A priority 6 thread that can run on only CPU 0 becomes ready. What happens? Windows won't move the priority 8 thread from CPU 0 to CPU 1 (preempting the priority 4 thread) so that the priority 6 thread can run; the priority 6 thread must stay in the ready state. Therefore, changing the affinity mask for a process or thread can result in threads getting less CPU time than they normally would because Windows is restricted from running the thread on certain processors. Therefore, setting affinity should be done with extreme care. In most cases, it is optimal to let Windows decide which threads run where.

#### **Extended affinity mask**

To support more than 64 processors, which is the limit enforced by the original affinity mask structure (composed of 64 bits on a 64-bit system), Windows uses an extended affinity mask, KAFFINITY\_EX. This is an array of affinity masks, one for each supported processor group (currently defined at 20).

When the scheduler needs to refer to a processor in the extended affinity masks, it first de-references the correct bitmask by using its group number and then accesses the resulting affinity directly. In the kernel API, extended affinity masks are not exposed; instead, the caller of the API inputs the group number as a parameter and receives the legacy affinity mask for that group. In the Windows API, on the other hand, only information about a single group can usually be queried, which is the group of the currently running thread (which is fixed).

The extended affinity mask and its underlying functionality are also how a process can escape the boundaries of its original assigned processor group. By using the extended affinity APIs, threads in a process can choose affinity masks on other processor groups. For example, if a process has four threads and the machine has 256 processors, thread 1 can run on processor 4, thread 2 can run on processor 68, thread 3 on processor 132, and thread 4 on processor 196, if each thread set an affinity mask of 0x10 (0b10000 in binary) on groups 0, 1, 2, and 3. Alternatively, the threads can each set an affinity of all 1 bits (0xFFFF...) for their given group, and the process then can execute its threads on any available processor on the system (with the limitation that each thread is restricted to running within its own group only).

You can take advantage of extended affinity at creation time by specifying a group number in the thread attribute list (PROC\_THREAD\_ATTRIBUTE\_GROUP\_AFFINITY) when creating a new thread or by calling SetThreadGroupAffinity on an existing thread.

#### System affinity mask

Windows drivers usually execute in the context of the calling thread or an arbitrary thread (that is, not in the safe confines of the System process). Therefore, currently running driver code might be subject to affinity rules set by the application developer. These are not currently relevant to the driver code and might even prevent correct processing of interrupts and other queued work. Driver developers therefore have a mechanism to temporarily bypass user thread affinity settings, by using the KeSetSystemAffinityThread(Ex)/KeSetSystemGroupAffinityThread APIs.

#### Ideal and last processor

Each thread has three CPU numbers stored in the kernel thread control block:

- **Ideal processor** This is the preferred processor that this thread should run on.
- Last processor This is the processor the thread last ran on.
- **Next processor** This is the processor that the thread will be or is already running on.

The ideal processor for a thread is chosen when a thread is created using a seed in the process control block. The seed is incremented each time a thread is created so that the ideal processor for each new thread in the process rotates through the available processors on the system. For example, the first thread in the first process on the system is assigned an ideal processor of 0 and the second thread in that process is assigned an ideal processor of 1. However, the next process in the system has its first thread's ideal processor set to 1, the second to 2, and so on. In that way, the threads within each process are spread across the processors. On SMT systems (hyper-threading), the next ideal processor

is selected from the next SMT set. For example, on a quad-core, hyper-threaded system, ideal processors for threads in a certain process could be 0, 2, 4, 6, 0, ...; 3, 5, 7, 1, 3, ...; etc. In this way, the threads are spread evenly across the physical processors.

Note that this assumes the threads within a process are doing an equal amount of work. This is typically not the case in a multithreaded process, which normally has one or more housekeeping threads and numerous worker threads. Therefore, a multithreaded application that wants to take full advantage of the platform might find it advantageous to specify the ideal processor numbers for its threads by using the SetThreadIdealProcessor function. To take advantage of processor groups, developers should call SetThreadIdealProcessorEx instead, which allows selection of a group number for the affinity.

In 64-bit Windows, the Stride field in the KNODE is used to balance the assignment of newly created threads within a process. The stride is a scalar number that represents the number of affinity bits within a given NUMA node that must be skipped to attain a new independent logical processor slice, where *independent* means on another core (if dealing with an SMT system) or another package (if dealing with a non-SMT but multicore system). Because 32-bit Windows doesn't support large processor-configuration systems, it doesn't use a stride. It simply selects the next processor number, trying to avoid sharing the same SMT set if possible.

#### Ideal node

On NUMA systems, when a process is created, an ideal node for the process is selected. The first process is assigned to node 0, the second process to node 1, and so on. Then the ideal processors for the threads in the process are chosen from the process's ideal node. The ideal processor for the first thread in a process is assigned to the first processor in the node. As additional threads are created in processes with the same ideal node, the next processor is used for the next thread's ideal processor, and so on.

#### **CPU** sets

You've seen how affinity (sometimes referred to as *hard affinity*) can limit threads to certain processors, which is always honored by the scheduler. The ideal processor mechanism tries to run threads on their ideal processors (sometimes referred to as *soft affinity*), generally expecting to have the thread's state be part of the processor's cache. The ideal processor may or may not be used, and it does not prevent the thread from being scheduled on other processors. Both these mechanisms don't work on system-related activity, such as system threads activity. Also, there is no easy way to set hard affinity to all processes on a system in one stroke. Even walking the process would not work. System processes are generally protected from external affinity changes because they require the PROCESS\_SET\_INFORMATION access right, which is not granted for protected processes.

Windows 10 and Server 2016 introduce a mechanism called *CPU sets*. These are a form of affinity that you can set for use by the system as a whole (including system threads activity), processes, and even individual threads. For example, a low-latency audio application may want to use a processor exclusively while the rest of the system is diverted to use other processors. CPU sets provide a way to achieve that.

The documented user mode API is somewhat limited at the time of this writing. GetSystemCpuSet-Information returns an array of SYSTEM\_CPU\_SET\_INFORMATION that contains data for each CPU set.

In the current implementation, a CPU set is equivalent to a single CPU. This means the returned array's length is the number of logical processors on the system. Each CPU set is identified by its ID, which is arbitrarily selected to be 256 (0x100) plus the CPU index (0, 1, ...). These IDs are the ones that must be passed to SetProcessDefaultCpuSets and SetThreadSelectedCpuSets functions to set default CPU sets for a process and a CPU set for a specific thread, respectively.

An example for setting thread CPU set would be for an "important" thread that should not be interrupted if possible. This thread could have a CPU set that contains one CPU, while setting the default process CPU set to include all other CPUs.

One missing function in the Windows API is the ability to reduce the system CPU set. This can be achieved by a call to the NtSetSystemInformation system call. For this to succeed, the caller must have SeIncreaseBasePriorityPrivilege.

#### **EXPERIMENT: CPU sets**

In this experiment, you'll view and modify CPU sets and watch the resulting effects.

- 1. Download the CpuSet.exe tool from the book's downloadable resources.
- 2. Open an administrative command window and navigate to the directory where CPUSET.exe exists.
- **3.** At the command window, type **cpuset.exe** without arguments to see the current system CPU sets. The output should be similar to the following:


```
System CPU Sets
_____
Total CPU Sets: 8
CPU Set 0
 Id: 256 (0x100)
 Group: 0
 Logical Processor: 0
 Core: 0
 Last Level Cache: 0
 NUMA Node: 0
 Flags: 0 (0x0) Parked: False Allocated: False Realtime: False Tag: 0
CPU Set 1
 Id: 257 (0x101)
 Group: 0
 Logical Processor: 1
 Core: 0
 Last Level Cache: 0
 NUMA Node: 0
 Flags: 0 (0x0) Parked: False Allocated: False Realtime: False Tag: 0
```

**4.** Run CPUSTRES.exe and configure it to run a thread or two with maximum activity level. (Aim for something around 25 percent CPU usage.)

- 5. Open Task Manager, click the Performance tab, and select the CPU label.
- **6.** Change the CPU graph view to show individual processors (if the view is configured for overall utilization).
- **7.** At the command window, run the following command, replacing the number after -p with the process ID of the CPUSTRES process on your system:

```
CpuSet.exe -p 18276 -s 3
```

The -s argument specifies the processor mask to set as the default for the process. Here, 3 means CPU 0 and 1. You should see Task Manager hard at work on these two CPUs:




 Let's look at CPU 0 more closely to see what threads it's running. For this, you'll use Windows Performance Recorder (WPR) and Windows Performance Analyzer (WPA) from the Windows SDK. Click the Start button, type WPR, and select Windows Performance Recorder. Then accept the elevation prompt. You should see the following dialog box:

Record system information			0
This tool will gather information about the interaction computer for analysis.	of the program	s and hardware runnir	ig on this
Status: Recording not started		Time: Buffer: Events dropped:	
Hide options		Start	Cancel
Select additional profiles for performance recording:		Performance scen	irio:
First level triage	^	General	~
First level triage		Detail level:	
		Verbose	0
Resource Analysis			
CPU usage		Louisver.	1.55
		Logging mode: Memory	¥

- 9. The default is to record CPU usage, which is what we want. This tool records Event Tracing for Windows (ETW) events. (See Chapter 8 in Part 2 for more on ETW.) Click the Start button in the dialog box and, after a second or two click the same button, now labeled Save.
- **10.** WPR will suggest a location to save the recorded data. Accept it or change to some other file/folder.
- **11.** After the file is saved, WPR suggests opening the file with WPA. Accept the suggestion.
- **12.** The WPA tool opens and loads the saved file. (WPA is a rich tool, well beyond the scope of this book). On the left, you'll see the various categories of information captured, something like so:

System Activity Processes	Lifetime By Process
Computation	
Memory	

- 13. Expand the Computation node and then expand the CPU Usage (Precise) node.
- 14. Double-click the Utilization by CPU graph. It should open in the main display:



**15.** At the moment, we're interested in CPU 0. In the next step, you'll make CPU 0 work for CPUSTRES only. To begin, expand the CPU 0 node. You should see various processes, including CPUSTRES, but certainly not exclusively:

#	Cpu	Count Count	New Process	Ne
1	- 0	2,321		1
		1		
3	granssarius	1	RuntimeBroker.exe (7596)	50 10 10 10 10 10 10 10 10 10 10 10 10 10
4		1	System (4)	
5		1	RuntimeBroker.exe (7596)	
6		1	System (4)	
7		1	MsMpEng.exe (3948)	
8		1	System (4)	
9		1	Searchindexer.exe (10784)	
10		1	System (4)	
11		1	CPUSTRES.exe (18276)	
12		1	conhost.exe (13580)	
13		1	System (4)	
14		1	conhost.exe (13580)	
15		1	System (4)	
16		1	SHSPipeHost.exe (12344)	
17		1	System (4)	
18		1	SHSPipeHost.exe (12344)	
19		1	System (4)	
20		1	SearchIndexer.exe (10784)	
21		1	System (4)	
22		1	Searchindexer.exe (10784)	

16. Enter the following command to restrict the system to use all processors except the first. In this system, the number of processors is eight, so a full mask is 255 (0xff). Removing CPU 0 produces 254 (0xfe). Replace the mask with the correct one for your system:

CpuSet.exe -s Oxfe

- **17.** The view in Task Manager should look about the same. Let's take a closer look at CPU 0. Run WPR again, and record a second or two with the same settings as before.
- 18. Open the trace in WPA and navigate to Utilization by CPU.
- **19.** Expand CPU 0. You should see CPUSTRES almost exclusively, with the System process appearing occasionally:

	Cpu	0	Count	Count	New Process			
1	-	0		15				
2				1	CPUSTRES.exe	e (182	76)	
2 3 4 5				1	CPUSTRES.exe	e (182	76)	
4				1	CPUSTRES.exe	(182	76)	
				1	CPUSTRES.exe	(182	76)	
67				1	System (4)			
7				1	CPUSTRES.exe	e (182	76)	
8				1	CPUSTRES.exe	e (182	76)	
9				1	CPUSTRES.exe	(182	76)	
		1	A ALL STRANGED IN					
1				1	CPUSTRES.exe	e (182	76)	
2				1	CPUSTRES.exe	e (182	76)	
3				1	CPUSTRES.exe	(182	76)	
4				1	CPUSTRES.exe	(182	76)	
5				1	CPUSTRES.exe	(182	76)	

- **20.** Notice in the CPU Usage (in View) (ms) column that the time spent in the System process is very small (micro seconds). Clearly, CPU 0 is dedicated to the CPUSTRES process.
- **21.** Run CPUSET.exe with no arguments again. The first set (CPU 0) is marked Allocated: True because it's now allocated to a particular process and not for general system use.

- 22. Close CPU Stress.
- 23. Enter the following command to restore the system CPU set to its default:

Cpuset -s 0

## Thread selection on multiprocessor systems

Before covering multiprocessor systems in more detail, let's summarize the algorithms discussed earlier in the "Thread selection" section. They either continued executing the current thread (if no new candidate was found) or started running the idle thread (if the current thread had to block). However, there is a third algorithm for thread selection called KiSearchForNewThread, which was hinted at earlier. This algorithm is called in one specific instance: when the current thread is about to block due to a wait on an object, including when doing an NtDelayExecutionThread call, also known as the Sleep API in Windows.

**Note** This shows a subtle difference between the commonly used Sleep(1) call, which makes the current thread block until the next timer tick, and the SwitchToThread call, which was shown earlier. The Sleep(1) call uses the algorithm about to be described, while the SwitchToThread call uses the previously shown logic.

KiSearchForNewThread initially checks whether there is already a thread that was selected for this processor (by reading the NextThread field). If so, it dispatches this thread immediately in the running state. Otherwise, it calls the KiSelectReadyThreadEx routine and, if a thread was found, performs the same steps.

If no thread was found, the processor is marked as idle (even though the idle thread is not yet executing) and a scan of the queues of other logical processors (shared) is initiated (unlike the other standard algorithms, which would now give up). If, however, the processor core is parked, the algorithm will not attempt to check other logical processors, as it is preferable to allow the core to enter the parking state instead of keeping it busy with new work.

Barring these two scenarios, the work-stealing loop now runs. This code looks at the current NUMA node and removes any idle processors (because they shouldn't have threads that need stealing). Then the code looks at the current CPU's shared ready queue and calls KiSearchForNewThreadOnProcessor in a loop. If no thread is found, the affinity is changed to the next group and the function is called again. This time, however, the target CPU points it to the next group's shared queue instead of the current one, causing this processor to find the best ready thread from the other processor group's ready queue. If this fails to find a thread to run, local queues of processors in that group are searched in the same manner. If this is unsuccessful, and if DFSS is enabled, a thread from the idle-only queue of the remote logical processor is released on the current processor instead, if possible.

If no candidate ready thread is found, the next-lower numbered logical processor is attempted, and so on, until all logical processors have been exhausted on the current NUMA node. In this case,

the algorithm keeps searching for the next-closest node, and so on, until all nodes in the current group have been exhausted. (Recall that Windows allows a given thread to have affinity only on a single group.) If this process fails to find any candidates, the function returns NULL and the processor enters the idle thread in the case of a wait (which will skip idle scheduling). If this work was already being done from the idle scheduler, the processor enters a sleep state.

## **Processor selection**

We've described how Windows picks a thread when a logical processor needs to make a selection (or when a selection must be made for a given logical processor) and assumed the various scheduling routines have an existing database of ready threads to choose from. Now we'll see how this database gets populated in the first place—in other words, how Windows chooses which LP's ready queues to associate with a given ready thread. Having described the types of multiprocessor systems supported by Windows as well as thread-affinity and ideal processor settings, we're now ready to examine how this information is used for this purpose.

#### Choosing a processor for a thread when there are idle processors

When a thread becomes ready to run, the KiDeferredReadyThread scheduler function is called. This prompts Windows to perform two tasks:

- Adjust priorities and refresh quantums as needed (as explained in the "Priority boosts" section).
- Pick the best logical processor for the thread.

Windows first looks up the thread's ideal processor and then it computes the set of idle processors within the thread's hard affinity mask. This set is then pruned as follows:

- Any idle logical processors that have been parked by the core-parking mechanism are removed. (See Chapter 6 for more information on core parking.) If this causes no idle processors to remain, idle processor selection is aborted, and the scheduler behaves as if no idle processors were available (described in the next section).
- 2. Any idle logical processors that are not on the ideal node (defined as the node containing the ideal processor) are removed (unless this would cause all idle processors to be eliminated).
- On an SMT system, any non-idle SMT sets are removed, even if this might cause the elimination of the ideal processor itself. In other words, Windows prioritizes a non-ideal, idle SMT set over an ideal processor.
- 4. Windows checks whether the ideal processor is among the remaining set of idle processors. If not, it must then find the most appropriate idle processor. To do this, it first checks whether the processor that the thread last ran on is part of the remaining idle set. If so, it considers this processor to be a temporary ideal processor and selects it. (Recall that the ideal processor attempts to maximize processor cache hits, and picking the last processor a thread ran on is a good way of doing so.) If the last processor is not part of the remaining idle set, Windows checks whether the current processor (that is, the processor currently executing this scheduling code) is part of this set. If so, it applies the same logic as before.

- 5. If neither the last nor the current processor is idle, Windows performs one more pruning operation, removing any idle logical processors that are not on the same SMT set as the ideal processor. If there are none left, Windows instead removes any processors not on the SMT set of the current processor (unless this, too, eliminates all idle processors). In other words, Windows prefers idle processors that share the same SMT set as the unavailable ideal processor and/or last processor it would've liked to pick in the first place. Because SMT implementations share the cache on the core, this has nearly the same effect as picking the ideal or last processor from a caching perspective.
- **6.** If after the previous step more than one processor remains in the idle set, Windows picks the lowest-numbered processor as the thread's current processor.

After a processor has been selected for the thread to run on, that thread is put in the standby state and the idle processor's PRCB is updated to point to this thread. If the processor is idle but not halted, a DPC interrupt is sent so that the processor handles the scheduling operation immediately. Whenever such a scheduling operation is initiated, KiCheckForThreadDispatch is called. It detects that a new thread has been scheduled on the processor and causes an immediate context switch if possible (as well as notifying Autoboost of the switch and delivering pending APCs). Alternatively, if no thread is pending, it causes a DPC interrupt to be sent.

#### Choosing a processor for a thread when there are no idle processors

If there are no idle processors when a thread wants to run, or if the only idle processors were eliminated by the first pruning (which got rid of parked idle processors), Windows first checks whether the latter situation has occurred. In this scenario, the scheduler calls KiSelectCandidateProcessor to ask the core-parking engine for the best candidate processor. The core-parking engine selects the highestnumbered processor that is unparked within the ideal node. If there are no such processors, the engine forcefully overrides the park state of the ideal processor and causes it to be unparked. Upon returning to the scheduler, it checks whether the candidate it received is idle; if so, it picks this processor for the thread, following the same last steps as in the previous scenario.

If this fails, Windows must decide whether to preempt the currently running thread. First, a target processor needs to be selected. The preference is in order of precedence: the ideal processor of the thread, the last processor the thread ran on, the first available processor in the current NUMA node, the closest processor on another NUMA node, and all these, barring affinity constraints, if any.

After a processor is selected, the next question is whether the new thread should preempt the current one on that processor. This is done by comparing the ranks of the two threads. This is an internal scheduling number that indicates the relative power of a thread based on its scheduling group and other factors. (See the section "Group-based scheduling" later in this chapter for a detailed discussion of group scheduling and rank.) If the rank of the new thread is zero (highest) or lower than the current thread's rank, or the ranks are equal but the priority of the new thread is higher than the currently executing one, then preemption should occur. The currently running thread is marked to be preempted, and Windows queues a DPC interrupt to the target processor to preempt the currently running thread in favor of this new thread. If the ready thread cannot be run right away, it is moved into the ready state on the shared or local queue (as appropriate based on affinity constraints), where it will await its turn to run. As seen in the scheduling scenarios earlier, the thread will be inserted either at the head or the tail of the queue, based on whether it entered the ready state due to preemption.

**Note** Regardless of the underlying scenario and various possibilities, threads are mostly put on their ideal processor's per-processor ready queues, guaranteeing the consistency of the algorithms that determine how a logical processor picks a thread to run.

## Heterogeneous scheduling (big.LITTLE)

The kernel assumes an SMP system, as previously described. However, some ARM-based processors contain multiple cores that are not the same. A typical ARM CPU (for example, from Qualcomm) contains some powerful cores, which should run for short periods at a time (and consume more energy), and a set of weaker cores, which can run for longer periods (and consume less energy). This is sometimes called *big.LITTLE*.

Windows 10 introduced the ability to distinguish between these cores and schedule threads based on the core's size and policy, including the foreground status of the thread, its priority, and its expected run time. Windows initializes the set of processors when the Power Manager is initialized by calling PopInitializeHeteroProcessors (and if processors are hot-added to the system). The function allows the simulation of hetero systems (for example, for testing purposes) by adding keys under the registry key HKLM\System\CurrentControlSet\Control\Session Manager\Kernel\KGroups as follows:

- A key should use two decimal digits to identify a processor group number. (Recall that each group holds at most 64 processors.) For example, 00 is the first group, 01 is the second, etc. (On most systems, one group would suffice.)
- Each key should contain a DWORD value named SmallProcessorMask that is a mask of processors that would be considered small. For example, if the value is 3 (the first two bits are on) and the group has six total processors, that would mean processors 0 and 1 (3 = 1 or 2) are small, while the other four processors are big. This is essentially the same as an affinity mask.

The kernel has several policy options that can be tweaked when dealing with hetero systems, stored in global variables. Table 4-5 shows some of these variables and their meaning.

Variable Name	Meaning	Default Value
KiHeteroSystem	Is the system heterogeneous?	False
PopHeteroSystem	System hetero type: None (0) Simulated (1) EfficiencyClass (2) FavoredCore (3)	None (0)

TABLE 4-5	Hetero kernel variables
-----------	-------------------------

PpmHeteroPolicy	Scheduling policy: None (0) Manual (1) SmallOnly (2) LargeOnly (3) Dynamic (4)	Dynamic(4)
KiDynamicHeteroCpuPolicyMask	Determine what is considered in assessing whether a thread is important	7 (foreground status = 1, priority = 2, expected run time = 4)
KiDefaultDynamicHeteroCpuPolicy	Behavior of Dynamic hetero policy (see above): All (0) (all available) Large (1) LargeOrIdle (2) Small(3) SmallOrIdle (4) Dynamic (5) (use priority and other metrics to decide) BiasedSmall (6) (use priority and other metrics, but prefer small) BiasedLarge (7)	Small (3)
KiDynamicHeteroCpuPolicyImportant	Policy for a dynamic thread that is deemed important (see possible values above)	LargeOrIdle (2)
KiDynamicHeterCpuPolicyImportantShort	Policy for dynamic thread that is deemed important but run a short amount of time	Small(3)
KiDynamicCpuPolicyExpectedRuntime	Run-time value that is considered heavy	5,200 msec
KiDynamicHeteroCpuPolicyImportantPriority	Priority above which threads are considered important if priority- based dynamic policy is chosen	8

Dynamic policies (refer to Table 4-5) must be translated to an importance value based on KiDynamic-HeteroPolicyMask and the thread's state. This is done by the KiConvertDynamicHeteroPolicy function, which checks, in order, the foreground state of the thread, its priority relative to KiDynamic-HeteroCpuPolicyImportantPriority, and its expected run time. If the thread is deemed important (if running time is the determining factor, then it could be short as well), the important-related policy is used for scheduling decisions. (In Table 4-5, this would be KiDynamicHeteroCpuPolicyImportant-Short or KiDynamicHeteroCpuPolicyImportant.)

## **Group-based scheduling**

The previous section described the standard thread-based scheduling implementation of Windows. Since its appearance in the first release of Windows NT (with scalability improvements done with each subsequent release), it has reliably served general user and server scenarios. However, because thread-based scheduling attempts to fairly share the processor or processors only among competing threads of the same priority, it does not account for higher-level requirements such as the distribution of threads to users and the potential for certain users to benefit from more overall CPU time at the expense of other users. This is problematic in terminal-services environments, in which dozens of users

compete for CPU time. If only thread-based scheduling is used, a single high-priority thread from a given user has the potential to starve threads from all users on the machine.

Windows 8 and Server 2012 introduced a group-based scheduling mechanism, built around the concept of a scheduling group (KSCHEDULING\_GROUP). A scheduling group maintains a policy, scheduling parameters (described shortly), and a list of kernel scheduling control blocks (KSCBs), one per processor, that are part of the scheduling group. The flip side is that a thread points to a scheduling group it belongs to. If that pointer is null, it means the thread is outside any scheduling group's control. Figure 4-19 shows the structure of a scheduling group. In this figure, threads T1, T2, and T3 belong to the scheduling group, while thread T4 does not.




FIGURE 4-19 Scheduling group.

Here are some terms related to group scheduling:

- **Generation** This is the amount of time over which to track CPU usage.
- Quota This is the amount of CPU usage allowed to a group per generation. Over quota means the group has used up all its budget. Under quota means the group has not used its full budget.
- Weight This is the relative importance of a group, between 1 and 9, where the default is 5.
- **Fair-share scheduling** With this type of scheduling, idle cycles can be given to threads that are over quota if no under-quota threads want to run.

The KSCB structure contains CPU-related information as follows:

- Cycle usage for this generation
- Long-term average cycle usage, so that a burst of thread activity can be distinguished from a true hog
- Control flags such as hard capping, which means that even if CPU time is available above the assigned quota, it will not be used to give the thread extra CPU time
- Ready queues, based on the standard priorities (0 to 15 only because real-time threads are never part of a scheduling group)

An important parameter maintained by a scheduling group is called *rank*, which can be considered a scheduling priority of the entire group of threads. A rank with a value of 0 is the highest. A higher-rank number means the group has used more CPU time and so is less likely to get more CPU time.

Rank always trumps priority. This means that given two threads with different ranks, the lower value rank is preferred, regardless of priority. Equal-rank threads are compared based on priority. The rank is adjusted periodically as cycle usage increases.

Rank 0 is the highest (so it always wins out) against a higher number rank, and is implicit for some threads. This can indicate one of the following:

- The thread is not in any scheduling group ("normal" threads)
- Under-quota threads
- Real-time priority threads (16–31)
- Threads executing at IRQL APC\_LEVEL (1) within a kernel critical or guarded region (see Chapter 8 in Part 2 for more on APCs and regions)

At various scheduling choices (for example, KiQuantumEnd), the decision of which thread to schedule next accounts for the scheduling group (if any) of the current and ready threads. If a scheduling group exists, the lowest value rank wins out, followed by priority (if ranks are equal), followed by the first arriving thread (if priorities are equal; round-robin at quantum end).

## Dynamic fair share scheduling

Dynamic fair share scheduling (DFSS) is a mechanism that can be used to fairly distribute CPU time among sessions running on a machine. It prevents one session from potentially monopolizing the CPU if some threads running under that session have a relatively high priority and run a lot. It's enabled by default on a Windows Server system that has the Remote Desktop role. However, it can be configured on any system, client or server. Its implementation is based on group scheduling described in the previous section.

During the very last parts of system initialization, as the registry SOFTWARE hive is initialized by Smss. exe, the process manager initiates the final post-boot initialization in PsBootPhaseComplete, which calls PspIsDfssEnabled. Here, the system decides which of the two CPU quota mechanisms (DFSS or legacy) will be employed. For DFSS to be enabled, the EnableCpuQuota registry value must be set to a non-zero value in both of the quota keys. The first of these is HKLM\SOFTWARE\Policies\Microsoft\ Windows\SessionManager\Quota System, for the policy-based setting. The second is HKLM\SYSTEM\ CurrentControlSet\Control\SessionManager\Quota System, under the system key. This determines whether the system supports the functionality (which, by default, is set to TRUE on Windows Server with the Remote Desktop role).

If DFSS is enabled, the PsCpuFairShareEnabled global variable is set to TRUE, which makes all threads belong to scheduling groups (except session 0 processes). DFSS configuration parameters are read from the aforementioned keys by a call to PspReadDfssConfigurationValues and stored in global variables. These keys are monitored by the system. If modified, the notification callback calls PspReadDfssConfigurationValues again to update the configuration values. Table 4-6 shows the values and their meaning.

#### TABLE 4-6 DFSS registry configuration parameters

Registry Value Name	Kernel Variable Name	Meaning	Default Value
DfssShortTermSharingMS	PsDfssShortTermSharingMS	The time it takes for the group rank to increase within a generation cycle	30 ms
DfssLongTermSharingMS	PsDfssLongTermSharingMS	The time it takes to jump from rank 0 to a non-zero rank when the threads exceed their quota within the genera- tion cycle	15 ms
DfssGenerationLengthMS	PsDfssGenerationLengthMS	The generation time over which to track CPU usage	600 ms
DfssLongTermFraction1024	PsDfssLongTermFraction1024	The value used in a formula for an exponential moving average used for long-term cycles computation	512

After DFSS is enabled, whenever a new session is created (other than session 0), MiSessionObject-Create allocates a scheduling group associated with the session with the default weight of 5, which is the middle ground between the minimum of 1 and the maximum of 9. A scheduling group manages either DFSS or CPU rate-control (see the next section) information based on a policy structure (KSCHEDULING\_ GROUP\_POLICY) that is part of a scheduling group. The Type member indicates whether it's configured for DFSS (WeightBased=0) or rate control (RateControl=1). MiSessionObjectCreate calls KeInsertSchedulingGroup to insert the scheduling group into a global system list (maintained in the global variable KiSchedulingGroupList, needed for weight recalculation if processors are hot-added). The resulting scheduling group is also pointed to by the SESSION\_OBJECT structure for the particular session.

#### **EXPERIMENT: DFSS in action**

In this experiment, you'll configure a system to use DFSS and watch it "do its thing".

- 1. Add the registry keys and values as described in this section to enable DFSS on the system. (You can try this experiment on a VM as well.) Then restart the system for the changes to take effect.
- To make sure DFSS is active, open a live kernel debug session and inspect the value of PsCpuFairShareEnabled by issuing the following command. A value of 1 indicates DFSS is active.

```
lkd> db nt!PsCpuFairShareEnabled L1
fffff800'5183722a 01
```

3. In the debugger, look at the current thread. (It should be one of the threads running WinDbg.) Notice that the thread is part of a scheduling group and that its KSCB is not NULL because the thread was running at the time of display.

```
lkd> !thread
THREAD ffffd28c07231640 Cid 196c.1a60 Teb: 000000f897f4b000 Win32Thread:
ffffd28c0b9b0b40 RUNNING on processor 1
IRP List:
```

```
ffffd28c06dfac10: (0006,0118) Flags: 00060000 Mdl: 00000000
    Not impersonating
                               ffffac0d33668340
    DeviceMap
                           ffffd28c071fd080 Image:
    Owning Process
                                                                       windbg.exe

        N/A
        Image:
        N/A

        6146
        Ticks: 33 (0:00:00:00.515)


        877
        IdealProcessor: 0

    Attached Process
    Wait Start TickCount 6146
Context Switch Count 877
                               00:00:00.468
    UserTime
    KernelTime
                               00:00:00.156
    Win32 Start Address 0x00007ff6ac53bc60
    Stack Init ffffbf81ae85fc90 Current ffffbf81ae85f980
    Base ffffbf81ae860000 Limit ffffbf81ae85a000 Call 000000000000000
    Priority 8 BasePriority 8 PriorityDecrement 0 IoPriority 2 PagePriority 5
    Scheduling Group: ffffd28c089e7a40 KSCB: ffffd28c089e7c68 rank 0
Enter the dt command to view the scheduling group:
    lkd> dt nt!_kscheduling_group ffffd28c089e7a40
       +0x000 Policy : _KSCHEDULING_GROUP_POLICY
       +0x008 RelativeWeight : 0x80
       +0x00c ChildMinRate : 0x2710
       +0x010 ChildMinWeight : 0
       +0x014 ChildTotalWeight : 0
       +0x018 QueryHistoryTimeStamp : 0xfed6177
       +0x020 NotificationCycles : 0n0
       +0x028 MaxQuotaLimitCycles : 0n0
       +0x030 MaxQuotaCyclesRemaining : 0n-73125382369
       +0x038 SchedulingGroupList : _LIST_ENTRY [ 0xfffff800'5179b110 -
    0xffffd28c'081b7078 ]
                              : _LIST_ENTRY [ 0xfffff800'5179b110 -
       +0x038 Sibling
    0xffffd28c'081b7078 ]
       +0x048 NotificationDpc : 0x0002eaa8'0000008e _KDPC
       +0x050 ChildList : _LIST_ENTRY [ 0xffffd28c'062a7ab8 -
    0xffffd28c'05c0bab8 ]
       +0x060 Parent
                              : (null)
       +0x080 PerProcessor : [1] _KSCB
```

- **5.** Create another local user on the machine.
- 6. Run CPU Stress in the current session.
- 7. Make a few threads run at maximum activity, but not enough to overwhelm the machine. For example, the following image shows two threads running at maximum activity on a three-processor virtual machine:

File	Process T	hread Optio	Proces	s Affinity: 111 s Priority Class: Hig	¢h.	
#	ID	Active?	Activity	Priority	Ideal CPU	Affi
1	8432	Yes	Maximum	Normal	2	
2			Maximum	Normal		
3	8048		Low	Normal	1	
4	7704		Low	Normal	2	

- 8. Press **Ctrl+Alt+Del** and select **Switch User**. Then select and log in to the account for the other user you created.
- 9. Run CPU Stress again, making the same number of threads run with maximum activity.
- 10. For the CPUSTRES process, open the **Process** menu, choose **Priority Class**, and select **High** to change the process priority class. Without DFSS, that higher-priority process should consume most of the CPU. This is because there are four threads competing for three processors. One of these will lose out, and it should be from the lower-priority process.
- 11. Open Process Explorer, double-click both CPUSTRES processes, and select the **Performance Graph** tab.
- **12.** Place both windows side by side. You should see the CPU consumed roughly evenly between the processes, even though their priorities are not the same:



- 13. Disable DFSS by removing the registry keys. Then restart the system.
- **14.** Rerun the experiment. You should clearly see the difference with the higher-priority process receiving the most CPU time.

## **CPU** rate limits

DFSS works by automatically placing new threads inside the session-scheduling group. This is fine for a terminal-services scenario, but is not good enough as a general mechanism to limit the CPU time of threads or processes.

The scheduling-group infrastructure can be used in a more granular fashion by using a job object. Recall from Chapter 3 that a job can manage one or more processes. One of the limitations you can place on a job is a CPU rate control, which you do by calling SetInformationJobObject with Job-ObjectCpuRateControlInformation as the job information class and a structure of type JOBOBJECT\_ CPU\_RATE\_CONTROL\_INFORMATION containing the actual control data. The structure contains a set of flags that enable you to apply one of three settings to limit CPU time:

**CPU rate** This value can be between 1 and 10000 and represents a percent multiplied by 100 (for example, for 40 percent the value should be 4000).

- Weight-based This value can be between 1 and 9, relative to the weight of other jobs. (DFSS is configured with this setting.)
- Minimum and maximum CPU rates These values are specified similarly to the first option. When the threads in the job reach the maximum percentage specified in the measuring interval (600 ms by default), they cannot get any more CPU time until the next interval begins. You can use a control flag to specify whether to use hard capping to enforce the limit even if there is spare CPU time available.

The net result of setting these limits is to place all threads from all processes that are in the job in a new scheduling group and configuring the group as specified.

#### **EXPERIMENT: CPU rate limit**

In this experiment, you'll look at CPU rate limit using a job object. It's best to perform this experiment on a virtual machine and attach to its kernel rather than using the local kernel because of a debugger bug at the time of writing.


1. Run CPU Stress on the test VM and configure a few threads to consume about 50 percent of CPU time. For example, on an eight-processor system, activate four threads that run with maximum activity level:

File	Process T	hread Optio	ins Help				
3		<b>A</b>	655	s Affinity: 111111 s Priority Class: No			
#	ID	Active?	Activity	Priority	Ideal CPU	A	ffinity
# 1	1D 6556	Active? Yes	Activity Maximum	Priority Normal	Ideal CPU 6		ffinity 11111
# 1 2	1.57	0.0700755	1.	10.000		111	
1	6556	Yes	Maximum	Normal		111 111	11111

- 2. Open Process Explorer, find the CPUSTRES instance, open its properties, and select the **Performance Graph** tab. The CPU usage should be roughly 50 percent.
- **3.** Download the CPULIMIT tool from the book's downloadable resources. This is a simple tool that allows you to limit the CPU usage of a single process through hard capping.
- **4.** Run the command shown to limit the CPU usage to 20 percent for the CPUSTRES process. (Replace the number 6324 with your process ID.)

#### CpuLimit.exe 6324 20

5. Look at the Process Explorer window. You should see the drop to around 20 percent:



- 6. Open WinDbg on the host system.
- 7. Attach to the kernel of the test system and break into it.
- 8. Enter the following command to locate the CPUSTRES process:

```
0: kd> !process 0 0 cpustres.exe
PROCESS ffff9e0629528080
SessionId: 1 Cid: 18b4 Peb: 009e4000 ParentCid: 1c4c
DirBase: 230803000 ObjectTable: ffffd78d1af6c540 HandleCount: <Data
Not Accessible>
Image: CPUSTRES.exe
```

9. Type the following command to list basic information for the process:

```
0: kd> !process ffff9e0629528080 1
PROCESS ffff9e0629528080
    SessionId: 1 Cid: 18b4
                               Peb: 009e4000 ParentCid: 1c4c
    DirBase: 230803000 ObjectTable: ffffd78d1af6c540 HandleCount: <Data
Not Accessible>
    Image: CPUSTRES.exe
    VadRoot ffff9e0626582010 Vads 88 Clone 0 Private 450. Modified 4. Locked 0.
    DeviceMap ffffd78cd8941640
                                      ffffd78cfe3db050
    Token
    ElapsedTime
                                      00:08:38.438
    UserTime
                                      00:00:00.000
    KernelTime
                                      00:00:00.000
    QuotaPoolUsage[PagedPool]
                                      209912
    QuotaPoolUsage[NonPagedPool]
                                      11880
    Working Set Sizes (now, min, max) (3296, 50, 345) (13184KB, 200KB, 1380KB)
    PeakWorkingSetSize
                                      3325
    VirtualSize
                                      108 Mb
    PeakVirtualSize
                                      128 Mb
    PageFaultCount
                                      3670
    MemoryPriority
                                      BACKGROUND
    BasePriority
                                      8
                                      568
    CommitCharge
    Job
                                      ffff9e06286539a0
```

10. Notice there is a non-NULL job object. Show its properties with the !job command. The tool creates a job (CreateJobObject), adds the process to the job (AssignProcessTo-JobObject), and calls SetInformationJobObject with the CPU rate information class and rate value of 2000 (20 percent).

```
0: kd> !job ffff9e06286539a0
Job at ffff9e06286539a0
Basic Accounting Information
TotalUserTime: 0x0
TotalKernelTime: 0x0
ThisPeriodTotalUserTime: 0x0
ThisPeriodTotalKernelTime: 0x0
```

0x0
0x1
0x1
0
0
0x0
0x248
0x248
s: 0x0)
LimitFlags: 0x800)
28d7c1c0

11. Rerun the CPULIMIT tool on the same process and again set the CPU rate to 20 percent. You should see the CPU consumption of CPUSTRES drop down to around 4 percent. This is because of job nesting. A new job is created, as is the process assigned to it, nested under the first job. The net result is 20 percent of 20 percent, which is 4 percent.

## Dynamic processor addition and replacement

As you've seen, developers can fine-tune which threads are allowed to (and in the case of the ideal processor, should) run on which processor. This works fine on systems that have a constant number of processors during their run time. For example, desktop machines require shutting down the computer to make any sort of hardware changes to the processor or their count. Today's server systems, however, cannot afford the downtime that CPU replacement or addition normally requires. In fact, you may be required to add a CPU at times of high load that is above what the machine can support at its current level of performance. Having to shut down the server during a period of peak usage would defeat the purpose.

To address this requirement, the latest generation of server motherboards and systems support the addition of processors (as well as their replacement) while the machine is still running. The ACPI BIOS and related hardware on the machine have been specifically built to allow and be aware of this need, but OS participation is required for full support.

Dynamic processor support is provided through the HAL, which notifies the kernel of a new processor on the system through the KeStartDynamicProcessor function. This routine does similar work to that performed when the system detects more than one processor at startup and needs to initialize the structures related to them. When a dynamic processor is added, various system components perform some additional work. For example, the memory manager allocates new pages and memory structures optimized for the CPU. It also initializes a new DPC kernel stack while the kernel initializes the global descriptor table (GDT), the interrupt dispatch table (IDT), the processor control region (PCR), the process control block (PRCB), and other related structures for the processor.

Other executive parts of the kernel are also called, mostly to initialize the per-processor look-aside lists for the processor that was added. For example, the I/O manager, executive look-aside list code, cache manager, and object manager all use per-processor look-aside lists for their frequently allocated structures.

Finally, the kernel initializes threaded DPC support for the processor and adjusts exported kernel variables to report the new processor. Different memory-manager masks and process seeds based on processor counts are also updated, and processor features need to be updated for the new processor to match the rest of the system—for example, enabling virtualization support on the newly added processor. The initialization sequence completes with the notification to the Windows Hardware Error Architecture (WHEA) component that a new processor is online.

The HAL is also involved in this process. It is called once to start the dynamic processor after the kernel is aware of it, and called again after the kernel has finished initialization of the processor. However, these notifications and callbacks only make the kernel aware and respond to processor changes. Although an additional processor increases the throughput of the kernel, it does nothing to help drivers.

To handle drivers, the system has a default executive callback object, ProcessorAdd, with which drivers can register for notifications. Similar to the callbacks that notify drivers of power state or system time changes, this callback allows driver code to, for example, create a new worker thread if desirable so that it can handle more work at the same time.

Once drivers are notified, the final kernel component called is the Plug and Play manager, which adds the processor to the system's device node and rebalances interrupts so that the new processor can handle interrupts that were already registered for other processors. CPU-hungry applications are also able to take advantage of the new processors.

However, a sudden change of affinity can have potentially breaking changes for a running application—especially when going from a single-processor to a multiprocessor environment—through the appearance of potential race conditions or simply misdistribution of work (because the process might have calculated the perfect ratios at startup, based on the number of CPUs it was aware of). As a result, applications do not take advantage of a dynamically added processor by default. They must request it.

The SetProcessAffinityUpdateMode and QueryProcessAffinityUpdateMode Windows APIs, which use the undocumented NtSet/QueryInformationProcess system call) tell the process manager that these applications should have their affinity updated (by setting the AffinityUpdateEnable flag in EPROCESS) or that they do not want to deal with affinity updates (by setting the AffinityPermanent flag in EPROCESS). This is a one-time change. After an application has told the system that its affinity is permanent, it cannot later change its mind and request affinity updates.

As part of KeStartDynamicProcessor, a new step has been added after interrupts are rebalanced: calling the process manager to perform affinity updates through PsUpdateActiveProcessAffinity. Some Windows core processes and services already have affinity updates enabled, while third-party software will need to be recompiled to take advantage of the new API call. The System process, Svchost processes, and Smss are all compatible with dynamic processor addition.

## Worker factories (thread pools)

Worker factories are the internal mechanism used to implement user-mode thread pools. The legacy thread-pool routines were completely implemented in user mode inside the Ntdll.dll library. In addition, the Windows API provided several functions for developers to call, which provided waitable timers (CreateTimerQueue, CreateTimerQueueTimer, and friends), wait callbacks (RegisterWaitForS-ingleObject), and work item processing with automatic thread creation and deletion (QueueUser-WorkItem), depending on the amount of work being done.

One issue with the old implementation was that only one thread pool could be created in a process, which made some scenarios difficult to implement. For example, trying to prioritize work items by building two thread pools which would serve a different set of requests was not directly possible. The other issue was the implementation itself, which was in user mode (in Ntdll.dll). Because the kernel can have direct control over thread scheduling, creation, and termination without the typical costs associated with doing these operations from user mode, most of the functionality required to support the user-mode thread pool implementation in Windows is now located in the kernel. This also simplifies the code that developers need to write. For example, creating a worker pool in a remote process can be done with a single API call instead of the complex series of virtual memory calls this normally requires. Under this model, Ntdll.dll merely provides the interfaces and high-level APIs required for interfacing with the worker factory kernel code.

This kernel thread pool functionality in Windows is managed by an object manager type called TpWorkerFactory, as well as four native system calls for managing the factory and its workers (NtCreateWorkerFactory, NtWorkerFactoryWorkerReady, NtReleaseWorkerFactoryWorker, and NtShutdownWorkerFactory); two query/set native calls (NtQueryInformationWorkerFactory and NtSetInformationWorkerFactory); and a wait call (NtWaitForWorkViaWorkerFactory). Just like other native system calls, these calls provide user mode with a handle to the TpWorkerFactory object, which contains information such as the name and object attributes, the desired access mask, and a security descriptor. Unlike other system calls wrapped by the Windows API, however, thread-pool management is handled by Ntdll.dll's native code. This means developers work with opaque descriptors: a TP\_POOL pointer for a thread pool and other opaque pointers for object created from a pool, including TP\_WORK (work callback), TP\_TIMER (timer callback), TP\_WAIT (wait callbacks), etc. These structures hold various pieces of information, such as the handle to the TpWorkerFactory object.

As its name suggests, the worker factory implementation is responsible for allocating worker threads (and calling the given user-mode worker thread entry point) and maintaining a minimum and maximum thread count (allowing for either permanent worker pools or totally dynamic pools) as well as other accounting information. This enables operations such as shutting down the thread pool to be performed with a single call to the kernel because the kernel has been the only component responsible for thread creation and termination.

Because the kernel dynamically creates new threads as needed (based on minimum and maximum numbers provided), this increases the scalability of applications using the new thread-pool implementation. A worker factory will create a new thread whenever all of the following conditions are met:

- Dynamic thread creation is enabled.
- The number of available workers is lower than the maximum number of workers configured for the factory (default of 500).
- The worker factory has bound objects (for example, an ALPC port that this worker thread is waiting on) or a thread has been activated into the pool.
- There are pending I/O request packets (IRPs; see Chapter 6 for more information) associated with a worker thread.

In addition, it will terminate threads whenever they've become idle—that is, they haven't processed any work item—for more than 10 seconds (by default). Furthermore, although developers have always been able to take advantage of as many threads as possible (based on the number of processors on the system) through the old implementation, it's now possible for applications using thread pools to automatically take advantage of new processors added at run time. This is through its support for dynamic processors in Windows Server (as discussed earlier in this chapter).

## Worker factory creation

The worker factory support is merely a wrapper to manage mundane tasks that would otherwise have to be performed in user mode (at a loss of performance). Much of the logic of the new thread-pool code remains in the Ntdll.dll side of this architecture. (Theoretically, by using undocumented functions, a different thread-pool implementation can be built around worker factories.) Also, it is not the worker factory code that provides the scalability, wait internals, and efficiency of work processing. Instead, it is a much older component of Windows: I/O completion ports or, more correctly, kernel queues (KQUEUE). In fact, when creating a worker factory, an I/O completion port must have already been created by user mode, and the handle needs to be passed in.

It is through this I/O completion port that the user-mode implementation will queue and wait for work—but by calling the worker factory system calls instead of the I/O completion port APIs. Internally, however, the "release" worker factory call (which queues work) is a wrapper around IoSetIoCompletionEx, which increases pending work, while the "wait" call is a wrapper around IoRemoveIoCompletion. Both these routines call into the kernel queue implementation. Therefore, the job of the worker factory code is to manage either a persistent, static, or dynamic thread pool; wrap the I/O completion port model into interfaces that try to prevent stalled worker queues by automatically creating dynamic threads; and simplify global cleanup and termination operations during a factory shutdown request (as well as easily block new requests against the factory in such a scenario).

The executive function that creates the worker factory, NtCreateWorkerFactory, accepts several arguments that allow customization of the thread pool, such as the maximum threads to create and the initial committed and reserved stack sizes. The CreateThreadpool Windows API, however, uses the default stack sizes embedded in the executable image (just like a default CreateThread would). The Windows API does not, however, provide a way to override these defaults. This is somewhat unfortunate, as in many cases thread-pool threads don't require deep call stacks, and it would be beneficial to allocate smaller stacks.

The data structures used by the worker factory implementation are not in the public symbols, but it is still possible to look at some worker pools, as you'll see in the next experiment. Additionally, the NtQueryInformationWorkerFactory API dumps almost every field in the worker factory structure.

#### **EXPERIMENT:** Looking at thread pools

Because of the advantages of the thread-pool mechanism, many core system components and applications use it, especially when dealing with resources such as ALPC ports (to dynamically process incoming requests at an appropriate and scalable level). One of the ways to identify which processes are using a worker factory is to look at the handle list in Process Explorer. Follow these steps to look at some details behind them:

- 1. Run Process Explorer.
- 2. Open the **View** menu and select **Show Unnamed Handles and Mappings**. (Unfortunately, worker factories aren't named by Ntdll.dll, so you need to take this step to see the handles.)
- 3. Select an instance of svchost.exe from the list of processes.
- 4. Open the **View** menu and choose **Show Lower Pane** to display the lower pane of the handle table.
- 5. Open the **View** menu, choose **Lower Pane View**, and select **Handles** to display the table in handle mode.
- 6. Right-click the lower pane column headers and choose Select Columns.
- 7. Make sure the **Type** and **Handle Value** columns are checked.
- 8. Click the **Type** header to sort by type.
- **9.** Scroll down the handles, looking at the Type column, until you find a handle of type TpWorkerFactory.
- 10. Click the **Handle** header to sort by handle value. You should see something similar to the following screenshot. Notice how the TpWorkerFactory handle is immediately preceded by an IoCompletion handle. As discussed, this occurs because a handle to an I/O completion port on which work will be sent must be created before creating a worker factory.

File Options View Process Find Har	ndle Users	Help				
🛃 🖪 🖻 🗖 🖻  🗚		-				
Process	PID	CPU	Start Time	Private Bytes	Working Set	Winds *
an appave axe	11872		09:18:13 11-Jul-16	16,116 K	16,940 K	
solwriter.exe	2896		05:19:56 11-Jul-16	1,856 K	7,384 K	
🖂 🧱 sublime_text.exe	13452		10:33:30 12-Jul-16	125,368 K	22.212 K	Second
🖃 💽 svchost.exe	640	0.10	05:19:32 11-Jul-16	9,652 K	26,100 K	
svchost.exe	800	0.15	05:19:33 11-Jul-16			
E svchost.exe	<	1.11				>
Handle Type	Nam	e :				
0x10 WaltCompletionPacket						
0x14 IoCompletion						
0x18 TpWorkerFactory						
0x1C IRTimer						
0x20 WaitCompletionPacket						
0x24 IRTimer						1
flv2R WallConnelionPanket						

 Double-click the selected process in the list of processes, click the **Threads** tab, and click the **Start Address** column. You should see something similar to the following screenshot. Worker factory threads are easily identified by their Ntdll.dll's entry point, TppWorkerThread. (*Tpp* stands for *thread pool private*.)

Image	Perform	ance i	Performan	ice Graph	Disk a	nd Network	GPU Gra	ph Service
Thread		TCP/I	9	Security		Enviro	onment	Strings
Count: 74	£							
TID	CPU	Cycles D	elta Ser	vice	Start	Address	Υ.	^
2108 4336 14492	< 0.01		Rasi Dsm		qmgr		ietBestCostNet viceMain+0x9f erThread	
14256						IITppWork		
17288	0.02	8,302,4				IIITppWork		
13720	< 0.01	1,090,2				IIITppWork		
15592	0.03	14,452,1	79			IITppWork		
10364						IITppWork		
19112	< 0.01					IITppWork		
19296 15232	< 0.01	645.1				IITppWork		
2328	< 0.01	643,1	oc iohlo			IITppWork		
4124			prop	anc.				
					ntdl c		ar Thread	
							erThread erThread	
			Cert	PropSvc	ntdl.d	IITppWork IITppWork IITppWork	erThread	~
2384 13392		17288	Cert	PropSvc	ntdl.d	IITppWork	erThread	Module
2384 13392 Thread ID:		17288 14:26:28			ntdl.d	IITppWork	erThread erThread	Module
2384 13392 Thread ID: Start Time:		1000	12-Jul-16		ntdi d ntdi d	IITppWork	erThread erThread	Module
2384 13392 Thread ID: Start Time: State:		14:26:28	12-Jul-16	5	ntdl c ntdl c	IITppWork IITppWork	erThread erThread	Module
2384 13392 Thread ID: Start Time: State: Kernel Time		14:26:28 Wait:WrQ	12-Jul-16 Jeue 15	Base Priori	ntdl d ntdl d ty:	IITppWork IITppWork	erThread erThread	Module
2384		14:26:28 Wait:WrQ 0:00:00.5	12-Jul-16 Jeue 15	5 Base Priori Dynamic P	ntdl.d ntdl.d ty: riority:	8 8	erThread erThread	Module
2384 13392 Start Time: Start Time: State: Kernel Time: User Time: Context Sw	itches:	14:26:28 Wait:WrQ 0:00:00.5 0:00:00.4	12-Jul-16 Jeue 15 21	Base Priori Dynamic P I/O Priority	ntdl o ntdl o ty: riority: /: iority:	8 Normal	erThread erThread	V Module
2384 13392 Thread ID: Start Time: State: Kernel Time User Time:	itches:	14:26:28 Wait:WrQ 0:00:00.5 0:00:00.4 11,800	12-Jul-16 Jeue 15 21	Base Priori Dynamic P I/O Priority Memory Pr	ty: riority: riority: essor:	8 8 Normal 5	erThread erThread	Module Suspend
2384 13392 Start Time: Start Time: State: Kernel Time: User Time: Context Sw	itches:	14:26:28 Wait:WrQ 0:00:00.5 0:00:00.4 11,800	12-Jul-16 Jeue 15 21	Base Priori Dynamic P I/O Priority Memory Pr	ty: riority: riority: essor:	8 8 Normal 5 2	erThread erThread Stack	

If you look at other worker threads, you'll see some are waiting for objects such as events. A process can have multiple thread pools, and each thread pool can have a variety of threads doing completely unrelated tasks. It's up to the developer to assign work and to call the thread-pool APIs to register this work through Ntdll.dll.

## Conclusion

This chapter examined the structure of threads, how they are created and managed, and how Windows decides which threads should run, for how long, and on which processor or processors. In the next chapter, you'll look at one of the most important aspects of any OS: memory management.

#### CHAPTER 5

# Memory management

n this chapter, you'll learn how Windows implements virtual memory and how it manages the subset of virtual memory kept in physical memory. We'll also describe the internal structure and components that make up the memory manager, including key data structures and algorithms. Before examining these mechanisms, we'll review the basic services provided by the memory manager and key concepts such as reserved memory versus committed memory and shared memory.

## Introduction to the memory manager

By default, the virtual size of a process on 32-bit Windows is 2 GB. If the image is marked specifically as large address space–aware, and the system is booted with a special option (described in the section "x86 address space layouts" later in this chapter), a 32-bit process can grow to be up to 3 GB on 32-bit Windows and to 4 GB on 64-bit Windows. The process virtual address space size on 64-bit Windows 8 and Server 2012 is 8192 GB (8 TB) and on 64 bit Windows 8.1 (and later) and Server 2012 R2 (and later), it is 128 TB.

As you saw in Chapter 2, "System architecture"—specifically in Table 2-2—the maximum amount of physical memory currently supported by Windows ranges from 2 GB to 24 TB, depending on which version and edition of Windows you are running. Because the virtual address space might be larger or smaller than the physical memory on the machine, the memory manager has two primary tasks:

- Translating, or mapping, a process's virtual address space into physical memory so that when a thread running in the context of that process reads or writes to the virtual address space, the correct physical address is referenced. (The subset of a process's virtual address space that is physically resident is called the *working set*. Working sets are described in more detail in the section "Working sets" later in this chapter.)
- Paging some of the contents of memory to disk when it becomes overcommitted—that is, when running threads try to use more physical memory than is currently available—and bringing the contents back into physical memory when needed.

In addition to providing virtual memory management, the memory manager provides a core set of services on which the various Windows environment subsystems are built. These services include memory-mapped files (internally called *section objects*), copy-on-write memory, and support for applications using large, sparse address spaces. The memory manager also provides a way for a process to allocate and use larger amounts of physical memory than can be mapped into the process virtual address space at one time—for example, on 32-bit systems with more than 3 GB of physical memory. This is explained in the section "Address Windowing Extensions" later in this chapter. **Note** There is a Control Panel applet (System) that provides control over the size, number, and locations of paging files. Its nomenclature suggests that virtual memory is the same thing as the paging file. This is not the case. The paging file is only one aspect of virtual memory. In fact, even if you run with no page file at all, Windows will still be using virtual memory. This distinction is explained in more detail later in this chapter.

## Memory manager components

The memory manager is part of the Windows executive and therefore exists in the file Ntoskrnl.exe. It's the largest component in the executive, hinting at its importance and complexity. No parts of the memory manager exist in the HAL. The memory manager consists of the following components:

- A set of executive system services for allocating, deallocating, and managing virtual memory, most of which are exposed through the Windows API or kernel-mode device driver interfaces
- A translation-not-valid and access fault trap handler for resolving hardware-detected memorymanagement exceptions and making virtual pages resident on behalf of a process
- Six key top-level routines, each running in one of six different kernel-mode threads in the System process:
  - The balance set manager (KeBalanceSetManager, priority 17) This calls an inner routine, the working set manager (MmWorkingSetManager), once per second as well as when free memory falls below a certain threshold. The working set manager drives the overall memory-management policies, such as working set trimming, aging, and modified page writing.
  - The process/stack swapper (KeSwapProcessOrStack, priority 23) This performs both process and kernel thread stack inswapping and outswapping. The balance set manager and the thread-scheduling code in the kernel awaken this thread when an inswap or outswap operation needs to take place.
  - **The modified page writer (MiModifiedPageWriter, priority 18)** This writes dirty pages on the modified list back to the appropriate paging files. This thread is awakened when the size of the modified list needs to be reduced.
  - The mapped page writer (MiMappedPageWriter, priority 18) This writes dirty pages in mapped files to disk or remote storage. It is awakened when the size of the modified list needs to be reduced or if pages for mapped files have been on the modified list for more than 5 minutes. This second modified page writer thread is necessary because it can generate page faults that result in requests for free pages. If there were no free pages and only one modified page writer thread, the system could deadlock waiting for free pages.
  - The segment dereference thread (MiDereferenceSegmentThread, priority 19) This is responsible for cache reduction as well as for page file growth and shrinkage. For example, if there is no virtual address space for paged pool growth, this thread trims the page cache so that the paged pool used to anchor it can be freed for reuse.

• The zero page thread (MiZeroPageThread, priority 0) This zeroes out pages on the free list so that a cache of zero pages is available to satisfy future demand-zero page faults. In some cases, memory zeroing is done by a faster function called MiZeroInParallel. See the note in the "Page list dynamics" section later in this chapter.

Each of these components is covered in more detail later in the chapter except for the segment dereference thread, which is covered in Chapter 14, "Cache manager," in Part 2.

## Large and small pages

Memory management is done in distinct chunks called *pages*. This is because the hardware memory management unit translates virtual to physical addresses at the granularity of a page. Hence, a page is the smallest unit of protection at the hardware level. (The various page-protection options are described in the section "Protecting memory" later in this chapter.) The processors on which Windows runs support two page sizes: small and large. The actual sizes vary based on the processor architecture, and they are listed in Table 5-1.

Architecture	Small Page Size	Large Page Size	Small Pages per Large Page		
x86 (PAE)	4 KB	2 MB	512		
x64	4 KB	2 MB	512		
ARM	4 KB	4 MB	1024		

TABLE 5-1 Page sizes

**Note** Some processors support configurable page sizes, but Windows does not use this feature.

The primary advantage of large pages is speed of address translation for references to data within the large page. This advantage exists because the first reference to any byte within a large page will cause the hardware's translation look-aside buffer (TLB) (described in the section "Address translation" later in this chapter), to have in its cache the information necessary to translate references to any other byte within the large page. If small pages are used, more TLB entries are needed for the same range of virtual addresses, thus increasing the recycling of entries as new virtual addresses require translation. This, in turn, means having to go back to the page table structures when references are made to virtual addresses outside the scope of a small page whose translation has been cached. The TLB is a very small cache; thus, large pages make better use of this limited resource.

To take advantage of large pages on systems with more than 2 GB of RAM, Windows maps with large pages the core operating system images (Ntoskrnl.exe and Hal.dll) as well as core operating system data (such as the initial part of non-paged pool and the data structures that describe the state of each physical memory page). Windows also automatically maps I/O space requests (calls by device drivers to MmMapIoSpace) with large pages if the request is of a satisfactorily large page length and alignment. In addition, Windows allows applications to map their images, private memory, and page

file-backed sections with large pages (see the MEM\_LARGE\_PAGES flag on the VirtualAlloc, Virtual-AllocEx, and VirtualAllocExNuma functions). You can also specify other device drivers to be mapped with large pages by adding a multistring registry value LargePageDrivers to the key HKLM\SYSTEM\ CurrentControlSet\Control\Session Manager\Memory Management and specifying the names of the drivers as separately null-terminated strings.

Attempts to allocate large pages may fail after the operating system has been running for an extended period because the physical memory for each large page must occupy a significant number (refer to Table 5-1) of physically contiguous small pages. This extent of physical pages must furthermore begin on a large page boundary. For example, physical pages 0–511 could be used as a large page on an x64 system, as could physical pages 512–1,023, but pages 10–521 could not. Free physical memory does become fragmented as the system runs. This is not a problem for allocations using small pages but can cause large page allocations to fail.

The memory is also always non-pageable because the page file system does not support large pages. Because the memory is non-pageable, the caller is required to have the SeLockMemoryPrivilege to be able to allocate using large pages. Also, the allocated memory is not considered part of the process working set (described in the section "Working sets" later in this chapter); nor are large page allocations subject to job-wide limits on virtual memory usage.

On Windows 10 version 1607 x64 and Server 2016 systems, large pages may also be mapped with huge pages, which are 1 GB in size. This is done automatically if the allocation size requested is larger than 1 GB, but it does not have to be a multiple of 1 GB. For example, an allocation of 1040 MB would result in using one huge page (1024 MB) plus 8 "normal" large pages (16 MB divided by 2 MB).

There is an unfortunate side effect of large pages. Each page (whether huge, large, or small) must be mapped with a single protection that applies to the entire page. This is because hardware memory protection is on a per-page basis. If a large page contains, for example, both read-only code and read/ write data, the page must be marked as read/write, meaning that the code will be writable. As a result, device drivers or other kernel-mode code could, either maliciously or due to a bug, modify what is supposed to be read-only operating system or driver code without causing a memory access violation. If small pages are used to map the operating system's kernel-mode code, the read-only portions of Ntoskrnl.exe and Hal.dll can be mapped as read-only pages. Using small pages does reduce efficiency of address translation, but if a device driver (or other kernel-mode code) attempts to modify a readonly part of the operating system, the system will crash immediately with the exception information pointing at the offending instruction in the driver. If the write were allowed to occur, the system would likely crash later (in a harder-to-diagnose way) when some other component tried to use the corrupted data.

If you suspect you are experiencing kernel code corruptions, enable Driver Verifier (described in Chapter 6, "I/O system"), which will disable the use of large pages.

**Note** The term *page* used in this and later chapters refers to a small page unless otherwise indicated or apparent by context.

# Examining memory usage

The Memory and Process performance-counter categories provide access to most of the details about system and process memory utilization. Throughout this chapter, we'll include references to specific performance counters that contain information related to the component being described. We've included relevant examples and experiments throughout the chapter. One word of caution, however: Different utilities use varying and sometimes inconsistent or confusing names when displaying memory information. The following experiment illustrates this point. (We'll explain the terms used in this example in subsequent sections.)

#### **EXPERIMENT:** Viewing system memory information

The Performance tab in the Windows Task Manager, shown in the following screenshot from a Windows 10 version 1607 system (click the **Memory** tab on the left in the **Performance** tab), displays basic system memory information. This information is a subset of the detailed memory information available through performance counters. It includes data on both physical and virtual memory usage. The table that follows shows the meaning of the memory-related values.

rocesses Performance App	history Startup Users Details Services	
CPU 9% 2.27 GHz	Memory	32.0 GB DDR3
Memory 14,1/31.9 GB (44		
Disk 0 (D:)	60 seconds Memory composition	
Disk 1 (C:)	Supervised Parallelaninger	
Ethernet S: 0.1 R: 1.4 Mbp	In use (Compressed) Available 13.9 GB (100 MB) 17.8 GB	Speed: 1600 MHz Slots used: 4 of 4
Wi-Fi Not connected	Committed Cached 15.6/36.9 GB 18.0 GB	Form factor: SODIMM Hardware reserved: 95.0 MB
Bluetooth Not connected	Paged pool 2.7 GB 1000 MB	

Task Manager Value	Definition
Memory usage histogram	The chart's line height reflects physical memory in use by Windows (not available as a performance counter). The area above the line is equal to the Available value in the bottom section. The total height of the graph is equal to the total value shown at the top right of the graph (31.9 GB in this example) This represents the total RAM usable by the operating system, and does not include BIOS shadow pages, device memory, and so on.
Memory composition	This details the relation between memory that is actively used, standby, modified, and free+zero (all described later in this chapter).

Task Manager Value	Definition
Total physical memory (top right of graph)	This shows the physical memory usable by Windows.
In Use (Compressed)	This is the physical memory currently being used. The amount of compressed physical memory is in parentheses. Hovering over the value shows the amount of memory saved by the compression. (Memory compression is discussed in the section "Memory compression" later in this chapter.)
Cached	This is the sum of the following performance counters in the Memory category: Cache Bytes, Modified Page List Bytes, Standby Cache Core Bytes, Standby Cache Normal Priority Bytes, and Standby Cache Reserve Bytes.
Available	This is the amount of memory that is immediately available for use by the operating system, processes, and drivers. It is equal to the combined size of the standby, free, and zero page lists.
Free	This shows the free and zero-page list bytes. To see this information, hover over the right-most part of the Memory Composition bar (assuming you have enough free memory to hover over it).
Committed	The two numbers shown here are equal to the values in the Committed Bytes and Commit Limit performance counters, respectively.
Paged Pool	This is the total size of the paged pool, including both free and allocated regions.
Non-Paged Pool	This is the total size of the non-paged pool, including both free and allocated regions.

To see the specific usage of the paged and non-paged pool, use the Poolmon utility, described later in this chapter in the "Monitoring pool usage" section.

The Process Explorer tool from Sysinternals can show considerably more data about physical and virtual memory. On its main screen, click the **View** menu, choose **System Information**, and click the **Memory** tab. Here is an example of a display from a 64-bit Windows 10 system. (We will explain most of these counters in the relevant sections later in this chapter.)

Summary CPU	Memory 1/O	GPU			
System Commit					_
16.0 GB					1
Physical Memor	Y				
14.5 GB		1 Mar. 10 (1997) - 10 (1997)			
Commit Charge	I DOWNSRUM TO A DOWN	Kernel Memory (K)	Paging Lists (K) Zeroed	1000	
Current	16,764,368	Paged WS 2,983,276 Paged Virtual 3,086,412	Free	114,372	
Peak	38,700,004 19,304,936	Paged Virtual 3,086,412 Paged Limit 16,642,998,272	Modified ModifiedNoWrite	142,040	
Peak/Limit	49.88%	Nonpaged 1,082,400	Standby	18, 157, 836	
Current/Limit	43.32%	Nonpaged Limit 16,777,216	Priority 0	540	
Physical Memor	V (K)	Paging	Priority 1	208,580	
Total	33,457,124	Page Fault Delta 78,919	Priority 2 Priority 3	126,572	
Available	18,272,208	Page Read Delta 1,543	Priority 4	29.672	
Cache WS	0	Paging File Write Delta 0	Priority 5	17,689,212	
Kernel WS	0	Mapped File Write Delta 0	Priority 6	0	
Driver WS	57,068		Priority 7 PageFileModified	103,036 141,408	
			r ayer semburned	171,700	

Two other Sysinternals tools show extended memory information:

- VMMap This shows the usage of virtual memory within a process to a fine level of detail.
- **RAMMap** This shows detailed physical memory usage.

These tools are featured in experiments found later in this chapter.

Finally, the !vm command in the kernel debugger shows the basic memory-management information available through the memory-related performance counters. This command can be useful if you're looking at a crash dump or hung system. Here's an example of its output from a 64-bit Windows 10 system with 32 GB of RAM:

lkd> !∨m				
Page File: $??\C:\pagef$	file.sys			
Current: 1048576 Kk	o Free Spac	ce:	1034696	Kb
Minimum: 1048576 Kk	Maximum:		4194304	Kb
Page File: \??\C:\swapf	file.sys			
Current: 16384 Kk	o Free Spac	ce:	16376	Kb
Minimum: 16384 Kk	Maximum:		24908388	Kb
No Name for Paging File	2			
Current: 58622948 Kb		ce:	57828340	Kb
Minimum: 58622948 Kb	Maximum:		58622948	Kb
Physical Memory:	8364281		33457124	-
Available Pages:	4627325	(	18509300	Kb)
ResAvail Pages:	7215930		28863720	Kb)
Locked IO Pages:	0		0	Kb)
Free System PTEs:	4295013448		7180053792	Kb)
Modified Pages:	68167		272668	
Modified PF Pages:	68158	(	272632	
Modified No Write Pages		(	0	
NonPagedPool Usage:	495	(	1980	
NonPagedPoolNx Usage:	269858	(	1079432	Kb)
NonPagedPool Max:	4294967296		7179869184	Kb)
PagedPool 0 Usage:	371703	(	1486812	Kb)
PagedPool 1 Usage:	99970	(	399880	
PagedPool 2 Usage:	100021		400084	
PagedPool 3 Usage:	99916	(	399664	Kb)
PagedPool 4 Usage:	99983	(	399932	-
PagedPool Usage:	771593	(	3086372	-
PagedPool Maximum:	4160749568		.6642998272	-
Session Commit: Shared Commit:	12210		48840	-
	344197	(	1376788	Kb)
Special Pool:	0	(	0	Kb)
Shared Process:	19244		76976	Kb)
Pages For MDLs:	419675	(	1678700	Kb)
Pages For AWE:	0	(	0	
NonPagedPool Commit:	270387	(	1081548	
PagedPool Commit:	771593	(	3086372	-
Driver Commit:	24984 100044	(	99936	
Boot Commit:	100044	(	400176	KD)

System PageT	ables:	5948	(	23792	Kb)
VAD/PageTab1	e Bitmaps:	18202	(	72808	Kb)
ProcessLocke	dFilePages:	299	(	1196	Kb)
Pagefile Has	n Pages:	33	(	132	Kb)
Sum System C	ommit:	1986816	(	7947264	Kb)
Total Privat	e:	2126069	(	8504276	Kb)
Misc/Transie	nt Commit:	18422	(	73688	Kb)
Committed pa	ges:	4131307	(	16525228	Kb)
Commit limit	:	9675001	(	38700004	Kb)

The values not in parentheses are in small pages (4 KB). We will describe many of the details of the output of this command throughout this chapter.

### Internal synchronization

Like all other components of the Windows executive, the memory manager is fully reentrant and supports simultaneous execution on multiprocessor systems. That is, it allows two threads to acquire resources in such a way that they don't corrupt each other's data. To accomplish the goal of being fully reentrant, the memory manager uses several different internal synchronization mechanisms, such as spinlocks and interlocked instructions, to control access to its own internal data structures. (Synchronization objects are discussed in Chapter 8, "System mechanisms", in Part 2.)

Some of the system-wide resources to which the memory manager must synchronize access include:

- Dynamically allocated portions of the system virtual address space
- System working sets
- Kernel memory pools
- The list of loaded drivers
- The list of paging files
- Physical memory lists
- Image base randomization address space layout randomization (ASLR) structures
- Each individual entry in the page frame number (PFN) database

Per-process memory-management data structures that require synchronization include the following:

- Working set lock This is held while changes are made to the working set list.
- **Address space lock** This is held whenever the address space is being changed.

Both these locks are implemented using pushlocks. These are described in Chapter 8 in Part 2.

# Services provided by the memory manager

The memory manager provides a set of system services to allocate and free virtual memory, share memory between processes, map files into memory, flush virtual pages to disk, retrieve information about a range of virtual pages, change the protection of virtual pages, and lock the virtual pages into memory.

Like other Windows executive services, memory-management services allow their caller to supply a process handle indicating the particular process whose virtual memory is to be manipulated. The caller can thus manipulate either its own memory or (with proper permissions) the memory of another process. For example, if a process creates a child process, by default it has the right to manipulate the child process's virtual memory. Thereafter, the parent process can allocate, deallocate, read, and write memory on behalf of the child process by calling virtual memory services and passing a handle to the child process as an argument. This feature is used by subsystems to manage the memory of their client processes. It is also essential for implementing debuggers because debuggers must be able to read and write to the memory of the process being debugged.

Most of these services are exposed through the Windows API. As shown in Figure 5-1, the Windows API has four groups of functions for managing memory in applications:

- Virtual API This is the lowest-level API for general memory allocations and deallocations. It always works on page granularity. It is also the most powerful, supporting the full capabilities of the memory manager. Functions include VirtualAlloc, VirtualFree, VirtualProtect, VirtualLock, and others.
- Heap API This provides functions for small allocations (typically less than a page). It uses the Virtual API internally, but adds management on top of it. Heap manager functions include HeapAlloc, HeapFree, HeapCreate, HeapReAlloc and others. The heap manager is discussed in the section "Heap manager" later in this chapter.
- Local/Global APIs These are leftovers from 16-bit Windows and are now implemented using the Heap API.
- Memory-mapped files These functions allow mapping files as memory and/or sharing memory between cooperating processes. Memory-mapped file functions include Create-FileMapping, OpenFileMapping, MapViewOfFile, and others.




FIGURE 5-1 Memory API groups in user mode.

The dotted box shows a typical C/C++ runtime implementation of memory management (functions such as malloc, free, realloc, C++ operator new and delete) using the Heap API. The box is dotted because this implementation is compiler-dependent and certainly not mandatory (although quite common). The C runtime equivalents that are implemented in Ntdll.dll use the Heap API.

The memory manager also provides several services to other kernel-mode components inside the executive as well as to device drivers. These include allocating and deallocating physical memory and locking pages in physical memory for direct memory access (DMA) transfers. These functions begin with the prefix Mm. In addition, although not strictly part of the memory manager, some executive support routines that begin with Ex are used to allocate and deallocate from the system heaps (paged and non-paged pool) as well as to manipulate look-aside lists. We'll touch on these topics later in this chapter in the section "Kernel-mode heaps (system memory pools)."

### Page states and memory allocations

Pages in a process virtual address space are either free, reserved, committed, or shareable. Committed and shareable pages are pages that, when accessed, ultimately translate to valid pages in physical memory. Committed pages are also referred to as private pages. This is because committed pages cannot be shared with other processes, whereas shareable pages can be (but might be in use by only one process).

Private pages are allocated through the Windows VirtualAlloc, VirtualAllocEx, and Virtual-AllocExNuma functions, which lead eventually to the executive in the function NtAllocateVirtual-Memory inside the memory manager. These functions are capable of committing memory as well as reserving memory. Reserving memory means setting aside a range of contiguous virtual addresses for possible future use (such as an array) while consuming negligible system resources, and then committing portions of the reserved space as needed as the application runs. Or, if the size requirements are known in advance, a process can reserve and commit in the same function call. In either case, the resulting committed pages can then be accessed by any thread in the process. Attempting to access free or reserved memory results in an access violation exception because the page isn't mapped to any storage that can resolve the reference.

If committed (private) pages have never been accessed before, they are created at the time of first access as zero-initialized pages (or *demand zero*). Private committed pages may later be automatically written to the paging file by the operating system if required by demand for physical memory. Private refers to the fact that these pages are normally inaccessible to any other process.

**Note** Some functions, such as ReadProcessMemory and WriteProcessMemory, appear to permit cross-process memory access, but these are implemented by running kernel-mode code in the context of the target process. (This is referred to as *attaching to the process*.) They also require that the security descriptor of the target process grant the accessor the PROCESS\_VM\_READ or PROCESS\_VM\_WRITE right, respectively, or that the accessor holds the SeDebugPrivilege, which is by default granted only to members of the administrators group.

Shared pages are usually mapped to a view of a section. This in turn is part or all of a file, but may instead represent a portion of page file space. All shared pages can potentially be shared with other processes. Sections are exposed in the Windows API as file-mapping objects.

When a shared page is first accessed by any process, it will be read in from the associated mapped file unless the section is associated with the paging file, in which case it is created as a zero-initialized page. Later, if it is still resident in physical memory, the second and subsequent processes accessing it can simply use the same page contents that are already in memory. Shared pages might also have been prefetched by the system.

Two upcoming sections of this chapter, "Shared memory and mapped files" and "Section objects," go into much more detail about shared pages. Pages are written to disk through a mechanism called *modified page writing*. This occurs as pages are moved from a process's working set to a system-wide list called the *modified page list*. From there, they are written to disk or remote storage. (Working sets and the modified list are explained later in this chapter.) Mapped file pages can also be written back to their original files on disk with an explicit call to FlushViewOfFile or by the mapped page writer as memory demands dictate.

You can decommit private pages and/or release address space with the VirtualFree or Virtual-FreeEx function. The difference between decommittal and release is similar to the difference between reservation and committal. Decommitted memory is still reserved, but released memory has been freed; it is neither committed nor reserved.

Using the two-step process of reserving and then committing virtual memory defers committing pages—and, thereby, defers adding to the system commit charge described in the next section—until needed, but keeps the convenience of virtual contiguity. Reserving memory is a relatively inexpensive operation because it consumes very little actual memory. All that needs to be updated or constructed is the relatively small internal data structures that represent the state of the process address space. We'll explain these data structures, called *page tables* and *Virtual Address Descriptors (VADs)*, later in this chapter.

One extremely common use for reserving a large space and committing portions of it as needed is the user-mode stack for each thread. When a thread is created, a stack is created by reserving a contiguous portion of the process address space. (The default size is 1 MB but you can override this size with the CreateThread and CreateRemoteThread(Ex) function calls or change it on an executable image basis by using the /STACK linker flag.) By default, the initial page in the stack is committed and the next page is marked as a guard page (which isn't committed) that traps references beyond the end of the committed portion of the stack and expands it.

### **EXPERIMENT:** Reserved versus committed pages

You can use the TestLimit Sysinternals utility to allocate large amounts of reserved or private committed virtual memory. You can then observe the difference via Process Explorer. Follow these steps:

1. Open two command prompt windows.

 Invoke TestLimit in one of the command prompt windows to create a large amount of reserved memory:

Testlimit v5.24 - test Windows limits Copyright (C) 2012-2015 Mark Russinovich Sysinternals - wwww.sysinternals.com

The operation completed successfully.

C:\temp>testlimit -r 1 -c 800

Process ID: 18468

Reserving private bytes 1 MB at a time ... Leaked 800 MB of reserved memory (800 MB total leaked). Lasterror: 0 The operation completed successfully.

3. In the other command prompt window, create a similar amount of committed memory:

C:\temp>testlimit -m 1 -c 800
Testlimit v5.24 - test Windows limits
Copyright (C) 2012-2015 Mark Russinovich
Sysinternals - wwww.sysinternals.com
Process ID: 14528
Leaking private bytes 1 KB at a time ...
Leaked 800 MB of private memory (800 MB total leaked). Lasterror: 0

- 4. Run Task Manager, click the **Details** tab, and add a **Commit Size** column.
- **5.** Find the two instances of TestLimit.exe in the list. They should look something like the following:

File Options View								
Processes Performance	ce App	history Startu	p Users Deta	ils Serv	vices			
Name	PID	Status	User name	CPU	Memory (p	Commit size	Description	1
SystemSettings.exe	19792	Suspended	pavely	00	1,716 K	17,160 K	Settings	
SystemSettingsBr	6816	Running	pavely	00	4,680 K	6,320 K	System Settings Br	
taskhostw.exe	6788	Running	pavely	00	6,184 K	14,508 K	Host Process for	
Taskhostw.exe	11068	Running	pavely	00	2,984 K	6,096 K	Host Process for	
🖓 Taskmgr.exe	15900	Running	pavely	01	15,224 K	18,112 K	Task Manager	
Testlimit.exe	18468	Running	pavely	00	788 K	1,088 K	Test Windows Lim	
Testlimit.exe	14528	Running	pavely	00	784 K	821,876 K	Test Windows Lim	
UevAppMonitor.e	11916	Running	pavely	00	18,092 K	87,944 K	UevAppMonitor.exe	
vcpkgsrv.exe	4448	Running	pavely	00	19,656 K	57,420 K	Microsoft (R) Visu	
Video.UI.exe	10512	Suspended	pavely	00	756 K	11,712 K	Video Application	
vmcompute.exe	5464	Running	SYSTEM	00	1,840 K	2,332 K	Hyper-V Host Co	
vmms.exe	3728	Running	SYSTEM	00	21,108 K	23,432 K	Virtual Machine M	
The later and	1160	Domaine	an an an har		17 104 1	30 400 10	Mal Inda and	•

6. Notice that Task Manager shows the committed size but it has no counters that reveal the reserved memory in the other TestLimit process.

- 7. Open Process Explorer.
- 8. Click the Process Memory tab and enable the Private Bytes and Virtual Size columns.
- 9. Find the two TestLimit.exe processes in the main display:

File Options View Process	Find Use	rs Help			101			-
Process	CPU	Private Bytes	Virtual Size	Working Set	PID	Description	Company Name	1
svchost.exe	-	3,096 K	2,147,540,888 K	11,832 K	3676	Host Process for Windows S	Microsoft Corporation	
svchost.exe		1,104 K	2,147,508,456 K	4,704 K	3752	Host Process for Windows S	Microsoft Corporation	
svchost.exe		1,456 K	2,147,515,644 K	4,296 K	4284	Host Process for Windows S	Microsoft Corporation	
svchost.exe		118,800 K	2,147,906,700 K	10,900 K	5388	Host Process for Windows S	Microsoft Corporation	
svchost.exe	< 0.01	8,908 K	2,148,148,456 K	31,328 K	6692	Host Process for Windows S	Microsoft Corporation	
E System	0.16	136 K	8,768 K	4,848 K	4			
System Idle Process	85.40	0 K	64 K	4 K	0			
System Settings.exe	Susp	17,160 K	2,147,826,124 K	41,268 K	19792	Settings	Microsoft Corporation	11
System Settings Broker.exe	Coloradore	6.320 K	2,147,619,084 K	25,632 K	6816	System Settings Broker	Microsoft Corporation	
taskhostw.exe		14,228 K	2,147,875,212 K	21,560 K	6788	Host Process for Windows T	Microsoft Corporation	
taskhostw.exe		6,096 K	2,147,611,212 K	19,136 K	11068	Host Process for Windows T	Microsoft Corporation	
Taskmgr.exe	0.58	18.032 K	2,147,666,080 K	41,532 K	15900	Task Manager	Microsoft® Windows® Op	
Testlimit.exe		1.088 K	892,752 K	5,552 K	18468	Test Windows Limits	Sysintemals - www.sysinter	
Testlimit.exe		821,876 K	892,752 K	5,548 K	14528	Test Windows Limits	Sysintemals - www.sysinter	
🔀 UevApp Monitor.exe	0.07	87,856 K	843,056 K	24,340 K	11916		Microsoft Corporation	
vcpkgsrv.exe		57,420 K	1,118,960 K	53.328 K	4448	Microsoft (R) Visual C++ Pac	Microsoft Corporation	
Video.Ul.exe	Susp	11,712 K	249,168 K	21,896 K	10512	Video Application	Microsoft Corporation	11
vmcompute.exe	< 0.01	2,332 K	2,147,522,368 K	9,844 K	5464	Hyper-V Host Compute Servi	Microsoft Corporation	
wmms.exe	0.01	23,380 K	2.147.627.928 K	39,804 K	3728	Virtual Machine Managemen	Microsoft Corporation	
VsHub.exe	CONTRACTOR INC.	30,304 K	242,560 K	49,424 K	3160	VsHub.exe	Microsoft Corporation	
WavesSvc64.exe	0.79	5,420 K	84,672 K	13,376 K	10280	Waves MaxAudio Service	Waves Audio Ltd.	
🗩 windbg exe	0.01	13,404 K	2,147,684,140 K	31,408 K	5792	Windows GUI symbolic debu	Microsoft	

10. Notice that the virtual sizes of the two processes are identical, but only one shows a Private Bytes value that is comparable to the Virtual Size value. The large difference in the other TestLimit process (process ID 18468) is due to the reserved memory. You could make the same comparison in Performance Monitor by looking at the Virtual Bytes and Private Bytes counters in the Process category.

## Commit charge and commit limit

On the Performance tab in Task Manager, on the Memory page, there is a Committed label with two numbers underneath it. The memory manager keeps track of private committed memory usage on a global basis, termed *commitment* or *commit charge*. This is the first of the two numbers, which represents the total of all committed virtual memory in the system.

There is a system-wide limit, called the *system commit limit* or simply the *commit limit*, on the amount of committed virtual memory that can exist at any one time. This limit corresponds to the current total size of all paging files plus the amount of RAM that is usable by the operating system. This is the second of the two numbers displayed under the Committed label. The memory manager can increase the commit limit automatically by expanding one or more of the paging files if they are not already at their configured maximum size.

Commit charge and the system commit limit are explained in more detail in the section "Commit charge and the system commit limit" later in this chapter.

# Locking memory

In general, it's better to let the memory manager decide which pages remain in physical memory. However, there might be special circumstances when it might be necessary for an application or device driver to lock pages in physical memory. Pages can be locked in memory in two ways:

- Windows applications can call the VirtualLock function to lock pages in their process working set. Pages locked using this mechanism remain in memory until explicitly unlocked or until the process that locked them terminates. The number of pages a process can lock can't exceed its minimum working set size minus eight pages. If a process needs to lock more pages, it can increase its working set minimum with the SetProcessWorkingSetSizeEx function, discussed later in this chapter in the section "Working set management."
- Device drivers can call the MmProbeAndLockPages, MmLockPagableCodeSection, MmLockPagable-DataSection, or MmLockPagableSectionByHandle kernel-mode functions. Pages locked using this mechanism remain in memory until explicitly unlocked. The last three of these APIs enforce no quota on the number of pages that can be locked in memory because the resident available page charge is obtained when the driver first loads. This ensures that it can never cause a system crash due to overlocking. For the first API, quota charges must be obtained or the API will return a failure status.

## **Allocation granularity**

Windows aligns each region of reserved process address space to begin on an integral boundary defined by the value of the system allocation granularity, which can be retrieved from the Windows Get-SystemInfo or GetNativeSystemInfo functions. This value is 64 KB, a granularity that is used by the memory manager to efficiently allocate metadata (for example, VADs, bitmaps, and so on) to support various process operations. In addition, if support were added for future processors with larger page sizes (for example, up to 64 KB) or virtually indexed caches that require system-wide physical-to-virtual page alignment, the risk of requiring changes to applications that made assumptions about allocation alignment would be reduced.


**Note** Windows kernel-mode code isn't subject to the same restrictions. It can reserve memory on a single-page granularity (although this is not exposed to device drivers for the reasons detailed earlier). This level of granularity is primarily used to pack TEB allocations more densely. Because this mechanism is internal only, this code can easily be changed if a future platform requires different values. Also, for the purposes of supporting 16-bit and MS-DOS applications on x86 systems only, the memory manager provides the MEM\_DOS\_LIM flag to the MapViewOfFilex API, which is used to force the use of single-page granularity.


Finally, when a region of address space is reserved, Windows ensures that the size and base of the region is a multiple of the system page size, whatever that might be. For example, because x86 systems use 4 KB pages, if you tried to reserve a region of memory 18 KB in size, the actual amount reserved on

an x86 system would be 20 KB. If you specified a base address of 3 KB for an 18 KB region, the actual amount reserved would be 24 KB. Note that the VAD for the allocation would then also be rounded to 64 KB alignment/length, thus making the remainder of it inaccessible.

## Shared memory and mapped files

As is true with most modern operating systems, Windows provides a mechanism to share memory among processes and the operating system. *Shared memory* can be defined as memory that is visible to more than one process or that is present in more than one process virtual address space. For example, if two processes use the same DLL, it would make sense to load the referenced code pages for that DLL into physical memory only once and share those pages between all processes that map the DLL, as illustrated in Figure 5-2.





Each process would still maintain its private memory areas to store private data but the DLL code and unmodified data pages could be shared without harm. As we'll explain later, this kind of sharing happens automatically because the code pages in executable images—EXE and DLL files, and several other types like screen savers (SCR), which are essentially DLLs under other names—are mapped as execute-only and writable pages are mapped as copy-on-write. (See the "Copy-on-write" section later in this chapter for more information.)

Figure 5-2 shows two processes, based on different images, that share a DLL mapped just once to physical memory. The images (EXE) code itself is not shared in this case because the two processes run different images. The EXE code would be shared between processes that run the same image, such as two or more processes running Notepad.exe.

The underlying primitives in the memory manager used to implement shared memory are called *section objects*, which are exposed as file-mapping objects in the Windows API. The internal structure and implementation of section objects are described later in this chapter in the section "Section objects."

This fundamental primitive in the memory manager is used to map virtual addresses whether in main memory, in the page file, or in some other file that an application wants to access as if it were in memory. A section can be opened by one process or by many. In other words, section objects don't necessarily equate to shared memory.

A section object can be connected to an open file on disk (called a *mapped file*) or to committed memory (to provide shared memory). Sections mapped to committed memory are called *page-file-backed sections* because the pages are written to the paging file (as opposed to a mapped file) if demands on physical memory require it. (Because Windows can run with no paging file, page-file-backed sections might in fact be "backed" only by physical memory.) As with any other empty page that is made visible to user mode (such as private committed pages), shared committed pages are always zero-filled when they are first accessed to ensure that no sensitive data is ever leaked.

To create a section object, call the Windows CreateFileMapping, CreateFileMappingFromApp, or CreateFileMappingNuma(Ex) function, specifying a previously opened file handle to map it to (or INVALID\_HANDLE\_VALUE for a page-file-backed section) and optionally a name and security descriptor. If the section has a name, other processes can open it with OpenFileMapping or the CreateFileMapping\* functions. Or you can grant access to section objects through either handle inheritance (by specifying that the handle be inheritable when opening or creating the handle) or handle duplication (by using DuplicateHandle). Device drivers can also manipulate section objects with the ZwOpenSection, ZwMapViewOfSection, and ZwUnmapViewOfSection functions.

A section object can refer to files that are much larger than can fit in the address space of a process. (If the paging file backs a section object, sufficient space must exist in the paging file and/or RAM to contain it.) To access a very large section object, a process can map only the portion of the section object that it requires (called a *view* of the section) by calling the MapViewOfFile(Ex), MapViewOfFile-FromApp, or MapViewOfFileExNuma function and then specifying the range to map. Mapping views permits processes to conserve address space because only the views of the section object needed at the time must be mapped into memory.

Windows applications can use mapped files to conveniently perform I/O to files by simply making them appear as data in memory within their address space. User applications aren't the only consumers of section objects; the image loader uses section objects to map executable images, DLLs, and device drivers into memory, and the cache manager uses them to access data in cached files. (For information on how the cache manager integrates with the memory manager, see Chapter 14 in Part 2.) The implementation of shared memory sections, both in terms of address translation and the internal data structures, is explained in the section "Section objects" later in this chapter.

### **EXPERIMENT: Viewing memory-mapped files**

You can list the memory-mapped files in a process by using Process Explorer. To do so, configure the lower pane to show the DLL view. (Open the **View** menu, select **Lower Pane View**, and choose **DLLs**.) Note that this is more than just a list of DLLs—it represents all memory-mapped files in the process address space. Some of these are DLLs, one is the image file (EXE) being run, and additional entries might represent memory-mapped data files.

The following display from Process Explorer shows a WinDbg process using several different memory mappings to access the memory dump file being examined. Like most Windows programs, it (or one of the Windows DLLs it is using) is also using memory mapping to access a Windows data file called Locale.nls, which is part of the internationalization support in Windows.

	1 🗖 🎯 💣	N DLL	Users Help					A		
Process		CPU	Private Bytes	Vitual Size	Working Set	PID Description	Company Name			
E wmcompute ex	0	< 0.01	2,460 K	2,147,523,392 K	10.072 K	5464 Hyper-V Host Compute Servi	Microsoft Corporation			
winconnect.exe		0.04	161.008 K	1.217.132 K	184,664 K	15148 Virtual Machine Connection	Microsoft Corporation			
vmms.exe		0.03	23,808 K	2,147,630,488 K	40,220 K	3728 Virtual Machine Managemen	Microsoft Corporation			
wmwp.exe		1.15	21,200 K	2,147,628,936 K	36.272 K	12316 Virtual Machine Worker Proc.	Microsoft Corporation			
VaHub.exe			30,180 K	241,280 K	49.504 K	3160 VaHub.exe	Microsoft Corporation			
WavesSvc64)	exe	0.71	6,344 K	90,816 K		10280 Waves MaxxAudio Service	Waves Audio Ltd.			
A winamo ave		1.14	JE 669 K	221 BRR M	59.330 K	4772 Winson	NullenB Ion			_
Name	Description		Compa	ny Name	Path		Base	Mapping	Image Base	e
kemel32.dl	Windows NT BASI	E API Clier	nt DLL Microso	ft Corporation	C:\Windows\9	stem32\kemel32.dl	0x7FFCD0F90000	Image	0x7FFCD0F90000	
KemelBase.dl	Windows NT BASI	E API Clier	nt DLL Microso	ft Corporation	C:\Windows\9	stem32\KemelBase.dl	0x7FFCD0870000	Image	0x7FFCD0B70000	1
kext.dl	Debugger Extensio	ins	Microso	tt	C:\Dbg\x64\wi		0x7FFCC3020000	Image	0x7FFCC3020000	
linkinfo.dll	Windows Volume	Tracking	Microso	ft Corporation		/stem32\linkinfo.dll	0x7FFCB8140000	Image	0x7FFCB8140000	
locale nis					C:\Windows\S	stem32\locale.nls	0x1CA86150000	Data	OxC	
MEMORY.DMP					D:\Temp\MEM	ORY.DMP	0x1CA88F40000	Data	0x0	
MEMORY.DMP					D:\Temp\MEM		0x1CA88F50000	Data	GxO	
MEMORY.DMP					D:\Temp\MEM		0x1CA88F60000	Data	0x0	
MEMORY DMP					D:\Temp\MEM		0x1CA88F70000	Data	Ox0	
MEMORY, DMP					D:\Temp\MEM	ORY DMP	0x1CA88F80000	Data	Ox0	
MEMORY.DMP					D:\Temp\MEM		0x1CA890F0000	Data	Ox0	
MEMORY DMP					D:\Temp\MEM	ORY DMP	0x1CA89100000	Data	Ox0	1

You can also search for memory-mapped files by opening the **Find** menu and choosing **Find Handle or DLL** (or pressing **Ctrl+F**). This can be useful when trying to determine which process(es) is using a DLL or a memory-mapped file that you are trying to replace.

## **Protecting memory**

As explained in Chapter 1, "Concepts and tools," Windows provides memory protection so that no user process can inadvertently or deliberately corrupt the address space of another process or the operating system. Windows provides this protection in four primary ways.

- All system-wide data structures and memory pools used by kernel-mode system components can be accessed only while in kernel mode. User-mode threads can't access these pages. If they attempt to do so, the hardware generates a fault, which the memory manager reports to the thread as an access violation.
- Each process has a separate, private address space, protected from access by any thread belonging to another process. Even shared memory is not really an exception to this because each process accesses the shared regions using addresses that are part of its own virtual address space. The only exception is if another process has virtual memory read or write access to the process object (or holds SeDebugPrivilege) and thus can use the ReadProcessMemory or WriteProcessMemory function. Each time a thread references an address, the virtual memory hardware, in concert with the memory manager, intervenes and translates the virtual address into a physical one. By controlling how virtual addresses are translated, Windows can ensure that threads running in one process don't inappropriately access a page belonging to another process.
- In addition to the implicit protection offered by virtual-to-physical address translation, all processors supported by Windows provide some form of hardware-controlled memory protection such as read/write, read-only, and so on. (The exact details of such protection vary according to the processor.) For example, code pages in the address space of a process are marked read-only and are thus protected from modification by user threads. Table 5-2 lists the memory-protection options defined in the Windows API. (See the documentation for the VirtualProtect, Virtual-ProtectEx, VirtualQuery, and VirtualQueryEx functions.)

Attribute	Description
PAGE_NOACCESS	Any attempt to read from, write to, or execute code in this region causes an access violation.
PAGE_READONLY	Any attempt to write to (and on processors with no execute support, execute code in) memory causes an access violation, but reads are permitted.
PAGE_READWRITE	The page is readable and writable but not executable.
PAGE_EXECUTE	Any attempt to write to code in memory in this region causes an access violation, but execution (and read operations on all existing processors) is permitted.
PAGE_EXECUTE_READ*	Any attempt to write to memory in this region causes an access violation, but executes and reads are permitted.
PAGE_EXECUTE_READWRITE*	The page is readable, writable, and executable. Any attempted access will succeed.
PAGE_WRITECOPY	Any attempt to write to memory in this region causes the system to give the process a private copy of the page. On processors with no-execute support, attempts to execute code in memory in this region cause an access violation.
PAGE_EXECUTE_WRITECOPY	Any attempt to write to memory in this region causes the system to give the process a private copy of the page. Reading and executing code in this region is permitted. (No copy is made in this case.)
PAGE_GUARD	Any attempt to read from or write to a guard page raises an EXCEPTION_GUARD_PAGE exception and turns off the guard page status. Guard pages thus act as a one-shot alarm. Note that this flag can be specified with any of the page protections listed in this table except PAGE_NOACCESS.
PAGE_NOCACHE	This uses physical memory that is not cached. This is not recommended for general usage. It is useful for device drivers—for example, mapping a video frame buffer with no caching.
PAGE_WRITECOMBINE	This enables write-combined memory accesses. When enabled, the processor does not cache memory writes (possibly causing significantly more memory traffic than if memory writes were cached), but it does try to aggregate write requests to optimize performance. For example, if multiple writes are made to the same address, only the most recent write might occur. Separate writes to adjacent addresses may be simi- larly collapsed into a single large write. This is not typically used for general applica- tions, but it is useful for device drivers—for example, mapping a video frame buffer as write combined.
PAGE_TARGETS_INVALID and PAGE_TARGETS_NO_UPDATE (Windows 10 and Windows Server 2016)	These values control behavior of Control Flow Guard (CFG) for executable code in these pages. Both constants have the same value but are used in different calls, essentially acting as a toggle. PAGE_TARGETS_INVALID indicates indirect calls should fail CFG and crash the process. PAGE_TARGETS_NO_UPDATE allows VirtualProtect calls that change the page range to allow execution to not update CFG state. See Chapter 7, "Security," for more information on CFG.

\*No execute protection is supported on processors that have the necessary hardware support (for example, all x64 processors) but not in older x86 processors. If unsupported, "execute" translates to "read."

Shared memory section objects have standard Windows access control lists (ACLs) that are checked when processes attempt to open them, thus limiting access of shared memory to those processes with the proper rights. Access control also comes into play when a thread creates a section to contain a mapped file. To create the section, the thread must have at least read access to the underlying file object or the operation will fail.

Once a thread has successfully opened a handle to a section, its actions are still subject to the memory manager and the hardware-based page protections described earlier. A thread can change the page-level protection on virtual pages in a section if the change doesn't violate the permissions

in the ACL for that section object. For example, the memory manager allows a thread to change the pages of a read-only section to have copy-on-write access but not to have read/write access. The copy-on-write access is permitted because it has no effect on other processes sharing the data.

## **Data Execution Prevention**

Data Execution Prevention (DEP), or no-execute (NX) page protection, causes an attempt to transfer control to an instruction in a page marked as "no execute" to generate an access fault. This can prevent certain types of malware from exploiting bugs in the system through the execution of code placed in a data page such as the stack. DEP can also catch poorly written programs that don't correctly set permissions on pages from which they intend to execute code. If an attempt is made in kernel mode to execute code in a page marked as "no execute," the system will crash with the bug check code ATTEMPTED\_EXECUTE\_OF\_NOEXECUTE\_MEMORY (0xFC). (See Chapter 15, "Crash dump analysis," in Part 2 for an explanation of these codes.) If this occurs in user mode, a STATUS\_ACCESS\_VIOLATION (0xC0000005) exception is delivered to the thread attempting the illegal reference. If a process allocates memory that needs to be executable, it must explicitly mark such pages by specifying the PAGE\_EXECUTE, PAGE\_EXECUTE\_READ, PAGE\_EXECUTE\_READWRITE, or PAGE\_EXECUTE\_WRITECOPY flags on the page-granularity memory-allocation functions.

On 32-bit x86 systems that support DEP, bit 63 in the page table entry (PTE) is used to mark a page as non-executable. Therefore, the DEP feature is available only when the processor is running in Physical Address Extension (PAE) mode, without which page table entries are only 32 bits wide. (See the section "x86 virtual address translation" later in this chapter.) Thus, support for hardware DEP on 32-bit systems requires loading the PAE kernel (%SystemRoot%\System32\Ntkrnlpa.exe), which currently is the only supported kernel on x86 systems.

On ARM systems, DEP is set to AlwaysOn.

On 64-bit versions of Windows, execution protection is always applied to all 64-bit processes and device drivers and can be disabled only by setting the nx BCD option to AlwaysOff. Execution protection for 32-bit programs depends on system configuration settings, described shortly. On 64-bit Windows, execution protection is applied to thread stacks (both user and kernel mode), user-mode pages not specifically marked as executable, the kernel paged pool, and the kernel session pool. For a description of kernel memory pools, see the section "Kernel-mode heaps (system memory pools)." However, on 32-bit Windows, execution protection is applied only to thread stacks and user-mode pages, not to the paged pool and session pool.

The application of execution protection for 32-bit processes depends on the value of the BCD nx option. To change the settings, open the **Data Execution Prevention** tab in the Performance Options dialog box (see Figure 5-3). (To open this dialog box, right-click **Computer**, select **Properties**, click **Advanced System Settings**, and choose **Performance Settings**.) When you configure no-execute protection in the Performance Options dialog box, the BCD nx option is set to the appropriate value. Table 5-3 lists the variations of the values and how they correspond to the Data Execution Prevention tab. The registry lists 32-bit applications that are excluded from execution protection under the HKLM\ SOFTWARE\Microsoft\Windows NT\CurrentVersion\AppCompatFlags\Layers key, with the value name being the full path of the executable and the data set to Di sab1eNXShowUI.

ual Effects	Advanced	Data Execution	Prevention	
		tion Prevention om viruses and <u>k?</u>		
Turn on	DEP for ess	ential Windows	programs and	d services only
) Turn on	DEP for all p	programs and s	ervices except	those I select:
				December 1
		_	Add.u.	Remove
four comp	uter's proce	ssor supports h		1
/our comp	uter's proce	ssor supports h		1
/our comp	uter's proce	ssor supports h		1

FIGURE 5-3 Data Execution Prevention tab settings.

BCD nx Value	Option on Data Execution Prevention Tab	Explanation
OptIn	Turn on DEP for Essential Windows Programs and Services Only	This enables DEP for core Windows system images. It enables 32-bit processes to dynamically configure DEP for their life- time.
OptOut	Turn on DEP for All Programs and Services Except Those I Select	This enables DEP for all executables except those specified. It enables 32-bit processes to dynamically configure DEP for their lifetime. It also enables system compatibility fixes for DEP.
Always0n	There is no dialog box option for this setting	This enables DEP for all components with no ability to exclude certain applications. It disables dynamic configuration for 32-bit processes and disables system compatibility fixes.
Always0ff	There is no dialog box option for this setting	This disables DEP (not recommended). It also disables dynamic configuration for 32-bit processes.

TABLE 5-3 BCD nx values

On Windows client versions (both 64-bit and 32-bit), execution protection for 32-bit processes is configured by default to apply only to core Windows operating system executables. That is, the nx BCD option is set to OptIn. This is to avoid breaking 32-bit applications that might rely on being able to execute code in pages not specifically marked as executable, such as self-extracting or packed applications. On Windows server systems, execution protection for 32-bit applications is configured by default to apply to all 32-bit programs. That is, the nx BCD option is set to OptOut.

Even if you force DEP to be enabled, there are still other methods through which applications can disable DEP for their own images. For example, regardless of which execution-protection options are enabled, the image loader will verify the signature of the executable against known copy-protection

mechanisms (such as SafeDisc and SecuROM) and disable execution protection to provide compatibility with older copy-protected software such as computer games. (See Chapter 3 for more information about the image loader.)

### **EXPERIMENT:** Looking at DEP protection on processes

Process Explorer can show you the current DEP status for all the processes on your system, including whether the process is opted in or benefiting from permanent protection. To look at the DEP status for processes, right-click any column in the process tree, choose **Select Columns**, and then select **DEP Status** on the **Process Image** tab. There are three possible values:

- DEP (permanent) This means the process has enabled DEP because it is a "necessary Windows program or service."
- DEP This means the process opted in to DEP. This may be due to a system-wide policy to opt in to all 32-bit processes, because of an API call such as SetProcessDEPPolicy, or because the /NXCOMPAT linker flag was set when the image was built.
- **Nothing** If the column displays no information for this process, DEP is disabled because of either a system-wide policy or an explicit API call or shim.

Additionally, to provide compatibility with older versions of the Active Template Library (ATL) framework (version 7.1 or earlier), the Windows kernel provides an ATL thunk emulation environment. This environment detects ATL thunk code sequences that have caused the DEP exception and emulates the expected operation. Application developers can request that ATL thunk emulation not be applied by using the latest Microsoft C++ compiler and specifying the /NXCOMPAT flag (which sets the IMAGE\_DLL-CHARACTERISTICS\_NX\_COMPAT flag in the PE header), which tells the system that the executable fully supports DEP. Note that ATL thunk emulation is permanently disabled if the A1waysOn value is set.

Finally, if the system is in OptIn or OptOut mode and executing a 32-bit process, the SetProcess-DEPPolicy function allows a process to dynamically disable DEP or to permanently enable it. When it is enabled through this API, DEP cannot be disabled programmatically for the lifetime of the process. This function can also be used to dynamically disable ATL thunk emulation if the image wasn't compiled with the /NXCOMPAT flag. On 64-bit processes or systems booted with AlwaysOff or AlwaysOn, the function always returns a failure. The GetProcessDEPPolicy function returns the 32-bit per-process DEP policy (it fails on 64-bit systems, where the policy is always the same—enabled), while GetSystem-DEPPolicy can be used to return a value corresponding to the policies in Table 5-3.

### Copy-on-write

Copy-on-write page protection is an optimization the memory manager uses to conserve physical memory. When a process maps a copy-on-write view of a section object that contains read/write pages, the memory manager delays the copying of pages until the page is written to instead of making a process private copy at the time the view is mapped. For example, in Figure 5-4, two processes are sharing three pages, each marked copy-on-write, but neither of the two processes has attempted to modify any data on the pages.





FIGURE 5-4 The "before" of copy-on-write.

If a thread in either process writes to a page, a memory-management fault is generated. The memory manager sees that the write is to a copy-on-write page, so instead of reporting the fault as an access violation, it does the following:

- 1. It allocates a new read/write page in physical memory.
- 2. It copies the contents of the original page to the new page.
- **3.** It updates the corresponding page-mapping information (explained later in this chapter) in this process to point to the new location.
- 4. It dismisses the exception, causing the instruction that generated the fault to be re-executed.

This time, the write operation succeeds. However, as shown in Figure 5-5, the newly copied page is now private to the process that did the writing and isn't visible to the other process still sharing the copy-on-write page. Each new process that writes to that same shared page will also get its own private copy.



**FIGURE 5-5** The "after" of copy-on-write.

One application of copy-on-write is to implement breakpoint support in debuggers. For example, by default, code pages start out as execute-only. If a programmer sets a breakpoint while debugging

a program, however, the debugger must add a breakpoint instruction to the code. It does this by first changing the protection on the page to PAGE\_EXECUTE\_READWRITE and then changing the instruction stream. Because the code page is part of a mapped section, the memory manager creates a private copy for the process with the breakpoint set, while other processes continue using the unmodified code page.

Copy-on-write is one example of an evaluation technique called *lazy evaluation* that the memory manager uses as often as possible. Lazy-evaluation algorithms avoid performing an expensive operation until absolutely required. If the operation is never required, no time is wasted on it.

To examine the rate of copy-on-write faults, see the Write Copies/Sec performance counter in the Memory category of the Performance Monitor tool.

## **Address Windowing Extensions**

Although the 32-bit version of Windows can support up to 64 GB of physical memory (refer to Table 2-2), each 32-bit user process has only a 2 GB virtual address space by default. (You can configure this to up to 3 GB when using the increaseuserva BCD option, described in the upcoming section "Virtual address space layouts.") An application that needs to make more than 2 GB (or 3 GB) of data easily available in a single process could do so via file mapping, remapping a part of its address space into various portions of a large file. However, significant paging would be involved upon each remap.

For higher performance (and more fine-grained control), Windows provides a set of functions called *Address Windowing Extensions (AWE)*. These functions allow a process to allocate more physical memory than can be represented in its virtual address space. It then can access the physical memory by mapping a portion of its virtual address space into selected portions of the physical memory at various times.

You allocate and use memory via the AWE functions in three steps:

- You allocate the physical memory to be used. The application uses the Windows functions AllocateUserPhysicalPages or AllocateUserPhysicalPagesNuma. (These require the SeLockMemoryPrivilege.)
- 2. You create one or more regions of virtual address space to act as windows to map views of the physical memory. The application uses the Win32 VirtualAlloc, VirtualAllocEx, or Virtual-AllocExNuma function with the MEM\_PHYSICAL flag.
- 3. Steps 1 and 2 are, generally speaking, initialization steps. To actually use the memory, the application uses MapUserPhysicalPages or MapUserPhysicalPagesScatter to map a portion of the physical region allocated in step 1 into one of the virtual regions, or windows, allocated in step 2.

Figure 5-6 shows an example. The application has created a 256 MB window in its address space and has allocated 4 GB of physical memory. It can then use MapUserPhysicalPages or MapUserPhysical-PagesScatter to access any portion of the physical memory by mapping the desired portion of memory into the 256 MB window. The size of the application's virtual address space window determines the amount of physical memory the application can access with any given mapping. To access another portion of the allocated RAM, the application can simply remap the area.




FIGURE 5-6 Using AWE to map physical memory.

The AWE functions exist on all editions of Windows and are usable regardless of how much physical memory a system has. However, AWE is most useful on 32-bit systems with more than 2 GB of physical memory because it provides a way for a 32-bit process to access more RAM than its virtual address space would otherwise allow. Another use is for security purposes. Because AWE memory is never paged out, the data in AWE memory can never have a copy in the paging file that someone could examine by rebooting into an alternate operating system. (VirtualLock provides the same guarantee for pages in general.)

Finally, there are some restrictions on memory allocated and mapped by the AWE functions:

- Pages can't be shared between processes.
- The same physical page can't be mapped to more than one virtual address.
- Page protection is limited to read/write, read-only, and no access.

AWE is less useful on 64 bit Windows systems because these systems support 128 TB of virtual address space per process, while allowing a maximum of only 24 TB of RAM (on Windows Server 2016 systems). Therefore, AWE is not necessary to allow an application to use more RAM than it has virtual address space; the amount of RAM on the system will always be smaller than the process virtual address space. AWE remains useful, however, for setting up non-pageable regions of a process address space. It provides finer granularity than the file-mapping APIs. (The system page size is 4 KB rather than 64 KB.)

For a description of the page table data structures used to map memory on systems with more than 4 GB of physical memory, see the section "x86 virtual address translation."

## Kernel-mode heaps (system memory pools)

At system initialization, the memory manager creates two dynamically sized memory pools, or heaps, that most kernel-mode components use to allocate system memory:

- Non-paged pool This consists of ranges of system virtual addresses that are guaranteed to reside in physical memory at all times. Thus, they can be accessed at any time without incurring a page fault—meaning they can be accessed from any IRQL. One of the reasons a non-paged pool is required is because page faults can't be satisfied at DPC/dispatch level or above. Therefore, any code and data that might execute or be accessed at or above DPC/dispatch level must be in non-pageable memory.
- Paged pool This is a region of virtual memory in system space that can be paged into and out of the system. Device drivers that don't need to access the memory from DPC/dispatch level or above can use paged pool. It is accessible from any process context.

Both memory pools are in the system part of the address space and are mapped in the virtual address space of every process. The executive provides routines to allocate and deallocate from these pools. For information on these routines, see the functions that start with ExAllocatePool, ExAllocatePoolWithTag, and ExFreePool in the Windows Development Kit (WDK) documentation.

Systems start with four paged pools, which are combined to make the overall system paged pool, and two non-paged pools. More are created—as many as 64—depending on the number of NUMA nodes on the system. Having more than one paged pool reduces the frequency of system code block-ing on simultaneous calls to pool routines. Additionally, the different pools created are mapped across different virtual address ranges that correspond to different NUMA nodes on the system. The different data structures, such as the large page look-aside lists, to describe pool allocations are also mapped across different NUMA nodes.

In addition to the paged and non-paged pools, there are a few other pools with special attributes or uses. For example, there is a pool region in session space that is used for data that is common to all processes in the session. Allocations from another pool, called *special pool*, are surrounded by pages marked as "no access" to help isolate problems in code that accesses memory before or after the region of pool it allocated.

### **Pool sizes**

A non-paged pool starts at an initial size based on the amount of physical memory on the system and then grows as needed. For a non-paged pool, the initial size is 3 percent of system RAM. If this is less than 40 MB, the system will instead use 40 MB as long as 10 percent of RAM results in more than 40 MB. Otherwise, 10 percent of RAM is chosen as a minimum. Windows dynamically chooses the maximum size of the pools and allows a given pool to grow from its initial size to the maximums shown in Table 5-4.

Pool Type	Maximum on 32-Bit Systems	Maximum on 64 bit Systems (Windows 8, Server 2012)	Maximum on 64-Bit Systems (Windows 8.1, 10, Server 2012 R2, 2016)
Non-paged	75 percent of physical memory or 2 GB, whichever is smaller	75 percent of physical memory or 128 GB, whichever is smaller	16 TB
Paged	2 GB	384 GB	15.5 TB

TABLE 5-4	Maximum pool sizes

Four of these computed sizes are stored in kernel variables in Windows 8.x and Server 2012/R2. Three of these are exposed as performance counters and one is computed only as a performance counter value. Windows 10 and Server 2016 moved the global variables into fields in a global memory management structure (MI\_SYSTEM\_INFORMATION) named MiState. Within this lies a variable named Vs (of type \_MI\_VISIBLE\_STATE) where this information resides. The global variable MiVisibleState also points to that Vs member. These variables and counters are listed in Table 5-5.

Kernel Variable	Performance Counter	Description
MmSizeOfNonPagedPoolInBytes	Memory: Pool non- paged bytes	This is the size of the initial non-paged pool. It can be reduced or enlarged automatically by the system if memory demands dictate. The kernel variable will not show these changes, but the performance counter will.
MmMaximumNonPagedPoolInBytes (Windows 8.x and Server 2012/R2)	Not available	This is the maximum size of a non-paged pool.
MiVisibleState->MaximumNonPagePool InBytes (Windows10 and Server 2016)	Not available	This is the maximum size of a non-paged pool.
Not available	Memory: Pool paged bytes	This is the current total virtual size of paged pool.
WorkingSetSize (number of pages) in the MmPagedPoolWs struct (type MMSUPPORT) (Windows 8.x and Server 2012/R2)	Memory: Pool paged resident bytes	This is the current physical (resident) size of paged pool.
MmSizeOfPagedPoolInBytes (Windows 8.x and Server 2012/R2)	Not available	This is the maximum (virtual) size of a paged pool.
MiState.Vs.SizeOfPagedPoolIn Bytes (Windows 10 and Server 2016)	Not available	This is the maximum (virtual) size of a paged pool.

TABLE 5-5	System pool size variables and performance counters
-----------	---

### **EXPERIMENT:** Determining the maximum pool sizes

You can obtain the pool maximums by using either Process Explorer or live kernel debugging (explained in Chapter 1). To view pool maximums with Process Explorer, select the **View** menu, choose **System Information**, and then click the **Memory** tab. The pool limits are displayed in the Kernel Memory section, as shown here:

lummary OPU	Memory I/D	GPU			
System Commit					
all and the second					_
16.0 GB	21				
Physical Nemon					
F	1				_
-					
14.5 GB					
Commit Charge		Kernel Menory (K)	Paging Lists (K)		
Current	35,754,368	Paged WS 2,983,276	Zeroed Pree	114,372	
Limit	38,700,004	Paged Virtual 3,086,412	Hodified	142,040	
Peak	29,304,936	Paged Limit 15,642,998,272	ModifedNoWrite	0	
Peak@mit	49,88%	Nonpaged 1,082,400		18,157,836	
Current,Limit	43.32%	Nonpaged Limit 16,777,215	Priority 0	540	
Physical Memor	× 00	Paging	Priority 1	208,580	
Total	33,457,124	Page Fault Delta 78,919	Priority Z	126,572	
Available	18,272,208	Page Read Delta 1,543	Priority 3 Priority 4	224 29.672	
Cache WS	0	Paging File Write Delta 0		17.689.212	
Kernel WS	0	Mapped File Write Delta 0	Priority 6	0	
Driver WS	\$7,068	Line and the second second second	Priority 7	103,036	
			PageFileModified	141,408	

÷	÷	÷	÷
-	_	_	
Ξ	=	=	
- 2	_	_	=
	+ 100	⋕	≣

**Note** For Process Explorer to retrieve this information, it must have access to the symbols for the kernel running on your system. For a description of how to configure Process Explorer to use symbols, see the experiment "Viewing process details with Process Explorer" in Chapter 1.

To view the same information by using the kernel debugger, you can use the 1 m command as was shown previously in this chapter.

# Monitoring pool usage

The Memory performance counter object has separate counters for the non-paged pool and paged pool (both virtual and physical). In addition, the Poolmon utility (in the WDK Tools directory) allows you to monitor the detailed usage of non-paged and paged pool. When you run Poolmon, you should see a display like the one shown in Figure 5-7.

		7124K Avail					InRam Krnl:369				^
	mmit:25130464K Limit:34505700K Peak:25253232K stem pool information						Pool N:174	7584K P:45796	580K		
		Allocs				Diff			Per Alloc		
Tag	Туре	Allocs		Frees		DITT	Bytes		Per Alloc		
-UMD	Nonp		9)	1 (	0)		144 (	0)	48		
.UMD	Nonp		0)	3 (	0)		128 (	Ø)	128		
2920	Nonp		0)	0 (	0)		128 (	0)	128		
2UuQ	Nonp	1967 (	0)	1963 (	<b>0</b> )		16384 (	0)	4096		
3DMN	Paged		0)	9 (	0)		144 (	0)	144		
4321	Nonp		0)	1 (	0)		0 (	0)			
8042	Nonp	60 (	0)	56 (	0)		4048 (	0)	1012		
8042	Paged	12 (	0)	12 (	0)		0 (	0)			
9472	Nonp	17 (	0)	13 (	0)		91888 (	0)	22972		
@CP	Nonp		0)	5 (	0)		160 (	0)	80		
@GM2	Nonp	463473 (	0)	461901 (	0)	1572	2364288 (	0)	1504		
@GM6	Nonp	420521 (	0)	418374 (	0)	2147	3229088 (	0)	1504		
@GM7	Nonp		0)	21 (	0)		0 (	0)			
@GM8	Nonp		0)	21 (	0)		0 (	<b>0</b> )			
@GMM	Nonp	14441 (	0)	14316 (	0)	125	128944 (	0)	1031		
@GMa	Nonp		0)	0 (	0)		9024 (	0)	1504		
@GMb	Nonp	54 (			0)		1504 (	0)	1504		
@GMe	Nonp			9 (	0)		7520 (	0)	1504		
@GMf	Nonp	3478 (	0)	3398 (	0)	80	120320 (	0)	1504		
@GMg	Nonp		0)	9 (	0)		1504 (	0)	1504		
@GMm	Nonp		0)	Θ (	0)		1504 (	9)	1504		
	Nonp				0)		0 (	0)			
@GMo	Nonp	16 (	0)	Θ (	0)	16	24064 (	0)	1504		
@GMp	Nonp	6999 (	0)	6460 (	0)	539	810656 (	0)	1504		
@GMa	Nonp		(9)	1 (	0)		0 (	0)	0		×



Any highlighted lines you might see represent changes to the display. (You can disable the highlighting feature by typing / while running Poolmon; type / again to re-enable highlighting.) Type ? while Poolmon is running to bring up its help screen. You can configure which pools you want to monitor (paged, non-paged, or both) and the sort order. For example, by pressing the **P** key until only nonpaged allocations are shown, and then the **D** key to sort by the Diff (differences) column, you can find out what kind of structures are most numerous in non-paged pool. Also, the command-line options are shown, which allow you to monitor specific tags (or every tag but one tag). For example, the command poolmon -iCM will monitor only CM tags (allocations from the configuration manager, which manages the registry). The columns have the meanings shown in Table 5-6.

#### TABLE 5-6 Poolmon columns

Column	Explanation
Tag	This is a four-byte tag given to the pool allocation.
Туре	This is the pool type (paged or non-paged).
Allocs	This is a count of all allocations. The number in parentheses shows the difference in the Allocs column since the last update.
Frees	This is the count of all frees. The number in parentheses shows the difference in the Frees column since the last update.
Diff	This is the count of allocations minus frees.
Bytes	This is the total bytes consumed by this tag. The number in parentheses shows the difference in the Bytes column since the last update.
Per Alloc	This is the size in bytes of a single instance of this tag.

For a description of the meaning of the pool tags used by Windows, see the Pooltag.txt file in the Triage subdirectory where the Debugging tools for Windows are located. Because third-party devicedriver pool tags are not listed in this file, you can use the –c switch on the 32-bit version of Poolmon that comes with the WDK to generate a local pool tag file (Localtag.txt). This file will contain pool tags used by drivers found on your system, including third-party drivers. (Note that if a device-driver binary has been deleted after it was loaded, its pool tags will not be recognized.)

Alternatively, you can search the device drivers on your system for a pool tag by using the Strings.exe tool from Sysinternals. For example, the following command displays drivers that contain the string "abcd":

```
strings %SYSTEMROOT%\system32\drivers\*.sys | findstr /i "abcd"
```

Device drivers do not necessarily have to be located in %SystemRoot%\System32\Drivers. They can be in any folder. To list the full path of all loaded drivers, follow these steps:

- 1. Open the Start menu and type Msinfo32 (System Information should appear).
- 2. Run System Information.
- 3. Select Software Environment.
- Choose System Drivers. If a device driver has been loaded and then deleted from the system, it will not be listed here.

An alternative way to view pool usage by device driver is to enable the pool-tracking feature of Driver Verifier, explained in Chapter 6. While this makes the mapping from pool tag to device driver unnecessary, it does require a reboot (to enable Driver Verifier on the desired drivers). After rebooting with pool tracking enabled, you can either run the graphical Driver Verifier Manager (%SystemRoot%\System32\ Verifier.exe) or use the Verifier /Log command to send the pool-usage information to a file.

Finally, you can view pool usage with the kernel debugger !poolused command. The !poolused 2 command shows non-paged pool usage sorted by pool tag using the most amount of pool. The !poolused 4 command lists paged-pool usage, again sorted by pool tag using the most amount of pool. The following example shows the partial output from these two commands:

lkd> !poolused 2

. . . . . . .

Sorting by NonPaged Pool Consumed

	No	onPaged		Paged	
Tag	Allocs	Used	Allocs	Used	
File	626381	260524032	0	0	File objects
Ntfx	733204	227105872	0	0	General Allocation , Binary: ntfs.sys
MmCa	513713	148086336	0	0	Mm control areas for mapped files , Binary: nt!mm
FMs1	732490	140638080	0	0	STREAM_LIST_CTRL structure , Binary: fltmgr.sys
CcSc	104420	56804480	0	0	Cache Manager Shared Cache Map , Binary: nt!cc
SQSF	283749	45409984	0	0	UNKNOWN pooltag 'SQSF', please update pooltag.txt
FMfz	382318	42819616	0	0	<pre>FILE_LIST_CTRL structure , Binary: fltmgr.sys</pre>
FMsc	36130	32950560	0	0	SECTION_CONTEXT structure , Binary: fltmgr.sys
EtwB	517	31297568	107	105119744	Etw Buffer , Binary: nt!etw
DFmF	382318	30585440	382318	91756320	UNKNOWN pooltag 'DFmF', please update pooltag.txt
DFmE	382318	18351264	0	0	UNKNOWN pooltag 'DFmE', please update pooltag.txt
FSfc	382318	18351264	0	0	Unrecoginzed File System Run Time allocations (update
smNp	4295	17592320	0	0	pooltag.w) , Binary: nt!fsrtl ReadyBoost store node pool allocations , Binary: nt!store or rdyboost.sys
Thre	5780	12837376	0	0	Thread objects , Binary: nt!ps
Pool	8	12834368	0	0	Pool tables, etc.

### **EXPERIMENT:** Troubleshooting a pool leak

In this experiment, you will fix a real paged pool leak on your system so that you can use the techniques described in the previous section to track down the leak. The leak will be generated by the Notmyfault tool from Sysinternals. Follow these steps:

- 1. Run Notmyfault.exe for your OS bitness (for example, the 64 bit on a 64-bit system).
- 2. Notmyfault.exe loads the Myfault.sys device driver and presents a Not My Fault dialog box with the Crash tab selected. Click the **Leak** tab. It should look something like this:

Crash         Hang         Leak           Copyright © 2002-2016 Mark Russinovich Contributions by Daniel Pearson         Options           Options         Leaking nonpaged or paged pool memory can cause the system to hang or crash or for applications to fail. Allocated memory is released when the application doses.           Leak/second:         IODI KB           Status         Paged pool leaking is currently inactive.           Nonpaged pool leaking is currently inactive.	×	ault
Contributions by Daniel Pearson Options Leaking nonpaged or paged pool memory can cause the system to hang or crash or for applications to fail, Allocated memory is released when the application closes. Leak/second: KB Status Paged pool leaking is currently inactive.		Hang Leak
Leaking nonpaged or paged pool memory can cause the system to hang or crash or for applications to fail. Allocated memory is released when the application doses. Leak/second: KB Status Paged pool leaking is currently inactive.		
system to hang or crash or for applications to fail. Allocated memory is released when the application closes. Leak/second: Status Paged pool leaking is currently inactive.		ons
Paged pool leaking is currently inactive.		em to hang or crash or for applications to fail. Allocate ory is released when the application closes.
		12 Sauted Marks (10) - 6250
Leak Paged Leak Nonpaged		Leak Paged Leak Nonpage
Cancel	4	670

- 3. Ensure that the Leak/Second setting is set to 1000 KB.
- 4. Click the Leak Paged button. This causes Notmyfault to begin sending requests to the Myfault device driver to allocate paged pool. Notmyfault will continue sending requests until you click the Stop Paged button. Paged pool is not normally released even when you close a program that has caused it to occur (by interacting with a buggy device driver). The pool is permanently leaked until you reboot the system. However, to make testing easier, the Myfault device driver detects that the process was closed and frees its allocations.
- 5. While the pool is leaking, open Task Manager, click the **Performance** tab, and select the **Memory** label. Notice the **Paged Pool** value climbing. You can also check this with Process Explorer's System Information display (select the **View** menu, choose **System Information**, and click the **Memory** tab).
- **6.** To determine which pool tag is leaking, run Poolmon and press the **B** key to sort by the number of bytes.
- **7.** Press **P** twice so that Poolmon shows only paged pool. Notice the Leak pool tag climbing to the top of the list. (Poolmon shows changes to pool allocations by highlighting the lines that change.)
- 8. Click the Stop Paged button so that you don't exhaust paged pool on your system.
- 9. Using the technique described in the previous section, run Strings (from Sysinternals) to look for driver binaries that contain the Leak pool tag. This should display a match on the file Myfault.sys, thus confirming it as the driver using the Leak pool tag.

```
Strings %SystemRoot%\system32\drivers\*.sys | findstr Leak
```

## Look-aside lists

Windows provides a fast memory-allocation mechanism called *look-aside lists*. The basic difference between pools and look-aside lists is that while general pool allocations can vary in size, a look-aside list contains only fixed-sized blocks. Although the general pools are more flexible in terms of what they can supply, look-aside lists are faster because they don't use any spinlocks.

Executive components and device drivers can create look-aside lists that match the size of frequently allocated data structures by using the ExInitializeNPagedLookasideList (for non-paged allocations) and ExInitializePagedLookasideList (for paged allocation) functions, as documented in the WDK. To minimize the overhead of multiprocessor synchronization, several executive subsystems such as the I/O manager, cache manager, and object manager create separate look-aside lists for each processor for their frequently accessed data structures. The executive also creates a general per-processor paged and non-paged look-aside list for small allocations (256 bytes or less).

If a look-aside list is empty (as it is when it's first created), the system must allocate from the paged or non-paged pool. But if it contains a freed block, the allocation can be satisfied very quickly. (The list grows as blocks are returned to it.) The pool-allocation routines automatically tune the number of freed buffers that look-aside lists store according to how often a device driver or executive subsystem allocates from the list. The more frequent the allocations, the more blocks are stored on a list. Lookaside lists are automatically reduced in size if they aren't being allocated from. (This check happens once per second when the balance set manager system thread wakes up and calls the ExAdjustLookasideDepth function.)

### **EXPERIMENT:** Viewing the system look-aside lists

You can display the contents and sizes of the various system look-aside lists with the kernel debugger !lookaside command. The following excerpt is from the output of this command:

lkd> !lookaside

Lookaside "nt!CcTwi	lightL	ookasideL	ist" @ Oxfff	ff80	0c6f54300	Tag(hex):	0x6b576343	"CcWk"
Туре	=	0200	NonPagedPoo	o1Nx				
Current Depth	=	0	Max Depth	=	4			
Size	=	128	Max Alloc	=	512			
AllocateMisses	=	728323	FreeMisses	=	728271			
TotalAllocates	=	1030842	TotalFrees	=	1030766			
Hit Rate	=	29%	Hit Rate	=	29%			
Lookaside "nt!IopSm	allIrp	LookasideL	ist" @ Oxffi	ff80	0c6f54500	Tag(hex):	0x73707249	"Irps"
Lookaside "nt!IopSm Type	allIrp =		ist" @ Oxff1 NonPagedPoo		0c6f54500	Tag(hex):	0x73707249	"Irps"
•	=	0200		olNx	0c6f54500 4	Tag(hex):	0x73707249	"Irps"
Туре	=	0200 0	NonPagedPoo	NXTC =	4	Tag(hex):	0x73707249	"Irps"
Type Current Depth	= =	0200 0 280	NonPagedPoo Max Depth	= =	4	Tag(hex):	0x73707249	"Irps"
Type Current Depth Size	=	0200 0 280 44683	NonPagedPoo Max Depth Max Alloc	= = =	4 1120 43576	Tag(hex):	0x73707249	"Irps"
Type Current Depth Size AllocateMisses	=	0200 0 280 44683 232027	NonPagedPoo Max Depth Max Alloc FreeMisses	01Nx = = = =	4 1120 43576	Tag(hex):	0x73707249	"Irps"

Lookaside "nt!IopLargeIrpLookasideList" @ 0xfffff800c6f54600 Tag(hex): 0x6c707249 "Irpl" Type = 0200 NonPagedPoolNx Current Depth = 0 Max Depth = 4 Size = 1216 Max Alloc = 4864 AllocateMisses = 143708 FreeMisses = 142551 TotalAllocates = 317297 TotalFrees = 316131 Hit Rate = 54% Hit Rate = 54% ... Total NonPaged currently allocated for above lists = 0 Total NonPaged potential for above lists = 13232 Total Paged currently allocated for above lists = 0 Total Paged currently allocated for above lists = 0 Total Paged potential for above lists = 0

### Heap manager

Most applications allocate smaller blocks than the 64-KB minimum allocation granularity possible using page-granularity functions such as VirtualAlloc. Allocating such a large area for relatively small allocations is not optimal from a memory usage and performance standpoint. To address this, Windows provides a component called the *heap manager*, which manages allocations inside larger memory areas reserved using the page-granularity memory-allocation functions. The allocation granularity in the heap manager is relatively small: 8 bytes on 32-bit systems, and 16 bytes on 64-bit systems. The heap manager has been designed to optimize memory usage and performance in the case of these smaller allocations.

The heap manager exists in two places: Ntdll.dll and Ntoskrnl.exe. The subsystem APIs (such as the Windows heap APIs) call the functions in Ntdll.dll, and various executive components and device drivers call the functions in Ntoskrnl.exe. Its native interfaces (prefixed with Rt1) are available only for use in internal Windows components or kernel-mode device drivers. The documented Windows API interfaces to the heap (prefixed with Heap) are forwarders to the native functions in Ntdll.dll. In addition, legacy APIs (prefixed with either Local or Global) are provided to support older Windows applications. These also internally call the heap manager, using some of its specialized interfaces to support legacy behavior. The most common Windows heap functions are:

- HeapCreate or HeapDestroy These create or delete, respectively, a heap. The initial reserved and committed size can be specified at creation.
- HeapAlloc This allocates a heap block. It is forwarded to RtlAllocateHeap in Ntdll.dll.
- HeapFree This frees a block previously allocated with HeapAlloc.
- HeapReAlloc This changes the size of an existing allocation, growing or shrinking an existing block. It is forwarded to RtlReAllocateHeap in Ntdll.dll.
- HeapLock and HeapUnlock These control mutual exclusion to heap operations.
- HeapWalk This enumerates the entries and regions in a heap.

## **Process heaps**

Each process has at least one heap: the default process heap. The default heap is created at process startup and is never deleted during the process's lifetime. It defaults to 1 MB in size, but you can make it bigger by specifying a starting size in the image file by using the /HEAP linker flag. This size is just the initial reserve, however. It will expand automatically as needed. You can also specify the initial committed size in the image file.

The default heap can be explicitly used by a program or implicitly used by some Windows internal functions. An application can query the default process heap by making a call to the Windows GetProcessHeap function. Processes can also create additional private heaps with the HeapCreate function. When a process no longer needs a private heap, it can recover the virtual address space by calling HeapDestroy. An array with all heaps is maintained in each process, and a thread can query them with the Windows GetProcessHeaps function.

A Universal Windows Platform (UWP) app process includes at least three heaps:

- The default process heap just described.
- A shared heap used to pass large arguments to the process' session Csrss.exe instance. This is created by the CsrClientConnectToServer Ntdll.dll function, which executes early in the process initialization done by Ntdll.dll. The heap handle is available in the global variable CsrPortHeap (in Ntdll.dll).
- A heap created by the Microsoft C runtime library. Its handle is stored in the global variable \_crtheap (in the msvcrt module). This heap is the one used internally by the C/C++ memoryallocation functions such as malloc, free, operator new/delete, and so on.

A heap can manage allocations either in large memory regions reserved from the memory manager via VirtualAlloc or from memory-mapped file objects mapped in the process address space. The latter approach is rarely used in practice (and is not exposed by the Windows API), but it's suitable for scenarios where the content of the blocks needs to be shared between two processes or between a kernel-mode and a user-mode component. The Win32 GUI subsystem driver (Win32k.sys) uses such a heap for sharing GDI and USER objects with user mode. If a heap is built on top of a memory-mapped file region, certain constraints apply with respect to the component that can call heap functions:

- The internal heap structures use pointers, and therefore do not allow remapping to different addresses in other processes.
- The synchronization across multiple processes or between a kernel component and a user process is not supported by the heap functions.
- In the case of a shared heap between user mode and kernel mode, the user-mode mapping should be read-only to prevent user-mode code from corrupting the heap's internal structures, which would result in a system crash. The kernel-mode driver is also responsible for not putting any sensitive data in a shared heap to avoid leaking it to user mode.

# Heap types

Until Windows 10 and Server 2016, there was just one heap type, which we'll call the *NT heap*. The NT heap is augmented by an optional front-end layer, which if used, consists of the *low-fragmentation heap* (*LFH*).

Windows 10 introduced a new heap type called *segment heap*. The two heap types include common elements but are structured and implemented differently. By default, the segment heap is used by all UWP apps and some system processes, while the NT heap is used by all other processes. This can be changed in the registry as described in the section "The segment heap" later in this chapter.

# The NT heap

As shown in Figure 5-8, the NT heap in user mode is structured in two layers: a front-end layer and the heap back end (sometimes called the heap core). The back end handles the basic functionality and includes the management of blocks inside segments, the management of the segments, policies for extending the heap, committing and decommitting memory, and management of large blocks.




FIGURE 5-8 NT heap layers in user mode.

For user-mode heaps only, a front-end heap layer can exist on top of the core functionality. Windows supports one optional front end layer, the LFH, described in the upcoming section "The low-fragmentation heap."

# Heap synchronization

The heap manager supports concurrent access from multiple threads by default. However, if a process is single threaded or uses an external mechanism for synchronization, it can tell the heap manager to avoid the overhead of synchronization by specifying the HEAP\_NO\_SERIALIZE flag either at heap creation or on a per-allocation basis. If heap synchronization is enabled, there is one lock per heap that protects all internal heap structures.

A process can also lock the entire heap and prevent other threads from performing heap operations for operations that would require consistent states across multiple heap calls. For instance, enumerating the heap blocks in a heap with the Windows function HeapWalk requires locking the heap if multiple threads can perform heap operations simultaneously. Locking and unlocking a heap can be done with the HeapLock and HeapUnlock functions, respectively.

### The low-fragmentation heap

Many applications running in Windows have relatively small heap memory usage—usually less than 1 MB. For this class of applications, the heap manager's best-fit policy helps keep a low memory footprint for each process. However, this strategy does not scale for large processes and multiprocessor machines. In these cases, memory available for heap usage might be reduced due to heap fragmentation. Performance can suffer in scenarios where only certain sizes are often used concurrently from different threads scheduled to run on different processors. This happens because several processors need to modify the same memory location (for example, the head of the look-aside list for that particular size) at the same time, thus causing significant contention for the corresponding cache line.

The LFH avoids fragmentation by managing allocated blocks in predetermined different block-size ranges called *buckets*. When a process allocates memory from the heap, the LFH chooses the bucket that maps to the smallest block large enough to hold the required size. (The smallest block is 8 bytes.) The first bucket is used for allocations between 1 and 8 bytes, the second for allocations between 9 and 16 bytes, and so on, until the 32nd bucket, which is used for allocations between 249 and 256 bytes, followed by the 33rd bucket, which is used for allocations between 257 and 272 bytes, and so on. Finally, the 128th bucket, which is the last, is used for allocations between 15,873 and 16,384 bytes. (This is known as a *binary buddy* system.) If the allocation is larger than 16,384 bytes, the LFH simply forwards it to the underlying heap back end. Table 5-7 summarizes the different buckets, their granularity, and the range of sizes they map to.

Buckets	Granularity	Range
1–32	8	1–256
33–48	16	257–512
49-64	32	513–1,024
65-80	64	1,025–2,048
81–96	128	2,049-4,096
97–112	256	4,097–8,192
113–128	512	8,193–16,384

TABLE 5-7	LFH buckets
-----------	-------------

The LFH addresses these issues by using the core heap manager and look-aside lists. The Windows heap manager implements an automatic tuning algorithm that can enable the LFH by default under certain conditions, such as lock contention or the presence of popular size allocations that have shown better performance with the LFH enabled. For large heaps, a significant percentage of allocations is

frequently grouped in a relatively small number of buckets of certain sizes. The allocation strategy used by LFH is to optimize the usage for these patterns by efficiently handling same-size blocks.

To address scalability, the LFH expands the frequently accessed internal structures to a number of slots that is two times larger than the current number of processors on the machine. The assignment of threads to these slots is done by an LFH component called the *affinity manager*. Initially, the LFH starts using the first slot for heap allocations; however, if a contention is detected when accessing some internal data, the LFH switches the current thread to use a different slot. Further contentions will spread threads on more slots. These slots are controlled for each size bucket to improve locality and minimize the overall memory consumption.

Even if the LFH is enabled as a front-end heap, the less frequent allocation sizes may continue to use the core heap functions to allocate memory, while the most popular allocation classes will be performed from the LFH. Once the LFH is enabled for a specific heap, it cannot be disabled. The HeapSetInformation API with the HeapCompatibilityInformation class that was able to remove the LFH layer in Windows 7 and earlier versions of Windows is now ignored.

## The segment heap

Figure 5-9 shows the architecture of the segment heap, introduced in Windows 10.




FIGURE 5-9 Segment heap.

The actual layer that manages an allocation depends on the allocation size as follows:

For small sizes (less than or equal to 16,368 bytes), the LFH allocator is used, but only if the size is determined to be a common one. This is a similar logic to the LFH front layer of the NT heap. If the LFH has not kicked in yet, the variable size (VS) allocator will be used instead.

- For sizes less than or equal to 128 KB (and not serviced by the LFH), the VS allocator is used. Both VS and LFH allocators use the back end to create the required heap sub-segments as necessary.
- Allocations larger than 128 KB and less than or equal to 508 KB are serviced directly by the heap back end.
- Allocations larger than 508 KB are serviced by calling the memory manager directly (Virtual-Alloc) since these are so large that using the default 64 KB allocation granularity (and rounding to the nearest page size) is deemed good enough.

Here is a quick comparison of the two heap implementations:

- In some scenarios, the segment heap may be somewhat slower than the NT heap. However, it's likely that future Windows versions would make it on par with the NT heap.
- The segment heap has a lower memory footprint for its metadata, making it better suited for low-memory devices such as phones.
- The segment heap's metadata is separated from the actual data, while the NT heap's metadata is interspersed with the data itself. This makes the segment heap more secure, as it's more difficult to get to the metadata of an allocation given just a block address.
- The segment heap can be used only for a growable heap. It cannot be used with a user-supplied memory mapped file. If such a segment heap creation is attempted, an NT heap is created instead.
- Both heaps support LFH-type allocations, but their internal implementation is completely different. The segment heap has a more efficient implementation in terms of memory consumption and performance.

As mentioned, UWP apps use segment heaps by default. This is mainly because of their lower memory footprint, which is suitable for low-memory devices. It's also used with certain system processes based on executable name: csrss.exe, lsass.exe, runtimebroker.exe, services.exe, smss.exe, and svchost. exe.

The segment heap is not the default heap for desktop apps because there are some compatibility concerns that may affect existing applications. It's likely that in future versions, however, it will become the default. To enable or disable the segment heap for a specific executable, you can set an Image File Execution Options value named FrontEndHeapDebugOptions (DWORD):

- Bit 2 (4) to disable segment heap
- Bit 3 (8) to enable segment heap

You can also globally enable or disable the segment heap by adding a value named Enabled (DWORD) to the HKLM\ SYSTEM\CurrentControlSet\Control\Session Manager\Segment Heap registry key. A zero value disables the segment heap and a non-zero value enables it.

### **EXPERIMENT:** Viewing basic heap information

In this experiment, we'll examine some heaps of a UWP process.

- Using Windows 10, run the Windows calculator. (Click the Start button and type Calculator to find it.)
- **2.** The calculator in Windows 10 has been turned into a UWP app (Calculator.Exe). Run WinDbg and attach to the calculator process.
- **3.** Once attached, WinDbg breaks into the process. Issue the !heap command to get a quick summary of heaps in the process:

0:033>	!heap Heap Address	NT/Segment	Неар
	2531eb90000	Segment	Неар
	2531e980000	NT	Неар
	2531eb10000	Segment	Неар
	25320a40000	Segment	Неар
	253215a0000	Segment	Неар
	253214f0000	Segment	Неар
	2531eb70000	Segment	Неар
	25326920000	Segment	Неар
	253215d0000	NT	Неар

- 4. Notice the various heaps with their handle and type (segment or NT). The first heap is the default process heap. Because it's growable and not using any preexisting memory block, it's created as a segment heap. The second heap is used with a user-defined memory block (described earlier in the "Process heaps" section). Because this feature is currently unsupported by the segment heap, it's created as an NT heap.
- 5. An NT heap is managed by the NtD11!\_HEAP structure. Let's view this structure for the second heap:

```
0:033> dt ntdll!_heap 2531e980000
+0x000 Segment : _HEAP_SEGMENT
+0x000 Entry : _HEAP_ENTRY
+0x010 SegmentSignature : 0xffeeffee
+0x014 SegmentFlags : 1
+0x018 SegmentListEntry : _LIST_ENTRY [ 0x00000253'1e980120 -
0x00000253'1e980120 ]
+0x028 Heap : 0x00000253'1e980000 _HEAP
+0x030 BaseAddress : 0x00000253'1e980000 Void
+0x038 NumberOfPages : 0x10
+0x040 FirstEntry : 0x00000253'1e980720 _HEAP_ENTRY
+0x048 LastValidEntry : 0x00000253'1e980720 _HEAP_ENTRY
+0x050 NumberOfUnCommittedPages : 0xf
+0x054 NumberOfUnCommittedRanges : 1
+0x058 SegmentAllocatorBackTraceIndex : 0
```

```
+0x05a Reserved
                          : 0
   +0x060 UCRSegmentList : _LIST_ENTRY [ 0x00000253'1e980fe0 -
0x00000253'1e980fe0 ]
  +0x070 Flags : 0x8000
+0x074 ForceFlags : 0
   +0x078 CompatibilityFlags : 0
   +0x07c EncodeFlagMask : 0x100000
   +0x080 Encoding : _HEAP_ENTRY
+0x090 Interceptor : 0
   +0x094 VirtualMemoryThreshold : 0xff00
   +0x098 Signature : 0xeeffeeff
   +0x0a0 SegmentReserve : 0x100000
   +0x0a8 SegmentCommit : 0x2000
   +0x0b0 DeCommitFreeBlockThreshold : 0x100
   +0x0b8 DeCommitTotalFreeThreshold : 0x1000
   +0x0c0 TotalFreeSize : 0x8a
   +0x0c8 MaximumAllocationSize : 0x00007fff'fffdefff
   +0x0d0 ProcessHeapsListIndex : 2
   +0x178 FrontEndHeap
                        : (null)
   +0x180 FrontHeapLockCount : 0
   +0x182 FrontEndHeapType : 0 ''
   +0x183 RequestedFrontEndHeapType : 0 ''
   +0x188 FrontEndHeapUsageData : (null)
   +0x190 FrontEndHeapMaximumIndex : 0
   +0x192 FrontEndHeapStatusBitmap : [129]
                                            .....
   +0x218 Counters : _HEAP_COUNTERS
   +0x290 TuningParameters : _HEAP_TUNING_PARAMETERS
```

- 6. Notice the FrontEndHeap field. This field indicates whether a front-end layer exists. In the preceding output, it's null, meaning there is no front-end layer. A non-null value indicates an LFH front-end layer (since it's the only one defined).
- A segment heap is defined with the NtD11!\_SEGMENT\_HEAP structure. Here's the default process heap:

```
0:033> dt ntdll!_segment_heap 2531eb90000
+0x000 TotalReservedPages : 0x815
+0x008 TotalCommittedPages : 0x6ac
+0x010 Signature : 0xddeeddee
+0x014 GlobalFlags : 0
+0x018 FreeCommittedPages : 0
+0x020 Interceptor : 0
+0x024 ProcessHeapListIndex : 1
+0x026 GlobalLockCount : 0
+0x028 GlobalLockCount : 0
+0x030 LargeMetadataLock : _RTL_SRWLOCK
+0x038 LargeAllocMetadata : _RTL_RB_TREE
+0x048 LargeReservedPages : 0
+0x050 LargeCommittedPages : 0
+0x058 SegmentAllocatorLock : _RTL_SRWLOCK
+0x060 SegmentListHead : _LIST_ENTRY [ 0x0000253'1ec00000 -
```

0x00000253'28a0000 ] +0x070 SegmentCount : 8 +0x078 FreePageRanges : \_RTL\_RB\_TREE +0x088 StackTraceInitVar : \_RTL\_RUN\_ONCE +0x090 ContextExtendLock : \_RTL\_SRWLOCK +0x098 AllocatedBase : 0x00000253'1eb93200 "" +0x0a0 UncommittedBase : 0x00000253'1eb94000 "--- memory read error at address 0x00000253'1eb94000 ---" +0x0a8 ReservedLimit : 0x00000253'1eba5000 "--- memory read error at address 0x00000253'1eba5000 ---" +0x0b0 VsContext : \_HEAP\_VS\_CONTEXT +0x120 LfhContext : \_HEAP\_LFH\_CONTEXT

- 8. Notice the Signature field. It's used to distinguish between the two types of heaps.
- 9. Notice the SegmentSignature field of the \_HEAP structure. It is in the same offset (0x10). This is how functions such as RtlAllocateHeap know which implementation to turn to based on the heap handle (address) alone.
- **10.** Notice the last two fields in the \_SEGMENT\_HEAP. These contain the VS and LFH allocator information.
- **11.** To get more information on each heap, issue the ! heap -s command:

0:033> !heap -s

		Global		Total Reserved			
Heap Address	Signature	Flags	List Index	Bytes (K)	Bytes (K)		
2531eb90000	ddeeddee	0	1	8276	6832		
2531eb10000	ddeeddee	0	3	1108	868		
25320a40000	ddeeddee	0	4	1108	16		
253215a0000	ddeeddee	0	5	1108	20		
253214f0000	ddeeddee	0	6	3156	816		
2531eb70000	ddeeddee	0	7	1108	24		
25326920000	ddeeddee	0	8	1108	32		
****	**************************************						
	,		0.556 41.00	2			
LFH Key		0xd7b666e	8756a4b98	5			
Termination on co		ENABLED					
Affinity manager - Virtual affi		2					
- Current entr	-						
- Statistics:		-	Allocs=0				
Heap Lock Fast	Flags Re	eserv Co	mmit Viı	rt Free	List UCR	Virt	

cont. heap	(k)	(k)	(k)	(k) 10	ength	b	locks
000002531e980000 00008000 0	64	4	64	2	1	1	0
00000253215d0000 00000001 N/A	16	16	16	10	1	1	0

**12.** Notice the first part of the output. It shows extended information on segment heaps (if any). The second part shows extended information on NT heaps in the process.

The !heap debugger command provides a multitude of options for viewing, investigating, and searching heaps. See the "Debugger Tools for Windows" documentation for more information.

### Heap security features

As the heap manager has evolved, it has taken an increased role in early detection of heap usage errors and in mitigating effects of potential heap-based exploits. These measures exist to lessen the security effect of potential vulnerabilities in applications. Both the NT-heap and the segment-heap implementations have multiple mechanisms that reduce the likelihood of memory exploitation.

The metadata used by the heaps for internal management is packed with a high degree of randomization to make it difficult for an attempted exploit to patch the internal structures to prevent crashes or conceal the attack attempt. These blocks are also subject to an integrity-check mechanism on the header to detect simple corruptions such as buffer overruns. Finally, the heap uses a small degree of randomization of the base address or handle. By using the HeapSetInformation API with the Heap-EnableTerminationOnCorruption class, processes can opt in for an automatic termination in case of detected inconsistencies to avoid executing unknown code.

As an effect of block metadata randomization, using the debugger to simply dump a block header as an area of memory is not that useful. For example, the size of the block and whether it is busy are not easy to spot from a regular dump. The same applies to LFH blocks. They have a different type of metadata stored in the header, also partially randomized. To dump these details, the !heap -i command in the debugger does all the work to retrieve the metadata fields from a block, also flagging checksum or free-list inconsistencies if they exist. The command works for both LFH and regular heap blocks. The total size of the blocks, the user-requested size, the segment owning the block, and the header partial checksum are available in the output, as shown in the following sample. Because the randomization algorithm uses the heap granularity, the !heap -i command should be used only in the proper context of the heap containing the block. In the example, the heap handle is 0x001a0000. If the current heap context were different, the decoding of the header would be incorrect. To set the proper context, the same !heap -i command with the heap handle as an argument must be executed first. 0:004> !heap -i 000001f72a5e0000 Heap context set to the heap 0x000001f72a5e0000

0:004> !heap -i 000001f72a5eb180					
Detailed information for block entry 000001f72a5eb180					
Assumed heap :	0x000001f72a5e0000 (Use !heap -i NewHeapHandle to change)				
Header content :	0x2FB544DC 0x1000021F (decoded : 0x7F01007E 0x10000048)				
Owning segment :	0x000001f72a5e0000 (offset 0)				
Block flags :	Ox1 (busy )				
Total block size :	0x7e units (0x7e0 bytes)				
Requested size :	0x7d0 bytes (unused 0x10 bytes)				
Previous block size:	0x48 units (0x480 bytes)				
Block CRC :	OK - 0x7f				
Previous block :	0x000001f72a5ead00				
Next block :	0x000001f72a5eb960				

### Segment heap-specific security features

The segment heap implementation uses many security mechanisms to make it harder to corrupt memory or to allow code injection by an attacker. Here are a few of them:

- Fail fast on linked list node corruption The segment heap uses linked lists to track segments and sub-segments. As with the NT heap, checks are added in the list node insertion and removal to prevent arbitrary memory writes due to corrupted list nodes. If a corrupted node is detected, the process is terminated via a call to RtlFailFast.
- Fail fast on red-black (RB) tree node corruption The segment heap uses RB trees to track free back-end and VS allocations. Node insertion and deletion functions validate the nodes involved or, if corrupted, invoke the fail-fast mechanism.
- Function pointer decoding Some aspects of the segment heap allow for callbacks (in VsContext and LfhContext structures, part of the \_SEGMENT\_HEAP structure). An attacker can override these callbacks to point to his or her own code. However, the function pointers are encoded by using a XOR function with an internal random heap key and the context address, both of which cannot be guessed in advance.
- Guard pages When LFH and VS sub-segments and large blocks are allocated, a guard page is added at the end. This helps to detect overflows and corruption of adjacent data. See the section "Stacks" later in this chapter for more information on guard pages.

### Heap debugging features

The heap manager includes several features to help detect bugs by using the following heap settings:

Enable tail checking The end of each block carries a signature that is checked when the block is released. If a buffer overrun destroys the signature entirely or partially, the heap will report this error.

- Enable free checking A free block is filled with a pattern that is checked at various points when the heap manager needs to access the block, such as at removal from the free list to satisfy an allocate request. If the process continues to write to the block after freeing it, the heap manager will detect changes in the pattern and the error will be reported.
- Parameter checking This function consists of extensive checking of the parameters passed to the heap functions.
- Heap validation The entire heap is validated at each heap call.
- Heap tagging and stack traces support This function supports the specification of tags for allocation and/or captures user-mode stack traces for the heap calls to help narrow the possible causes of a heap error.

The first three options are enabled by default if the loader detects that a process is started under the control of a debugger. (A debugger can override this behavior and turn off these features.) You can specify the heap debugging features for an executable image by setting various debugging flags in the image header using the Gflags tool. (See the next experiment and the section "Windows global flags" in Chapter 8 in Part 2.) Alternatively, you can enable heap debugging options using the !heap command in the standard Windows debuggers. (See the debugger help for more information.)

Enabling heap-debugging options affects all heaps in the process. Also, if any of the heap-debugging options are enabled, the LFH will be disabled automatically and the core heap will be used (with the required debugging options enabled). The LFH is also not used for heaps that are not expandable (because of the extra overhead added to the existing heap structures) or for heaps that do not allow serialization.

# Pageheap


Because the tail and free checking options described in the preceding sections might discover corruptions that occurred well before the problem was detected, an additional heap debugging capability, called *pageheap*, is provided. Pageheap directs all or part of the heap calls to a different heap manager. You can enable pageheap using the Gflags tool (part of the Debugging Tools for Windows). When enabled, the heap manager places allocations at the end of pages and reserves the page that immediately follows. Because reserved pages are not accessible, any buffer overruns that occur will cause an access violation, making it easier to detect the offending code. Optionally, pageheap allows for the placement of blocks at the beginning of the pages, with the preceding page reserved, to detect buffer underrun problems (a rare occurrence). Pageheap also can protect freed pages against any access to detect references to heap blocks after they have been freed.

Note that using the pageheap can cause you to run out of address space (in 32-bit processes) because of the significant overhead added for small allocations. Also, performance can suffer due to the increase of references to demand zero pages, loss of locality, and additional overhead caused by frequent calls to validate heap structures. A process can reduce the impact by specifying that the pageheap be used only for blocks of certain sizes, address ranges, and/or originating DLLs.

## **EXPERIMENT: Using pageheap**

In this experiment, you'll turn on pageheap for Notepad.exe and see its effects.

- 1. Run Notepad.exe.
- 2. Open Task Manager, click to the **Details** tab, and add the **Commit Size** column to the display.
- 3. Notice the commit size of the notepad instance you just launched.
- **4.** Run Gflags.exe, located in the folder where Debugging Tools for Windows is installed (requires elevation).
- 5. Click the Image File tab.
- 6. In the **Image** text box, type **notepad.exe**. Then press the **Tab** key. The various check boxes should be selected.
- 7. Select the Enable Page Heap check box. The dialog box should look like this:



#### 8. Click Apply.

- 9. Run another instance of Notepad. (Don't close the first one.)
- 10. In Task Manager, compare the commit size of both notepad instances. Notice that the second instance has a much larger commit size even though both are empty notepad processes. This is due to the extra allocations that pageheap provides. Here's a screen-shot from 32-bit Windows 10:

Task Manager					
File Options View					
Processes Performance	App hist	ory Startup Us	ers Details	Services	
Name	PID	User name	Commit siz	e CPU	Memory (p. ^
MsMpEng.exe	2460	SYSTEM	95,416	c 00	49,7201
NisSrv.exe	4116	LOCAL SERVI	9,056 H	< 00	3,0241
notepad.exe	8168	Administrator	10,248	C 00	8,4521
notepad.exe	3552	Administrator	1,532 1	< 00	1,0201
ConeDrive.exe	3220	Administrator	8,620	C 00	5,0881

**11.** To get a better sense of the extra memory allocated, use the VMMap Sysinternals tool. While the notepad processes are still running, open VMMap.exe and select the notepad instance that is using pageheap:

Proce	100			
PID:	View a running process Launch and trac	e a new pro	cess	
committed:	Name	PID	User	•
	ApplicationFrameHost.exe	5860	WIN10X86VM\Administrator	
rivate Bytes:	browser_broker.exe	3036	WIN10X86VM\Administrator	
The by cest	III dihost.exe	6024	WIN10X86VM\Administrator	
	explorer.exe	3376	WIN10X86VM\Administrator	
orking Set:	explorer.exe	5224	WIN10X86VM\Administrator	
	InstallAgent.exe	272	WIN10X86VM\Administrator	
	C MicrosoftEdge.exe	5448	WIN10X86VM\Administrator	
ype	C MicrosoftEdgeCP.exe	7072	WIN10X86VM\Administrator	
	HSASCuiL.exe	5964	WIN10X86VM\Administrator	
	notepad exe	8168	WIN10X86VM\Administrator	
	notepad.exe	3552	WIN10X86VM\Administrator	
	ConeDrive.exe	3220	WIN10X86VM\Administrator	
	III rdpclip.exe	3752	WIN10X86VM\Administrator	
	RuntimeBroker.exe	2212	WIN10X86VM\Administrator	
	SearchUI.exe	6752	WIN10X86VM\Administrator	
	SettingSyncHost.exe	5788	WIN10X86VM\Administrator	
	<			
	Refresh Show All Proces	ses		
ddress				
			OK Cance	st

**12.** Open another instance of VMMap and select the other notepad instance. Place the windows side by side to see both:

	ysinternals: www.aysin v Tools Options					8 9	Contraction 1	Contract of Contractory	lysinternals: www.sysi		300.000				×
		rneip					-		w Tools Options	Help					_
PID:	notepad.exe 8168							Process PID:	notepad.exe 3552						
Committed:						100,50	ж	Committed:						91,4	56)
Private Bytes:						10.28	1X	Private Bytes:							140
Contraction of the															1
Working Set:						19,86	ж	Working Set:						12.	648
						0.0000								0.250	
Туре	Size		ommitted	Private	Total \		1.0	Туре	Size	ċ	omnitted	Private	Total V	NS	ŝ
Total	177.252 K		100,500 K	10.284 K	19,8			Total	133.001 K		91,456 K	1.640 K	12,16		
mage	54.628 K		54,628 K	876 K	7,9	54 K		Image	54,236 K		54,236 K	800 K	7,74		
Mapped File Shareable	21,356 K 51,540 K		21,356 K		3.7	IS K		Mapped File	21.356 K		21,356 K			36 K	
	51,540 K		15,044 K 80 K	16 K		28 K 30 K		Shareable	51.540 K		15.060 K	328 K	3.71		
Heap Managed Heap	1.200 K		OU N.	16 K		OVK		Heap Managed Heap	1,290 K		392 K	328 K	- 34	20 K	
Stack	256 K		76 K	76 K	-	IG K		Stack	256 K		76 K	76 K		16 K	
Private Data	45.648 K		8,960 K	8.960 K	7.7			Private Data	2.640 K		32 K	32 K		12 K	
Page Table	356 K		356 K	356 K		56 K		Page Table	304 K		304 K	304 K		M K	
Unusable	2,188 K				10.0	200		Unusable	2.195 K			202.0		2.0	
Free	1.920.192 K						¥.	Free	1,963,584 K						
	<					3		(	¢						5
Address	Туре	Size	Committed	Private	Total WS	Private	~	Address	Туре	Sire	Committed	Private	Total WS	Private	
± 00610000	Heap (Private Data)	64 K	4K	4.8	4 K	4 K		+ 00CC0000	(Image (ASLR)	248 K	248 K	12.6	184 K		ĸ
· 00620000	Sharwable	4.K	4.6	4.0	4 K		10	# 00020000	Shareable	32.768 K	9.895 K	16.0	292 K	10	K
· 006C0800	Heap (Private Data)	1.024 K	4K	4 K	4 K			± 02020000	Heap (Shareable)	64 K	64 K	1000	4 K		1
± 007C0000	Mapped File	772 K	772 K					E 02030000	Heap (Private Data)	32 K	4.6	4 K	4 K	15 24	ĸ
008E0000	Heap (Private Data)	64 K	4K	4.K	4 K			··· 02D40000	Shareable	88 K	88 K		88 K	W	
ODBF0000	Private Data	1.024 K	412 K	412 K	324 K			02060000	Thread Stack	256 K	76 K	76 K	16 K		K
■ 009F0000	Pitvate Data	1.024 K	440 K	440 K	208 K	208 K	~	E 02DA0000	Shareable	12 K	12 K		12 K		
■ 00AF0000	¢					>			٤						>
			-		-		- A.			11			-		
			New All											TFROM.	

- **13.** Notice that the difference in the commit size is clearly visible in the Private Data (yellow) part.
- **14.** Click the **Private Data** line in the middle display on both VMMap instances to see its parts in the bottom display (sorted by size in the screenshot):

Address	Type	Size	Committed	Private	Total WS	Private	<u>^</u>	Address	Type	Size	Committed	Private	Total WS	Private	S
E 02000000	Private Data	16,384 K	292 K	292 K	292 K	292 K		B 02E00000	Private Data	2,048 K	BK	8 K	8 K	8 K	
+ 00200000	Private Data	2,048 K	8K	8 K	8 K	8 K		B 058C0000	Private Data	512 K	4K	4 K	4 K	4 K	
E 00400000	Private Data	1.024 K	452 K	452 K	320 K	320 K		38 7FFE0000	Private Data	64 K	4 K	4 K	4 K		
00500000	Private Data	1,024 K	BK	8.K	3.K	8 K		02000000	Pitvate Data	8K	8K	8 K.	8K	8 K	
1 008F0000	Private Data	1,024 K	412 K	412 K	324 K	324 K		# 02DE0000	Private Data	4 K	4 K	4 K	4 K	4 K	
E 009F0000	Private Data	1,024 K	440 K	440 K	208 K	208 K		E 020F0000	Private Data	4K	4 K	4 K	4 K	4 K	
+ 00AF0000	Pitvate Data	1,024 K	512 K	512 K	264 K	264 K		Contraction New	A CONTRACTOR ON						
E 03000000	Private Data	1,024 K	252 K	252 K	228 K	228 K			<						
@ 048F0000	Private Data	1.024 K	512 K	512 K	472 K	472 K	<b>~</b>								
E 04CF0000	¢					>				Titteli	te Heap Ala	ations Ca	al Tree.II	Trace	
														_	1.0
		Timel	Henry Menny Man	abors Ca	# Trees	Trace									

**15.** The left screenshot (notepad with pageheap) clearly consumes more memory. Open one of the 1,024 KB chunks. You should see something like this:

Address	Туре	Size	Committed	Private	Total WS	Private	Sharea.
009F2000	Private Data	4 K	4 K	4 K			
009F3000	Private Data	4 K					
009F4000	Private Data	4 K	4 K	4 K	4 K	4 K	
009F5000	Private Data	4 K					
009F6000	Private Data	4 K	4 K	4 K			
009F7000	Private Data	4 K					
009F8000	Private Data	4 K	4 K	4 K	4 K	4 K	
009F9000	Private Data	4 K					
009FA000	Private Data	4 K	4 K	4 K	4 K	4 K	
009FB000	2	2.17					

**16.** You can clearly see the reserved pages between committed pages that help catch buffer overruns and underruns courtesy of pageheap. Uncheck the **Enable Page Heap** option in Gflags and click **Apply** so future instances of notepad will run without pageheap.

For more information on pageheap, see the "Debugging Tools for Windows" help file.

# Fault-tolerant heap

Microsoft has identified the corruption of heap metadata as one of the most common causes of application failures. Windows includes a feature called the *fault-tolerant heap* (*FTH*) to mitigate these problems and to provide better problem-solving resources to application developers. The FTH is implemented in two primary components:

- The detection component (FTH server)
- The mitigation component (FTH client)

The detection component is a DLL called Fthsvc.dll that is loaded by the Windows Security Center service (Wscsvc.dll), which in turn runs in one of the shared service processes under the local service account. It is notified of application crashes by the Windows Error Reporting (WER) service.

Suppose an application crashes in Ntdll.dll with an error status indicating either an access violation or a heap-corruption exception. If it is not already on the FTH service's list of watched applications, the service creates a "ticket" for the application to hold the FTH data. If the application subsequently crashes more than four times in an hour, the FTH service configures the application to use the FTH client in the future.

The FTH client is an application-compatibility shim. This mechanism has been used since Windows XP to allow applications that depend on a particular behavior of older Windows systems to run on later systems. In this case, the shim mechanism intercepts the calls to the heap routines and redirects them to its own code. The FTH code implements numerous mitigations that attempt to allow the application to survive despite various heap-related errors.

For example, to protect against small buffer overrun errors, the FTH adds 8 bytes of padding and an FTH reserved area to each allocation. To address a common scenario in which a block of heap is accessed after it is freed, HeapFree calls are implemented only after a delay. "Freed" blocks are put on a list, and freed only when the total size of the blocks on the list exceeds 4 MB. Attempts to free regions that are not actually part of the heap, or not part of the heap identified by the heap handle argument to HeapFree, are simply ignored. In addition, no blocks are actually freed once exit or RtlExitUser-Process has been called.

The FTH server continues to monitor the failure rate of the application after the mitigations have been installed. If the failure rate does not improve, the mitigations are removed.

You can observe the activity of the fault-tolerant heap in the Event Viewer. Follow these steps:

- 1. Open a Run prompt and type **eventvwr.msc**.
- 2. In the left pane, choose Event Viewer, select Applications and Services Logs, choose Microsoft, select Windows, and click Fault-Tolerant-Heap.
- 3. Click the **Operational** log.
- **4.** The FTH may be disabled completely in the registry. in the HKLM\Software\Microsoft\FTH key, set the Enabled value to 0.

That same key contains the various FTH settings, such as the delay mentioned earlier and an exclusion list of executables (which includes by default system processes such as smss.exe, csrss.exe, wininit. exe, services.exe, winlogon.exe and taskhost.exe). A rule list is also included (RuleList value), which lists the modules and exception type (and some flags) to watch for in order for FTH to kick in. By default, a single rule is listed, indicating heap problems in Ntdll.dll of type STATUS\_ACCESS\_VIOLATION (0xc0000005).

The FTH does not normally operate on services, and it is disabled on Windows server systems for performance reasons. A system administrator can manually apply the shim to an application or service executable by using the Application Compatibility Toolkit.

# Virtual address space layouts

This section describes the components in the user and system address space, followed by the specific layouts on 32-bit (x86 and ARM) and 64-bit (x64) systems. This information will help you to understand the limits on process and system virtual memory on these platforms.

Three main types of data are mapped into the virtual address space in Windows:

- Per-process private code and data As explained in Chapter 1, each process has a private address space that cannot be accessed by other processes. That is, a virtual address is always evaluated in the context of the current process and cannot refer to an address defined by any other process. Threads within the process can therefore never access virtual addresses outside this private address space. Even shared memory is not an exception to this rule, because shared memory regions are mapped into each participating process, and so are accessed by each process using per-process addresses. Similarly, the cross-process memory functions (Read-ProcessMemory and WriteProcessMemory) operate by running kernel-mode code in the context of the target process. The process virtual address space, called *page tables*, is described in the "Address translation" section. Each process has its own set of page tables. They are stored in kernel-mode-only accessible pages so that user-mode threads in a process cannot modify their own address space layout.
- Session-wide code and data Session space contains information that is common to each session. (For a description of sessions, see Chapter 2.) A session consists of the processes and other system objects such as the window station, desktops, and windows that represent a single user's logon session. Each session has a session-specific paged pool area used by the kernel-mode portion of the Windows subsystem (Win32k.sys) to allocate session-private GUI data structures. In addition, each session has its own copy of the Windows subsystem process (Csrss.exe) and logon process (Winlogon.exe). The Session Manager process (Smss.exe) is responsible for creating new sessions, which includes loading a session-private copy of Win32k.sys, creating the session-private object manager namespace (see Chapter 8 in Part 2 for more details on the object manager), and creating the session-specific instances of the Csrss.exe and Winlogon.exe processes. To virtualize sessions, all session-wide data structures are mapped into a region of system space called *session space*. When a process is created, this range of addresses is mapped to the pages associated with the session that the process belongs to.

- System-wide code and data System space contains global operating system code and data structures visible by kernel-mode code regardless of which process is currently executing. System space consists of the following components:
  - System code This contains the OS image, HAL, and device drivers used to boot the system.
  - **Nonpaged pool** This is the non-pageable system memory heap.
  - **Paged pool** This is the pageable system memory heap.
  - **System cache** This is virtual address space used to map files open in the system cache. (See Chapter 11, "Startup and shutdown," in Part 2 for detailed information.)
  - **System page table entries (PTEs)** This is the pool of system PTEs used to map system pages such as I/O space, kernel stacks, and memory descriptor lists. You can see how many system PTEs are available by using Performance Monitor to examine the value of the Memory: Free System Page Table Entries counter.
  - **System working set lists** These are the working set list data structures that describe the three system working sets: system cache, paged pool, and system PTEs.
  - **System mapped views** This is used to map Win32k.sys, the loadable kernel-mode part of the Windows subsystem, as well as kernel-mode graphics drivers it uses. (See Chapter 2 for more information on Win32k.sys.)
  - **Hyperspace** This is a special region used to map the process working set list and other per-process data that doesn't need to be accessible in arbitrary process context. Hyperspace is also used to temporarily map physical pages into the system space. One example of this is invalidating page table entries in page tables of processes other than the current one, such as when a page is removed from the standby list.
  - **Crash dump information** This is reserved to record information about the state of a system crash.
  - HAL usage This is system memory reserved for HAL-specific structures.

Now that we've described the basic components of the virtual address space in Windows, let's examine the specific layout on the x86, ARM, and x64 platforms.

# x86 address space layouts

By default, each user process on 32-bit versions of Windows has a 2 GB private address space. (The operating system takes the remaining 2 GB.) However, for x86, the system can be configured with the increaseuserva BCD boot option to permit user address spaces up to 3 GB. Two possible address space layouts are shown in Figure 5-10.

The ability of a 32-bit process to grow beyond 2 GB was added to accommodate the need for 32-bit applications to keep more data in memory than could be done with a 2 GB address space. Of course, 64-bit systems provide a much larger address space.




FIGURE 5-10 x86 virtual address space layouts (2 GB on the left, 3 GB on the right).

For a process to grow beyond 2 GB of address space, the image file must have the IMAGE\_FILE\_ LARGE\_ADDRESS\_AWARE flag set in the image header (in addition to the global increaseuserva setting). Otherwise, Windows reserves the additional address space for that process so that the application won't see virtual addresses greater than 0x7FFFFFF. Access to the additional virtual memory is opt-in because some applications assume they'll be given at most 2 GB of the address space. Because the high bit of a pointer referencing an address below 2 GB is always zero (31 bits are needed to reference a 2 GB address space), these applications would use the high bit in their pointers as a flag for their own data—clearing it, of course, before referencing the data. If they ran with a 3 GB address space, they would inadvertently truncate pointers that have values greater than 2 GB, causing program errors, including possible data corruption. You set this flag by specifying the /LARGEADDRESSAWARE linker flag when building the executable. Alternatively, use the Property page in Visual Studio (choose Linker, select System, and click Enable Large Addresses). You can add the flag to an executable image even without building (no source code required) by using a tool such as Editbin.exe (part of the Windows SDK tools), assuming the file is not signed. This flag has no effect when running the application on a system with a 2 GB user address space.

Several system images are marked as large address space aware so that they can take advantage of systems running with large process address spaces. These include the following:

- Lsass.exe The Local Security Authority Subsystem
- Inetinfo.exe Internet Information Server
- Chkdsk.exe The Check Disk utility

- Smss.exe The Session Manager
- Dllhst3g.exe A special version of Dllhost.exe (for COM+ applications)

### EXPERIMENT: Checking whether an application is large address aware

You can use the Dumpbin utility from the Visual Studio Tools (and older versions of the Windows SDK) to check other executables to see if they support large address spaces. Use the /headers flag to display the results. Here's a sample output of Dumpbin on the Session Manager:

```
dumpbin /headers c:\windows\system32\smss.exe
Microsoft (R) COFF/PE Dumper Version 14.00.24213.1
Copyright (C) Microsoft Corporation. All rights reserved.
Dump of file c:\windows\system32\smss.exe
PE signature found
File Type: EXECUTABLE IMAGE
FILE HEADER VALUES
            14C machine (x86)
              5 number of sections
        57898F8A time date stamp Sat Jul 16 04:36:10 2016
              O file pointer to symbol table
              0 number of symbols
              EO size of optional header
             122 characteristics
                   Executable
                   Application can handle large (>2GB) addresses
                   32 bit word machine
```

Finally, memory allocations using VirtualAlloc, VirtualAllocEx, and VirtualAllocExNuma start with low virtual addresses and grow higher by default. Unless a process allocates a lot of memory or has a very fragmented virtual address space, it will never get back very high virtual addresses. Therefore, for testing purposes, you can force memory allocations to start from high addresses by using the MEM\_TOP\_DOWN flag to the VirtualAlloc\* functions or by adding a DWORD registry value named AllocationPreference to the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Memory Management key and setting its value to 0x100000.

The following output shows runs of the TestLimit utility (shown in previous experiments) leaking memory on a 32-bit Windows machine booted without the increaseuserva option:

```
Testlimit.exe -r
```

```
Testlimit v5.24 - test Windows limits
Copyright (C) 2012-2015 Mark Russinovich
Sysinternals - www.sysinternals.com
```

Process ID: 5500

```
Reserving private bytes (MB)...
Leaked 1978 MB of reserved memory (1940 MB total leaked). Lasterror: 8
```

The process managed to reserve close to the 2 GB limit (but not quite). The process address space has the EXE code and various DLLs mapped, so naturally it's not possible in a normal process to reserve the entire address space.

On that same system, you can switch to a 3 GB address space by running the following command from an administrative command window:

#### C:\WINDOWS\system32>bcdedit /set increaseuserva 3072

The operation completed successfully.

Notice that the command allows you to specify any number (in MB) between 2,048 (the 2 GB default) to 3,072 (the 3 GB maximum). After you restart the system so that the setting can take effect, running TestLimit again produces the following:

```
Testlimit.exe -r

Testlimit v5.24 - test Windows limits

Copyright (C) 2012-2015 Mark Russinovich

Sysinternals - www.sysinternals.com

Process ID: 2308

Reserving private bytes (MB)...

Leaked 2999 MB of reserved memory (2999 MB total leaked). Lasterror: 8
```

TestLimit was able to leak close to 3 GB, as expected. This is only possible because TestLimit was linked with /LARGEADDRESSAWARE. Had it not been, the results would have been essentially the same as on the system booted without increaseuserva.

**Note** To revert a system to the normal 2 GB address space per process, run the bcdedit / deletevalue increaseuserva command.

# x86 system address space layout

The 32-bit versions of Windows implement a dynamic system address space layout by using a virtual address allocator. (We'll describe this functionality later in this section.) There are still a few specifically reserved areas, as shown in Figure 5-10. However, many kernel-mode structures use dynamic address space allocation. These structures are therefore not necessarily virtually contiguous with themselves. Each can easily exist in several disjointed pieces in various areas of system address space. The uses of system address space that are allocated in this way include the following:

- Non-paged pool
- Paged pool
- Special pool

- System PTEs
- System mapped views
- File system cache
- PFN database
- Session space

# x86 session space

For systems with multiple sessions (which is almost always the case, as session 0 is used by system processes and services, while session 1 is used for the first logged on user), the code and data unique to each session are mapped into system address space but shared by the processes in that session. Figure 5-11 shows the general layout of session space. The sizes of the components of session space, just like the rest of kernel system address space, are dynamically configured and resized by the memory manager on demand.



FIGURE 5-11 x86 session space layout (not proportional).

# **EXPERIMENT:** Viewing sessions

You can display which processes are members of which sessions by examining the session ID. You can do this using Task Manager, Process Explorer, or the kernel debugger. Using the kernel debugger, you can list the active sessions with the !session command as follows:

```
lkd> !session
Sessions on machine: 3
Valid Sessions: 0 1 2
Current Session 2
```

You can then set the active session using the !session -s command and display the address of the session data structures and the processes in that session with the !sprocess command:

```
lkd> !session -s 1
Sessions on machine: 3
```

Implicit process is now d4921040 Using session 1

lkd> !sprocess
Dumping Session 1

#### \_MM\_SESSION\_SPACE d9306000

\_MMSESSION d9306c80
PROCESS d4921040 SessionId: 1 Cid: 01d8 Peb: 00668000 ParentCid: 0138
DirBase: 179c5080 ObjectTable: 00000000 HandleCount: 0.
Image: smss.exe

- PROCESS d186c180 SessionId: 1 Cid: 01ec Peb: 00401000 ParentCid: 01d8 DirBase: 179c5040 ObjectTable: d58d48c0 HandleCount: <Data Not Accessible> Image: csrss.exe
- PROCESS d49acc40 SessionId: 1 Cid: 022c Peb: 03119000 ParentCid: 01d8 DirBase: 179c50c0 ObjectTable: d232e5c0 HandleCount: <Data Not Accessible> Image: winlogon.exe
- PROCESS dc0918c0 SessionId: 1 Cid: 0374 Peb: 003c4000 ParentCid: 022c DirBase: 179c5160 ObjectTable: dc28f6c0 HandleCount: <Data Not Accessible> Image: LogonUI.exe
- PROCESS dc08e900 SessionId: 1 Cid: 037c Peb: 00d8b000 ParentCid: 022c DirBase: 179c5180 ObjectTable: dc249640 HandleCount: <Data Not Accessible> Image: dwm.exe

To view the details of the session, dump the MM\_SESSION\_SPACE structure using the dt command, as follows:

```
1kd> dt nt!_mm_session_space d9306000
  +0x000 ReferenceCount : 0n4
  +0x004 u
                           : <unnamed-tag>
  +0x008 SessionId
                          : 1
  +0x00c ProcessReferenceToSession : 0n6
  +0x010 ProcessList : _LIST_ENTRY [ 0xd4921128 - 0xdc08e9e8 ]
  +0x018 SessionPageDirectoryIndex : 0x1617f
  +0x01c NonPagablePages : 0x28
  +0x020 CommittedPages : 0x290
  +0x024 PagedPoolStart : 0xc0000000 Void
  +0x028 PagedPoolEnd : 0xffbfffff Void
  +0x02c SessionObject : 0xd49222b0 Void
  +0x030 SessionObjectHandle : 0x800003ac Void
  +0x034 SessionPoolAllocationFailures : [4] 0
  +0x044 ImageTree : _RTL_AVL_TREE
  +0x048 LocaleId
                          : 0x409
  +0x04c AttachCount
                         : 0
  +0x050 AttachGate
                          : _KGATE
  +0x060 WsListEntry : _LIST_ENTRY [ 0xcdcde060 - 0xd6307060 ]
+0x080 Lookaside : [24] _GENERAL_LOOKASIDE
+0xc80 Session : _MMSESSION
  +0xc80 Session
                           : _MMSESSION
```

```
354 CHAPTER 5 Memory management
```

# **EXPERIMENT:** Viewing session space utilization

You can view session space memory utilization with the !vm 4 command in the kernel debugger. For example, the following output was taken from a 32-bit Windows client system with a remote desktop connection, resulting in three sessions—the default two sessions plus the remote session. (The addresses are for the MM\_SESSION\_SPACE objects shown earlier.)

```
1kd> !vm 4
...
Terminal Server Memory Usage By Session:
Session ID 0 @ d6307000:
Paged Pool Usage: 2012 Kb
NonPaged Usage: 108 Kb
Commit Usage: 2292 Kb
Session ID 1 @ d9306000:
Paged Pool Usage: 2288 Kb
NonPaged Usage: 160 Kb
Commit Usage: 2624 Kb
Session ID 2 @ cdcde000:
Paged Pool Usage: 7740 Kb
NonPaged Usage: 208 Kb
Commit Usage: 8144 Kb
Session Summary
Paged Pool Usage: 12040 Kb
NonPaged Usage: 476 Kb
Commit Usage: 13060 Kb
```

# System page table entries

System page table entries (PTEs) are used to dynamically map system pages such as I/O space, kernel stacks, and the mapping for memory descriptor lists (MDLs, discussed to some extent in Chapter 6). System PTEs aren't an infinite resource. On 32-bit Windows, the number of available system PTEs is such that the system can theoretically describe 2 GB of contiguous system virtual address space. On Windows 10 64 bit and Server 2016, system PTEs can describe up to 16 TB of contiguous virtual address space.

# **EXPERIMENT:** Viewing system PTE information

You can see how many system PTEs are available by examining the value of the Memory: Free System Page Table Entries counter in Performance Monitor or by using the <code>!sysptes</code> or <code>!vm</code> command in the debugger. You can also dump the <code>\_MI\_SYSTEM\_PTE\_TYPE</code> structure as part of the memory state (MiState) variable (or the MiSystemPteInfo global variable on Windows 8.x/2012/R2). This will also show you how many PTE allocation failures occurred on the system. A high count indicates a problem and possibly a system PTE leak.

```
kd> !sysptes
System PTE Information
 Total System Ptes 216560
    starting PTE: c0400000
  free blocks: 969 total free: 16334 largest free block: 264
kd> ? MiState
Evaluate expression: -2128443008 = 81228980
kd> dt nt!_MI_SYSTEM_INFORMATION SystemPtes
   +0x3040 SystemPtes : _MI_SYSTEM_PTE_STATE
kd> dt nt!_mi_system_pte_state SystemViewPteInfo 81228980+3040
   +0x10c SystemViewPteInfo : _MI_SYSTEM_PTE_TYPE
kd> dt nt!_mi_system_pte_type 81228980+3040+10c
  +0x000 Bitmap : _RTL_BITMAP
+0x008 BasePte : 0xc0400000 _MMPTE
+0x00c Flags : 0xe
+0x010 VaType : c ( MiVaDriverImages )
+0x014 FailureCount : 0x8122bae4 -> 0
+0x018 PteFailures : 0
  +0x01c SpinLock : 0
+0x01c GlobalPushLock : (null)
   +0x020 Vm : 0x8122c008 _MMSUPPORT_INSTANCE
  +0x024 TotalSystemPtes : 0x120
   +0x028 Hint : 0x2576
   +0x02c LowestBitEverAllocated : 0xc80
   +0x030 CachedPtes : (null)
   +0x034 TotalFreeSystemPtes : 0x73
```

If you are seeing lots of system PTE failures, you can enable system PTE tracking by creating a new DWORD value in the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Memory Management key called TrackPtes and setting its value to 1. You can then use ! sysptes 4 to show a list of allocators.

# ARM address space layout

As shown in Figure 5-12, the ARM address space layout is nearly identical to the x86 address space. The memory manager treats ARM-based systems exactly as x86 systems in terms of pure memory management. The differences are at the address translation layer, described in the section "Address translation" later in this chapter.




FIGURE 5-12 ARM virtual address space layout.

# 64-bit address space layout

The theoretical 64-bit virtual address space is 16 exabytes (EB), or 18,446,744,073,709,551,616 bytes. Current processor limitations allow for 48 address lines only, limiting the possible address space to 256 TB (2 to the 48th power). The address space is divided in half, where the lower 128 TB are available as private user processes and the upper 128 TB are system space. System space is divided into several different-sized regions (Windows 10 and Server 2016), as shown in Figure 5-13. Clearly, 64 bits provides a tremendous leap in terms of address space sizes as opposed to 32 bit. The actual starts of various kernel sections are not necessarily those shown, as ASLR is in effect in kernel space in the latest versions of Windows.




FIGURE 5-13 x64 address space layout.

**Note** Windows 8 and Server 2012 are limited to 16 TB of address space. This is because of Windows implementation limitations, described in Chapter 10 of the sixth edition of *Windows Internals Part 2*. Of these, 8 TB is per process and the other 8 TB is used for system space.

Thirty-two-bit images that are large address space aware receive an extra benefit while running on 64-bit Windows (under Wow64). Such an image will actually receive all 4 GB of user address space available. After all, if the image can support 3 GB pointers, 4 GB pointers should not be any different, because unlike the switch from 2 GB to 3 GB, there are no additional bits involved. The following output shows TestLimit running as a 32-bit application, reserving address space on a 64-bit Windows machine.

```
C:\Tools\Sysinternals>Testlimit.exe -r
```

Testlimit v5.24 - test Windows limits Copyright (C) 2012-2015 Mark Russinovich Sysinternals - www.sysinternals.com

Process ID: 264

Reserving private bytes (MB)... Leaked 4008 MB of reserved memory (4008 MB total leaked). Lasterror: 8 Not enough storage is available to process this command. These results depend on TestLimit having been linked with the /LARGEADDRESSAWARE option. Had it not been, the results would have been about 2 GB for each. Sixty-four-bit applications linked without / LARGEADDRESSAWARE are constrained to the first 2 GB of the process virtual address space, just like 32-bit applications. (This flag is set by default in Visual Studio for 64-bit builds.)

# x64 virtual addressing limitations

As discussed, 64 bits of virtual address space allow for a possible maximum of 16 EB of virtual memory —a notable improvement over the 4 GB offered by 32-bit addressing. Obviously, neither today's computers nor tomorrow's are even close to requiring support for that much memory.

Accordingly, to simplify chip architecture and avoid unnecessary overhead—particularly in address translation (described later)—AMD's and Intel's current x64 processors implement only 256 TB of virtual address space. That is, only the low-order 48 bits of a 64-bit virtual address are implemented. However, virtual addresses are still 64 bits wide, occupying 8 bytes in registers or when stored in memory. The high-order 16 bits (bits 48 through 63) must be set to the same value as the highest-order implemented bit (bit 47), in a manner similar to sign extension in two's complement arithmetic. An address that conforms to this rule is said to be a *canonical address*.

# Dynamic system virtual address space management

Thirty-two-bit versions of Windows manage the system address space through an internal kernel virtual allocator mechanism, described in this section. Currently, 64-bit versions of Windows have no need to use the allocator for virtual address space management (and thus bypass the cost) because each region is statically defined (refer to Figure 5-13).

When the system initializes, the MiInitializeDynamicVa function sets up the basic dynamic ranges and sets the available virtual address to all available kernel space. It then initializes the address space ranges for boot loader images, process space (hyperspace), and the HAL through the MiInitialize-SystemVaRange function, which is used to set hard-coded address ranges (on 32-bit systems only). Later, when non-paged pool is initialized, this function is used again to reserve the virtual address ranges for it. Finally, whenever a driver loads, the address range is relabeled to a driver-image range instead of a boot-loaded range.

After this point, the rest of the system virtual address space can be dynamically requested and released through MiObtainSystemVa (and its analogous MiObtainSessionVa) and MiReturnSystemVa. Operations such as expanding the system cache, the system PTEs, non-paged pool, paged pool, and/or special pool; mapping memory with large pages; creating the PFN database; and creating a new session all result in dynamic virtual address allocations for a specific range.

Each time the kernel virtual address space allocator obtains virtual memory ranges for use by a certain type of virtual address, it updates the MiSystemVaType array, which contains the virtual address type for the newly allocated range. The values that can appear in MiSystemVaType are shown in Table 5-8.

Region	Description	Limitable
MiVaUnused (0)	Unused	N/A
MiVaSessionSpace (1)	Addresses for session space	Yes
MiVaProcessSpace (2)	Addresses for process address space	No
MiVaBootLoaded (3)	Addresses for images loaded by the boot loader	No
MiVaPfnDatabase (4)	Addresses for the PFN database	No
MiVaNonPagedPool (5)	Addresses for the non-paged pool	Yes
MiVaPagedPool (6)	Addresses for the paged pool	Yes
MiVaSpecialPoolPaged (7)	Addresses for the special pool (paged)	No
MiVaSystemCache (8)	Addresses for the system cache	No
MiVaSystemPtes (9)	Addresses for system PTEs	Yes
MiVaHal (10)	Addresses for the HAL	No
MiVaSessionGlobalSpace (11)	Addresses for session global space	No
MiVaDriverImages (12)	Addresses for loaded driver images	No
MiVaSpecialPoolNonPaged (13)	Addresses for the special pool (non-paged)	Yes
MiVaSystemPtesLarge (14)	Addresses for large page PTEs	Yes

TABLE 5-8	System virtual address	types
-----------	------------------------	-------

Although the ability to dynamically reserve virtual address space on demand allows better management of virtual memory, it would be useless without the ability to free this memory. As such, when the paged pool or system cache can be shrunk, or when special pool and large page mappings are freed, the associated virtual address is freed. Another case is when the boot registry is released. This allows dynamic management of memory depending on each component's use. Additionally, components can reclaim memory through MiReclaimSystemVa, which requests virtual addresses associated with the system cache to be flushed out (through the dereference segment thread) if available virtual address space has dropped below 128 MB. Reclaiming can also be satisfied if initial non-paged pool has been freed.

In addition to better proportioning and better management of virtual addresses dedicated to different kernel memory consumers, the dynamic virtual address allocator also has advantages when it comes to memory footprint reduction. Instead of having to manually pre-allocate static page table entries and page tables, paging-related structures are allocated on demand. On both 32-bit and 64-bit systems, this reduces boot-time memory usage because unused addresses won't have their page tables allocated. It also means that on 64-bit systems, the large address space regions that are reserved don't need to have their page tables mapped in memory. This allows them to have arbitrarily large limits, especially on systems that have little physical RAM to back the resulting paging structures.

# EXPERIMENT: Querying system virtual address usage (Windows 10 and Server 2016)

You can look at the current and peak usage of each system virtual address type by using the kernel debugger. The global variable MiVisibleState (of type MI\_VISIBLE\_STATE) provides information available in the public symbols. (The example is on x86 Windows 10.)

1. To get a sense of the data provided by MiVisibleState, dump the structure with values:

```
lkd> dt nt!_mi_visible_state poi(nt!MiVisibleState)
  +0x000 SpecialPool : _MI_SPECIAL_POOL
  +0x048 SessionWsList : _LIST_ENTRY [ 0x91364060 - 0x9a172060 ]
  +0x050 SessionIdBitmap : 0x8220c3a0 _RTL_BITMAP
  +0x054 PagedPoolInfo : _MM_PAGED_POOL_INFO
  +0x070 MaximumNonPagedPoolInPages : 0x80000
  +0x074 SizeOfPagedPoolInPages : 0x7fc00
  +0x078 SystemPteInfo : _MI_SYSTEM_PTE_TYPE
  +0x0b0 NonPagedPoolCommit : 0x3272
  +0x0b4 BootCommit : 0x186d
  +0x0b8 MdlPagesAllocated : 0x105
  +0x0bc SystemPageTableCommit : 0x1e1
  +0x0c0 SpecialPagesInUse : 0
  +0x0c4 Ws0verheadPages : 0x775
  +0x0c8 VadBitmapPages : 0x30
  +0x0cc ProcessCommit : 0xb40
  +0x0d0 SharedCommit : 0x712a
  +0x0d4 DriverCommit : 0n7276
+0x100 SystemWs : [3] _MMSUPPORT_FULL
  +0x2c0 SystemCacheShared : _MMSUPPORT_SHARED
  +0x2e4 MapCacheFailures : 0
  +0x2e8 PagefileHashPages : 0x30
  +0x2ec PteHeader : _SYSPTES_HEADER
  +0x378 SessionSpecialPool : 0x95201f48 _MI_SPECIAL_POOL
  +0x37c SystemVaTypeCount : [15] 0
  +0x3b8 SystemVaType : [1024] ""
  +0x7b8 SystemVaTypeCountFailures : [15] 0
  +0x7f4 SystemVaTypeCountLimit : [15] 0
  +0x830 SystemVaTypeCountPeak : [15] 0
  +0x86c SystemAvailableVa : 0x38800000
```

 Notice the last arrays with 15 elements each, corresponding to the system virtual address types from Table 5-8. Here are the SystemVaTypeCount and SystemVaType-CountPeak arrays:

```
lkd> dt nt!_mi_visible_state poi(nt!mivisiblestate) -a SystemVaTypeCount
+0x37c SystemVaTypeCount :
  [00] 0
  [01] 0x1c
  [02] 0xb
  [03] 0x15
  [04] 0xf
  [05] 0x1b
```

[06] 0x46 [07] 0 [08] 0x125 [09] 0x38 [10] 2 [11] Oxb [12] 0x19 [13] 0 [14] 0xd lkd> dt nt!\_mi\_visible\_state poi(nt!mivisiblestate) -a SystemVaTypeCountPeak +0x830 SystemVaTypeCountPeak : [00] 0 [01] 0x1f [02] 0 [03] 0x1f [04] 0xf [05] 0x1d [06] 0x51 [07] 0 [08] 0x1e6 [09] 0x55 [10] 0 [11] Oxb [12] 0x5d [13] 0 [14] Oxe

## EXPERIMENT: Querying system virtual address usage (Windows 8.x and Server 2012/R2)

You can look at the current and peak usage of each system virtual address type by using the kernel debugger. For each system virtual address type described in Table 5-8, the MiSystemVa-TypeCount, MiSystemVaTypeCountFailures, and MiSystemVaTypeCountPeak global arrays in the kernel contain the sizes, count failures, and peak sizes for each type. The size is in multiples of a PDE mapping (see the "Address translation" section later in this chapter), which is effectively the size of a large page (2 MB on x86). Here's how you can dump the usage for the system, followed by the peak usage. You can use a similar technique for the failure counts. (The example is from a 32-bit Windows 8.1 system.)

lkd> dd /c 1 MiSystemVaTypeCount L f
81c16640 0000000
81c16644 0000000b
81c16648 0000000b
81c1664c 00000018
81c16650 0000000f
81c16654 00000017
81c16658 0000005f
81c1665c 00000000
81c16660 000000c7

81c16664	0000021
81c16668	0000002
81c1666c	0000008
81c16670	0000001c
81c16674	0000000
81c16678	000000b
lkd≻ dd ∕o	c 1 MiSystemVaTypeCountPeak L f
81c16b60	0000000
81c16b64	0000021
81c16b68	0000000
81c16b6c	0000022
81c16b70	000000f
81c16b74	0000001e
81c16b78	0000007e
81c16b7c	0000000
81c16b80	00000e3
81c16b84	0000027
81c16b88	0000000
81c16b8c	0000008
81c16b90	00000059
81c16b94	0000000
81c16b98	000000b

Theoretically, the different virtual address ranges assigned to components can grow arbitrarily in size if enough system virtual address space is available. In practice, on 32-bit systems, the kernel allocator implements the ability to set limits on each virtual address type for the purposes of both reliability and stability. (On 64-bit systems, kernel address space exhaustion is currently not a concern.) Although no limits are imposed by default, system administrators can use the registry to modify these limits for the virtual address types that are currently marked as limitable (see Table 5-8).

If the current request during the MiObtainSystemVa call exceeds the available limit, a failure is marked (see the previous experiment) and a reclaim operation is requested regardless of available memory. This should help alleviate memory load and might allow the virtual address allocation to work during the next attempt. Recall, however, that reclaiming affects only system cache and non-paged pool.

## **EXPERIMENT: Setting system virtual address limits**

The MiSystemVaTypeCountLimit array contains limitations for system virtual address usage that can be set for each type. Currently, the memory manager allows only certain virtual address types to be limited, and it provides the ability to use an undocumented system call to set limits for the system dynamically during run time. (These limits can also be set through the registry, as described at *http://msdn.microsoft.com/en-us/library/bb870880.aspx*.) These limits can be set for those types marked in Table 5-8.

You can use the MemLimit utility (found in this book's downloadable resources) on 32-bit systems to query and set the different limits for these types and to see the current and peak virtual address space usage. Here's how you can query the current limits with the -q flag:

C:\Tools>MemLimit.exe -q

MemLimit v1.01 - Query and set hard limits on system VA space consumption Copyright (C) 2008-2016 by Alex Ionescu www.alex-ionescu.com

System Va Consumption:

Туре	Current		Peak		Limit
Non Paged Pool	45056	KB	55296	KB	0 KB
Paged Pool	151552	KB	165888	KB	0 KB
System Cache	446464	KB	479232	KB	0 KB
System PTEs	90112	KB	135168	KB	0 KB
Session Space	63488	KB	73728	KB	0 KB

As an experiment, use the following command to set a limit of 100 MB for paged pool:

```
memlimit.exe -p 100M
```

Now use the Sysinternals TestLimit tool to create as many handles as possible. Normally, with enough paged pool, the number should be around 16 million. But with the limit to 100 MB, it's less:

```
C:\Tools\Sysinternals>Testlimit.exe -h
```

```
Testlimit v5.24 - test Windows limits
Copyright (C) 2012-2015 Mark Russinovich
Sysinternals - www.sysinternals.com
```

Process ID: 4780

```
Creating handles...
Created 10727844 handles. Lasterror: 1450
```

See Chapter 8 in Part 2 for more information about objects, handles, and page-pool consumption.

# System virtual address space quotas

The system virtual address space limits described in the previous section allow for the limiting of system-wide virtual address space usage of certain kernel components. However, they work only on 32-bit systems when applied to the system as a whole. To address more specific quota requirements that system administrators might have, the memory manager collaborates with the process manager to enforce either system-wide or user-specific quotas for each process.

You can configure the PagedPoolQuota, NonPagedPoolQuota, PagingFileQuota, and Working-SetPagesQuota values in the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Memory Management key to specify how much memory of each type a given process can use. This information is read at initialization, and the default system quota block is generated and then assigned to all system processes. (User processes get a copy of the default system quota block unless per-user quotas have been configured, as explained next.) To enable per-user quotas, you can create subkeys under the HKLM\SYSTEM\CurrentControlSet\ Session Manager\Quota System registry key, each one representing a given user SID. The values mentioned previously can then be created under this specific SID subkey, enforcing the limits only for the processes created by that user. Table 5-9 shows how to configure these values (which can be done at run time or not) and which privileges are required.

Value Name	Description	Value Type	Dynamic	Privilege
PagedPoolQuota	This is the maxi- mum size of paged pool that can be allocated by this process.	Size in MB	Only for processes running with the system token	SeIncreaseQuotaPrivilege
NonPagedPoolQuota	This is the maxi- mum size of non- paged pool that can be allocated by this process.	Size in MB	Only for processes running with the system token	SeIncreaseQuotaPrivilege
PagingFileQuota	This is the maxi- mum number of pages that a process can have backed by the page file.	Pages	Only for processes running with the system token	SeIncreaseQuotaPrivilege
WorkingSetPagesQuota	This is the maxi- mum number of pages that a pro- cess can have in its working set (in physical memory).	Pages	Yes	SeIncreaseBasePriorityPrivilege unless operation is a purge request

TABLE 5-9 Process quota types

# User address space layout

Just as address space in the kernel is dynamic, the user address space is also built dynamically. The addresses of the thread stacks, process heaps, and loaded images (such as DLLs and an application's executable) are dynamically computed (if the application and its images support it) through the ASLR mechanism.

At the operating system level, user address space is divided into a few well-defined regions of memory, as shown in Figure 5-14. The executable and DLLs themselves are present as memory-mapped image files, followed by the heap(s) of the process and the stack(s) of its thread(s). Apart from these regions (and some reserved system structures such as the TEBs and PEB), all other memory allocations are run-time dependent and generated. ASLR is involved with the location of all these run time– dependent regions and, combined with DEP, provides a mechanism for making remote exploitation of a system through memory manipulation harder to achieve. Because Windows code and data are placed at dynamic locations, an attacker cannot typically hard-code a meaningful offset into either a program or a system-supplied DLL.




FIGURE 5-14 User address space layout with ASLR enabled.

## **EXPERIMENT:** Analyzing user virtual address space

The VMMap utility from Sysinternals can show you a detailed view of the virtual memory being used by any process on your machine. This information is divided into categories for each type of allocation, summarized as follows:

- Image This displays memory allocations used to map the executable and its dependencies (such as dynamic libraries) and any other memory-mapped image (portable executable format) files.
- Mapped File This displays memory allocations for memory mapped data files.
- Shareable This displays memory allocations marked as shareable, typically including shared memory (but not memory-mapped files, which are listed under either Image or Mapped File).
- Heap This displays memory allocated for the heap(s) that this process owns.
- Managed Heap This displays memory allocated by the .NET CLR (managed objects). It would show nothing for a process that does not use .NET.
- **Stack** This displays memory allocated for the stack of each thread in this process.
- Private Data This displays memory allocations marked as private other than the stack and heap, such as internal data structures.

The following shows a typical view of Explorer (64 bit) as seen through VMMap:

ile Edit View Too	ils Options Help					_					_	
Process: explor PED: 7272	er.exe											
Committed:							_				-	485,528
Private Bytes:												85,528
Working Set:												141,164
Туре	Size	Committed	Private	Total V		vate WS	Shareab		Shared W		Blocks	Larges
fotai	2.148.113.208 K	485.528 K	85.528 K	141.164		77.008 K		156 K	49,692			
mage	284,976 K	284,976 K	8,068 K	60,564		5,724 K		840 K	41,136		1585	21,536
lapped File	95,208 K	95,208 K		3,588				588 K	3,292		81	25,604
hareable	2,147,510,096 K	27,756 K		5,856		196 K	5,0	660 K	5,196			,147,483,648
leap	54,168 K	34,860 K	34,732 K	34,140	IK I	34,076 K		64 K	64	K	98	16,192
fanaged Heap			20224								246	
rivate Data	41,984 K 104,824 K	6,264 K 34,424 K	6,264 K 34,424 K	3,080		3,080 K 31,892 K		4.K	4	10	240	512 32,768
age Table	2,040 K	2,040 K	2,040 K	2,040		2.040 K		4.6		N.	100	32,/00
Inusable	19,912 K	2/040 K	2,040 K	2,040	I N	2/040 K						60
ree	19,914 N										207.12	
	¢											,
Address	Туре	Size	Comm	Private	Total	Privat	Shar	Sha	Loc Blo	c Protection	Details	
000000000000000000	000 Free	5.952 K										
0000000005000	000 Heap (Shareable)	64 K	64 K		4 K		4 K	4 K		1 Read/Write	Heap IC	: 2 [COMPATA
00000000005E00		8 K	8 K		8 K		BK	8 K		1 Read		
0000000005E20		56 K										
0000000005F00		8 K	8 K	BK	8 K	8 K				1 Read/Write		
0000000005F20		56 K										
00000000006000		2,048 K	660 K	660 K	660 K	660 K				65 Read/Write	Thread	Environment I
00000000008000		88 K 40 K	88 K		76 K		76 K	76 K		1 Read		
00000000008160			100.0	100.17	116 K	110.00				3 Read/Write/Guard	wheread	ID. NO.
000000000008400		512 K 8 K	128 K 8 K	128 K	110 K	116 K 8 K				1 Read/Write	Inread	10: 7276
00000000008A20		56 K	on	O K	ON	ON				1 Ready value		
E 00000000008800		16 K	16 K		16 K		16 K	16 K		1 Read		
00000000008840		48 K	10.10		10 1		10 h	40 h				
+ 00000000008C00		8 K	8 K		8 K		BK			1 Read		
0000000008C20		56 K								A CONTRACTOR		
00000000008000	000 Private Data	8 K	8 K	8 K	8 K	8 K				1 Read/Write		
00000000008D20	000 Unusable	56 K										
0000000008E00			116 K	116 K	116 K	116 K				2 Read/Write	Heap II	1 LOW FRA
00000000009120		56 K										
	000 Mapped File	24 K	24 K		8 K		BK			1 Read	C:\Wind	lows\en-U5\e
0000000009200												

Depending on the type of memory allocation, VMMap can show additional information such as file names (for mapped files), heap IDs and types (for heap allocations), and thread IDs (for stack allocations). Furthermore, each allocation's cost is shown both in committed memory and working set memory. The size and protection of each allocation is also displayed.

ASLR begins at the image level, with the executable for the process and its dependent DLLs. Any image file that has specified ASLR support in its PE header (IMAGE\_DLL\_CHARACTERISTICS\_DYNAMIC\_ BASE), typically specified by using the /DYNAMICBASE linker flag in Microsoft Visual Studio, and contains a relocation section will be processed by ASLR. When such an image is found, the system selects an image offset valid globally for the current boot. This offset is selected from a bucket of 256 values, all of which are 64 KB aligned.

## Image randomization

For executables, the load offset is calculated by computing a delta value each time an executable is loaded. This value is a pseudo-random 8-bit number from 0x10000 to 0xFE0000, calculated by taking the current processor's time stamp counter (TSC), shifting it by four places, and then performing a division modulo 254 and adding 1. This number is then multiplied by the allocation granularity of 64 KB discussed earlier. By adding 1, the memory manager ensures that the value can never be 0, so executables will never load at the address in the PE header if ASLR is being used. This delta is then added to the executable's preferred load address, creating one of 256 possible locations within 16 MB of the image address in the PE header.

For DLLs, computing the load offset begins with a per-boot, system-wide value called the *image bias*. This is computed by MiInitializeRelocations and stored in the global memory state structure (MI\_SYSTEM\_INFORMATION) in the MiState.Sections.ImageBias fields (MiImageBias global variable in Windows 8.x/2012/R2). This value corresponds to the TSC of the current CPU when this function was called during the boot cycle, shifted and masked into an 8-bit value. This provides 256 possible values on 32 bit systems; similar computations are done for 64-bit systems with more possible values as the address space is vast. Unlike executables, this value is computed only once per boot and shared across the system to allow DLLs to remain shared in physical memory and relocated only once. If DLLs were remapped at different locations inside different processes, the code could not be shared. The loader would have to fix up address references differently for each process, thus turning what had been shareable read-only code into process-private data. Each process using a given DLL would have to have its own private copy of the DLL in physical memory.

Once the offset is computed, the memory manager initializes a bitmap called ImageBitMap (MiImageBitMap global variable in Windows 8.x/2012/R2), which is part of the MI\_SECTION\_STATE structure. This bitmap is used to represent ranges from 0x50000000 to 0x78000000 for 32-bit systems (see the numbers for 64-bit systems below), and each bit represents one unit of allocation (64 KB, as mentioned). Whenever the memory manager loads a DLL, the appropriate bit is set to mark its location in the system. When the same DLL is loaded again, the memory manager shares its section object with the already relocated information.

As each DLL is loaded, the system scans the bitmap from top to bottom for free bits. The ImageBias value computed earlier is used as a start index from the top to randomize the load across different boots as suggested. Because the bitmap will be entirely empty when the first DLL (which is always Ntdll. dll) is loaded, its load address can easily be calculated. (Sixty-four-bit systems have their own bias.)

- **32 bit** 0x78000000 (ImageBias + NtD11Sizein64KBChunks) \* 0x10000
- 64 bit 0x7FFFFFF0000 (ImageBias64High + NtD11Sizein64KBChunks) \* 0x10000

Each subsequent DLL will then load in a 64 KB chunk below. Because of this, if the address of Ntdll. dll is known, the addresses of other DLLs could easily be computed. To mitigate this possibility, the order in which known DLLs are mapped by the Session Manager during initialization is also randomized when Smss.exe loads.

Finally, if no free space is available in the bitmap (which would mean that most of the region defined for ASLR is in use), the DLL relocation code defaults back to the executable case, loading the DLL at a 64 KB chunk within 16 MB of its preferred base address.

## EXPERIMENT: Calculating the load address of Ntdll.dll

With what you learned in the previous section, you can calculate the load address of Ntdll.dll with the kernel variable information. The following calculation is done on a Windows 10 x86 system:

1. Start local kernel debugging.

2. Find the ImageBias value:

```
lkd> ? nt!mistate
Evaluate expression: -2113373760 = 820879c0
lkd> dt nt!_mi_system_information sections.imagebias 820879c0
+0x500 Sections :
    +0x0dc ImageBias : 0x6e
```

- 3. Open Explorer and find the size of Ntdll.dll in the System32 directory. On this system, it's 1547 KB = 0x182c00, so the size in 64 KB chunks is 0x19 (always rounding up). The result is 0x78000000 (0x6E + 0x19) \* 0x10000 = 0x77790000.
- 4. Open Process Explorer, find any process, and look at the load address (in the Base or Image Base columns) of Ntdll.dll. You should see the same value.
- 5. Try to do the same for a 64-bit system.

# Stack randomization

The next step in ASLR is to randomize the location of the initial thread's stack and, subsequently, of each new thread. This randomization is enabled unless the StackRandomizationDisabled flag was enabled for the process, and consists of first selecting one of 32 possible stack locations separated by either 64 KB or 256 KB. You select this base address by finding the first appropriate free memory region and then choosing the *x*th available region, where *x* is once again generated based on the current processor's TSC shifted and masked into a 5-bit value. (This allows for 32 possible locations.)

When this base address has been selected, a new TSC-derived value is calculated—this one 9 bits long. The value is then multiplied by 4 to maintain alignment, which means it can be as large as 2,048 bytes (half a page). It is added to the base address to obtain the final stack base.

# Heap randomization

ASLR randomizes the location of the initial process heap and subsequent heaps when created in user mode. The RtlCreateHeap function uses another pseudo-random TSC-derived value to determine the base address of the heap. This value, 5 bits this time, is multiplied by 64 KB to generate the final base address, starting at 0, giving a possible range of 0x00000000 to 0x001F0000 for the initial heap. Additionally, the range before the heap base address is manually deallocated to force an access violation if an attack is doing a brute-force sweep of the entire possible heap address range.

# ASLR in kernel address space

ASLR is also active in kernel address space. There are 64 possible load addresses for 32-bit drivers and 256 for 64-bit drivers. Relocating user-space images requires a significant amount of work area in kernel space, but if kernel space is tight, ASLR can use the user-mode address space of the System process for this work area. On Windows 10 (version 1607) and Server 2016, ASLR is implemented for most system memory regions, such as paged and non-paged pools, system cache, page tables, and the PFN database (initialized by MiAssignTopLevelRanges).

# **Controlling security mitigations**

As you've seen, ASLR and many other security mitigations in Windows are optional because of their potential compatibility effects: ASLR applies only to images with the IMAGE\_DLL\_CHARACTERISTICS\_ DYNAMIC\_BASE bit in their image headers, hardware no-execute (DEP) can be controlled by a combination of boot options and linker options, and so on. To allow both enterprise customers and individual users more visibility and control of these features, Microsoft publishes the Enhanced Mitigation Experience Toolkit (EMET). EMET offers centralized control of the mitigations built into Windows and adds several more mitigations not yet part of the Windows product. Additionally, EMET provides notification capabilities through the event log to let administrators know when certain software has experienced access faults because mitigations have been applied. Finally, EMET enables manual opt-out for certain applications that might exhibit compatibility issues in certain environments, even though they were opted in by the developer.

**Note** EMET is in version 5.51 at the time of this writing. Its end of support has been extended to the end of July 2018. However, some of its features are integrated in current Windows versions.

## **EXPERIMENT:** Looking at ASLR protection on processes

You can use Process Explorer from Sysinternals to look over your processes (and, just as important, the DLLs they load) to see if they support ASLR. Even if just one DLL loaded by a process does not support ASLR, it can make the process much more vulnerable to attacks.

To look at the ASLR status for processes, follow these steps:

- 1. Right-click any column in the process tree and choose Select Columns.
- 2. Select ASLR Enabled on the Process Image and DLL tabs.
- **3.** Notice that all in-box Windows programs and services are running with ASLR enabled, but third-party applications may or may not run with ASLR.

In the example, we have highlighted the Notepad.exe process. In this case, its load address is 0x7FF7D76B0000. If you were to close all instances of Notepad and then start another, you would find it at a different load address. If you shut down and reboot the system and then try the experiment again, you will find that the ASLR-enabled DLLs are at different load addresses after each boot.

File Options View Proc	ess Find DLL Users Help	1					
	) 🖻 🛪 🗛 🕘 🛴				and I have a second	سر کا است	manum
Process	PID CPU P	ivate Bytes	Virtual Size	Working Set	Description	ASLR	1
notepad exe	12564	3.760 K 2.1	47.611.260 K	15,804 K		ASLR	
1 OfficeClickToRun.exe	3788	36,548 K	245,076 K	50,864 K	Microsoft Office Click to -Run	ASLR	
🗆 🐔 OneDrive.exe	10176	10.232 K	191.392 K	34,468 K	Microsoft OneDrive	ASLR	
Name	Description		Base ASLR	Mapping	Size	Image Base	
msvcrt.dl	Windows NT CRT DLL	0x7FFE1C450	000 ASLR	Image	0x9E000	0x7FFE1C450000	
notepad exe	Notepad	0x7FF7D76B0	000 ASLR	Image	0x41000	0x7FF7D76B0000	
notepad exe mui	Notepad	0x197ED650	000 n/a	Data	0x3000	0x0	
ntdi di	NT Layer DLL	0x7FFE1E520	000 ASLR	Image	0x1D1000	0x7FFE1E520000	
ntmarta di	Windows NT MARTA provider	0x7FFE19AB0	000 ASLR	Image	0x32000	0x7FFE19AB0000	
ole32 dl	Microsoft OLE for Windows	0x7FFE1CBA0	000 ASLR	Image	0x137000	0x7FFE1CBA0000	
pleaut 32 dl		0x7FFE1E460	000 ASLR	Image	0x8C000	0x7FFE1E460000	
powrprof.dll	Power Profile Helper DLL	0x7FFE1AA30	000 ASLR	Image	0x4C000	0x7FFE1AA30000	
profapi dl	User Profile Basic API	0x7FFE1AA80	000 ASLR	Image	0x14000	0x7FFE1AA80000	
propeys dl	Microsoft Property System	0x7EEE167E0	000 ASLR	Image	0x185000	0x7FFE167E0000	
R0000000000d clb		0x197EDA70	000 n/a	Data	0x8000	0x0	
port4 dl	Remote Procedure Call Runtime	0x7FFE1CE10	000 ASLR	Image	0x121000	0x7FFE1CE10000	
saech dli	Microsoft Enhanced Cryptographi	0x7FFE19C40	000 ASLR	Image	0x33000	0x7FFE19C40000	
sechost dl	Host for SCM/SDDL/LSA Lookup			Image	0x59000	0x7FFE1BAB0000	
SHCore dl	SHCORE	0x7FFE1AF70		Image	0xA9000	0x7FFE1AF70000	
shell 32 dl	Windows Shell Common Dil	0x7FFE1CF40	000 ASLR	Image	0x1508000	0x7FFE1CF40000	
shiwapi.dl	Shell Light-weight Utility Library	0x7FFE1C3F0	000 ASLR	Image	0x52000	0x7FFE1C3F0000	
Sort Default nis		0x197EF1D0	000 n/a	Data	0x337000	0x0	
StaticCache dat		0x197F1050	000 n/a	Data	0x10E0000	0x0	
winapi appcore dl	twinapi.appcore	0x7FFE19100	000 ASLR	Image	0x11C000	0x7FFE19100000	
ucrtbase dll	Microsoft® C Runtime Library	0x7FFE1AC80		Image	0xF5000	0x7FFE1AC80000	
urimon di	OLE32 Extensions for Win32	0x7FFE113F0		Image	0x1C2000	0x7FFE113F0000	
user32 dll	Mutti-Liser Windows LISEB APLC			Image	0x165000	0x7FFE1C280000	


# **Address translation**

Now that you've seen how Windows structures the virtual address space, let's look at how it maps these address spaces to real physical pages. User applications and system code reference virtual addresses. This section starts with a detailed description of 32-bit x86 address translation in PAE mode (the only mode supported in recent versions of Windows) and continues with a description of the differences on the ARM and x64 platforms. The next section describes what happens when such a translation doesn't resolve to a physical memory address (page fault) and explains how Windows manages physical memory via working sets and the page frame database.

# x86 virtual address translation

The original x86 kernel supported no more than 4 GB of physical memory, based on the CPU hardware available at the time. The Intel x86 Pentium Pro processor introduced a memory-mapping mode called *Physical Address Extension (PAE)*. With the proper chipset, the PAE mode allows 32-bit operating systems access to up to 64 GB of physical memory on current Intel x86 processors (up from 4 GB without PAE) and up to 1,024 GB of physical memory when running on x64 processors in legacy mode (although Windows currently limits this to 64 GB due to the size of the PFN database required to describe so much memory). Since then, Windows has maintained two separate x86 kernels—one that did not support PAE and one that did. Starting with Windows Vista, an x86 Windows installation always installs the PAE kernel even if the system's physical memory is not higher than 4 GB. This allows Microsoft to maintain a single x86 kernel, as the benefits of the non-PAE kernel in terms of performance and memory footprint became negligible (and is required for hardware no-execute support). Thus, we'll describe only x86 PAE address translation. Interested readers can read the relevant section in the sixth edition of this book for the non-PAE case.

Using data structures that the memory manager creates and maintains called *page tables*, the CPU translates virtual addresses into physical addresses. Each page of virtual address space is associated with a system-space structure called a *page table entry (PTE)*, which contains the physical address to which the virtual one is mapped. For example, Figure 5-15 shows how three consecutive virtual pages might be mapped to three physically discontiguous pages on an x86 system. There may not even be any PTEs for regions that have been marked as reserved or committed but never accessed, because the page table itself might be allocated only when the first page fault occurs. (The dashed line connecting the virtual pages to the PTEs in Figure 5-15 represents the indirect relationship between virtual pages and physical memory.)





**Note** Even kernel-mode code (such as device drivers) cannot reference physical memory addresses directly, but it may do so indirectly by first creating virtual addresses mapped to them. For more information, see the memory descriptor list (MDL) support routines described in the WDK documentation.

The actual translation process and the layout of the page tables and page directories (described shortly), are determined by the CPU. The operating system must follow suit and build the structures correctly in memory for the whole concept to work. Figure 5-16 depicts a general diagram of x86 translation. The general concept, however, is the same for other architectures.

As shown in Figure 5-16, the input to the translation system consists of a 32-bit virtual address (since this is the addressable range with 32 bit) and a bunch of memory-related structures (page tables, page directories, a single page directory pointer table [PDPT], and translation lookaside buffers, all described

shortly). The output should be a 36-bit physical address in RAM where the actual byte is located. The number 36 comes from the way the page tables are structured and, as mentioned, dictated by the processor. When mapping small pages (the common case, shown in Figure 5-16), the least significant 12 bits from the virtual address are copied directly to the resulting physical address. 12 bits is exactly 4 KB—the size of a small page.




FIGURE 5-16 Virtual address translation overview.

If the address cannot be translated successfully (for example, the page may not be in physical memory but resides in a page file), the CPU throws an exception known as a *page fault* that indicates to the OS that the page cannot be located. Because the CPU has no idea where to find the page (page file, mapped file, or something else), it relies on the OS to get the page from wherever it's located (if possible), fix the page tables to point to it, and request that the CPU tries translation again. (Page faults are described in the section "Page files" later in this chapter.)




Figure 5-17 depicts the entire process of translating x86 virtual to physical addresses.

FIGURE 5-17 x86 virtual address translation.

The 32-bit virtual address to be translated is logically segregated into four parts. As you've seen, the lower 12 bits are used as-is to select a specific byte within a page. The translation process starts with a single PDPT per process, which resides in physical memory at all times. (Otherwise, how would the system locate it?) Its physical address is stored in the KPROCESS structure for each process. The special x86 register CR3 stores this value for the currently executing process (that is, one of its threads made the access to the virtual address). This means that when a context switch occurs on a CPU, if the new thread is running under a different process than the old thread, then the CR3 register must be loaded with the new process's page directory pointer address from its KROCESS structure. The PDPT must be aligned on a 32-byte boundary and must furthermore reside in the first 4 GB of RAM (because CR3 on x86 is still a 32-bit register).

Given the layout in Figure 5-17, the sequence of translating a virtual address to a physical one goes as follows:

- The two most significant bits of the virtual address (bits 30 and 31) provide an index into the PDPT. This table has four entries. The entry selected—the page directory pointer entry (PDPE)—points to the physical address of a page directory.
- 2. A page directory contains 512 entries, one of which is selected by bits 21 to 29 (9 bits) from the virtual address. The selected page directory entry (PDE) points to the physical address of a page table.
- A page table also contains 512 entries, one of which is selected by bits 13 to 28 (9 bits) from the virtual address. The selected page table entry (PTE) points to the physical address of the start of the page.
- **4.** The virtual address offset (lower 12 bits) is added to the PTE pointed-to address to give the final physical address requested by the caller.

Every entry value in the various tables is also called a page frame number (PFN) because it points to a page-aligned address. Each entry is 64 bits wide—so the size of a page directory or page table is no larger than a 4 KB page—but only 24 bits are strictly necessary to describe a 64 GB physical range (combined with the 12 bits of the offset for an address range with a total of 36 bits). This means there are more bits than needed for the actual PFN values.

One of the extra bits in particular is paramount to the whole mechanism: the valid bit. This bit indicates whether the PFN data is indeed valid and therefore whether the CPU should execute the procedure just outlined. If the bit is clear, however, it indicates a page fault. The CPU raises an exception and expects the OS to handle the page fault in some meaningful way. For example, if the page in question was previously written to disk, then the memory manager should read it back to a free page in RAM, fix the PTE, and tell the CPU to try again.

Because Windows provides a private address space for each process, each process has its own PDPT, page directories, and page tables to map that process's private address space. However, the page directories and page tables that describe system space are shared among all processes (and session space is shared only among processes in a session). To avoid having multiple page tables describing the same virtual memory, the page directory entries that describe system space are initialized to point

to the existing system page tables when a process is created. If the process is part of a session, session space page tables are also shared by pointing the session space page directory entries to the existing session page tables.

## Page tables and page table entries

Each PDE points to a page table. A page table is a simple array of PTEs. So, too, is a PDPT. Every page table has 512 entries and each PTE maps a single page (4 KB). This means a page table can map a 2 MB address space (512 x 4 KB). Similarly, a page directory has 512 entries, each pointing to a page table. This means a page directory can map 512 x 2 MB or 1 GB of address space. This makes sense because there are four PDPEs, which together can map the entire 32-bit 4 GB address space.

For large pages, the PDE points with 11 bits to the start of a large page in physical memory, where the byte offset is taken for the low 21 bits of the original virtual address. This means such a PDE mapping a large page does not point to any page table.

The layout of a page directory and page table is essentially the same. You can use the kernel debugger !pte command to examine PTEs. (See the upcoming experiment "Translating addresses.") We'll discuss valid PTEs here and invalid PTEs in the section "Page fault handling." Valid PTEs have two main fields: the PFN of the physical page containing the data or of the physical address of a page in memory, and some flags that describe the state and protection of the page. (See Figure 5-18.)




FIGURE 5-18 Valid x86 hardware PTEs.

The bits labeled "Software" and "Reserved" in Figure 5-18 are ignored by the memory management unit (MMU) inside the CPU regardless of whether the PTE is valid. These bits are stored and interpreted by the memory manager. Table 5-10 briefly describes the hardware-defined bits in a valid PTE.

Name of Bit	Meaning	
Accessed	The page has been accessed.	
Cache disabled	This disables CPU caching for that page.	
Copy-on-write	Copy-on-write The page is using copy-on-write (described earlier).	

TABLE 5-10 PTE status and protection bits

Name of Bit	Meaning		
Dirty	The page has been written to.		
Global	Translation applies to all processes. For example, a translation buffer flush won't affect this PTE.		
Large page	This indicates that the PDE maps a 2 MB page. (Refer to the section "Large and small pages" earlier in this chapter.)		
No execute	This indicates that code cannot execute in the page. (It can be used for data only.)		
Owner	This indicates whether user-mode code can access the page or whether the page is limited to kernel-mode access.		
Prototype	The PTE is a prototype PTE, which is used as a template to describe shared memory associated with section objects.		
Valid	This indicates whether the translation maps to a page in physical memory.		
Write through	This marks the page as write-through or, if the processor supports the page attribute table, write- combined. This is typically used to map video frame buffer memory.		
Write	This indicates to the MMU whether the page is writable.		

 TABLE 5-10
 PTE status and protection bits (continued)

On x86 systems, a hardware PTE contains two bits that can be changed by the MMU: the dirty bit and the accessed bit. The MMU sets the accessed bit whenever the page is read or written (provided it is not already set). The MMU sets the dirty bit whenever a write operation occurs to the page. The operating system is responsible for clearing these bits at the appropriate times. They are never cleared by the MMU.

The x86 MMU uses a write bit to provide page protection. When this bit is clear, the page is readonly. When it is set, the page is read/write. If a thread attempts to write to a page with the write bit clear, a memory-management exception occurs. In addition, the memory manager's access fault handler (described later in the section "Page fault handling") must determine whether the thread can be allowed to write to the page (for example, if the page was really marked copy-on-write) or whether an access violation should be generated.

## Hardware versus software write bits in page table entries

The additional write bit implemented in software (refer to Table 5-10) is used to force an update of the dirty bit to be synchronized with updates to Windows memory management data. In a simple implementation, the memory manager would set the hardware write bit (bit 1) for any writable page. A write to any such page will cause the MMU to set the dirty bit in the PTE. Later, the dirty bit will tell the memory manager that the contents of that physical page must be written to backing store before the physical page can be used for something else.

In practice, on multiprocessor systems, this can lead to race conditions that are expensive to resolve. At any time, the MMUs of the various processors can set the dirty bit of any PTE that has its hardware write bit set. The memory manager must, at various times, update the process working set list to reflect the state of the dirty bit in a PTE. The memory manager uses a pushlock to synchronize access to the working set list. But on a multiprocessor system, even while one processor is holding the lock, the dirty bit might be changed by MMUs of other CPUs. This raises the possibility of missing an update to a dirty bit. To avoid this, the Windows memory manager initializes both read-only and writable pages with the hardware write bit (bit 1) of their PTEs set to 0 and records the true writable state of the page in the software write bit (bit 11). On the first write access to such a page, the processor will raise a memory-management exception because the hardware write bit is clear, just as it would be for a true read-only page. In this case, though, the memory manager learns that the page actually *is* writable (via the software write bit), acquires the working set pushlock, sets the dirty bit and the hardware write bit in the PTE, updates the working set list to note that the page has been changed, releases the working set pushlock, and dismisses the exception. The hardware write operation then proceeds as usual, but the setting of the dirty bit is made to happen with the working set list pushlock held.

On subsequent writes to the page, no exceptions occur because the hardware write bit is set. The MMU will redundantly set the dirty bit, but this is benign because the "written-to" state of the page is already recorded in the working set list. Forcing the first write to a page to go through this exception handling may seem to be excessive overhead. However, it happens only once per writable page as long as the page remains valid. Furthermore, the first access to almost any page already goes through memory-management exception handling because pages are usually initialized in the invalid state (the PTE bit 0 is clear). If the first access to a page is also the first write access to the page, the dirty bit handling just described will occur within the handling of the first-access page fault, so the additional overhead is small. Finally, on both uniprocessor and multiprocessor systems, this implementation allows flushing of the translation look-aside buffer (described in the next section) without holding a lock for each page being flushed.

# Translation look-aside buffer

As you've learned, each hardware address translation requires three lookups:

- One to find the right entry in the PDPT
- One to find the right entry in the page directory (which provides the location of the page table)
- One to find the right entry in the page table

Because doing three additional memory lookups for every reference to a virtual address would quadruple the required bandwidth to memory, resulting in poor performance, all CPUs cache address translations so that repeated accesses of the same addresses don't have to be repeatedly translated. This cache is an array of associative memory called the *translation lookaside buffer (TLB)*. Associative memory is a vector whose cells can be read simultaneously and compared to a target value. In the case of the TLB, the vector contains the virtual-to-physical page mappings of the most recently used pages, as shown in Figure 5-19, and the type of page protection, size, attributes, and so on applied to each page. Each entry in the TLB is like a cache entry whose tag holds portions of the virtual address and whose data portion holds a physical page number, protection field, valid bit, and usually a dirty bit indicating the condition of the page to which the cached PTE corresponds. If a PTE's global bit is set (as is done by Windows for system space pages that are visible to all processes), the TLB entry isn't invalidated on process context switches.




FIGURE 5-19 Accessing the TLB.

Frequently used virtual addresses are likely to have entries in the TLB, which provides extremely fast virtual-to-physical address translation and, therefore, fast memory access. If a virtual address isn't in the TLB, it might still be in memory, but multiple memory accesses are needed to find it, which makes the access time slightly slower. If a virtual page has been paged out of memory or if the memory manager changes the PTE, the memory manager is required to explicitly invalidate the TLB entry. If a process accesses it again, a page fault occurs, and the memory manager brings the page back into memory (if needed) and re-creates its PTE (which then results in an entry for it in the TLB).

# **EXPERIMENT:** Translating addresses

To clarify how address translation works, this experiment shows an example of translating a virtual address on an x86 PAE system using the available tools in the kernel debugger to examine the PDPT, page directories, page tables, and PTEs. In this example, you'll work with a process that has virtual address 0x3166004, currently mapped to a valid physical address. In later examples, you'll see how to follow address translation for invalid addresses with the kernel debugger.

First convert 0x3166004 to binary and break it into the three fields used to translate an address. In binary, 0x3166004 is 11.0001.0110.0110.0000.0000.0100. Breaking it into the component fields yields the following:

31 30	29 21	20 12	11 0
00	00.0011.000	1.0110.0110	0000.0000.0100
Page Directory Pointer Index (0	, , ,	Page Table Index (0x166 or 358)	Byte Offset (4)

To start the translation process, the CPU needs the physical address of the process's PDPT. This is found in the CR3 register while a thread in that process is running. You can display this address by looking at the DirBase field in the output of the !process command, as shown here:

```
lkd> !process -1 0
PROCESS 99aa3040 SessionId: 2 Cid: 1690 Peb: 03159000 ParentCid: 0920
DirBase: 01024800 ObjectTable: b3b386c0 HandleCount: <Data Not Accessible>
Image: windbg.exe
```

The Di rBase field shows that the PDPT is at physical address 0x1024800. As shown in the preceding illustration, the PDPT index field in the sample virtual address is 0. Therefore, the PDPT entry that contains the physical address of the relevant page directory is the first entry in the PDPT, at physical address 0x1024800.

The kernel debugger !pte command displays the PDE and PTE that describe a virtual address, as shown here:

```
1kd> !pte 3166004
VA 03166004
PDE at C06000C0 PTE at C0018B30
contains 000000056238867 contains 800000005DE61867
pfn 56238 ---DA--UWEV pfn 5de61 ---DA--UW-V
```

The debugger does not show the PDPT, but it is easy to display given its physical address:

```
1kd> !dq 01024800 L4
# 1024800 0000000'53c88801 00000000'53c89801
# 1024810 0000000'53c8a801 00000000'53c8d801
```

Here we have used the debugger extension command !dq. This is similar to the dq command (display as quadwords—64 bit values) but lets us examine memory by physical rather than virtual address. Because we know the PDPT is only four entries long, we added the L 4 length argument to keep the output uncluttered.

As illustrated, the PDPT index (the two most significant bits) from the sample virtual address equal 0, so the PDPT entry you want is the first displayed quadword. PDPT entries have a format similar to PDEs and PTEs, so you can see that this one contains a PFN of 0x53c88 (always page-aligned), for a physical address of 0x53c88000. That's the physical address of the page directory.

The !pte output shows the PDE address 0xC06000C0 as a virtual address, not physical. On x86 systems, the first process page directory starts at virtual address 0xC0600000. In this case, the PDE address is 0xC0—that is, 8 bytes (the size of an entry) times 24 added to the page directory start address. Therefore, the page directory index field of the sample virtual address is 24. That means you're looking at the 25th PDE in the page directory.

The PDE provides the PFN of the needed page table. In this example, the PFN is 0x56238, so the page table starts at physical address 0x56238000. To this the MMU will add the page table index field (0x166) from the virtual address multiplied by 8 (the size of a PTE in bytes). The resulting physical address of the PTE is 0x56238B30.

The debugger shows that this PTE is at *virtual* address 0xC0018B30. Notice that the byte offset portion (0xB30) is the same as that from the physical address, as is always the case in address translation. Because the memory manager maps page tables starting at 0xC0000000, adding 0xB30 to 0xC0018000 (the 0x18 is entry 24 as you've seen) yields the virtual address shown in the kernel debugger output: 0xC0018B30. The debugger shows that the PFN field of the PTE is 0x5DE61.

Finally, you can consider the byte offset from the original address. As described, the MMU concatenates the byte offset to the PFN from the PTE, giving a physical address of 0x5DE61004. This is the physical address that corresponds to the original virtual address of 0x3166004...at the moment.

The flags bits from the PTE are interpreted to the right of the PFN number. For example, the PTE that describes the page being referenced has flags of ---DA--UW-V. Here, A stands for accessed (the page has been read), U for user-mode accessible (as opposed to kernel-mode accessible only), W for writable page (rather than just readable), and V for valid (the PTE represents a valid page in physical memory).

To confirm the calculation of the physical address, look at the memory in question via both its virtual and its physical addresses. First, using the debugger's dd (display dwords) command on the virtual address, you see the following:

1kd> dd 3166004 L 10 03166004 0000034 0000006 00003020 000004e 03166014 0000000 00020020 0000a000 0000014

And with the !dd command on the physical address just computed, you see the same contents:


1kd> !dd 5DE61004 L 10
#5DE61004 00000034 00000006 00003020 0000004e
#5DE61014 0000000 00020020 0000a000 00000014


You could similarly compare the displays from the virtual and physical addresses of the PTE and PDE.

### x64 virtual address translation

Address translation on x64 is similar to x86, but with a fourth level added. Each process has a top-level extended page directory called the *page map level 4 table* that contains the physical locations of 512 third-level structures, called *page directory pointers*. The page parent directory is analogous to the x86 PAE PDPT, but there are 512 of them instead of just one, and each page parent directory is an entire page containing 512 entries instead of just four. Like the PDPT, the page parent directory's entries contain the physical locations of second-level page directories, each of which in turn contains 512 entries providing the locations of the individual page tables. Finally, the page tables, each of which contains 512 page table entries, contain the physical locations of the pages in memory. All the "physical locations" in the preceding description are stored in these structures as PFNs.

Current implementations of the x64 architecture limit virtual addresses to 48 bits. The components that make up this 48-bit virtual address and the connection between the components for translation purposes are shown in Figure 5-20, and the format of an x64 hardware PTE is shown in Figure 5-21.








FIGURE 5-21 x64 hardware PTE.

#### ARM virtual address translation

Virtual address translation on ARM 32-bit processors uses a single page directory with 1,024 entries, each 32 bits in size. The translation structures are shown in Figure 5-22.






FIGURE 5-22 ARM virtual address translation structures.

Every process has a single page directory, with its physical address stored in the TTBR register (similar to the CR3 x86/x64 register). The 10 most significant bits of the virtual address select a PDE that may point to one of 1,024 page tables. A specific PTE is selected by the next 10 bits of the virtual address. Each valid PTE points to the start of a page in physical memory, where the offset is given by the lower 12 bits of the address (just as in the x86 and x64 cases). The scheme in Figure 5-22 suggests that the addressable physical memory is 4 GB because each PTE is smaller (32 bits) than the x86/x64 case (64 bits), and indeed only 20 bits are used for the PFN. ARM processors do support a PAE mode (similar to x86), but Windows does not use this functionality. Future Windows versions may support the ARM 64-bit architecture, which will alleviate the physical address limitations as well as dramatically increase the virtual address space for processes and the system.

Curiously, the layout of valid PTE, PDE, and large page PDE are not the same. Figure 5-23 shows the layout of a valid PTE for ARMv7, currently used by Windows. For more information, consult the official ARM documentation.







## Page fault handling

Earlier, you saw how address translations are resolved when the PTE is valid. When the PTE valid bit is clear, this indicates that the desired page is for some reason not currently accessible to the process. This section describes the types of invalid PTEs and how references to them are resolved.

**Note** Only the 32-bit x86 PTE formats are detailed in this section. PTEs for 64-bit and ARM systems contain similar information, but their detailed layout is not presented.

A reference to an invalid page is called a *page fault*. The kernel trap handler (see the section "Trap dispatching" in Chapter 8 in Part 2) dispatches this kind of fault to the memory manager fault handler function, MmAccessFault, to resolve. This routine runs in the context of the thread that incurred the fault and is responsible for attempting to resolve the fault (if possible) or raise an appropriate exception. These faults can be caused by a variety of conditions, as listed in Table 5-11.

Reason for Fault	Result					
Corrupt PTE/PDE	Bug-check (crash) the system with code 0x1A (MEMORY_MANAGEMENT).					
Accessing a page that isn't resident in memory but is on disk in a page file or a mapped file	Allocate a physical page and read the desired page from disk and into the relevant working set.					
Accessing a page that is on the standby or modified list	Transition the page to the relevant process, session, or system working set.					
Accessing a page that isn't committed (for example, reserved address space or address space that isn't allocated)	Access violation exception.					
Accessing a page from user mode that can be accessed only in kernel mode	Access violation exception.					
Writing to a page that is read-only	Access violation exception.					
Accessing a demand-zero page	Add a zero-filled page to the relevant working set.					
Writing to a guard page	Guard-page violation (if there is a reference to a user- mode stack, perform automatic stack expansion).					
Writing to a copy-on-write page	Make a process-private (or session-private) copy of the page and use it to replace the original in the process, session, or system working set.					
Writing to a page that is valid but hasn't been written to the current backing store copy	Set the dirty bit in the PTE.					
Executing code in a page that is marked as no execute	Access violation exception.					
PTE permissions don't match enclave permissions (see the sec- tion "Memory enclaves" later in this chapter and the Windows SDK documentation for the CreateEnclave function)	User mode: access violation exception. Kernel mode: bug-check with code 0x50 (PAGE_FAULT_IN_NONPAGED_AREA).					

#### TABLE 5-11 Reasons for access faults

The following section describes the four basic kinds of invalid PTEs that are processed by the access fault handler. Following that is an explanation of a special case of invalid PTEs, called *prototype PTEs*, which are used to implement shareable pages.

## **Invalid PTEs**

If the valid bit of a PTE encountered during address translation is zero, the PTE represents an invalid page—one that will raise a memory-management exception, or page fault, upon reference. The MMU ignores the remaining bits of the PTE, so the operating system can use these bits to store information about the page that will assist in resolving the page fault.

The following list details the four kinds of invalid PTEs and their structure. These are often referred to as *software PTEs* because they are interpreted by the memory manager rather than the MMU. Some of the flags are the same as those for a hardware PTE, as described in Table 5-10, and some of the bit fields have either the same or similar meanings to corresponding fields in the hardware PTE.

Page file The desired page resides within a paging file. As illustrated in Figure 5-24, 4 bits in the PTE indicate in which of 16 possible page files the page resides, and 32 bits provide the page number within the file. The pager initiates an in-page operation to bring the page into memory and make it valid. The page file offset is always non-zero and never all ones (that is, the very first and last pages in the page file are not used for paging) to allow for other formats, described next.




FIGURE 5-24 A PTE representing a page in a page file.

- Demand zero This PTE format is the same as the page file PTE shown in the previous entry but the page file offset is zero. The desired page must be satisfied with a page of zeroes. The pager looks at the zero page list. If the list is empty, the pager takes a page from the free list and zeroes it. If the free list is also empty, it takes a page from one of the standby lists and zeroes it.
- Virtual Address Descriptor This PTE format is the same as the page file PTE shown previously but in this case the page file offset field is all one. This indicates a page whose definition and backing store, if any, can be found in the process's Virtual Address Descriptor (VAD) tree. This format is used for pages that are backed by sections in mapped files. The pager finds the VAD that defines the virtual address range encompassing the virtual page and initiates an in-page operation from the mapped file referenced by the VAD. (VADs are described in more detail in the section "Virtual address descriptors" later in this chapter.)
- Transition The transition bit is one. The desired page is in memory on either the standby, modified, or modified-no-write list or not on any list. The pager will remove the page from the list (if it is on one) and add it to the process working set. This is known as a *soft page fault* because no I/O is involved.
- Unknown The PTE is zero or the page table doesn't yet exist. (The PDE that would provide the physical address of the page table contains zero.) In both cases, the memory manager must

examine the VADs to determine whether this virtual address has been committed. If so, page tables are built to represent the newly committed address space. If not—that is, if the page is reserved or hasn't been defined at all—the page fault is reported as an access violation exception.

### **Prototype PTEs**

If a page can be shared between two processes, the memory manager uses a software structure called *prototype page table entries* (*prototype PTEs*) to map these potentially shared pages. For page-file–backed sections, an array of prototype PTEs is created when a section object is first created. For mapped files, portions of the array are created on demand as each view is mapped. These prototype PTEs are part of the segment structure (described in the section "Section objects" later in this chapter).

When a process first references a page mapped to a view of a section object (recall that VADs are created only when the view is mapped), the memory manager uses the information in the prototype PTE to fill in the real PTE used for address translation in the process page table. When a shared page is made valid, both the process PTE and the prototype PTE point to the physical page containing the data. To track the number of process PTEs that reference a valid shared page, a counter in its PFN database entry is incremented. Thus, the memory manager can determine when a shared page is no longer referenced by any page table and thus can be made invalid and moved to a transition list or written out to disk.

When a shareable page is invalidated, the PTE in the process page table is filled in with a special PTE that points to the prototype PTE that describes the page, as shown in Figure 5-25. Thus, when the page is accessed, the memory manager can locate the prototype PTE using the information encoded in this PTE, which in turn describes the page being referenced.




FIGURE 5-25 Structure of an invalid PTE that points to the prototype PTE.

A shared page can be in one of six different states, as described by the prototype PTE:

- Active/valid The page is in physical memory because of another process that accessed it.
- **Transition** The desired page is in memory on the standby or modified list (or not on any list).
- Modified-no-write The desired page is in memory and on the modified-no-write list. (Refer to Table 5-11.)
- **Demand zero** The desired page should be satisfied with a page of zeroes.
- Page file The desired page resides within a page file.
- Mapped file The desired page resides within a mapped file.

Although the format of these prototype PTEs is the same as that of the real PTEs described earlier, the prototype PTEs aren't used for address translation. They are a layer between the page table and the PFN database and never appear directly in page tables.

By having all the accessors of a potentially shared page point to a prototype PTE to resolve faults, the memory manager can manage shared pages without needing to update the page tables of each process sharing the page. For example, a shared code or data page might be paged out to disk at some point. When the memory manager retrieves the page from disk, it needs only to update the prototype PTE to point to the page's new physical location. The PTEs in each of the processes sharing the page remain the same, with the valid bit clear and still pointing to the prototype PTE. Later, as processes reference the page, the real PTE will get updated.

Figure 5-26 illustrates two virtual pages in a mapped view. One is valid and the other is invalid. As shown, the first page is valid and is pointed to by the process PTE and the prototype PTE. The second page is in the paging file—the prototype PTE contains its exact location. The process PTE (and any other processes with that page mapped) points to this prototype PTE.




FIGURE 5-26 Prototype page table entries.

# In-paging I/O

In-paging I/O occurs when a read operation must be issued to a file (paging or mapped) to satisfy a page fault. Also, because page tables are themselves pageable, the processing of a page fault can incur additional I/O if necessary when the system is loading the page table page that contains the PTE or the prototype PTE that describes the original page being referenced.

The in-page I/O operation is synchronous—that is, the thread waits on an event until the I/O completes—and isn't interruptible by asynchronous procedure call (APC) delivery. The pager uses a special modifier in the I/O request function to indicate paging I/O. Upon completion of paging I/O, the I/O system triggers an event, which wakes up the pager and allows it to continue in-page processing.

While the paging I/O operation is in progress, the faulting thread doesn't own any critical memory management synchronization objects. Other threads within the process can issue virtual memory

functions and handle page faults while the paging I/O takes place. But there are a few interesting conditions that the pager must recognize when the I/O completes are exposed:

- Another thread in the same process or a different process could have faulted the same page (called a *collided page fault* and described in the next section).
- The page could have been deleted and remapped from the virtual address space.
- The protection on the page could have changed.
- The fault could have been for a prototype PTE, and the page that maps the prototype PTE could be out of the working set.

The pager handles these conditions by saving enough state on the thread's kernel stack before the paging I/O request such that when the request is complete, it can detect these conditions and, if necessary, dismiss the page fault without making the page valid. When and if the faulting instruction is reissued, the pager is again invoked and the PTE is reevaluated in its new state.

# Collided page faults

The case when another thread in the same process or a different process faults a page that is currently being in-paged is known as a *collided page fault*. The pager detects and handles collided page faults optimally because they are common occurrences in multithreaded systems. If another thread or process faults the same page, the pager detects the collided page fault, noticing that the page is in transition and that a read is in progress. (This information is in the PFN database entry.) In this case, the pager may issue a wait operation on the event specified in the PFN database entry. Alternatively, it can choose to issue a parallel I/O to protect the file systems from deadlocks. (The first I/O to complete "wins," and the others are discarded.) This event was initialized by the thread that first issued the I/O needed to resolve the fault.


When the I/O operation completes, all threads waiting on the event have their wait satisfied. The first thread to acquire the PFN database lock is responsible for performing the in-page completion operations. These operations consist of checking I/O status to ensure that the I/O operation completed successfully, clearing the read-in-progress bit in the PFN database, and updating the PTE.

When subsequent threads acquire the PFN database lock to complete the collided page fault, the pager recognizes that the initial updating has been performed because the read-in-progress bit is clear and checks the in-page error flag in the PFN database element to ensure that the in-page I/O completed successfully. If the in-page error flag is set, the PTE isn't updated, and an in-page error exception is raised in the faulting thread.

# **Clustered page faults**

The memory manager prefetches large clusters of pages to satisfy page faults and populate the system cache. The prefetch operations read data directly into the system's page cache instead of into a working set in virtual memory. Therefore, the prefetched data does not consume virtual address space, and the size of the fetch operation is not limited to the amount of virtual address space that is available.

Also, no expensive TLB-flushing inter-processor interrupt (IPI) is needed if the page will be repurposed. The prefetched pages are put on the standby list and marked as in transition in the PTE. If a prefetched page is subsequently referenced, the memory manager adds it to the working set. However, if it is never referenced, no system resources are required to release it. If any pages in the prefetched cluster are already in memory, the memory manager does not read them again. Instead, it uses a dummy page to represent them so that an efficient single large I/O can still be issued, as shown in Figure 5-27.



Pages Y and Z are already in memory, so the corresponding MDL entries point to the system-wide dummy page



In the figure, the file offsets and virtual addresses that correspond to pages A, Y, Z, and B are logically contiguous, although the physical pages themselves are not necessarily contiguous. Pages A and B are nonresident, so the memory manager must read them. Pages Y and Z are already resident in memory, so it is not necessary to read them. (In fact, they might already have been modified since they were last read in from their backing store, in which case it would be a serious error to overwrite their contents.) However, reading pages A and B in a single operation is more efficient than performing one read for page A and a second read for page B. Therefore, the memory manager issues a single read request that comprises all four pages (A, Y, Z, and B) from the backing store. Such a read request includes as many pages as it makes sense to read, based on the amount of available memory, the current system usage, and so on.

When the memory manager builds the MDL that describes the request, it supplies valid pointers to pages A and B. However, the entries for pages Y and Z point to a single system-wide dummy page X. The memory manager can fill the dummy page X with the potentially stale data from the backing store because it does not make X visible. However, if a component accesses the Y and Z offsets in the MDL, it sees the dummy page X instead of Y and Z.

The memory manager can represent any number of discarded pages as a single dummy page, and that page can be embedded multiple times in the same MDL or even in multiple concurrent MDLs that are being used for different drivers. Consequently, the contents of the locations that represent the discarded pages can change at any time. (See Chapter 6 for more on MDLs.)

# Page files

Page files store modified pages that are still in use by some process but have had to be written to disk because they were unmapped or memory pressure resulted in a trim. Page file space is reserved when the pages are initially committed, but the actual optimally clustered page file locations cannot be chosen until pages are written out to disk.

When the system boots, the Session Manager process (Smss.exe) reads the list of page files to open by examining the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Memory Management\ PagingFiles registry value. This multistring registry value contains the name, minimum size, and maximum size of each paging file. Windows supports up to 16 paging files on x86 and x64 and up to 2 page files on ARM. On x86 and x64 systems, each page file can be up to 16 TB in size, while the maximum is 4 GB on ARM systems. Once open, the page files can't be deleted while the system is running because the System process maintains an open handle to each page file.

Because the page file contains parts of process and kernel virtual memory, for security reasons, the system can be configured to clear the page file at system shutdown. To enable this, set the ClearPage-FileAtShutdown registry value in the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\ Memory Management key to 1. Otherwise, after shutdown, the page file will contain whatever data happened to have been paged out while the system was up. This data could then be accessed by some-one who gained physical access to the machine.

If the minimum and maximum paging file sizes are both zero (or not specified), this indicates a system-managed paging file. Windows 7 and Server 2008 R2 used a simple scheme based on RAM size alone as follows:

- Minimum size Set to the amount of RAM or 1 GB, whichever is larger
- Maximum size Set to 3 \* RAM or 4 GB, whichever is larger

These settings are not ideal. For example, today's laptops and desktop machines can easily have 32 GB or 64 GB of RAM, and server machines can have hundreds of gigabytes of RAM. Setting the initial page file size to the size of RAM may result in a considerable loss of disk space, especially if disk sizes are relatively small and based on solid-state device (SSD). Furthermore, the amount of RAM in a system is not necessarily indicative of the typical memory workload on that system.

The current implementation uses a more elaborate scheme to derive a "good" minimum page file size based not only on RAM size, but also on page file history usage and other factors. As part of page-file creation and initialization, Smss.exe calculates page file minimum sizes based on four factors, stored in global variables:

- **RAM (SmpDesiredPfSizeBasedOnRAM)** This is the recommended page file size based on RAM.
- Crash dump (SmpDesiredPfSizeForCrashDump) This is the recommended page file size needed to be able to store a crash dump.
- **History (SmpDesiredPfSizeBasedOnHistory)** This is the recommended page file size based on usage history. Smss.exe uses a timer that triggers once an hour and records the page file usage.

- **Apps (SmpDesiredPfSizeForApps)** This is the recommended page file for Windows apps.
- These values are computed as shown in Table 5-12.

Recommendation Base	Recommended Page File Size
RAM	If RAM <= 1 GB, then size = 1 GB. If RAM > 1 GB, then add 1/8 GB for every extra gigabyte of RAM, up to a maximum of 32 GB.
Crash dump	If a dedicated dump file is configured, then no page file is required for storing a dump file, and the size = 0. (You can configure this for a dedicated dump file by adding the value DedicatedDumpFile in the HKLM\System\CurrentControlSet\Control\CrashControl key.) If the dump type configured is set to Automatic (the default), then: If RAM < 4 GB, then size = RAM / 6. Otherwise, size = 2/3 GB + 1/8 GB for each extra gigabyte above 4 GB, capped to 32 GB. If there was a recent crash for which the page file was not large enough, then recommend- ed size is increased to RAM size or 32 GB, whichever is smaller. If a full dump is configured, returned size = RAM size plus additional information size pres- ent in a dump file. If a kernel dump is configured, then size = RAM.
History	If enough samples have been logged, returns the 90 <sup>th</sup> percentile as the recommended size. Otherwise, returns the size based on RAM (above).
Apps	If it's a server, return zero. The recommended size is based on a factor that the Process Lifecycle Manager (PLM) uses to determine when to terminate an app. Current factor is 2.3 * RAM, which was considered with RAM = 1 GB (rough minimum for mobile devices). The recommended size (based on the mentioned factor) is around 2.5 GB. If this is more than RAM, RAM is subtracted. Otherwise, zero is returned.

**TABLE 5-12** Base calculation for page file size recommendation

The maximum page file size for a system-managed size is set at three times the size of RAM or 4 GB, whichever is larger. The minimum (initial) page file size is determined as follows:

- If it's the first system-managed page file, then the base size is set based on page file history (refer to Table 5-12). Otherwise, the base size is based on RAM.
- If it's the first system-managed page file:
  - If the base size is smaller than the computed page file size for apps (SmpDesiredPfSize-ForApps), then set the new base as the size computed for apps (refer to Table 5-12).
  - If the (new) base size is smaller than the computed size for crash dumps (SmpDesiredPf-SizeForCrashDump), then set the new base to be the size computed for crash dumps.

#### **EXPERIMENT:** Viewing page files

To view the list of page files, look in the registry at the PagingFiles value in the HKLM\SYSTEM\ CurrentControlSet\Control\Session Manager\Memory Management key. This entry contains the paging file configuration settings modified through the Advanced System Settings dialog box. To access these settings, follow these steps:

1. Open Control Panel.

- Click System and Security and then click System. This opens the System Properties dialog box, which you can also access by right-clicking on Computer in Explorer and selecting Properties.
- 3. Click Advanced System Settings.
- **4.** In the Performance area, click **Settings**. This opens the Performance Options dialog box.
- 5. Click the Advanced tab.
- 6. In the Virtual Memory area, click Change.

#### **EXPERIMENT:** Viewing page file recommended sizes

To view the actual variables calculated in Table 5-12, follow these steps (this experiment was done using an x86 Windows 10 system):

- 1. Start local kernel debugging.
- 2. Locate Smss.exe processes:

```
lkd> !process 0 0 smss.exe
PROCESS 8e54bc40 SessionId: none Cid: 0130 Peb: 02bab000 ParentCid:
0004
DirBase: bffe0020 ObjectTable: 8a767640 HandleCount: <Data Not
Accessible>
Image: smss.exe
```

- PROCESS 9985bc40 SessionId: 1 Cid: 01d4 Peb: 02f9c000 ParentCid: 0130 DirBase: bffe0080 ObjectTable: 00000000 HandleCount: 0. Image: smss.exe
- PROCESS a122dc40 SessionId: 2 Cid: 02a8 Peb: 02fcd000 ParentCid: 0130 DirBase: bffe0320 ObjectTable: 00000000 HandleCount: 0. Image: smss.exe
- Locate the first one (with a session ID of none), which is the master Smss.exe. (Refer to Chapter 2 for more details.)
- 4. Switch the debugger context to that process:

```
lkd> .process /r /p 8e54bc40
Implicit process is now 8e54bc40
Loading User Symbols
```

. .

5. Show the four variables described in the previous section. (Each one is 64 bits in size.)

```
lkd> dq smss!SmpDesiredPfSizeBasedOnRAM L1
00974cd0 0000000'4fff1a00
```

lkd> dq smss!SmpDesiredPfSizeBasedOnHistory L1 00974cd8 0000000'05a24700 lkd> dq smss!SmpDesiredPfSizeForCrashDump L1 00974cc8 0000000'1ffecd55 lkd> dq smss!SmpDesiredPfSizeForApps L1 00974ce0 0000000'0000000

6. Because there is a single volume (C:\) on this machine, a single page file would be created. Assuming it wasn't specifically configured, it would be system managed. You can look at the actual file size of C:\PageFile.Sys on disk or use the !vm debugger command:

```
1kd> !vm 1
Page File: \??\C:\pagefile.sys
Current: 524288 Kb Free Space: 524280 Kb
Minimum: 524288 Kb Maximum: 8324476 Kb
Page File: \??\C:\swapfile.sys
Current: 262144 Kb Free Space: 262136 Kb
Minimum: 262144 Kb Maximum: 4717900 Kb
No Name for Paging File
Current: 11469744 Kb Free Space: 11443108 Kb
Minimum: 11469744 Kb Maximum: 11469744 Kb
...
```

Notice the minimum size of C:\PageFIle.sys (524288 KB). (We'll discuss the other page file entries in the next section). According to the variables, SmpDesiredPfSizeForCrashDump is the largest, so must be the determining factor (0x1FFECD55 = 524211 KB), which is very close to the listed value. (Page file sizes round up to multiple of 64 MB.)

To add a new page file, Control Panel uses the internal NtCreatePagingFile system service defined in Ntdll.dll. (This requires the SeCreatePagefilePrivilege.) Page files are always created as noncompressed files, even if the directory they are in is compressed. Their names are *PageFile.Sys* (except some special ones described in the next section). They are created in the root of partitions with the Hidden file attribute so they are not immediately visible. To keep new page files from being deleted, a handle is duplicated into the System process so that even after the creating process closes the handle to the new page file, a handle is nevertheless always open to it.

#### The swap file

In the UWP apps world, when an app goes to the background—for example, it is minimized—the threads in that process are suspended so that the process does not consume any CPU. The private physical memory used by the process can potentially be reused for other processes. If memory pressure is high, the private working set (physical memory used by the process) may be swapped out to disk to allow the physical memory to be used for other processes.

Windows 8 added another page file called a *swap file*. It is essentially the same as a normal page file but is used exclusively for UWP apps. It's created on client SKUs only if at least one normal page file was created (the normal case). Its name is *SwapFile.sys* and it resides in the system root partition—for example, C:\SwapFile.Sys.

After the normal page files are created, the HKLM\System\CurrentControlSet\Control\Session Manager\Memory Management registry key is consulted. If a DWORD value named SwapFileControl exists and its value is zero, swap file creation is aborted. If a value named SwapFile exists, it's read as a string with the same format as a normal page file, with a filename, an initial size, and a maximum size. The difference is that a value of zero for the sizes is interpreted as no swap file creation. These two registry values do not exist by default, which results in the creation of a SwapFile.sys file on the system root partition with a minimum size of 16 MB on fast (and small) disks (for example, SSD) or 256 MB on slow (or large SSD) disks. The maximum size of the swap file is set to 1.5 \* RAM or 10 percent of the system root partition size, whichever is smaller. See Chapter 7 in this book and Chapter 8, "System mechanisms," and Chapter 9, "Management mechanisms," in Part 2 for more on UWP apps.

Note The swap file is not counted against the maximum page files supported.

#### The virtual page file

The !vm debugger command hints at another page file called "No Name for Paging File." This is a virtual page file. As the name suggests, it has no actual file, but is used indirectly as the backing store for memory compression (described later in this chapter in the section "Memory compression"). It is large, but its size is set arbitrarily as not to run out of free space. The invalid PTEs for pages that have been compressed point to this virtual page file and allow the memory compression store to get to the compressed data when needed by interpreting the bits in the invalid PTE leading to the correct store, region, and index.

#### EXPERIMENT: Viewing swap file and virtual page file information

The !vm debugger command shows the information on all page files, including the swap file and the virtual page file:

```
1kd> !vm 1
Page File: \??\C:\pagefile.sys
Current: 524288 Kb Free Space: 524280 Kb
Minimum: 524288 Kb Maximum: 8324476 Kb
Page File: \??\C:\swapfile.sys
Current: 262144 Kb Free Space: 262136 Kb
Minimum: 262144 Kb Maximum: 4717900 Kb
No Name for Paging File
Current: 11469744 Kb Free Space: 11443108 Kb
Minimum: 11469744 Kb Maximum: 11469744 Kb
```

On this system, the swap file minimum size is 256 MB, as the system is a Windows 10 virtual machine. (The VHD behind the disk is considered a slow disk.) The maximum size of the swap file is about 4.5 GB, as the RAM on the system is 3 GB and disk partition size is 64 GB (the minimum of 4.5 GB and 6.4 GB).

### Commit charge and the system commit limit

We are now in a position to more thoroughly discuss the concepts of commit charge and the system commit limit.

Whenever virtual address space is created—for example, by a VirtualAlloc (for committed memory) or MapViewOfFile call—the system must ensure that there is room to store it, either in RAM or in backing store, before successfully completing the create request. For mapped memory (other than sections mapped to the page file), the file associated with the mapping object referenced by the MapViewOfFile call provides the required backing store. All other virtual allocations rely on system-managed shared resources for storage: RAM and the paging file(s). The purpose of the system commit limit and commit charge is to track all uses of these resources to ensure they are never overcommit-ted—that is, that there is never more virtual address space defined than there is space to store its contents, either in RAM or in backing store (on disk).

**Note** This section makes frequent references to paging files. It is possible (though not generally recommended) to run Windows without any paging files. Essentially, this means that when RAM is exhausted, there is no room to grow and memory allocations fail, generating a blue screen. You can consider every reference to paging files here to be qualified by "if one or more paging files exist."

Conceptually, the system commit limit represents the total committed virtual address space that can be created in addition to virtual allocations that are associated with their own backing store—that is, in addition to sections mapped to files. Its numeric value is simply the amount of RAM available to Windows plus the current sizes of any page files. If a page file is expanded or new page files are created, the commit limit increases accordingly. If no page files exist, the system commit limit is simply the total amount of RAM available to Windows.

Commit charge is the system-wide total of all committed memory allocations that must be kept in either RAM or in a paging file. From the name, it should be apparent that one contributor to commit charge is process-private committed virtual address space. However, there are many other contributors, some of them not so obvious.

Windows also maintains a per-process counter called the *process page file quota*. Many of the allocations that contribute to commit charge also contribute to the process page file quota. This represents each process's private contribution to the system commit charge. Note, however, that this does not represent current page file usage. It represents the potential or maximum page file usage, should all these allocations have to be stored there.

The following types of memory allocations contribute to the system commit charge and, in many cases, to the process page file quota. (Some of these will be described in detail in later sections of this chapter.)

 Private committed memory This is memory allocated with the VirtualAlloc call with the MEM\_COMMIT option. This is the most common type of contributor to the commit charge. These allocations are also charged to the process page file quota.

- Page-file-backed mapped memory This is memory allocated with a MapViewOfFile call that references a section object, which in turn is not associated with a file. The system uses a portion of the page file as the backing store instead. These allocations are not charged to the process page file quota.
- Copy-on-write regions of mapped memory (even if it is associated with ordinary mapped files) The mapped file provides backing store for its own unmodified content. However, should a page in the copy-on-write region be modified, it can no longer use the original mapped file for backing store. It must be kept in RAM or in a paging file. These allocations are not charged to the process page file quota.
- Non-paged and paged pool and other allocations in system space that are not backed by explicitly associated files Even the currently free regions of the system memory pools contribute to commit charge. The non-pageable regions are counted in the commit charge even though they will never be written to the page file because they permanently reduce the amount of RAM available for private pageable data. These allocations are not charged to the process page file quota.
- **Kernel stacks** Threads' stacks when executing in kernel mode.
- Page tables Most of these are themselves pageable, and they are not backed by mapped files. However, even if they are not pageable, they occupy RAM. Therefore, the space required for them contributes to commit charge.
- Space for page tables that are not yet actually allocated As you'll see, where large areas of virtual space have been defined but not yet referenced (for example, private committed virtual space), the system need not actually create page tables to describe it. However, the space for these as-yet-nonexistent page tables is charged to commit charge to ensure that the page tables can be created when they are needed.
- Allocations of physical memory made via the Address Windowing Extension (AWE) APIs As discussed previously, consume physical memory directly.

For many of these items, the commit charge may represent the potential use of storage rather than its actual use. For example, a page of private committed memory does not actually occupy either a physical page of RAM or the equivalent page file space until it's been referenced at least once. Until then, it is a *demand-zero page* (described later). But commit charge accounts for such pages when the virtual space is first created. This ensures that when the page is later referenced, actual physical storage space will be available for it.

A region of a file mapped as copy-on-write has a similar requirement. Until the process writes to the region, all pages in it are backed by the mapped file. However, the process may write to any of the pages in the region at any time. When that happens, those pages are thereafter treated as private to the process. Their backing store is, thereafter, the page file. Charging the system commit for them when the region is first created ensures that there will be private storage for them later, if and when the write accesses occur.

A particularly interesting case occurs when reserving private memory and later committing it. When the reserved region is created with VirtualAlloc, system commit charge is not charged for the actual virtual region. On Windows 8 and Server 2012 and earlier versions, it is charged for any new page table pages that will be required to describe the region, even though these might not yet exist or even be eventually needed. Starting with Windows 8.1 and Server 2012 R2, page table hierarchies for reserved regions are not charged immediately; this means that huge reserved memory regions can be allocated without exhausting page tables. This becomes important in some security features, such as Control Flow Guard (CFG, see Chapter 7 for more details). If the region or a part of it is later committed, system commit is charged to account for the size of the region (and page tables), as is the process page file quota.

To put it another way, when the system successfully completes, for example, a VirtualAlloc commit or MapViewOfFile call, it makes a commitment that the necessary storage will be available when needed, even if it wasn't needed at that moment. Thus, a later memory reference to the allocated region can never fail for lack of storage space. (Of course, it could still fail for other reasons, such as page protection, the region being deallocated, and so on.) The commit charge mechanism allows the system to keep this commitment.

The commit charge appears in the Performance Monitor counters as Memory: Committed Bytes. It is also the first of the two numbers displayed on the Task Manager's Performance tab with the legend Commit (the second being the commit limit), and it is displayed by Process Explorer's System Information Memory tab as Commit Charge – Current.

The process page file quota appears in the performance counters as Process: Page File Bytes. The same data appears in the Process: Private Bytes performance counter. (Neither term exactly describes the true meaning of the counter.)

If the commit charge ever reaches the commit limit, the memory manager will attempt to increase the commit limit by expanding one or more page files. If that is not possible, subsequent attempts to allocate virtual memory that uses commit charge will fail until some existing committed memory is freed. The performance counters listed in Table 5-13 allow you to examine private committed memory usage on a system-wide, per-process, or per-page-file, basis.

Performance Counter	Description
Memory: Committed Bytes	This is the number of bytes of virtual (not reserved) memory that has been committed. This number doesn't necessarily represent page file usage because it includes private committed pages in physical memory that have never been paged out. Rather, it repre- sents the charged amount that must be backed by page file space and/or RAM.
Memory: Commit Limit	This is the number of bytes of virtual memory that can be committed without having to extend the paging files. If the paging files can be extended, this limit is soft.
Process: Page File Quota	This is the process's contribution to Memory: Committed Bytes.
Process: Private Bytes	This is the same as Process: Page File Quota.
Process: Working Set – Private	This is the subset of Process: Page File Quota that is currently in RAM and can be refer- enced without a page fault. It is also a subset of Process: Working Set.
Process: Working Set	This is the subset of Process: Virtual Bytes that is currently in RAM and can be referenced without a page fault.
Process: Virtual Bytes	This is the total virtual memory allocation of the process, including mapped regions, private committed regions, and private reserved regions.
Paging File: % Usage	This is the percentage of the page file space that is currently in use.
Paging File: % Usage Peak	This is the highest observed value of Paging File: % Usage.

**TABLE 5-13** Committed memory and page file performance counters

# Commit charge and page file size

The counters in Table 5-13 can assist you in choosing a custom page file size. The default policy based on the amount of RAM works acceptably for most machines, but depending on the workload, it can result in a page file that's unnecessarily large or not large enough.

To determine how much page-file space your system really needs based on the mix of applications that have run since the system booted, examine the peak commit charge in the Memory tab of Process Explorer's System Information display. This number represents the peak amount of page file space since the system booted that would have been needed if the system had to page out the majority of private committed virtual memory (which rarely happens).

If the page file on your system is too big, the system will not use it any more or less. In other words, increasing the size of the page file does not change system performance. It simply means the system can have more committed virtual memory. If the page file is too small for the mix of applications you are running, you might get a "system running low on virtual memory" error message. In this case, check to see whether a process has a memory leak by examining the process private bytes count. If no process appears to have a leak, check the system paged pool size. If a device driver is leaking paged pool, this might also explain the error. Refer to the "Troubleshooting a pool leak" experiment in the "Kernel-mode heaps (system memory pools)" section for information on troubleshooting a pool leak.

#### EXPERIMENT: Viewing page file usage with Task Manager

You can view committed memory usage with Task Manager. To do so, click its **Performance** tab. You'll see the following counters related to page files:

ocesses Performance App hi	story Startup Users Details Services		
CPU 85% 2.79 GHz	Memory Memory usage		2.0 GB
Memory 1.6/2.0 GB (80%)		~	
Disk 0 (C:)			
Ethernet S: 40.0 R: 0 Kbps	60 seconds Memory composition		0
	In use (Compressed) Available 1.6 GB (50.2 MB) 446 MB Committed Cached 1.8/3.1 GB 414 MB	Slots used: Hardware reserved: Maximum memory:	
	Paged pool Non-paged pool 159 MB 88.9 MB		

The system commit total is displayed under the **Committed** label as two numbers. The first number represents *potential* page file usage, not actual page file usage. It is how much page file space would be used if all the private committed virtual memory in the system had to be paged out all at once. The second number displayed is the *commit limit*, which is the maximum virtual memory usage that the system can support before running out of virtual memory. (This includes virtual memory backed in physical memory as well as by the paging files.) The commit limit is essentially the size of RAM plus the current size of the paging files. It therefore does not account for possible page file expansion.

Process Explorer's System Information display shows an additional piece of information about system commit usage—namely, the percentage of the peak as compared to the limit and the current usage as compared to the limit:

System Commit					
	-				
	-				
1.7 GB					
Physical Memory					
1.5 GB					
A DEPOSIT					
Commit Charge (	ACC CONTRACTORIES COLLES	Kernel Memory (K)	Paging Lists (K) Zeroed	79,604	
Current	1,781,668	Paged WS 155,372	Free	28	
Limit	3,276,340	Paged Virtual 161,824	Modified	16,336	
Peak	1,909,232	Paged Limit no symbols	ModifiedNoWrite	0	
Peak/Limit	58.27%	Nonpaged 90,508	Standby	430,656	
Current/Limit	54.38%	Nonpaged Limit no symbols	Priority 0	804	
Physical Memory	00	Paging	Priority 1	896	
Total	2,096,692	Page Fault Delta 1,569	Priority 2 Priority 3	15,860	
Available	510,288	Page Read Delta 0	Priority 4	2.060	
Cache WS	0	Paging File Write Delta 0	Priority 5	360,532	
Kernel WS	3,216	Mapped File Write Delta 0	Priority 6	16,988	
Driver WS	16,372		Priority 7	33,344	
			PageFileModified	16,272	

### **Stacks**

Whenever a thread runs, it must have access to a temporary storage location in which to store function parameters, local variables, and the return address after a function call. This part of memory is called a *stack*. On Windows, the memory manager provides two stacks for each thread: the user stack and the kernel stack, as well as per-processor stacks called DPC stacks. Chapter 2 briefly discussed how system calls cause the thread to switch from a user stack to its kernel stack. Now we'll look at some extra services the memory manager provides to efficiently use stack space.

### **User stacks**

When a thread is created, the memory manager automatically reserves a predetermined amount of virtual memory, which by default is 1 MB. This amount can be configured in the call to the Create-Thread or CreateRemoteThread(Ex) function or when compiling the application by using the / STACK: reserve switch in the Microsoft C/C++ compiler, which stores the information in the image header. Although 1 MB is reserved, only the first page of the stack will be committed (unless the PE header of the image specifies otherwise), along with a guard page. When a thread's stack grows large enough to touch the guard page, an exception occurs, causing an attempt to allocate another guard. Through this mechanism, a user stack doesn't immediately consume all 1 MB of committed memory but instead grows with demand. (However, it will never shrink back.)

#### **EXPERIMENT:** Creating the maximum number of threads

With only 2 GB of user address space available to each 32-bit process, the relatively large memory that is reserved for each thread's stack allows for an easy calculation of the maximum number of threads that a process can support: a little less than 2,048, for a total of nearly 2 GB of memory (unless the increaseuserva BCD option is used and the image is large address space aware). By forcing each new thread to use the smallest possible stack reservation size, 64 KB, the limit can grow to about 30,000 threads. You can test this for yourself by using the TestLimit utility from Sysinternals. Here is some sample output:

```
C:\Tools\Sysinternals>Testlimit.exe -t -n 64
```

Testlimit v5.24 - test Windows limits Copyright (C) 2012-2015 Mark Russinovich Sysinternals - www.sysinternals.com

Process ID: 17260

Creating threads with 64 KB stacks... Created 29900 threads. Lasterror: 8

If you attempt this experiment on a 64-bit Windows installation (with 128 TB of user address space available), you would expect to see potentially hundreds of thousands of threads created (assuming sufficient memory was available). Interestingly, however, TestLimit actually creates fewer threads than on a 32-bit machine. This has to do with the fact that Testlimit.exe is a 32-bit application and thus runs under the Wow64 environment. (See Chapter 8 in Part 2 for more information on Wow64.) Each thread will therefore have not only its 32-bit Wow64 stack but also its 64-bit stack, thus consuming more than twice the memory, while keeping only 2 GB of address space. To properly test the thread-creation limit on 64-bit Windows, use the Testlimit64. exe binary instead.

You will need to terminate TestLimit with Process Explorer or Task Manager. You cannot use Ctrl+C to break the application because this operation itself creates a new thread, which will not be possible once memory is exhausted.

### **Kernel stacks**

Although user stack sizes are typically 1 MB, the amount of memory dedicated to the kernel stack is significantly smaller: 12 KB on 32-bit systems and 16 KB on 64-bit systems, followed by another guard page, for a total of 16 or 20 KB of virtual address space. Code running in the kernel is expected to have less recursion than user code, as well as contain more efficient variable use and keep stack buffer sizes low. Because kernel stacks live in system address space (which is shared by all processes), their memory usage has a bigger impact of the system.

Although kernel code is usually not recursive, interactions between graphics system calls handled by Win32k.sys and its subsequent callbacks into user mode can cause recursive re-entries in the kernel on the same kernel stack. As such, Windows provides a mechanism for dynamically expanding and shrinking the kernel stack from its initial size. As each additional graphics call is performed from the same thread, another 16 KB kernel stack is allocated. (This happens anywhere in system address space. The memory manager provides the ability to jump stacks when nearing the guard page.) Whenever each call returns to the caller (unwinding), the memory manager frees the additional kernel stack that had been allocated, as shown in Figure 5-28. This mechanism allows reliable support for recursive system calls as well as efficient use of system address space. It is provided for use by driver developers when performing recursive callouts through the KeExpandKernelStackAndCallout(Ex) APIs, as necessary.




FIGURE 5-28 Kernel stack jumping.

#### EXPERIMENT: Viewing kernel-stack usage

You can use the RamMap tool from Sysinternals to display the physical memory currently being occupied by kernel stacks. Here's a screenshot from the **Use Counts** tab:

Driver Locked	3,419,852 K	3,419,852 K		
Kernel Stack	47,496 K	41,380 K	6,116 K	
Unused	10,773,740 K	77,504 K		

To view kernel-stack usage, try the following:

- 1. Repeat the previous TestLimit experiment, but don't terminate TestLimit yet.
- 2. Switch to RamMap.
- **3.** Open the **File** menu and select **Refresh** (or press **F5**). You should see a much higher kernel stack size:

Driver Locked	3,419,852 K	3,419,852 K	
Kernel Stack	346,076 K	339,916 K	6,160 K
Unused	10,318,232 K	77,680 K	

Running TestLimit a few more times (without closing previous instances) would easily exhaust physical memory on a 32-bit system, and this limitation results in one of the primary limits on system-wide 32-bit thread count.

## **DPC** stack

Windows keeps a per-processor DPC stack available for use by the system whenever DPCs are executing. This approach isolates the DPC code from the current thread's kernel stack. (This is unrelated to the DPC's actual operation because DPCs run in arbitrary thread context. See Chapter 6 for more on DPCs.) The DPC stack is also configured as the initial stack for handling the sysenter (x86), svc (ARM), or syscall (x64) instruction during a system call. The CPU is responsible for switching the stack when these instructions are executed, based on one of the model-specific registers (MSRs on x86/x64). However, Windows does not want to reprogram the MSR for every context switch because that is an expensive operation. Windows therefore configures the per-processor DPC stack pointer in the MSR.

### Virtual address descriptors

The memory manager uses a demand-paging algorithm to know when to load pages into memory, waiting until a thread references an address and incurs a page fault before retrieving the page from disk. Like copy-on-write, demand paging is a form of *lazy evaluation*—waiting to perform a task until it is required.

The memory manager uses lazy evaluation not only to bring pages into memory but also to construct the page tables required to describe new pages. For example, when a thread commits a large region of virtual memory with VirtualAlloc, the memory manager could immediately construct the page tables required to access the entire range of allocated memory. But what if some of that range is never accessed? Creating page tables for the entire range would be a wasted effort. Instead, the memory manager waits to create a page table until a thread incurs a page fault. It then creates a page table for that page. This method significantly improves performance for processes that reserve and/or commit a lot of memory but access it sparsely.

The virtual address space that would be occupied by such as-yet-nonexistent page tables is charged to the process page file quota and to the system commit charge. This ensures that space will be available for them should they actually be created. With the lazy-evaluation algorithm, allocating even large blocks of memory is a fast operation. When a thread allocates memory, the memory manager must respond with a range of addresses for the thread to use. To do this, the memory manager maintains another set of data structures to keep track of which virtual addresses have been reserved in the process's address space and which have not. These data structures are known as *Virtual Address Descriptors (VADs*). VADs are allocated in non-paged pool.

### **Process VADs**

For each process, the memory manager maintains a set of VADs that describes the status of the process's address space. VADs are organized into a self-balancing AVL tree (named after its inventors, Adelson-Velsky and Landis, where the heights of the two child subtrees of any node differ by at most 1; this makes the insertion, lookup, and deletion very fast). On average, this results in the fewest comparisons when searching for a VAD corresponding with a virtual address. There is one VAD for each virtually contiguous range of not-free virtual addresses that all have the same characteristics (reserved versus committed versus mapped, memory access protection, and so on). Figure 5-29 shows a diagram of a VAD tree.




FIGURE 5-29 VADs.

When a process reserves address space or maps a view of a section, the memory manager creates a VAD to store any information supplied by the allocation request, such as the range of addresses being reserved, whether the range will be shared or private, whether a child process can inherit the contents of the range, and the page protection applied to pages in the range.

When a thread first accesses an address, the memory manager must create a PTE for the page containing the address. To do so, it finds the VAD whose address range contains the accessed address and uses the information it finds to fill in the PTE. If the address falls outside the range covered by the VAD or in a range of addresses that are reserved but not committed, the memory manager knows that the thread didn't allocate the memory before attempting to use it and therefore generates an access violation.

#### **EXPERIMENT: Viewing VADs**


You can use the kernel debugger's !vad command to view the VADs for a given process. First find the address of the root of the VAD tree with the !process command. Then specify that address to the !vad command, as shown in the following example of the VAD tree for a process running Explorer.exe:

```
1kd> !process 0 1 explorer.exe
PROCESS ffffc8069382e080
SessionId: 1 Cid: 43e0 Peb: 00bc5000 ParentCid: 0338
DirBase: 554ab7000 ObjectTable: ffffda8f62811d80 HandleCount: 823.
Image: explorer.exe
VadRoot ffffc806912337f0 Vads 505 Clone 0 Private 5088. Modified 2146. Locked 0.
...
```

lkd> !vad <b>ffffc806</b>	58ae1e42	70							
VAD Leve	el s	Start		End	Commit				
ffffc80689bc52b0	9	640		64f	0	Mapped	R	EADWRITE	
Pagefile section,	shared	commit	0x10						
ffffc80689be6900	8	650		651	0	Mapped	R	EADONLY	
Pagefile section,	shared	commit	0x2						
ffffc80689bc4290	9	660		675	0	Mapped	R	EADONLY	
Pagefile section,	shared	commit	0x16						
ffffc8068ae1f320	7	680		6ff	32	Private	R	EADWRITE	
ffffc80689b290b0	9	700		701	2	Private	R	EADWRITE	
ffffc80688da04f0	8	710		711	2	Private	R	EADWRITE	
ffffc80682795760	6	720		723	0	Mapped	R	EADONLY	
Pagefile section,	shared	commit	0x4						
ffffc80688d85670 1	LO	730		731	0	Mapped	R	EADONLY	
Pagefile section,	shared	commit	0x2						
ffffc80689bdd9e0	9	740		741	2	Private	R	EADWRITE	
ffffc80688da57b0	8	750		755	0	Mapped	R	EADONLY	
\Windows\en-US\exp	olorer.	exe.mui							
Total VADs: 574, a	average	level:	8, m	axin	num dept	th: 10			
Total private comm	nit: Oxá	3420 pag	ges (	5337	76 KB)				
Total shared commi	it: 0x4	178 page	es (4	576	KB)				

#### **Rotate VADs**

A video card driver must typically copy data from the user-mode graphics application to various other system memory, including the video card memory and the AGP port's memory, both of which have different caching attributes as well as addresses. To quickly allow these different views of memory to be mapped into a process, and to support the different cache attributes, the memory manager implements rotate VADs, which allow video drivers to transfer data directly by using the GPU and to rotate unneeded memory in and out of the process view pages on demand. Figure 5-30 shows an example of how the same virtual address can rotate between video RAM and virtual memory.





### NUMA

Each new release of Windows provides new enhancements to the memory manager to make better use of non-uniform memory architecture (NUMA) machines, such as large server systems as well as Intel i7 and AMD Opteron SMP workstations. The NUMA support in the memory manager adds intelligent knowledge of node information such as location, topology, and access costs to allow applications and drivers to take advantage of NUMA capabilities, while abstracting the underlying hardware details.

When the memory manager is initializing, it calls the MiComputeNumaCosts function to perform various page and cache operations on different nodes. It then computes the time it took for those operations to complete. Based on this information, it builds a node graph of access costs (the distance between a node and any other node on the system). When the system requires pages for a given operation, it consults the graph to choose the most optimal node (that is, the closest). If no memory is available on that node, it chooses the next closest node, and so on.

Although the memory manager ensures that, whenever possible, memory allocations come from the ideal processor's node (the *ideal node*) of the thread making the allocation, it also provides functions that allow applications to choose their own node, such as the VirtualAllocExNuma, Create-FileMappingNuma, MapViewOfFileExNuma, and AllocateUserPhysicalPagesNuma APIs.

The ideal node isn't used only when applications allocate memory but also during kernel operation and page faults. For example, when a thread running on a non-ideal processor takes a page fault, the memory manager won't use the current node. Instead, it will allocate memory from the thread's ideal node. Although this might result in slower access time while the thread is still running on this CPU, overall memory access will be optimized as the thread migrates back to its ideal node. In any case, if the ideal node is out of resources, the closest node to the ideal node is chosen and not a random other node. Just like user-mode applications, however, drivers can specify their own node when using APIs such as MmAllocatePagesForMdlEx or MmAllocateContiguousMemorySpecifyCacheNode.

Various memory manager pools and data structures are also optimized to take advantage of NUMA nodes. The memory manager tries to evenly use physical memory from all the nodes on the system to hold the non-paged pool. When a non-paged pool allocation is made, the memory manager uses the ideal node as an index to choose a virtual memory address range inside non-paged pool that corresponds to physical memory belonging to this node. In addition, per-NUMA node pool free lists are created to efficiently leverage these types of memory configurations. Apart from non-paged pool, the system cache and system PTEs are also similarly allocated across all nodes, as well as the memory manager's look-aside lists.

Finally, when the system needs to zero pages, it does so in parallel across different NUMA nodes by creating threads with NUMA affinities that correspond to the nodes in which the physical memory is located. The logical prefetcher and SuperFetch (described in the section "Proactive memory management [SuperFetch]") also use the ideal node of the target process when prefetching, while soft page faults cause pages to migrate to the ideal node of the faulting thread.

### **Section objects**

As noted earlier in this chapter in the "Shared memory and mapped files" section, the *section object*, which the Windows subsystem calls a *file mapping object*, represents a block of memory that two or more processes can share. A section object can be mapped to the paging file or to another file on disk.

The executive uses sections to load executable images into memory, and the cache manager uses them to access data in a cached file. (See Chapter 14 in Part 2 for more information on how the cache manager uses section objects.) You can also use section objects to map a file into a process address space. The file can then be accessed as a large array by mapping different views of the section object and reading or writing to memory rather than to the file—an activity called *mapped file I/O*. When the program accesses an invalid page (one not in physical memory), a page fault occurs and the memory manager automatically brings the page into memory from the mapped file or page file. If the application modifies the page, the memory manager writes the changes back to the file during its normal paging operations. (Alternatively, the application can flush a view explicitly by using the Windows FlushViewOfFile function.)

Like other objects, section objects are allocated and deallocated by the object manager. The object manager creates and initializes an object header, which it uses to manage the objects; the memory manager defines the body of the section object. (See Chapter 8 in Part 2 for more on the object manager). The memory manager also implements services that user-mode threads can call to retrieve and change the attributes stored in the body of section objects. The structure of a section object is shown in Figure 5-31. Table 5-14 summarizes the unique attributes stored in section objects.




FIGURE 5-31 A section object.

Attribute	Purpose
Maximum size	This is the largest size to which the section can grow in bytes. If mapping a file, this is the maximum size of the file.
Page protection	This is page-based memory protection assigned to all pages in the section when it is created.
Paging file or mapped file	This indicates whether the section is created empty (backed by the paging file—as explained earlier page-file-backed sections use page-file resources only when the pages need to be written out to disk) or loaded with a file (backed by the mapped file).
Based or not based	This indicates whether a section is a based section, which must appear at the same virtual address for all processes sharing it, or a non-based section, which can appear at different virtual addresses for different processes.

 TABLE 5-14
 Section object body attributes

#### **EXPERIMENT:** Viewing section objects

You can use Process Explorer from Sysinternals to see files mapped by a process. Follow these steps:

- 1. Open the View menu, choose Lower Pane View, and select DLLs.
- 2. Open the View menu, choose Select Columns, choose DLL, and enable the Mapping Type column.
- 3. Notice the files marked as Data in the Mapping column. These are mapped files rather than DLLs and other files the image loader loads as modules. Section objects that are backed by a page file are indicated in the Name column as <Pagefile Backed>. Otherwise, the file name is shown.

Eile Options View Process	Find DLL		Telb				
Process	PID	CPU	Private Bytes	Virtual Size	Working Set	WS Private W	S Shareable Des
dwm.exe	1328	0.37	343,908 K	2,148,652,504 K	150,348 K	113,380 K	36,968 K Desk
🖃 🦮 explorer.exe	6308	0.03	74,864 K	2,148,095,044 K	92,540 K	29,368 K	63,172 K Wind
🛛 🦰 explorer.exe	3824	< 0.01	102,588 K	2.147,982,996 K	81,396 K	41,360 K	40.036 K Wind
FileCoAuth exe	16944		2,308 K	87.016 K	6.804 K	712 K	6.092 K Micro
- 📵 firefox.exe	13152	0.04	360,216 K	963,504 K	291,364 K	244,564 K	46,800 K Firefc
fontdrvhost.exe	7010		740 6	3 147 EA1 340 W	270 1/	40 W	300 K I loos
EnvitConnectedPDEService av							>
Name			Base	Mapping	Image Base	Size	Description
Pagefile Backed>		0x102	90000	Data	0x0	0x2000	
Pagefile Backed>		0x102	A0000	Data	OxO	0x2000	
Pagefile Backed>		0x102	80000	Data	0x0	0x2000	
Pagefile Backed>		0x7DF5FF6	E0000	Data	0x0	0x0	
Pagefile Backed>		0x7FF730C	B0000	Data	0x0	0x100000	
Pagefile Backed>		0x7FF730D	B0000	Data	OxO	0x23000	
769810105.pri			40000	Data	0x0	0x7000	
boveLockAppHost.dl		0x7FF810E		Image	0x7FF810EE0000	0x4B000	AboveLockAppHo
ActionCenter.dl		0x7FF80A4		Image	0x7FF80A490000	0x4F000	Security and Maint
ctionCenter.dll.mui			10000	Data	OxO	0xA000	Security and Maint
ctiveds.dll		0x7FF82CS		Image	0x7FF82C950000	0x45000	ADs Router Layer
ictopoty dll		0x7FF8262		Image	0x7FF826210000	0x365000	ActiveX Interface I
dsldpc.dl		0x7FF82C8		Image	0x7FF82C870000	0x42000	ADs LDAP Provide
idvapi32.dll		0x7FF834F		Image	0x7FF834F40000	0xA2000	Advanced Windov
pphelp.dll		0x7FF8316		Image	0x7FF831630000	0x7A000	Application Compa
oplicationFrame.dll		0x7FF8114		Image	0x7FF811470000	0x110000	Application Frame
pplicationFrame.dll.mui			90000	Data	0x0	0x1000	Application Frame
ppVEntSubsystems64.dll		0x7FF8165		Image	0x7FF8165C0000	0x216000	Client Virtualization
ticfx64.dl		0x7FF82EA	F0000	Image	0x7FF82EAF0000	0x162000	aticfx64.dll

Another way to view section objects is to switch to handle view (open the **View** menu, choose **Lower Pane View**, and select **Handles**) and look for objects of type Section. In the following screenshot, the object name (if it exists) is shown. This is not the file name backing the section (if any); it's the name given to the section in the object manager's namespace. (See Chapter 8 in Part 2 for more on the object manager.) Double-clicking the entry shows more information on the object, such as the number of open handles and its security descriptor.

Eile Options View Process	100 C	ndle Users	: Help					
Process	PID	CPU	Private Bytes	Virtual Size	Working Set	WS Private	WS Shareable De	19 A
🖂 🥁 explorer.exe	6308	0.50	77,036 K	2,148,096,848 K	95,368 K	32,312 K	63,176 K Wir	nd
E hexplorer.exe	3824	3.91	102,696 K	2.147,995,736 K	85,768 K	42,412 K	43.388 K Wir	br
FileCoAuth.exe	16944		2,308 K	87,016 K	6,808 K	720 K	6,088 K Mic	ac .
🖃 🚭 firefox.exe	13152	0.06	334,472 K	966,032 K	267,796 K	221,048 K	46,748 K Fire	fc
fontdrvhost.exe	7812		748 K	2.147,541,348 K	328 K	48 K	280 K Use	n .
FoxtConnectedPDFService.exe	9E10	0.01	X 100 V	¥ 117 70	A 900 M	1 200 1	3 000 L' E	5
Туре	Handle	Name				Object Address	Decoded Access	^
Mutant	0x3068	\BaseNamed	dObiects\C::Usen	spavely: AppData:Los	al Micr.	0xFFFFC008B3929FC0	READ_CONTROL	110
Mutant	0x30A4			spavely AppData:Los		0xFFFFC008B08A0C30	READ_CONTROL	
Mutant	0x30E0			pavely AppData Los		0xFFFFC008B32643E0	READ_CONTROL	11
Mutant	Dx3128	\BaseNamed	Objects\C::Usen	pavely: App Data: Loo	al:Micr	DxFFFFC008A66AA650	READ_CONTROL	11
Mutant	0x3148			s pavely AppData:Los		0xFFFFC008B3930630	READ_CONTROL	11
Mutant	0x32D0			pavely:AppData:Los		DxFFFFC008AD011AA0	READ_CONTROL	
Mutant	0x33D8	BaseNamed	Objects\C::Usen	s pavely: App Data: Los	al Micr	0xFFFFC008A6EF5EA0	READ_CONTROL	11
Process	0x9A0	sihost.exe(15				0xFFFFC008AB9EB6C0	SET_INFORMATIC	
Process	0x2648	sihost.exe(15				0xFFFFC008AB9EB6C0	QUERY_LIMITED_	JR
Process	0x2BF0	ApplicationFi	rameHost.exe(754	48)		0xFFFFC008B0B8B080 0xFFFFD382712E7B80	SYNCHRONIZE	
Section Section	0x278	Semione\1	BaceNamadObie	cts\windows_shell_g	ichal c	0xFFFFD382717BEE20	MAP WRITE I MAI	
Section	0x298		dObjects\_Com(		0000_0	0xFFFFD3825F41D750	MAP_READ	-
Section	0x2A0	and the second s		renered and the		0xFFFFD3827605BAE0	READ_CONTROL	11
Section	0x334	\Sessions\1	BaseNamedObie	cts\UHZonesSM pa	velv	0xFFFFD38275FCDE20	READ CONTROL	
Section	0x368	50000000000000000000000000000000000000			1000	0xFFFFD38275BFA960	READ CONTROL	
Section	0x374	\BaseNamed	Objects\ Com	CatalogCache		0xFFFFD3825F41D750	MAP READ	
Section	0x380		Section States	SUMPORT STATE		0xFFFFD382760ED210	READ_CONTROL	11
Section	0x448		Windows \Them			0xFFFFD3825F561930	MAP_READ	
e la	0.110	1140 1 17	*******	8		A FFFEDDOOFFFEDDOOF	****	1

The data structures maintained by the memory manager that describe mapped sections are shown in Figure 5-32. These structures ensure that data read from mapped files is consistent regardless of the type of access (open file, mapped file, and so on). For each open file (represented by a file object), there is a single section object pointers structure. This structure is the key to maintaining data consistency for all types of file access as well as to providing caching for files. The section object pointers structure points to one or two control areas. One control area is used to map the file when it is accessed as a data file and the other is used to map the file when it is run as an executable image. A control area in turn points to subsection structures that describe the mapping information for each section of the file (read-only, read/write, copy-on-write, and so on). The control area also points to a segment structure allocated in paged pool, which in turn points to the prototype PTEs used to map to the actual pages mapped by the section object. As described earlier in this chapter, process page tables point to these prototype PTEs, which in turn map the pages being referenced.




FIGURE 5-32 Internal section structures.

Although Windows ensures that any process that accesses (reads or writes) a file will always see the same consistent data, there is one case in which two copies of pages of a file can reside in physical memory. (Even in this case, all accessors get the latest copy and data consistency is maintained.) This duplication can happen when an image file has been accessed as a data file (having been read or written) and is then run as an executable image. (An example might be when an image is linked and then run; the linker had the file open for data access, and then when the image was run, the image loader mapped it as an executable.) Internally, the following actions occur:

- 1. If the executable file was created using the file-mapping APIs or the cache manager, a data control area is created to represent the data pages in the image file being read or written.
- 2. When the image is run and the section object is created to map the image as an executable, the memory manager finds that the section object pointers for the image file point to a data control area and flushes the section. This step is necessary to ensure that any modified pages have been written to disk before accessing the image through the image control area.
- 3. The memory manager creates a control area for the image file.
- **4.** As the image begins execution, its (read-only) pages are faulted in from the image file or copied directly over from the data file if the corresponding data page is resident.

Because the pages mapped by the data control area might still be resident (on the standby list), this is the one case in which two copies of the same data are in two different pages in memory. However, this duplication doesn't result in a data consistency issue. This is because, as mentioned, the data control area has already been flushed to disk, so the pages read from the image are up to date (and these pages are never written back to disk).

#### **EXPERIMENT:** Viewing control areas

To find the address of the control area structures for a file, you must first get the address of the file object in question. You can obtain this address through the kernel debugger by dumping the process handle table with the !handle command and noting the object address of a file object. Although the kernel debugger !file command displays the basic information in a file object, it doesn't display the pointer to the section object pointers structure. Then, using the dt command, format the file object to get the address of the section object pointers structure. This structure consists of three pointers: a pointer to the data control area, a pointer to the shared cache map (explained in Chapter 14 in Part 2), and a pointer to the image control area. From the section object pointers structure, you can obtain the address of a control area for the file (if one exists) and feed that address into the !ca command.

For example, if you open a PowerPoint file and use !handle to display the handle table for that process, you will find an open handle to the PowerPoint file (you can do a text search). (For more information on using !handle, see the "Object manager" section in Chapter 8 in Part 2 or the debugger documentation.)

lkd> !process 0 0 powerpnt.exe
PROCESS ffffc8068913e080

```
SessionId: 1 Cid: 2b64 Peb: 01249000 ParentCid: 1d38
    DirBase: 252e25000 ObjectTable: ffffda8f49269c40 HandleCount: 1915.
    Image: POWERPNT.EXE
1kd> .process /p ffffc8068913e080
Implicit process is now ffffc806'8913e080
lkd> !handle
0c08: Object: ffffc8068f56a630 GrantedAccess: 00120089 Entry: ffffda8f491d0020
Object: ffffc8068f56a630 Type: (ffffc8068256cb00) File
    ObjectHeader: ffffc8068f56a600 (new version)
        HandleCount: 1 PointerCount: 30839
        Directory Object: 00000000 Name: \WindowsInternals\7thEdition\Chapter05\
diagrams.pptx {HarddiskVolume2}
. . .
  Taking the file object address (FFFFC8068F56A630) and formatting it with dt results in this:
lkd> dt nt!_file_object ffffc8068f56a630

      +0x000 Type
      : 0n5

      +0x002 Size
      : 0n216

      +0x008 DeviceObject
      : 0xffffc806'8408cb40 _DEVICE_OBJECT

      +0x010 Vpb
      : 0xffffc806'82feba00 _VPB

      +0x018 FsContext
      : 0xffffda8f'5137cbd0 Void

   +0x020 FsContext2 : 0xffffda8f'4366d590 Void
   +0x028 SectionObjectPointer : 0xffffc806'8ec0c558 _SECTION_OBJECT_POINTERS
  Taking the address of the section object pointers structure and formatting it with dt results in
this:
lkd> dt nt!_section_object_pointers 0xffffc806'8ec0c558
   +0x000 DataSectionObject : 0xffffc806'8e838c10 Void
   +0x008 SharedCacheMap : 0xffffc806'8d967bd0 Void
   +0x010 ImageSectionObject : (null)
   Finally, you can use ! ca to display the control area using the address:
1kd> !ca 0xffffc806'8e838c10
ControlArea @ ffffc8068e838c10
  Segment ffffda8f4d97fdc0 Flink ffffc8068ecf97b8 Blink
ffffc8068ecf97b8
  Section Ref 1 Pfn Ref
User Ref 0 WaitForDel
                                                             58 Mapped Views
                                                                                           2
                                                             0 Flush Count
                                                                                           0
  File Object ffffc8068e5d3d50 ModWriteCount
                                                              0 System Views
                                                                                           2
                     0
  WritableRefs
  Flags (8080) File WasPurged \WindowsInternalsBook\7thEdition\Chapter05\diagrams.pptx
Segment @ ffffda8f4d97fdc0
  ControlArea ffffc8068e838c10 ExtendInfo
                                                       Total Ptes80Segment Size80000Committed
                                                                        0
  Flags (c0000) ProtectionMask
```

ffffc8068e838c90					
ffffc8068e838c10	Starting	g Sector	0	Number Of Sectors	58
ffffda8f48eb6d40	Ptes In	Subsect	58	Unused Ptes	0
d	Sector (	Offset	0	Protection	6
ffffc8068bb7fcf0	Blink	ffffc8068bb7	7fcf0	MappedViews	2
ffffc8068c2e05b0					
ffffc8068e838c10	Starting	g Sector	58	Number Of Sectors	28
ffffda8f3cc45000	Ptes In	Subsect	28	Unused Ptes	1d8
d	Sector (	Offset	0	Protection	6
	ffffc8068e838c10 ffffda8f48eb6d40 d ffffc8068bb7fcf0 ffffc8068c2e05b0 ffffc8068e838c10 ffffda8f3cc45000	ffffc8068e838c10 Startin ffffda8f48eb6d40 Ptes In d Sector 0 ffffc8068bb7fcf0 Blink ffffc8068c2e05b0 ffffc8068e838c10 Startin ffffda8f3cc45000 Ptes In	<pre>ffffc8068e838c10 Starting Sector ffffda8f48eb6d40 Ptes In Subsect</pre>	ffffc8068e838c10Starting Sector0ffffda8f48eb6d40Ptes In Subsect58dSector Offset0ffffc8068bb7fcf0Blinkffffc8068bb7fcf0ffffc8068c2e05b0Starting Sector58ffffda8f3cc45000Ptes In Subsect28	ffffc8068e838c10Starting Sector0Number Of Sectorsffffda8f48eb6d40Ptes In Subsect58Unused PtesdSector Offset0Protectionffffc8068bb7fcf0Blinkffffc8068bb7fcf0MappedViewsffffc8068c2e05b0Starting Sector58Number Of Sectorsffffda8f3cc45000Ptes In Subsect28Unused Ptes

Another technique is to display the list of all control areas with the !memusage command. The following excerpt is from the output of this command. (The command might take a long time to complete on a system with a large amount of memory.)

lkd> !memusage loading PFN database loading (100% complete)

Compiling memory usage data (99% Complete).

Zeroed:	98533	(	394132	kb)
Free:	1405	(	5620	kb)
Standby:	331221	(	1324884	kb)
Modified:	83806	(	335224	kb)
ModifiedNoWrite:	116	(	464	kb)
Active/Valid:	1556154	(	6224616	kb)
Transition:	5	(	20	kb)
SLIST/Bad:	1614	(	6456	kb)
Unknown:	0	(	0	kb)
TOTAL:	2072854	(	8291416	kb)
Dangling Yes Commit:	130	(	520	kb)
Dangling No Commit:	514812	(	2059248	kb)
Building kernel map				
Finished building k	ernel map	5		
(Master1 0 for 1c0)				
(Master1 0 for e80)				
(Master1 0 for ec0)				
(Master1 0 for f00)				
Scanning PFN database	- (02% d	cor	nplete)	
(Master1 0 for de80)				
Scanning PFN database	- (100%	С	omplete)	

Usage Summary (in Kb): Control Valid Standby Dirty Shared Locked PageTables name fffffffd 1684540 0 0 0 1684540 0 AWE ffff8c0b7e4797d0 64 0 0 0 0 0 mapped\_file( Microsoft-Windows-Kernel-PnP%4Configuration.evtx ) ffff8c0b7e481650 0 4 0 0 0 0 mapped\_file( No name for file ) ffff8c0b7e493c00 0 0 0 0 0 mapped\_file( FSD-{ED5680AF-40 0543-4367-A331-850F30190B44}.FSD ) ffff8c0b7e4a1b30 8 12 0 0 0 0 mapped\_file( msidle.dll ) ffff8c0b7e4a7c40 128 0 0 0 0 0 mapped\_file( Microsoft-Windows-Diagnosis-PCW%40perational.evtx ) ffff8c0b7e4a9010 16 8 0 16 0 0 mapped\_file( netjoin.dll )8a04db00 . . . ffff8c0b7f8cc360 8212 0 0 0 mapped\_file( OUTLOOK.EXE ) 0 0 
 ffff8c0b7f8cd1a0
 52
 28

 ffff8c0b7f8ce910
 0
 4
 0 0 0 0 mapped\_file( verdanab.ttf ) 0 0 0 0 mapped\_file( No name for file ) ffff8c0b7f8d3590 0 4 0 0 0 0 mapped\_file( No name for file )

The Control column points to the control area structure that describes the mapped file. You can display control areas, segments, and subsections with the kernel debugger ! ca command. For example, to dump the control area for the mapped file Outlook.exe in this example, type the ! ca command followed by the Control column number, as shown here:

```
1kd> !ca ffff8c0b7f8cc360
```

```
ControlArea @ ffff8c0b7f8cc360
 Segment ffffdf08d8a55670 Flink
                                     ffff8c0b834f1fd0 Blink
ffff8c0b834f1fd0
 Section Ref
                         1 Pfn Ref
                                                806 Mapped Views
                                                                        1
                         2 WaitForDel
                                                0 Flush Count
 User Ref
                                                                      c5a0
 File Object ffff8c0b7f0e94e0 ModWriteCount
                                                0 System Views
                                                                      ffff
 WritableRefs
                  80000161
 Flags (a0) Image File
     \Program Files (x86)\Microsoft Office\root\Office16\OUTLOOK.EXE
Segment @ ffffdf08d8a55670
 ControlArea ffff8c0b7f8cc360 BasedAddress 000000000be0000
 Total Ptes
                          1609
 Segment Size
                      1609000 Committed
                                                         0
 Image Commit
                           f4 Image Info ffffdf08d8a556b8
              ffffdf08dab6b000
 ProtoPtes
 Flags (c20000) ProtectionMask
Subsection 1 @ ffff8c0b7f8cc3e0
 ControlArea ffff8c0b7f8cc360 Starting Sector
                                                 0 Number Of Sectors
                                                                      2
 Base Pte ffffdf08dab6b000 Ptes In Subsect
                                               1 Unused Ptes
                                                                      0
                                               0 Protection
                         2 Sector Offset
 Flags
                                                                      1
Subsection 2 @ ffff8c0b7f8cc418
 ControlArea ffff8c0b7f8cc360 Starting Sector 2 Number Of Sectors 7b17
```

0 Base Pte ffffdf08dab6b008 Ptes In Subsect f63 Unused Ptes 0 Protection Flags 6 Sector Offset 3 Subsection 3 @ ffff8c0b7f8cc450 ControlArea ffff8c0b7f8cc360 Starting Sector 7b19 Number Of Sectors 19a4 Base Pte ffffdf08dab72b20 Ptes In Subsect 335 Unused Ptes 0 2 Sector Offset 0 Protection 1 Flags Subsection 4 @ ffff8c0b7f8cc488 ControlArea ffff8c0b7f8cc360 Starting Sector 94bd Number Of Sectors 764 Base Pte ffffdf08dab744c8 Ptes In Subsect f2 Unused Ptes 0 0 Protection 5 Flags a Sector Offset Subsection 5 @ ffff8c0b7f8cc4c0 ControlArea ffff8c0b7f8cc360 Starting Sector 9c21 Number Of Sectors 1 Base Pte ffffdf08dab74c58 Ptes In Subsect 1 Unused Ptes 0 Flags a Sector Offset 0 Protection 5 Subsection 6 @ ffff8c0b7f8cc4f8 ControlArea ffff8c0b7f8cc360 Starting Sector 9c22 Number Of Sectors 1 Base Pte ffffdf08dab74c60 Ptes In Subsect 1 Unused Ptes 0 a Sector Offset Flags 0 Protection 5 Subsection 7 @ ffff8c0b7f8cc530 ControlArea ffff8c0b7f8cc360 Starting Sector 9c23 Number Of Sectors c62 Base Pte ffffdf08dab74c68 Ptes In Subsect 18d Unused Ptes 0 2 Sector Offset 0 Protection Flags 1 Subsection 8 @ ffff8c0b7f8cc568 ControlArea ffff8c0b7f8cc360 Starting Sector a885 Number Of Sectors 771 Base Pte ffffdf08dab758d0 Ptes In Subsect ef Unused Ptes 0 2 Sector Offset Flags 0 Protection 1

#### Working sets

Now that you've looked at how Windows keeps track of physical memory and how much memory it can support, we'll explain how Windows keeps a subset of virtual addresses in physical memory.

As you'll recall, a subset of virtual pages resident in physical memory is called a *working set*. There are three kinds of working sets:

- Process working sets These contain the pages referenced by threads within a single process.
- **System working sets** These contain the resident subset of the pageable system code (for example, Ntoskrnl.exe and drivers), paged pool, and the system cache.
- Session's working set Each session has a working set that contains the resident subset of the kernel-mode session-specific data structures allocated by the kernel-mode part of the Windows subsystem (Win32k.sys), session paged pool, session mapped views, and other session-space device drivers.

Before examining the details of each type of working set, let's look at the overall policy for deciding which pages are brought into physical memory and how long they remain.

### **Demand paging**

The Windows memory manager uses a demand-paging algorithm with clustering to load pages into memory. When a thread receives a page fault, the memory manager loads into memory the faulted page plus a small number of pages preceding and/or following it. This strategy attempts to minimize the number of paging I/Os a thread will incur. Because programs—especially large ones—tend to execute in small regions of their address space at any given time, loading clusters of virtual pages reduces the number of disk reads. For page faults that reference data pages in images, the cluster size is three pages. For all other page faults, the cluster size is seven pages.

However, a demand-paging policy can result in a process incurring many page faults when its threads first begin executing or when they resume execution at a later point. To optimize the startup of a process (and the system), Windows has an intelligent prefetch engine called the *logical prefetcher*, described in the next section. Further optimization and prefetching is performed by another component, called *SuperFetch*, described later in the chapter.

### Logical prefetcher and ReadyBoot

During a typical system boot or application startup, the order of faults is such that some pages are brought in from one part of a file, then perhaps from a distant part of the same file, then from a different file, then perhaps from a directory, and then again from the first file. This jumping around slows down each access considerably. Indeed, analysis shows that disk seek times are a dominant factor in slowing boot and application startup times. By prefetching batches of pages all at once, you can achieve a more sensible ordering of access without excessive backtracking, thus improving the overall time for system and application startup. The pages that are needed can be known in advance because of the high correlation in accesses across boots or application starts.

The prefetcher tries to speed the boot process and application startup by monitoring the data and code accessed by boot and application startups and using that information at the beginning of a subsequent boot or application startup to read in the code and data. When the prefetcher is active, the memory manager notifies the prefetcher code in the kernel of page faults—those that require that data be read from disk (hard faults) and those that simply require data already in memory to be added to a process's working set (soft faults). The prefetcher monitors the first 10 seconds of application startup. For boot, the prefetcher by default traces from system start through the 30 seconds following the start of the user's shell (typically Explorer) or, failing that, through 60 seconds following Windows service initialization or through 120 seconds, whichever comes first.

The trace assembled in the kernel notes faults taken on the NTFS master file table (MFT) metadata file (if the application accesses files or directories on NTFS volumes), referenced files, and referenced directories. With the trace assembled, the kernel prefetcher code waits for requests from the prefetcher component of the Superfetch service (%SystemRoot%\System32\Sysmain.dll), running in an instance of Svchost. The Superfetch service is responsible for both the logical prefetching component in the kernel

and the SuperFetch component that we'll talk about later. The prefetcher signals the \KernelObjects\ PrefetchTracesReady event to inform the Superfetch service that it can now query trace data.

**Note** You can enable or disable prefetching of the boot or application startups by editing the DWORD registry value EnablePrefetcher in the HKLM\SYSTEM\CurrentControlSet\ Control\Session Manager\Memory Management\PrefetchParameters key. Set it to 0 to disable prefetching altogether, 1 to enable prefetching of only applications, 2 for prefetching of boot only, and 3 for both boot and applications.

The Superfetch service (which hosts the logical prefetcher, although it is a completely separate component from the actual SuperFetch functionality) performs a call to the internal NtQuerySystem-Information system call requesting the trace data. The logical prefetcher post-processes the trace data, combining it with previously collected data, and writes it to a file in the %SystemRoot%\Prefetch folder. (See Figure 5-33.) The file's name is the name of the application to which the trace applies followed by a dash and the hexadecimal representation of a hash of the file's path. The file has a .pf extension. An example would be NOTEPAD.EXE-9FB27C0E.PF.

File Home Share	View				~ (	
n to Quick Copy Paste access Clipboard		े 🦰 🖣 🖓 र	Properties	Select all		
→ ~ ↑ 🧧 « OSD	isk (C:) > Windows > Prefe	etch >	v ♂ Sei	rch Prefetch	Q	
Name	^	Date modified	Type	Size		
	.EXE-D7598153.pf	17-Aug-16 12:00	PF File	24 KB		
	UNCHER.EXE-F7092719.pf	11-Sep-16 10:00	PF File	5 KB		
E CL.EXE-54784		11-Sep-16 11:03	PF File	19 KB		
1 CL.EXE-78059	5EE.pf	11-Sep-16 10:02	PF File	15 KB		
CMD.EXE-8E7	58588.pf	11-Sep-16 12:37	PF File	7 KB		
CMD.EXE-FOO	53CFF.pf	11-Sep-16 10:47	PF File	7 KB		
COMPATADA	IIN.EXE-A2F9CAD0.pf	30-Aug-16 16:19	9 KB			
	UNNER.EXE-6FC4C746.pf	10-Sep-16 17:45	17 KB			
	E-E6AFC9F5.pf	11-Sep-16 12:51	PF File	6 KB		
F CONSENT.EX	E-1A8D0661.pf	11-Sep-16 12:24	PF File	39 KB		
	E-361A28C6.pf	20-Aug-16 13:37	PF File	4 KB		
CPUSET.EXE-	BDA2C8AA.pf	20-Aug-16 22:14	PF File	3 KB		
S OI CPUSET.EXE-	F734A0F0.pf	20-Aug-16 19:35	PF File	4 KB		
TH CPUSTRES.EX	E-0A6E949A.pf	17-Aug-16 10:59	PF File	10 KB		
CPUSTRES.EX	E-F6A3F1A4.pf	20-Aug-16 21:14	PF File	7 KB		
CRASHREPOF	TER.EXE-2F69777B.pf	17-Aug-16 12:51	PF File	7 KB		
CREDENTIAL	JIBROKER.EXE-4704BBB5.pf	06-Sep-16 09:22	PF File	37 KB		
CSC.EXE-4AD	BD99D.pf	11-Sep-16 11:03	PF File	10 KB		

FIGURE 5-33 Prefetch folder.

There is an exception to the file name rule for images that host other components, including the Microsoft Management Console (%SystemRoot%\System32\Mmc.exe), the service hosting process (%SystemRoot%\System32\Svchost.exe), the RunDLL component (%SystemRoot%\System32\Rundll32.exe), and Dllhost (%SystemRoot%\System32\Dllhost.exe). Because add-on components are specified on the command line for these applications, the prefetcher includes the command line in the generated hash.

Thus, invocations of these applications with different components on the command line will result in different traces.

For a system boot, a different mechanism is used, called *ReadyBoot*. ReadyBoot tries to optimize I/O operations by creating large and efficient I/O reads and storing the data in RAM. When system components require the data, it's serviced through the stored RAM. This especially benefits mechanical disks, but can be also useful for SSDs. Information on the files to prefetch is stored after boot in the ReadyBoot subdirectory of the Prefetch directory shown in Figure 5-33. Once boot is complete, the cached data in RAM is deleted. For very fast SSDs, ReadyBoot is off by default because its gains are marginal, if any.

When the system boots or an application starts, the prefetcher is called to give it an opportunity to prefetch. The prefetcher looks in the prefetch directory to see if a trace file exists for the prefetch scenario in question. If it does, the prefetcher calls NTFS to prefetch any MFT metadata file references, reads in the contents of each of the directories referenced, and finally opens each file referenced. It then calls the memory manager function MmPrefetchPages to read in any data and code specified in the trace that's not already in memory. The memory manager initiates all the reads asynchronously and then waits for them to complete before letting an application's startup continue.

#### **EXPERIMENT:** Watching prefetch file reads and writes

If you capture a trace of application startup with Process Monitor from Sysinternals on a client edition of Windows (Windows Server editions disable prefetching by default), you can see the prefetcher check for and read the application's prefetch file (if it exists). In addition, you can see the prefetcher write out a new copy of the file roughly 10 seconds after the application starts. Here is a capture of Notepad startup with an Include filter set to prefetch so that Process Monitor shows only accesses to the %SystemRoot%\Prefetch directory:

File E	Edit Event	Filter	Tools	Options	Help							
6	3   🕺 🛙	• 5	🗢	▲ 🕀	<u>(</u>	#	5	<u> 1</u>	4 2	7		
Seq	Time o	of Day	Process I	Vame	P	DO	peration	15		Path	Result	
1 2 3 4 5 6 7 8 9 10 11 12	13:13:31.78 13:13:31.78 13:13:31.78 13:13:31.78 13:13:32.78 13:13:32.78 13:13:32.78 13:13:32.78 13:13:32.78 13:13:41.87 13:13:13:41.87 13:13:13:13:13:13 13:13:13:	30387 30849 33540 78077 78601 79327 46941 47703 48088 48748 51343	svchos	d exe d exe d exe r exe r exe t exe t exe t exe t exe t exe t exe t exe	1424 1424 385 385 385 145 145 145 145 145	40 10 10 10 10 10 10 10 10 10 10 10 10 10	ReadFil CloseFil QueryS CloseFil CreateFi QueryS CreateFil CreateFil	e ecuntyFile e ile ecuntyFile ileMapping e		C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch C:\Windows\Prefetch C:\Windows\Prefetch C:\Windows\Prefetch C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-9F827C0E.pf	SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS	ED W
13 14 15 16 17 18 19 20 21	13:13:41.87 13:13:41.87 13:13:41.87 13:13:41.87 13:13:41.87 13:13:41.87 13:13:41.87 13:13:41.87 13:13:41.87 13:13:41.87 13:13:43.29	69154 70269 71900 72168 73249 73476 75078	<ul> <li>svchos</li> <li>svchos</li> <li>svchos</li> <li>svchos</li> </ul>	t.exe t.exe t.exe t.exe t.exe t.exe t.exe	143		CloseFil CreateFil QueryS WrteFil QueryB CloseFil CreateFi	ile ecuntyFile e asicInformat e	tionFile	C:\Windows\Prefetch\NOTEPAD_EXE-SF827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-SF827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-SF827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-SF827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-SF827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-SF827C0E.pf C:\Windows\Prefetch\NOTEPAD_EXE-SF827C0E.pf C:\Windows\Prefetch	SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS SUCCESS	
22 23	13:13:43:29 13:13:43:29 13:13:43:29	76794	explore	r.exe	382	24	QueryD CloseFi	irectory		C: Windows VPrefetch C: Windows VPrefetch	SUCCESS	

Lines 0–3 show the Notepad prefetch file being read in the context of the Notepad process during its startup. Lines 7–19 (which have time stamps 10 seconds later than the first four lines) show the Superfetch service—running in the context of a Svchost process—writing out the updated prefetch file.

To minimize seeking even further, every three days or so, during system idle periods, the Superfetch service organizes a list of files and directories in the order that they are referenced during a boot or application start and stores it in a file named %SystemRoot%\Prefetch\Layout.ini (see Figure 5-34). This list also includes frequently accessed files tracked by Superfetch.




FIGURE 5-34 Prefetch defragmentation layout file.

It then launches the system defragmenter with a command-line option that tells the defragmenter to defragment based on the contents of the file instead of performing a full defrag. The defragmenter finds a contiguous area on each volume large enough to hold all the listed files and directories that reside on that volume and then moves them in their entirety into that area so that they are stored one after the other. Thus, future prefetch operations will even be more efficient because all the data read in is now stored physically on the disk in the order it will be read. Because the files defragmented for prefetching usually number only in the hundreds, this defragmentation is much faster than full-volume defragmentations.

## **Placement policy**

When a thread receives a page fault, the memory manager must determine where in physical memory to put the virtual page. The set of rules it uses to determine the best position is called a *placement policy*. Windows considers the size of CPU memory caches when choosing page frames to minimize unnecessary thrashing of the cache.

If physical memory is full when a page fault occurs, Windows uses a replacement policy to determine which virtual page must be removed from memory to make room for the new page. Common replacement policies include least recently used (LRU) and first in, first out (FIFO). The LRU algorithm (also known as the *clock algorithm*, as implemented in most versions of UNIX) requires the virtual memory system to track when a page in memory is used. When a new page frame is required, the page that hasn't been used for the greatest amount of time is removed from the working set. The FIFO algorithm is somewhat simpler: It removes the page that has been in physical memory for the greatest amount of time, regardless of how often it's been used.

Replacement policies can be further characterized as either global or local. A global replacement policy allows a page fault to be satisfied by any page frame, regardless of whether that frame is owned by another process. For example, a global replacement policy using the FIFO algorithm would locate the page that has been in memory the longest and would free it to satisfy a page fault. A local replacement policy would limit its search for the oldest page to the set of pages already owned by the process that incurred the page fault. Be aware that global replacement policies make processes vulnerable to the behavior of other processes. For example, an ill-behaved application can undermine the entire operating system by inducing excessive paging activity in all processes.

Windows implements a combination of local and global replacement policies. When a working set reaches its limit and/or needs to be trimmed because of demands for physical memory, the memory manager removes pages from working sets until it has determined there are enough free pages.

# Working set management

Every process starts with a default working set minimum of 50 pages and a working set maximum of 345 pages. Although it has little effect, you can change these working set limits with the Windows SetProcessWorkingSetSize function, although you must have the increase scheduling priority (SeIncreaseBasePriorityPrivilege) privilege to do this. However, unless you have configured the process to use hard working set limits, these limits are ignored. That is, the memory manager will permit a process to grow beyond its maximum if it is paging heavily and there is ample memory. (Conversely the memory manager will shrink a process below its working set minimum if it is not paging and there is a high demand for physical memory on the system.) You can set hard working set limits using the SetProcessWorkingSetSizeEx function along with the QUOTA\_LIMITS\_MARDWS\_MAX\_ENABLE flag, but it is almost always better to let the system manage your working set.

On 32 bit systems, the maximum working set size can't exceed the system-wide maximum calculated at system initialization time, stored in the MiMaximumWorkingSet kernel variable. On x64 systems, physical memory would be the practical upper limit, as the virtual address space is so vast. The working set maximums are listed in Table 5-15.

Windows Version	Working Set Maximum
x86, ARM	2 GB—64 KB (0x7FFF0000)
x86 versions of Windows booted with increaseuserva	2 GB—64 KB + user virtual address increase
x64 (Windows 8, Server 2012)	8,192 GB (8 TB)
X64 (Windows 8.1, 10, Server 2012 R2, 2016)	128 TB

TABLE 5-15 Upper limit for working set maximums

When a page fault occurs, the process's working set limits and the amount of free memory on the system are examined. If conditions permit, the memory manager allows a process to grow to its working set maximum (or beyond if the process does not have a hard working set limit and there are enough free pages available). However, if memory is tight, Windows replaces rather than adds pages in a working set when a fault occurs.

Windows attempts to keep memory available by writing modified pages to disk. Still, when modified pages are being generated at a very high rate, more memory is required to meet memory demands. Therefore, when physical memory runs low, the working set manager, a routine that runs in the context of the balance set manager system thread (described in the next section), initiates automatic working set trimming to increase the amount of free memory available in the system. You can also initiate working set trimming of your own process—for example, after process initialization—with the aforementioned Windows SetProcessWorkingSetSizeEx function.

The working set manager examines available memory and decides which, if any, working sets need to be trimmed. If there is ample memory, the working set manager calculates how many pages could be removed from working sets if needed. If trimming is needed, it looks at working sets that are above their minimum setting. It also dynamically adjusts the rate at which it examines working sets and arranges the list of processes that are candidates to be trimmed into an optimal order. For example, processes with many pages that have not been accessed recently are examined first; larger processes that have been idle longer are considered before smaller processes that are running more often; the process running the foreground application is considered last; and so on.

When the working set manager finds processes that are using more than their minimums, it looks for pages to remove from the working sets, making the pages available for other uses. If the amount of free memory is still too low, the working set manager continues removing pages from processes' working sets until it achieves a minimum number of free pages on the system.

The working set manager tries to remove pages that haven't been accessed recently by checking the accessed bit in the hardware PTE to see whether a page has been accessed. If the bit is clear, the page is said to be *aged*. That is, a count is incremented indicating that the page hasn't been referenced since the last working set trim scan. Later, the age of pages is used to locate candidate pages to remove from the working set.

If the hardware PTE accessed bit is set, the working set manager clears it and goes on to examine the next page in the working set. In this way, if the accessed bit is clear the next time the working set manager examines the page, it knows that the page hasn't been accessed since the last time it was examined. This scan for pages to remove continues through the working set list until either the number of desired pages has been removed or the scan has returned to the starting point. The next time the working set is trimmed, the scan picks up where it left off last.

#### **EXPERIMENT:** Viewing process working set sizes

You can use Performance Monitor to examine process working set sizes by looking at the performance counters shown in the following table. Several other process viewer utilities (such as Task Manager and Process Explorer) also display the process working set size.

Counter	Description
Process: Working Set	This notes the current size of the selected process's working set in bytes.
Process: Working Set Peak	This tracks the peak size of the selected process's working set in bytes.
Process: Page Faults/Sec	This indicates the number of page faults for the process that occur each second.

You can also get the total of all the process working sets by selecting the \_Total process in the instance box in Performance Monitor. This process isn't real; it's simply a total of the process-specific counters for all processes currently running on the system. The total you see is larger than the actual RAM being used, however, because the size of each process working set includes pages being shared by other processes. Thus, if two or more processes share a page, the page is counted in each process's working set.

#### **EXPERIMENT:** Working set versus virtual size

Earlier in this chapter, you used the TestLimit utility to create two processes: one with a large amount of memory that was merely reserved, and one in which the memory was private committed. You then examined the difference between them with Process Explorer. Now we will create a third TestLimit process—one that not only commits the memory but also accesses it, thus bringing it into its working set. Follow these steps:

1. Create a new TestLimit process.

C:\Users\pavely>testlimit -d 1 -c 800

Testlimit v5.24 - test Windows limits Copyright (C) 2012-2015 Mark Russinovich Sysinternals - www.sysinternals.com

Process ID: 13008

Leaking private bytes with touch 1 MB at a time... Leaked 800 MB of private memory (800 MB total leaked). Lasterror: 0 The operation completed successfully.

- 2. Open Process Explorer.
- 3. Open the View menu, choose Select Columns, and click the Process Memory tab.
- Enable the Private Bytes, Virtual Size, Working Set Size, WS Shareable Bytes, and WS Private Bytes counters.
- 5. Find the three instances of TestLimit, as shown in the display:

File Options View Process	Find Han		<u>H</u> elp					
	* * #	٠				An		
Process	PID	CPU	Private Bytes	Virtual Size	Working Set	WS Private	WS Shareable	Des
SystemSettings.exe	12024 S	uspended	17,288 K	2,147,827,164 K	33.532 K	576 K	32,956	K Setti
System Settings Broker.exe	20836		4,156 K	2,147,599,952 K	17,136 K	1,448 K	15,688	K Syste
taskhostw.exe	2036		12,404 K	2,147,870,484 K	16,988 K	4,748 K	12,240	K Host
1 Taskmgr.exe	2112	80.0	21,716 K	2,147,683,040 K	25,696 K	8,632 K	17,064 1	K Task
Testimit.exe	25264		1,096 K	892,740 K	5,544 K	780 K	4,764	K Test
Testlimit.exe	19552		821,884 K	892,740 K	5,528 K	784 K	4,744 8	K Test
Testlimit.exe	13008		821,888 K	892,740 K	824,720 K	819,984 K	4,7361	K Test
Twitter Windows exe	24652 S	uspended	58,660 K	388,224 K	29,236 K		28,644	K Twitt
S UcMapi.exe	13556	< 0.01	25,192 K	347,316 K	24,776 K	4,940 K	19,836	K Skyr
UevAppMontor.exe	12716	< 0.01	104,836 K	872,720 K	22,244 K	15,844 K	6,400 1	K
E wmcompute.exe	<							>

The new TestLimit process is the third one shown, PID 13008. It is the only one of the three that actually referenced the memory allocated, so it is the only one with a working set that reflects the size of the test allocation.

Note that this result is possible only on a system with enough RAM to allow the process to grow to such a size. Even on this system, not quite all of the private bytes (821,888 K) are in the WS Private portion of the working set. A small number of the private pages have been pushed out of the process working set due to replacement or have not been paged in yet.

#### EXPERIMENT: Viewing the working set list in the debugger

You can view the individual entries in the working set by using the kernel debugger !wsle command. The following example shows a partial output of the working set list of WinDbg (32-bit system):

c0004209	1	0	1
72a37805	4	0	1
b50409	2	0	1
b52809	4	0	1
7731dc05	6	0	1
bbec09	6	0	1
bbfc09	6	0	1
6c801805	4	0	1
772a1405	2	0	1
944209	1	0	1
77316a05	5	0	1
773a4209	1	0	1
77317405	2	0	1
772d6605	3	0	1
a71409	2	0	1
c1d409	2	0	1
772d4a05	5	0	1
77342c05	6	0	1
6c80f605	3	0	1
77320405	2	0	1
77323205	1	0	1
77321405	2	0	1
7ffe0215	1	0	2
a5fc09	6	0	1
7735cc05	6	0	1

...

Notice that some entries in the working set list are page table pages (the ones with addresses greater than 0xC000000), some are from system DLLs (the ones in the 0x7nnnnnn range), and some are from the code of Windbg.exe itself.

### Balance set manager and swapper

Working set expansion and trimming take place in the context of a system thread called the *balance set manager* (KeBalanceSetManager function). The balance set manager is created during system initialization. Although the balance set manager is technically part of the kernel, it calls the memory manager's working set manager (MmWorkingSetManager) to perform working set analysis and adjustment.

The balance set manager waits for two different event objects: an event that is signaled when a periodic timer set to fire once per second expires and an internal working set manager event that the memory manager signals at various points when it determines that working sets need to be adjusted. For example, if the system is experiencing a high page fault rate or the free list is too small, the memory manager wakes up the balance set manager so that it will call the working set manager to begin trimming working sets. When memory is more plentiful, the working set manager permits faulting processes to gradually increase the size of their working sets by faulting pages back into memory. However, the working sets will grow only as needed.

When the balance set manager wakes up because its 1-second timer has expired, it takes the following steps:

- 1. If the system supports Virtual Secure Mode (VSM, Windows 10 and Server 2016), then the secure kernel is called to do its periodic housekeeping (Vs1SecureKernelPeriodicTick).
- 2. Calls a routine to adjust IRP credits to optimize the usage of the per-processor look-aside lists used in IRP completion (IoAdjustIrpCredits). This allows better scalability when certain processors are under heavy I/O load. (See Chapter 6 for more on IRPs.)
- 3. Checks the look-aside lists and adjusts their depths (if necessary) to improve access time and reduce pool usage and pool fragmentation (ExAdjustLookasideDepth).
- 4. Calls to adjust the Event Tracing for Windows (ETW) buffer pool size to use ETW memory buffers more efficiently (EtwAdjustTraceBuffers). (For more on ETW, see Chapter 8 in Part 2.)
- 5. Calls the memory manager's working set manager. The working set manager has its own internal counters that regulate when to perform working set trimming and how aggressively to trim.
- 6. Enforces execution time for jobs (PsEnforceExecutionLimits).
- 7. Every eighth time the balance set manager wakes up because its 1-second timer has expired, it signals an event that wakes up another system thread called the *swapper* (KeSwapProcess-OrStack). It attempts to outswap kernel stacks for threads that have not executed for a long time. The swapper thread (which runs at priority 23) looks for threads that have been in a user mode wait state for 15 seconds. If it finds one, it puts the thread's kernel stack in transition (moving the pages to the modified or standby lists) to reclaim its physical memory, operating on the principle that if a thread has been waiting that long, it's going to be waiting even longer. When the last thread in a process has its kernel stack removed from memory, the process is marked to be entirely outswapped. That's why, for example, processes that have been idle for a long time (such as Wininit or Winlogon) can have a working set size of zero.

# System working sets

Just as processes have working sets that manage pageable portions of the process address space, the pageable code and data in the system address space is managed using three global working sets, collectively known as the *system working sets*. These global working sets are as follows:

- **System cache working set** This contains pages that are resident in the system cache.
- **Paged pool working set** This contains pages that are resident in the paged pool.
- **System PTEs working set** This contains pageable code and data from loaded drivers and the kernel image and pages from sections that have been mapped into the system space.

Table 5-16 shows where these system working set types are stored.

#### TABLE 5-16 System working sets

System Working Set Type	Stored in (Windows 8.x, Server 2012/R2)	Stored in (Windows 10, Server 2016)
System cache	MmSystemCacheWs	MiState.SystemVa.SystemWs[0]
Paged pool	MmPagedPoolWs	MiState.SystemVa.SystemWs[2]
System PTEs	MmSystemPtesWs	MiState.SystemVa.SystemWs[1]

You can examine the sizes of these working sets or the sizes of the components that contribute to them with the performance counters or system variables shown in Table 5-17. (Note that the performance counter values are in bytes, whereas the system variables are measured in pages.)

TABLE 5-17 System working set performance counters

Performance Counter (in Bytes)	System Variable (in Pages)	Description
Memory: Cache Bytes Memory: System Cache Resident Bytes	WorkingSetSize member	This is the physical memory consumed by the file system cache.
Memory: Cache Bytes Peak	PeakWorkingSetSize member (Windows 10 and 2016) Peak member (Windows 8.x and 2012/R2)	This is the peak system working set size.
Memory: System Driver Resident Bytes	SystemPageCounts.SystemDriverPage (global, Windows 10 and Server 2016) MmSystemDriverPage (global, Windows 8.x and Server 2012/R2)	This is the physical memory consumed by pageable device driver code.
Memory: Pool Paged Resident Bytes	WorkingSetSize member	This is the physical memory consumed by paged pool.

You can also examine the paging activity in the system cache working set by examining the Memory: Cache Faults/Sec performance counter. This counter describes page faults that occur in the system cache working set (both hard and soft). The PageFaultCount member in the system cache working set structure contains the value for this counter.

## Memory notification events

Windows provides a way for user-mode processes and kernel-mode drivers to be notified when physical memory, paged pool, non-paged pool, and commit charge are low and/or plentiful. This information can be used to determine memory usage as appropriate. For example, if available memory is low, the application can reduce memory consumption. If available paged pool is high, the driver can allocate more memory. Finally, the memory manager also provides an event that permits notification when corrupted pages have been detected.

User-mode processes can be notified only of low or high memory conditions. An application can call the CreateMemoryResourceNotification function, specifying whether low or high memory notification is desired. The returned handle can be provided to any of the wait functions. When memory is low (or high), the wait completes, thus notifying the thread of the condition. Alternatively, the QueryMemory-ResourceNotification can be used to query the system memory condition at any time without blocking the calling thread.

Drivers, on the other hand, use the specific event name that the memory manager has set up in the \ KernelObjects object manager directory. This is because notification is implemented by the memory manager signaling one of the globally named event objects it defines, shown in Table 5-18. When a given memory condition is detected, the appropriate event is signaled, thus waking up any waiting threads.

Event Name	Description
HighCommitCondition	This event is set when the commit charge is near the maximum commit limit—in other words, memory usage is very high, very little space is available in physical memory or paging files, and the operating system cannot increase the size of its paging files.
HighMemoryCondition	This event is set whenever the amount of free physical memory exceeds the defined amount.
HighNonPagedPoolCondition	This event is set whenever the amount of non-paged pool exceeds the defined amount.
HighPagedPoolCondition	This event is set whenever the amount of paged pool exceeds the defined amount.
LowCommitCondition	This event is set when the commit charge is low relative to the current commit limit—in other words, memory usage is low and a lot of space is available in physical memory or paging files.
LowMemoryCondition	This event is set whenever the amount of free physical memory falls below the defined amount.
LowNonPagedPoolCondition	This event is set whenever the amount of free non-paged pool falls below the defined amount.
LowPagedPoolCondition	This event is set whenever the amount of free paged pool falls below the defined amount.
MaximumCommitCondition	This event is set when the commit charge is near the maximum commit limit—in other words, memory usage is very high, very little space is available in physical memory or paging files, and the operating system cannot increase the size or number of paging files.
MemoryErrors	This indicates that a bad page (non-zeroed zero page) has been detected.

 TABLE 5-18
 Memory manager notification events

**Note** You can override the high and low memory values by adding the LowMemoryThreshold or HighMemoryThreshold DWORD registry value under HKLM\SYSTEM\CurrentControlSet\ Control\Session Manager\Memory Management. This specifies the number of megabytes to use as the low or high threshold. You can also configure the system to crash when a bad page is detected instead of signaling a memory error event by setting the PageValidationAction DWORD registry value in the same key to 1.

### **EXPERIMENT:** Viewing the memory resource notification events

To see the memory resource notification events, run WinObj from Sysinternals and click the **KernelObjects** folder. You will see both the low and high memory condition events shown in the pane on the right:

Eile View Help	1			
<ul> <li>ArcName</li> <li>BaseNamedObjects</li> <li>Callback</li> <li>Device</li> <li>Driver</li> <li>FileSystem</li> <li>GLOBAL??</li> <li>KnownDls</li> <li>KnownDls32</li> <li>NLS</li> <li>ObjectTypes</li> <li>RPC Control</li> <li>Security</li> <li>Sessions</li> <li>Windows</li> </ul>	Name / B GdSyncMutant CritiSecOutOfMemoryEvent HighMemoryCondition HighMemoryCondition HighPagedPoolCondition LowNonPagedPoolCondition LowNonPagedPoolCondition LowNonPagedPoolCondition MemoryErrors MemoryPartition0 MemoryPartition0 MemoryPartition0 MemoryPartition0 Session1 SuperfetchParametersChanged Session1 SuperfetchParametersChanged SuperfetchParametersChanged Session1	Type Mutant KeyedEvent Event Event Event Event Event Event Event Event Event Event Session Session Event Eve	SymLink	

If you double-click either event, you can see how many handles and/or references have been made to the objects. To see whether any processes in the system have requested memory resource notification, search the handle table for references to LowMemoryCondition or HighMemoryCondition. To do so, use Process Explorer's **Find** menu (choose **Find Handle or DLL**) or use WinDbg. (For a description of the handle table, see the section "Object manager" in Chapter 8 in Part 2.)

# Page frame number database

Several previous sections concentrated on the virtual view of a Windows process—page tables, PTEs, and VADs. The remainder of this chapter will explain how Windows manages physical memory, starting with how Windows keeps track of physical memory. Whereas working sets describe the resident pages owned by a process or the system, the PFN database describes the state of each page in physical memory. The page states are listed in Table 5-19.

Status	Description
Active (also called valid)	The page is part of a working set (either a process working set, a session working set, or a system working set), or it's not in any working set (for example, a non-paged kernel page) and a valid PTE usually points to it.
Transition	This is a temporary state for a page that isn't owned by a working set and isn't on any paging list. A page is in this state when an I/O to the page is in progress. The PTE is encoded so that collided page faults can be recognized and handled properly. (This use of the term transition differs from the use of the word in the section on invalid PTEs. An invalid transition PTE refers to a page on the standby or modified list.)
Standby	The page previously belonged to a working set but was removed or was prefetched/clustered directly into the standby list. The page wasn't modified since it was last written to disk. The PTE still refers to the physical page but it is marked invalid and in transition.

TABLE 5-19 Physical page states

#### TABLE 5-19 Physical page states (continued)

Status	Description
Modified	The page previously belonged to a working set but was removed. However, the page was modified while it was in use and its current contents haven't yet been written to disk or remote storage. The PTE still refers to the physical page but is marked invalid and in transition. It must be written to the backing store before the physical page can be reused.
Modified no-write	This is the same as a modified page except that the page has been marked so that the memory manager's modified page writer won't write it to disk. The cache manager marks pages as modified no-write at the request of file system drivers. For example, NTFS uses this state for pages containing file system metadata so that it can first ensure that transaction log entries are flushed to disk before the pages they are protecting are written to disk. (NTFS transaction logging is explained in Chapter 13, "File systems," in Part 2.)
Free	The page is free but has unspecified dirty data in it. For security reasons, these pages can't be given as a user page to a user process without being initialized with zeroes, but they can be overwritten with new data (for example, from a file) before being given to a user process.
Zeroed	The page is free and has been initialized with zeroes by the zero page thread or was determined to already contain zeroes.
Rom	The page represents read-only memory.
Bad	The page has generated parity or other hardware errors and can't be used (or used as part of an enclave).

The PFN database consists of an array of structures that represent each physical page of memory on the system. The PFN database and its relationship to page tables are shown in Figure 5-35. As this figure shows, valid PTEs usually point to entries in the PFN database (and the PFN index points to the page in physical memory), and the PFN database entries (for non-prototype PFNs) point back to the page table that is using them (if it is being used by a page table). For prototype PFNs, they point back to the prototype PTE.




FIGURE 5-35 Page tables and the PFN database.

Of the page states listed in Table 5-19, six are organized into linked lists so that the memory manager can quickly locate pages of a specific type. (Active/valid pages, transition pages, and overloaded "bad" pages aren't in any system-wide page list.) Additionally, the standby state is associated with eight different lists ordered by priority. (We'll talk about page priority later in this section.) Figure 5-36 shows an example of how these entries are linked together.




FIGURE 5-36 Page lists in the PFN database.

In the next section, you'll find out how these linked lists are used to satisfy page faults and how pages move to and from the various lists.

#### **EXPERIMENT:** Viewing the PFN database

You can use the MemInfo tool from the *Windows Internals* book's website to dump the size of the various paging lists by using the –s flag. The following is the output from this command:

```
C:\Tools>MemInfo.exe -s
MemInfo v3.00 - Show PFN database information
Copyright (C) 2007-2016 Alex Ionescu
www.alex-ionescu.com
Initializing PFN Database... Done
PFN Database List Statistics
Zeroed: 4867 ( 19468 kb)
```

Free:	3076	( 12304	kb)
Standby:	4669104	(18676416	kb)
Modified:	7845	( 31380	kb)
ModifiedNoWrite:	117	( 468	kb)
Active/Valid:	3677990	(14711960	kb)
Transition:	5	( 20	kb)
Bad:	0	( 0	kb)
Unknown:	1277	( 5108	kb)
TOTAL:	8364281	(33457124	kb)

Using the kernel debugger !memusage command, you can obtain similar information, although this will take considerably longer to execute.

# Page list dynamics

Figure 5-37 shows a state diagram for page frame transitions. For simplicity, the modified-no-write, bad and ROM lists aren't shown.




FIGURE 5-37 State diagram for physical pages.

Page frames move between the paging lists in the following ways:

When the memory manager needs a zero-initialized page to service a demand-zero page fault (a reference to a page that is defined to be all zeroes or to a user-mode committed private page that has never been accessed), it first attempts to get one from the zero page list. If the list is empty, it gets one from the free page list and zeroes the page. If the free list is empty, it goes to the standby list and zeroes that page. One reason zero-initialized pages are needed is to meet security requirements such as the Common Criteria (CC). Most CC profiles specify that user-mode processes be given initialized page frames to prevent them from reading a previous process's memory contents. Thus, the memory manager gives user-mode processes zeroed page frames unless the page is being read in from a backing store. In that case, the memory manager prefers to use non-zeroed page frames, initializing them with the data off the disk or remote storage. The zero page list is populated from the free list by the zero page thread system thread (thread 0 in the System process). The zero page thread waits on a gate object to signal it to go to work. When the free list has eight or more pages, this gate is signaled. However, the zero page thread will run only if at least one processor has no other threads running, because the zero page thread runs at priority 0 and the lowest priority that a user thread can be set to is 1.

**Note** When memory needs to be zeroed as a result of a physical page allocation by a driver that calls MmAllocatePagesForMdl(Ex), by a Windows application that calls AllocateUserPhysicalPages or AllocateUserPhysicalPagesNuma, or when an application allocates large pages, the memory manager zeroes the memory by using a higher-performing function called MiZeroInParallel that maps larger regions than the zero page thread, which only zeroes a page at a time. In addition, on multiprocessor systems, the memory manager creates additional system threads to perform the zeroing in parallel (and in a NUMA-optimized fashion on NUMA platforms).

- When the memory manager doesn't require a zero-initialized page, it goes first to the free list. If that's empty, it goes to the zeroed list. If the zeroed list is empty, it goes to the standby lists. Before the memory manager can use a page frame from the standby lists, it must first backtrack and remove the reference from the invalid PTE (or prototype PTE) that still points to the page frame. Because entries in the PFN database contain pointers back to the previous user's page table page (or to a page of prototype PTE pool for shared pages), the memory manager can quickly find the PTE and make the appropriate change.
- When a process must give up a page out of its working set either because it referenced a new page and its working set was full or the memory manager trimmed its working set, the page goes to the standby lists if the page was clean (not modified) or to the modified list if the page was modified while it was resident.
- When a process exits, all the private pages go to the free list. Also, when the last reference to a page-file-backed section is closed, and the section has no remaining mapped views, these pages also go to the free list.

### **EXPERIMENT:** The free and zero page lists

You can observe the release of private pages at process exit with Process Explorer's System Information display. Begin by creating a process with numerous private pages in its working set. We did this in an earlier experiment with the TestLimit utility:

```
C:\Tools\Sysinternals>Testlimit.exe -d 1 -c 1500
Testlimit v5.24 - test Windows limits
Copyright (C) 2012-2015 Mark Russinovich
Sysinternals - www.sysinternals.com
Process ID: 13928
Leaking private bytes with touch 1 MB at a time...
Leaked 1500 MB of private memory (1500 MB total leaked). Lasterror: 0
The operation completed successfully.
```

The -d option causes TestLimit to not only allocate the memory as private committed, but to touch it—that is, to access it. This causes physical memory to be allocated and assigned to the process to realize the area of private committed virtual memory. If there is sufficient available RAM on the system, the entire 1,500 MB should be in RAM for the process. The process will now wait until you cause it to exit or terminate (perhaps by pressing **Ctrl+C** in its command window). After you do, follow these steps:

- 1. Open Process Explorer.
- 2. Open the View menu, choose System Information, and click the Memory tab.
- 3. Observe the size of the Free and Zeroed lists.
- 4. Terminate or exit the TestLimit process.

You *may* see the free page list briefly increase in size. We say "may" because the zero page thread is awakened as soon as there are only eight pages on the free list, and it acts very quickly. Process Explorer updates this display only once per second, and it is likely that most of the pages were already zeroed and moved to the zeroed page list before it happened to "catch" this state. If you can see the temporary increase in the free list, you will then see it drop to zero, and a corresponding increase will occur in the zeroed page list. If not, you will simply see the increase in the zeroed list.

#### **EXPERIMENT:** The modified and standby page lists

You can observe the movement of pages from process working set to the modified page list and then to the standby page list with the VMMap and RAMMap Sysinternals tools and the live kernel debugger. Follow these steps:

 Open RAMMap and observe the state of the quiet system. This is an x86 system with 3 GB of RAM. The columns in this display represent the various page states shown in Figure 5-37 (a few of the columns not important to this discussion have been narrowed for ease of reference).

e Counts	Processes Priority Su	ummary Physical Pa	ges Physical Range	es File Summary	File Details		
_	Usage	Total	Active	Standby	Modified	Zeroed	Free M
	Process Private	448,284 K	404,448 K	13,412 K	30,424 K		
	Mapped File	1,631,144 K	97,088 K	1,533,328 K	728 K		
	Shareable	48,876 K	32,840 K	1,044 K	14,992 K		
	Page Table	23,060 K	23,060 K				
	Paged Pool	145,792 K	144,860 K	848 K	84 K		
	Nonpaged Pool	66,108 K	66,096 K				
	System PTE	27,964 K	27,964 K				
	Session Private	12,416 K	12,416 K				
	Metafile AWE	297,956 K	9,816 K	288,036 K	104 K		
	Driver Locked	988 K	988 K				
	Kernel Stack	10,912 K	10,672 K		240 K		
	Unused Large Page	431,768 K	8,016 K			5,064 K	418,688 K
	Total	3,145,268 K	838,264 K	1,836,668 K	46,572 K	5,064 K	418,688 K

- 2. The system has about 420 MB of RAM free (sum of the free and zeroed page lists). About 580 MB is on the standby list (hence part of "available," but likely containing data recently lost from processes or being used by SuperFetch). About 830 MB is "active," being mapped directly to virtual addresses via valid page table entries.
- 3. Each row further breaks down into page state by usage or origin (process private, mapped file, and so on). For example, at the moment, of the active 830 MB, about 400 MB is due to process private allocations.
- 4. Now, as in the previous experiment, use the TestLimit utility to create a process with a large number of pages in its working set. Again, we will use the -d option to cause TestLimit to write to each page, but this time we will use it without a limit, so as to create as many private modified pages as possible:

C:\Tools\Sysinternals>Testlimit.exe -d

Testlimit v5.24 - test Windows limits Copyright (C) 2012-2015 Mark Russinovich Sysinternals - www.sysinternals.com

Process ID: 7548

Leaking private bytes with touch (MB)... Leaked 1975 MB of private memory (1975 MB total leaked). Lasterror: 8

 TestLimit has now created 1975 allocations of 1 MB each. In RAMMap, use the File | Refresh command to update the display (because of the cost of gathering its information, RAMMap does not update continuously).

e <u>E</u> mpty	Help					
Use Counts	Processes Priority Su	mmary Physical Pages	Physical Range	s File Summary	File Details	
	Usage	Total	Active	Standby	Modified	Zeroed
	Process Private	2,505,828 K	2,467,236 K	11,296 K	27,296 K	And a second second second
	Mapped File	243,416 K	106,836 K	135,820 K	760 K	
	Shareable	46,348 K	41,256 K	48 K	5,044 K	
	Page Table	27,956 K	27,956 K		12424223326	
	Paged Pool	73,536 K	73,380 K	60 K	96 K	
	Nonpaged Pool	66,120 K	66,108 K			
	System PTE	25,164 K	25,164K			
	Session Private	18,828 K	18,828 K			
	Metafile	26,668 K	8,408 K	18,160 K	100 K	
	AWE					
	Driver Locked	988 K	988 K			
	Kernel Stack	10,024 K	10,024K			
	Unused	100,392 K	17,244 K			38,856 K
	Large Page					
	Total	3,145,268 K	2,863,428 K	165,384 K	33,296 K	38,856 K

- 6. You will see that over 2.8 GB are now active, of which 2.4 GB are in the Process Private row. This is due to the memory allocated and accessed by the TestLimit process. Note also that the standby, zeroed, and free lists are now much smaller. Most of the RAM allocated to TestLimit came from these lists.
- Next, in RAMMap, check the process's physical page allocations. Change to the Physical Pages tab, and set the filter at the bottom to the Process column and the value Testlimit.exe. This display shows all the physical pages that are part of the process working set.

se Count	Processe	s Priority S	ummary Physical Page	Physical Range	s File Summary File Details		
Physic	al Address	List	Use	Priority	Virtual Address	Image	^
	0x2D000	Active	Process Private	5	0x14AE2000		
	0x9D000	Active	Process Private		0x67E44000		
	0x9E000	Active	Process Private	5	0x7E3F6000		
	0x10F000	Active	Process Private	5	0x55534000		
	0x181000	Active	Process Private	5	0×5555F000		
	0x183000	Active	Process Private	5	0x5555E000		
	0x191000	Active	Process Private	5	0x37672000		
	0x192000	Active	Process Private	5	0x2F3A4000		
	0x195000	Active	Process Private	5	0x4AE25000		
	0x197000	Active	Process Private	5	0x73384000		
	0x1B1000	Active	Process Private	5	0x57E6D000		
	0x1B4000	Active	Process Private	5	0x57E71000		
	0x1B5000	Active	Process Private	5	0x446D5000		
	0x1B6000	Active	Process Private	5	0x60CFC000		
	0x1B7000	Active	Process Private	5	0x3CE60000		
	0x1B8000	Active	Process Private	5	0x58A43000		
	0x1B9000	Active	Process Private	5	0x3767C000		
	0x188000	Active	Process Private	5	0x78139000		
	0v18C000	Active	Process Private	5	0v18380000		, ×

8. We would like to identify a physical page involved in the allocation of virtual address space done by TestLimit's –d option. RAMMap does not give an indication about which virtual allocations are associated with RAMMap's VirtualAlloc calls. However, we can get a good hint of this through the VMMap tool. Using VMMap on the same process, we find the following:


and the second second	ysinternals: www.sysin w Tools Options		om							×
Process: PID:		Teh								
Committed:									2	.071,696
Private Bytes:									2	,027,204
Working Set:									2	.031.284
training sect									-	1001/201
Туре	Size	c	ommitted	Private	Total V	VS	Private WS	Shareal	ble WS	S
otal	2.090.436 K	2(	)71.696 K	2.027.204 K	2.031.28	AK .	K 2.027.144 K		4.140 K	
тасе	42.228 K		42.228 K	488 K	4.17	4,176 K 440 K			3.736 K	
lapped File	976 K		976 K		17	76 K			176 K	
hareable	15,400 K		1,712 K		220 K				220 K	
leap	1.248 K		232 K	168 K	17	2 K	168 K		4 K	
Aanaged Heap										
Btack	256 K		20 K	20 K	1	2 K	12 K			
Private Data	2.024.528 K	2.0	022.428 K	2.022.428 K	2.022.42	8 K	2,022,424 K		4 K	
age Table	4,100 K		4,100 K	4,100 K	4,10		4,100 K			
Inusable	1,700 K									
ree	10,752 K									
	<					1				>
	1			1000	-	-		~	1002	
Address	Туре	Size	Committed	Private	Total WS	Private	Sharea	Share	Lock	Blocks
± 00010000	Private Data	1,024 K	1,024 K	1,024 K	1,024 K	1,024 K				
⊞ 00110000	Private Data	1,024 K	1,024 K	1,024 K	1,024 K	1,024 K				
00210000	Private Data	1,024 K	1,024 K	1,024 K	1,024 K	1,024 K				annan an Air
+ 00310000	Private Data	1.024 K	1.024 K	1.024 K	1.024 K	1.024 K				
± 00410000	Private Data	1.024 K	1,024 K	1,024 K	1,024 K	1,024 K				
00510000	Private Data	1.024 K	1.024 K	1,024 K	1,024 K	1,024 K				
0000000     000000     000000     000000	Heap (Shareable)	64 K	64 K	100	4 K	6 100	4 K	4 K		
± 00670000	Heap (Private Data)	32 K	4K	4 K	4 K	4 K		00.15		2
D0680000	Shareable	88 K	88 K		88 K		88 K	88 K		1
1 006A0000	Thread Stack	256 K	20 K	20 K	12 K	12 K	94	8 K		3
<ul> <li>■ 006E0000</li> <li>■ 006F0000</li> </ul>	Charashla K	12 K	12 K		8 K		ak	88		>
					Timeline	Hann A	locations	Call Tree.	1	Trace

- **9.** In the lower part of the display, we find hundreds of allocations of process private data, each 1 MB in size and with 1 MB committed. These match the size of the allocations done by TestLimit. One of these is highlighted in the preceding screenshot. Note the starting virtual address, 0x310000.
- **10.** Now go back to RAMMap's physical memory display. Arrange the columns to make the Virtual Address column easily visible, click it to sort by that value, and you can find that virtual address:

Use Counts Processes Prior	ity Summary Physical Pages	Physical Rang	es File Summary File Details			
Physical Address List	Use	Priority	Virtual Address	8	Image	
0x21233000 Active	Process Private	5	0x30A000			
0x2122AD00 Active	Process Private	5	0x308000			
0x212EF000 Active	Process Private	5	0x30C000			
0x212E9000 Active	Process Private	5	0x30D000			
0x21200000 Active	Process Private	5	0x30E000			
0x212D9000 Active	Process Private	5	0x30/000			
0x212D1000 Active	Process Private					
0x2182D000 Active	Process Private	5	0x315000			
0x211D6000 Active	Process Private	5	0x312000			
0x211D8000 Active	Process Private	5	0x313000			
0x211D9000 Active	Process Private	5	0x314000			
0x211DC000 Active	Process Private	5	0x315000			
0x211BC000 Active	Process Private	5	0x316000			
0x211A5000 Active	Process Private	5	0x317000			
0x211A6000 Active	Process Private	5	0x318000			
0x21194000 Active	Process Private	5	0x319000			
0x21195000 Active	Process Private	5	0x31A000			
0x21197006 Active	Process Private	5	0x31B000			
0v21190000 Artise	Dvv/wee Dvisate	<ul> <li>E</li> </ul>	0/310000			

**11.** This shows that the virtual page starting at 0x310000 is currently mapped to physical address 0x212D1000. TestLimit's –d option writes the program's own name to the first bytes of each allocation. We can demonstrate this with the !dc (display characters using physical address) command in the local kernel debugger:

- **12.** If you're not quick enough, this may fail—the page may be removed from the working set. For the final leg of the experiment, we will demonstrate that this data remains intact (for a while, anyway) after the process working set is reduced and this page is moved to the modified and then the standby page list.
- In VMMap, having selected the TestLimit process, open the View menu and choose Empty Working Set to reduce the process's working set to the bare minimum. VMMap's display should now look like this:



14. Notice that the Working Set bar graph is practically empty. In the middle section, the process shows a total working set of only 4 KB, and almost all of it is in page tables. Now return to RAMMap and refresh it. On the Use Counts tab, you will find that active pages have been reduced tremendously, with a large number of pages on the modified list and some on the standby list:

Use Counts	Processes Priority St	ummary Physical Pa	pes   Physical Rang	es File Summary 1	File Details		
	Usage	Total	Active	Standby	Modified	Zeroed	Free
	Process Private	799,060 K	279,780 K	76,504 K	442,776 K		PENNETIC STREET
	Mapped File	248,212 K	100,640 K	145,995 K	1,576 K		
	Shareable	54,044 K	53,992 K	32 K	20 K		
	Page Table	25,888 K	25,888 K				
	Paged Pool	62,608 K	62,424 K	184 K			
	Nonpaged Pool	73,024 K	73,012 K				
	System PTE	23,520 K	23,520 K				
	Session Private	15,764 K	15,764 K				
	Metafie	11,504K	7,084 K	4,320 K	100 K		
	AWE						
	Driver Locked	988 K	988 K				
	Kernel Stack	6,484 K	6,484 K				
	Unused	1,824,172 K	9,976 K			825,776 K	988,420 K
	Large Page						
	Total	3,145,268 K	659,552 K	227,036 K	444,472 K	825,776 K	988,420 K

**15.** RAMMap's Processes tab confirms that the TestLimit process contributed most of those pages to those lists:

Empty	Help									
se Counts	Processes	Priority :	Summary	Physical Pages	Physical Ranges	File Summary	File Details			
Process	v.	Session	PID	Private	Stan	dby	Modified	Page Table	Total	^
winlog	on.exe	2	2196	332 K	1	OK	OK	160 K	492 K	
winlog	on.exe	1	564	84 K		OK	OK	144 K	228 K	
wininit	t.exe	0	476	64 K		OK	BK	112 K	184 K	
windb	g.exe	2	4012	1,448 K	1	OK	OK	328 K	1,776 K	
VSSVC	.exe	0	1524	324 K	1	OK	OK	160 K	484 K	
vmma	p.exe	2	7792	7,108 K	1 13	28 K	OK	316 K	7,452 K	
userin	it.exe	2	280	0 K		OK	OK	28 K	28 K	
Testin	nit.exe		4544	44 K		16 K -	139,784 K	4,076 K	443,920 K	
Taskm	ngr.exe	2	5800	4,772 K	1	OK	OK	424 K	5, 196 K	
taskho	ostw.exe	2	7268	36 K	1	OK	OK	200 K	236 K	
taskho	ostw.exe	2	3444	1,428 K	6	OK	OK	288 K	1,716 K	
Syster	m	-1	4	OK	1	OK	OK	36 K	36 K	
sycho	st.exe	0	6612	296 K	6	OK	OK	240 K	536 K	
sycho	st.exe	0	1768	592 K	8	OK	OK	216 K	808 K	
sycho	st.exe	0	1876	512 K		OK	OK	172 K	684 K	
sycho	st.exe	0	1404	652 K		OK	12 K	200 K	864 K	
sycho	st.exe	0	2580	884 K	1	OK	412 K	212 K	1,508 K	
sycho	st.exe	0	1828	2,700 K	6	OK	OK	292 K	2,992 K	
sycho	st.exe	2	4064	2,764 K	1	OK	OK	480 K	3,244 K	
sycho	st.exe	0	1916	2,808 K		OK	OK	388 K	3, 195 K	
	st.exe	0	2588	340 K		OK	OK	152 K	492 K	
sucho	ct eve	n	748	2 676 K	2	0K	41	216 K	2 896 K	Y

# Page priority

Every physical page in the system has a page priority value assigned to it by the memory manager. The page priority is a number in the range 0 to 7. Its main purpose is to determine the order in which pages are consumed from the standby list. The memory manager divides the standby list into eight sublists that each stores pages of a particular priority. When the memory manager wants to take a page from the standby list, it takes pages from low-priority lists first.

Each thread and process in the system is also assigned a page priority. A page's priority usually reflects the page priority of the thread that first causes its allocation. (If the page is shared, it reflects the highest page priority among the sharing threads.) A thread inherits its page-priority value from the process to which it belongs. The memory manager uses low priorities for pages it reads from disk speculatively when anticipating a process's memory accesses.

By default, processes have a page-priority value of 5, but the SetProcessInformation and SetThreadInformation user-mode functions allow applications to change process and thread page-priority values. These functions call the native NtSetInformationProcess and NtSetInformation-Thread functions. You can look at the memory priority of a thread with Process Explorer (per-page priority can be displayed by looking at the PFN entries, as you'll see in an experiment later in the chapter). Figure 5-38 shows Process Explorer's Threads tab displaying information about Winlogon's main thread. Although the thread priority itself is high, the memory priority is still the standard 5.

	formance		nance Graph			d Network
GPU Graph Th	reads TO	P/IP :	Security	Enviro	nment	Strings
Count: 4						
TID ČPL	U Cycles Delt	ta Start A	ddress			
572			n exełWinM		Startup	
1208			TppWorker1			
15740			TppWorker1 TppWorker1			
K						>
< Thread ID:	572			Stack		> Yodule
Thread ID:	572 08:36:51 0	8-Sep-16		Stack		
Thread ID: Start Time: State:	08:36:51 0 Wait:UserRe	equest	Base Priorit	ty:	15	
Thread ID: Start Time: State: Kernel Time:	08:36:51 0 Wait:UserRe 0:00:00.125	equest	Base Priorit Dynamic Pri	ty: iority:	15 15	<u>M</u> odule
Thread ID: Start Time: State: Kernel Time: User Time:	08:36:51 0 Wait:UserRe 0:00:00.125 0:00:00.000	equest	Base Priorit Dynamic Pri I/O Priority	ty: iority: :	15 15 Norma	<u>M</u> odule
Thread ID: Start Time: State: Kernel Time: User Time: Context Switches:	08:36:51 0 Wait:UserRe 0:00:00.125 0:00:00.000 305	equest i	Base Priorit Dynamic Pri I/O Priority Memory Pri	ty: iority: : iority:	15 15 Norma 5	<u>M</u> odule
Thread ID: Start Time: State: Kernel Time: User Time:	08:36:51 0 Wait:UserRe 0:00:00.125 0:00:00.000	equest i	Base Priorit Dynamic Pri I/O Priority	ty: iority: : iority:	15 15 Norma	<u>M</u> odule

FIGURE 5-38 Process Explorer's Threads tab.

The real power of memory priorities is realized only when the relative priorities of pages are understood at a high level, which is the role of SuperFetch, covered at the end of this chapter.

### **EXPERIMENT:** Viewing the prioritized standby lists

You can use Process Explorer to look at the size of each standby paging list by opening the System Information dialog box and selecting the **Memory** tab:

Summary CPU	Memory I/O	GPU					
System Commit							
1.4 GB						1	
Commit Charge	00	Kernel Memory (K)		Paging Lists (K)			
Current Limit Peak	1,362,892 3,669,556 1,368,572	Paged Virtual 1	03,648 04,988 symbols	Zeroed Free Modified ModifiedNoWrite	1,390,928 0 37,896 0		
Peak/Limit Current/Limit	37.30% 37.14%	Nonpaged Nonpaged Limit	59,004 2,048	Standby Priority 0	308,224 8,764		
Physical Memor	y (K)	Paging		Priority 1 Priority 2	47,704 68,968		
Total Available Cache WS Kernel WS Driver WS	3,145,268 1,699,152 0 0 15,620	Page Fault Delta Page Read Delta Paging File Write Delta Mapped File Write Delta	15,119 87 0 0	Priority 3 Priority 4 Priority 5 Priority 6 Priority 7	0 99,144 83,644 0 0		
				PageFileModified	37,752		

On the recently started x86 system used in this experiment, there is about 9 MB of data cached at priority 0, about 47 MB at priority 1, about 68 MB at priority 2, etc. The following shows what happens when we use the TestLimit tool from Sysinternals to commit and touch as much memory as possible:

Summary CPU	Memory I/O	GPU				
System Commit						
				-		
2.9 GB				1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 -	1	-
Physical Memory						_
	8			-		 1
28GB				and the second s		 -1
Commit Charge	0/1	Kernel Memory (K)	Paging Lists (K)	(0)		_
Current	3,011,884	Paged WS 61,300	Zeroed	90,740		
Limit	3,669,556	Paged Virtual 113,152	Free	0		
Peak	3.012.268	Paged Limit no symbols	Modified	412		
	82.09%		ModifiedNoWrite	0		
Peak/Limit Current/Limit	82.09%	Nonpaged 43,660 Nonpaged Limit 2,048	Standby	317,480 904		
			Priority 0 Priority 1	4,136		
Physical Memory		Paging	Priority 2	24,584		
Total	3,145,268	Page Fault Delta 22,475 Page Read Delta 479	Priority 3	0		
	408,220	Page Read Delta 479 Paging File Write Delta 13,213	Priority 4	163, 148		
Available	0	Mapped File Write Delta 0	Priority 5 Priority 6	54,360 9,136		
Cache WS		copped the state bend	Priority 7	61,212		
	8,460		PageFileModified			

C:\Tools\Sysinternals>Testlimit.exe -d

Note how the lower-priority standby page lists were used first (shown by the repurposed count) and are now much smaller, while the higher lists still contain valuable cached data.

# Modified page writer and mapped page writer

The memory manager employs two system threads to write pages back to disk and move those pages back to the standby lists (based on their priority). One system thread writes out modified pages (MiModifiedPageWriter) to the paging file, and a second one writes modified pages to mapped files (MiMappedPageWriter). Two threads are required to avoid creating a deadlock. This would occur if the writing of mapped file pages caused a page fault that in turn required a free page when no free pages were available, thus requiring the modified page writer to create more free pages. By having the modified page writer perform mapped file paging I/Os from a second system thread, that thread can wait without blocking regular page file I/O.

Both threads run at priority 18, and after initialization they wait for separate event objects to trigger their operation. The mapped page writer waits on 18 event objects:

- An exit event, signaling the thread to exit (not relevant to this discussion).
- The mapped writer event, stored in the global variable MiSystemPartition.Modwriter.
   MappedPageWriterEvent (MmMappedPageWriterEvent on Windows 8.x and Server 2012/R2).
   This event can be signaled in the following instances:
  - During a page list operation (MiInsertPageInList); this routine inserts a page into one of the lists (standby, modified, etc.) based on its input arguments. The routine signals this event if the number of file-system-destined pages on the modified page list has reached more than 16 and the number of available pages has fallen below 1024.
  - In an attempt to obtain free pages (MiObtainFreePages).
  - By the memory manager's working set manager (MmWorkingSetManager), which runs as part of the kernel's balance set manager (once every second). The working set manager signals this event if the number of file-system-destined pages on the modified page list has reached more than 800.
  - Upon a request to flush all modified pages (MmFlushAllPages).
  - Upon a request to flush all file-system-destined modified pages (MmFlushAllFilesystem-Pages). Note that in most cases, writing modified mapped pages to their backing store files does not occur if the number of mapped pages on the modified page list is less than the maximum write cluster size, which is 16 pages. This check is not made in MmFlushAllFilesystemPages or MmFlushAllPages.
- An array of 16 events associated with 16 mapped page lists, stored in MiSystemPartition. PageLists.MappedPageListHeadEvent (MiMappedPageListHeadEvent on Windows 8.x and Server 2012/R2). Each time a mapped page is dirtied, it is inserted into one of these 16 mapped page lists based on a bucket number, stored in MiSystemPartition.WorkingSetControl->CurrentMappedPageBucket (MiCurrentMappedPageBucket on Windows 8.x and Server 2012/R2). This bucket number is updated by the working set manager whenever the system considers that mapped pages have gotten old enough, which is currently 100 seconds (stored in the WriteGapCounter variable in the same structure [MiWriteGapCounter on Windows 8.x

and Server 2012/R2] and incremented whenever the working set manager runs). The reason for these additional events is to reduce data loss in the case of a system crash or power failure by eventually writing out modified mapped pages even if the modified list hasn't reached its threshold of 800 pages.

The modified page writer waits on two events: the first is an Exit event, and the second stored in MiSystemPartition.Modwriter.ModifiedPageWriterEvent (on Windows 8.x and Server 2012/R2 waits on a kernel gate stored in MmModifiedPageWriterGate), which can be signaled in the following scenarios:

- A request to flush all pages has been received.
- The number of available pages—stored in MiSystemPartition.Vp.AvailablePages (MmAvailablePages on Windows 8.x and Server 2012/R2)—drops below 128 pages.
- The total size of the zeroed and free page lists drops below 20,000 pages, and the number of modified pages destined for the paging file is greater than the smaller of one-sixteenth of the available pages or 64 MB (16,384 pages).
- When a working set is being trimmed to accommodate additional pages, if the number of pages available is less than 15,000.
- During a page list operation (MiInsertPageInList). This routine signals this event if the number of page-file-destined pages on the modified page list has reached more than 16 pages and the number of available pages has fallen below 1,024.

Additionally, the modified page writer waits on two other events after the preceding event is signaled. One is used to indicate rescanning of the paging file is required (for example, a new page file may have been created), stored in MiSystemPartition.Modwriter.RescanPageFilesEvent (MiRescanPageFilesEvent on Windows 8.x and Server 2012/R2). The second event is internal to the paging file header (MiSystemPartition.Modwriter.PagingFileHeader [MmPagingFileHeader on Windows 8.x and Server 2012/R2]), which allows the system to manually request flushing out data to the paging file when needed.

When invoked, the mapped page writer attempts to write as many pages as possible to disk with a single I/O request. It accomplishes this by examining the original PTE field of the PFN database elements for pages on the modified page list to locate pages in contiguous locations on the disk. Once a list is created, the pages are removed from the modified list, an I/O request is issued, and, at successful completion of the I/O request, the pages are placed at the tail of the standby list corresponding to their priority.

Pages that are in the process of being written can be referenced by another thread. When this happens, the reference count and the share count in the PFN entry that represents the physical page are incremented to indicate that another process is using the page. When the I/O operation completes, the modified page writer notices that the reference count is no longer 0 and doesn't place the page on any standby list.

# **PFN data structures**

Although PFN database entries are of fixed length, they can be in several different states, depending on the state of the page. Thus, individual fields have different meanings depending on the state. Figure 5-39 shows the formats of PFN entries for different states.


> Forward Link PTE address | Lock D 1 1111

We	Working Set Index							
PT	PTE address   Lock							
Share Count								
Flags	Туре	9	Priority					
Caching Att	ributes	Reference Count						
Orig	ginal PT	E Co	ntent					
PFN of PTI	E Fla	gs	Page Color					

PFN for a page in a worki

	В	аскwа	ra Li	пк		
riority	Flags	Тур	е	Priority		
ice Count	Caching Attributes Reference Co					
nt	Orig	inal PT	E Co	ntent		
ge Color	PFN of PTE	Fla	gs	Page Color		
ing set	PFN for a or modifie		on th	e standby		
And the	10 mm		775, T. T.			

er L	ink to	Next Stack PFN			
ddres	ss	Lock			
Share Count					
Туре		Priority			
utes	Reference Count				
al PT	E Co	ntent			
Fla	gs	Page Color			
	ddre: are ( Type ites al PTI	ddress   are Coun Type			



PFN for a page belonging to a kernel stack

PFN for a page with I/O in progress

FIGURE 5-39 States of PFN database entries (specific layouts are conceptual).

Several fields are the same for several PFN types, but others are specific to a given type of PFN. The following fields appear in more than one PFN type:

- **PTE address** This is the virtual address of the PTE that points to this page. Also, since PTE addresses will always be aligned on a 4-byte boundary (8 bytes on 64-bit systems), the two low-order bits are used as a locking mechanism to serialize access to the PFN entry.
- **Reference count** This is the number of references to this page. The reference count is incremented when a page is first added to a working set and/or when the page is locked in memory for I/O (for example, by a device driver). The reference count is decremented when the share count becomes 0 or when pages are unlocked from memory. When the share count becomes 0, the page is no longer owned by a working set. Then, if the reference count is also zero, the PFN database entry that describes the page is updated to add the page to the free, standby, or modified list.
- **Type** This is the type of page represented by this PFN. (Types include active/valid, standby, modified, modified-no-write, free, zeroed, bad, and transition.)
- **Flags** The information contained in the flags field is shown in Table 5-20.
- **Priority** This is the priority associated with this PFN, which will determine on which standby list it will be placed.

- Original PTE contents All PFN database entries contain the original contents of the PTE that pointed to the page (which could be a prototype PTE). Saving the contents of the PTE allows it to be restored when the physical page is no longer resident. PFN entries for AWE allocations are exceptions; they store the AWE reference count in this field instead.
- **PFN of PTE** This is the physical page number of the page table page containing the PTE that points to this page.
- Color Besides being linked together on a list, PFN database entries use an additional field to link physical pages by "color," which is the page's NUMA node number.
- **Flags** A second flags field is used to encode additional information on the PTE. These flags are described in Table 5-21.

Flag	Meaning
Write in progress	This indicates that a page write operation is in progress. The first DWORD contains the ad- dress of the event object that will be signaled when the I/O is complete.
Modified state	This indicates whether the page was modified. (If the page was modified, its contents must be saved to disk before removing it from memory.)
Read in progress	This indicates that an in-page operation is in progress for the page. The first DWORD contains the address of the event object that will be signaled when the I/O is complete.
ROM	This indicates that this page comes from the computer's firmware or another piece of read-only memory such as a device register.
In-page error	This indicates that an I/O error occurred during the in-page operation on this page. (In this case, the first field in the PFN contains the error code.)
Kernel stack	This indicates that this page is being used to contain a kernel stack. In this case, the PFN entry contains the owner of the stack and the next stack PFN for this thread.
Removal requested	This indicates that the page is the target of a remove (due to ECC/scrubbing or hot memory removal).
Parity error	This indicates that the physical page contains parity or error correction control errors.

TABLE 5-20 Flags within PFN database entries

#### TABLE 5-21 Secondary flags within PFN database entries

Flag	Meaning
PFN image verified	This indicates that the code signature for this PFN (contained in the cryptographic signature catalog for the image being backed by this PFN) has been verified.
AWE allocation	This indicates that this PFN backs an AWE allocation.
Prototype PTE	This indicates that the PTE referenced by the PFN entry is a prototype PTE. For example, this page is shareable.

The remaining fields are specific to the type of PFN. For example, the first PFN in Figure 5-39 represents a page that is active and part of a working set. The share count field represents the number of PTEs that refer to this page. (Pages marked read-only, copy-on-write, or shared read/write can be shared by multiple processes.) For page table pages, this field is the number of valid and transition PTEs in the page table. As long as the share count is greater than 0, the page isn't eligible for removal from memory. The working set index field is an index into the process working set list (or the system or session working set list, or zero if not in any working set) where the virtual address that maps this physical page resides. If the page is a private page, the working set index field refers directly to the entry in the working set list because the page is mapped only at a single virtual address. In the case of a shared page, the working set index is a hint that is guaranteed to be correct only for the first process that made the page valid. (Other processes will try to use the same index where possible.) The process that initially sets this field is guaranteed to refer to the proper index and doesn't need to add a working set list hash entry referenced by the virtual address into its working set hash tree. This guarantee reduces the size of the working set hash tree and makes searches faster for these entries.

The second PFN in Figure 5-39 is for a page on either the standby or the modified list. In this case, the forward and backward link fields link the elements of the list together within the list. This linking allows pages to be easily manipulated to satisfy page faults. When a page is on one of the lists, the share count is by definition 0 (because no working set is using the page) and therefore can be overlaid with the backward link. The reference count is also 0 if the page is on one of the lists. If it is non-zero (because an I/O could be in progress for this page—for example, when the page is being written to disk), it is first removed from the list.

The third PFN in Figure 5-39 is for a page that belongs to a kernel stack. As mentioned earlier, kernel stacks in Windows are dynamically allocated, expanded, and freed whenever a callback to user mode is performed and/or returns, or when a driver performs a callback and requests stack expansion. For these PFNs, the memory manager must keep track of the thread actually associated with the kernel stack, or if it is free it keeps a link to the next free look-aside stack.

The fourth PFN in Figure 5-39 is for a page that has an I/O in progress (for example, a page read). While the I/O is in progress, the first field points to an event object that will be signaled when the I/O completes. If an in-page error occurs, this field contains the Windows error status code representing the I/O error. This PFN type is used to resolve collided page faults.

In addition to the PFN database, the system variables in Table 5-22 describe the overall state of physical memory.

Variable (Windows 10 and Server 2016)	Variable (Windows 8.x and Server 2012/R2)	Description
MiSystemPartition.Vp.NumberOfPhysicalPages	MmNumberOfPhysicalPages	This is the total number of physical pages avail- able on the system.
MiSystemPartition.Vp.AvailablePages	MmAvailablePages	This is the total number of available pages on the system—the sum of the pages on the zeroed, free, and standby lists.
MiSystemPartition.Vp.ResidentAvailablePages	MmResidentAvailablePages	This is the total number of physical pages that would be available if every pro- cess was trimmed to its minimum working set size and all modified pages were flushed to disk.

TABLE 5-22	System variables that describe physical memory
------------	--

### **EXPERIMENT: Viewing PFN entries**

You can examine individual PFN entries with the kernel debugger !pfn command. You need to supply the PFN as an argument. (For example, !pfn 0 shows the first entry, !pfn 1 shows the second, and so on.) In the following example, the PTE for virtual address 0xD20000 is displayed, followed by the PFN that contains the page directory, and then the actual page:

```
1kd> !pte d20000
               VA 00d20000
PDE at C0600030 PTE at C0006900
contains 00000003E989867 contains 800000093257847
pfn 3e989 ---DA--UWEV pfn 93257 ---D---UW-V
1kd> !pfn 3e989
   PFN 0003E989 at address 868D8AFC
   flink 00000071 blink / share count 00000144 pteaddress C0600030
   reference count 0001 Cached color 0 Priority 5
   restore pte 00000080 containing page 0696B3 Active
                                                     М
   Modified
1kd> !pfn 93257
   PFN 00093257 at address 87218184
   flink 000003F9 blink / share count 00000001 pteaddress C0006900
   reference count 0001 Cached color 0 Priority 5
   restore pte 00000080 containing page 03E989 Active
                                                     М
   Modified
```

You can also use the MemInfo tool to obtain information about a PFN. MemInfo can sometimes give you more information than the debugger's output, and it does not require being booted into debugging mode. Here's MemInfo's output for those same two PFNs:

C:\Tools>MemInfo.exe -p 3e989							
0x3E989000 Active	Page Table	5	N/A	0xC0006000	0x8E499480		
C:\Tools>MemInfo.exe -p 93257							
0x93257000 Active	Process Private	5	windba.exe	0x00D20000	N/A		

From left to right, the information shown includes the physical address, type, page priority, process name, virtual address, and potential extra information. MemInfo correctly recognized that the first PFN was a page table and that the second PFN belongs to WinDbg, which was the active process when the !pte d20000 command was used in the debugger.

## Page file reservation

We have already seen some mechanisms used by the memory manager to attempt to reduce physical memory consumption and thus reduce accessing page files. Using the standby and modified list is one such mechanism, and so is memory compression (see the "Memory compression" section later in this chapter). Another optimization the memory uses is directly related to accessing page files themselves.

Rotational hard disks have a moving head that travels to a target sector before the disk can actually read or write. This seek time is relatively expensive (in the order of milliseconds) and so the total disk activity is the seek time added to the actual read/write time. If the amount of data accessed contiguously from the seek position is large, then the seek time may be negligible. But if the head must seek a lot while accessing scattered data on the disk, the aggregated seek time becomes the main issue.


When the Session Manager (Smss.exe) creates a page file, it queries the disk of the file's partition to find whether it's a rotational disk or a solid-state drive (SSD). If it's rotational, it activates a mechanism called *page file reservations* that tries to keep contiguous pages in physical memory contiguous in the page file as well. If the disk is an SSD (or a hybrid, which for the sake of page file reservation is treated as SSD), then page file reservation adds no real value (since there is no moving head), and the feature is not utilized for this particular page file.

Page file reservation is handled in three locations within the memory manager: working set manager, modified page writer, and page fault handler. The working set manager performs working set trimming by calling the MiFreeWsleList routine. The routine takes a list of pages from a working set and for each page it decrements its share count. If it reaches zero, the page can be placed on the modified list, changing the relevant PTE into a transition PTE. The old valid PTE is saved in the PFN.

The invalid PTE has two bits related to page file reservation: page file reserved and page file allocated (refer to Figure 5-24). When a physical page is needed and is taken from one of the "free" page lists (free, zero or standby) to become an active (valid) page, an invalid PTE is saved into the Original PTE field of the PFN. This field is the key for tracking page file reservation.

The MiCheckReservePageFileSpace routine tries to create page file reservation cluster starting from a specified page. It checks if page file reservation is disabled for the target page file and if there is already page file reservation for this page (based on the original PTE), and if any of these conditions is true, the function aborts further processing for this page. The routine also checks if the page type is of user pages, and if not, it bails out. Page file reservation is not attempted for other page types (such as paged pool), because it was not found to be particularly beneficial (because of unpredictable usage patterns, for example), which led to small clusters. Finally, MiCheckReservePageFileSpace calls MiReservePageFileSpace to do the actual work.

The search for page file reservation starts backward from the initial PTE. The goal is to locate eligible consecutive pages where reservation is possible. If the PTE that maps the neighboring page represents a decommitted page, a non-paged pool page, or if it's already reserved, then the page cannot be used; the current page will become the lower limit of the reservation cluster. Otherwise, the search continues backward. Then the search starts from the initial page forward, trying to gather as many eligible pages as possible. The cluster size must be at least 16 pages for the reservation to take place (the maximum cluster size is 512 pages). Figure 5-40 shows an example of a cluster bound by invalid page on one hand and an existing cluster on the other (note that it can span page tables within the same page directory).





Once the page cluster is computed, free page file space must be located to be reserved for this cluster of pages. Page file allocations are managed by a bitmap (where each set bit indicates a used page in the file). For page file reservation, a second bitmap is used that indicates pages that have been reserved (but not necessarily written to yet—this is the job of the page file allocation bitmap). Once there is page file space that is not reserved and not allocated (based on these bitmaps), the relevant bits are set in the reservation bitmap only. It is the job of the modified page writer to set these bits in the allocation bitmap when it writes the contents of the pages to disk. If not enough page file space could be found for the required cluster size, page file expansion is attempted, and if that already happened (or the maximum page file size is the expanded size), then the cluster size is reduced to fit in the reservation size that was located.

**Note** The clustered pages (except the original starting PTE) are not linked to any of the physical page lists. The reservation information is placed in the Original PTE of the PFN.

The modified page writer needs to handle writing pages that have reservations as a special case. It uses all the gathered information described previously to build an MDL that contains the correct PFNs for the cluster that is used as part of writing to the page file. Building the cluster includes finding contiguous pages that can span reservation clusters. If there are "holes" between clusters, a dummy page is added in between (a page that contains all bytes with 0xFF value). If the dummy page count is above 32, the cluster is broken. This "walk" is done going forward and then backward to build the final cluster to write. Figure 5-41 shows an example of the state of pages after such a cluster has been built by the modified page writer.




FIGURE 5-41 Cluster built before writing.

Finally, the page fault handler uses the built information from the reservation bitmap and the PTEs to determine the start and end points of clusters, to efficiently load back needed pages with minimal seeking of the mechanical disk head.

# **Physical memory limits**

Now that you've learned how Windows keeps track of physical memory, we'll describe how much of it Windows can actually support. Because most systems access more code and data than can fit in physical memory as they run, physical memory is essentially a window into the code and data used over time. The amount of memory can therefore affect performance because when data or code that a process or the operating system needs is not present, the memory manager must bring it in from disk or remote storage.

Besides affecting performance, the amount of physical memory affects other resource limits. For example, the amount of non-paged pool is backed by physical memory, thus obviously constrained by physical memory. Physical memory also contributes to the system virtual memory limit, which is the sum of roughly the size of physical memory plus the current configured size of all paging files. Physical memory also can indirectly limit the maximum number of processes.

Windows support for physical memory is dictated by hardware limitations, licensing, operating system data structures, and driver compatibility. The following URL shows the memory limits of the various Windows editions: *https://msdn.microsoft.com/en-us/library/windows/desktop/aa366778.aspx*. Table 5-23 summarizes the limits in Windows 8 and higher versions.

**TABLE 5-23** Limitations on physical memory support in Windows

Operating System Version/Edition	32-Bit Maximum	64-Bit Maximum
Windows 8.x Professional and Enterprise	4 GB	512
Windows 8.x (all other editions)	4 GB	128 GB
Windows Server 2012/R2 Standard and Datacenter	N/A	4 TB
Windows Server 2012/R2 Essentials	N/A	64 GB
Windows Server 2012/R2 Foundation	N/A	32 GB
Windows Storage Server 2012 Workgroup	N/A	32 GB
Windows Storage Server 2012 Standard Hyper-V Server 2012	N/A	4 TB
Windows 10 Home	4 GB	128 GB
Windows 10 Pro, Education and Enterprise	4 GB	2 TB
Windows Server 2016 Standard and Datacenter	N/A	24 TB

At the time of this writing, the maximum supported physical memory is 4 TB on some Server 2012/R2 editions and 24 TB on Server 2016 editions. The limitations don't come from any implementation or hardware limitation, but because Microsoft will support only configurations it can test. As of this writing, these were the largest tested and supported memory configurations.

# Windows client memory limits

64-bit Windows client editions support different amounts of memory as a differentiating feature, with the low end being 4 GB increasing to 2 TB for Enterprise and Professional editions. All 32-bit Windows client editions, however, support a maximum of 4 GB of physical memory, which is the highest physical address accessible with the standard x86 memory management mode.

Although client SKUs support PAE addressing modes on x86 systems in order to provide hardware no-execute protection (which would also enable access to more than 4 GB of physical memory), testing revealed that systems would crash, hang, or become unbootable because some device drivers, commonly those for video and audio devices found typically on clients but not servers, were not programmed to expect physical addresses larger than 4 GB. As a result, the drivers truncated such addresses, resulting in memory corruptions and corruption side effects. Server systems commonly have more generic devices, with simpler and more stable drivers, and therefore had not generally revealed these problems. The problematic client driver ecosystem led to the decision for client editions to ignore physical memory that resides above 4 GB, even though they can theoretically address it. Driver developers are encouraged to test their systems with the nolowmem BCD option, which will force the kernel to use physical addresses above 4 GB only if sufficient memory exists on the system to allow it. This will immediately lead to the detection of such issues in faulty drivers.

Although 4 GB is the licensed limit for 32-bit client editions, the effective limit is actually lower and depends on the system's chipset and connected devices. This is because the physical address map includes not only RAM but device memory, and x86 and x64 systems typically map all device memory below the 4 GB address boundary to remain compatible with 32-bit operating systems that don't know

how to handle addresses larger than 4 GB. Newer chipsets do support PAE-based device remapping, but client editions of Windows do not support this feature for the driver compatibility problems explained earlier. (Otherwise, drivers would receive 64-bit pointers to their device memory.)

If a system has 4 GB of RAM and devices such as video, audio, and network adapters that implement windows into their device memory that sum to 500 MB, then 500 MB of the 4 GB of RAM will reside above the 4 GB address boundary, as shown in Figure 5-42.




FIGURE 5-42 Physical memory layout on a 4 GB system.

The result is that if you have a system with 3 GB or more of memory and you are running a 32-bit Windows client, you may not get the benefit of all the RAM. You can see how much RAM Windows has detected as being installed in the System Properties dialog box, but to see how much memory is *really* available to Windows, you need to look at Task Manager's Performance page or the Msinfo32 utility. For example, on a Hyper-V virtual machine configured with 4 GB of RAM, with 32-bit Windows 10 installed, the amount of physical memory available is 3.87 GB, as shown in the Msinfo32 utility:

```
Installed Physical Memory (RAM) 4.00 GB
Total Physical Memory 3.87 GB
```

You can see the physical memory layout with the MemInfo tool. The following output is from MemInfo when run on a 32-bit system, using the -r switch to dump physical memory ranges:

```
C:\Tools>MemInfo.exe -r

MemInfo v3.00 - Show PFN database information

Copyright (C) 2007-2016 Alex Ionescu

www.alex-ionescu.com

Physical Memory Range: 00001000 to 0009F000 (158 pages, 632 KB)

Physical Memory Range: 00100000 to 00102000 (2 pages, 8 KB)

Physical Memory Range: 00103000 to F7FF0000 (1015533 pages, 4062132 KB)

MmHighestPhysicalPage: 1015792
```

Note the gap in the memory address range from A0000 to 100000 (384 KB), and another gap from F8000000 to FFFFFFF (128 MB).

You can use Device Manager on your machine to see what is occupying the various reserved memory regions that can't be used by Windows (and that will show up as holes in MemInfo's output). To check Device Manager, follow these steps:

- 1. Run Devmgmt.msc.
- 2. Open the View menu and select Resources by Connection.
- **3.** Expand the **Memory** node. On the laptop computer used for the output shown in Figure 5-43, the primary consumer of mapped device memory is, unsurprisingly, the video card (Hyper-V S3 Cap), which consumes 128 MB in the range F8000000–FBFFFFF.

~	Memory
	time [00000000 - 0009FFFF] System board
	to 000A0000 - 000BFFFF] PCI Bus
	E [000C0000 - 000DFFFF] System board
	tem [000E0000 - 000FFFFF] System board
	🏣 [00100000 - F7FFFFF] System board
	IE0000000 - FFFFFFF] PCI Bus
	🏣 [FF800000 - FFFFFFF] Microsoft Hyper-V Video
	Image: The second se
	🏣 [F8000000 - FBFFFFF] Microsoft Hyper-V S3 Cap
	👮 [FEBFF000 - FEBFFFFF] Intel 21140-Based PCI Fast Ethernet Adapter (Emulated)
	🏣 [FEC00000 - FEC00FFF] Motherboard resources
	Tail [FEE00000 - FEE00FFF] Motherboard resources
	E [FFFC0000 - FFFFFFF] System board



Other miscellaneous devices account for most of the rest, and the PCI bus reserves additional ranges for devices as part of the conservative estimation the firmware uses during boot.

# **Memory compression**

The Windows 10 memory manager implements a mechanism that compresses private and page-filebacked section pages that are on the modified page list. The primary candidates for compression are private pages belonging to UWP apps because compression works very well with the working set swapping and emptying that already occurs for such applications if memory is tight. After an application is suspended and its working set is outswapped, the working set can be emptied at any time and dirty pages can be compressed. This will create additional available memory that may be enough to hold another application in memory without making the first application's pages leave memory.

c	÷	÷	÷	÷	2	
L	=			-		
L	Ξ					
L					J	

**Note** Experiments have shown that pages compress to around 30–50 percent of their original size using Microsoft's Xpress algorithm, which balances speed with size, thus resulting in considerable memory savings.

The memory compression architecture must adhere to the following requirements:

A page cannot be in memory in a compressed and an uncompressed form because this would waste physical memory due to duplication. This means that whenever a page is compressed, it must become a free page after successful compression.

- The compression store must maintain its data structures and store the compressed data such that it is always saving memory for the system overall. This means that if a page doesn't compress well enough, it will not be added to the store.
- Compressed pages must appear as available memory (because they can really be repurposed if needed) to avoid creating a perception issue that compressing memory somehow increases memory consumption.

Memory compression is enabled by default on client SKUs (phone, PC, Xbox, and so on). Server SKUs do not currently use memory compression, but that is likely to change in future server versions.




**Note** In Windows 2016, Task Manager still shows a number in parentheses for compressed memory, but that number is always zero. Also, the memory compression process does not exist.

During system startup, the Superfetch service (sysmain.dll, hosted in a svchost.exe instance, described in the upcoming "Proactive memory management (SuperFetch)" section) instructs the Store Manager in the executive through a call to NtSetSystemInformation to create a single system store (always the first store to be created), to be used by non-UWP applications. Upon app startup, each UWP application communicates with the Superfetch service and requests the creation of a store for itself.


# **Compression illustration**

To get a sense of how memory compression works, let's look at an illustrative example. Assume that at some point in time, the following physical pages exist:




The zero and free page lists contain pages that have garbage and zeroes, respectively, and can be used to satisfy memory commits; for the sake of this discussion, we'll treat them as one list. The active pages belong to various processes, while the modified pages have dirty data that has not yet been written to a page file, but can be soft-faulted without an I/O operation to a process working set if that process references a modified page.


Now assume the memory manager decides to trim the modified page list—for example, because it has become too large or the zero/free pages have become too small. Assume three pages are to be removed from the modified list. The memory manager compresses their contents into a single page (taken from the zero/free list):




Pages 11, 12 and 13 are compressed into page 1. After that's done, page 1 is no longer free and is in fact active, part of the working set of the memory compression process (described in the next section). Pages 11, 12, and 13 are no longer needed and move to the free list; the compression saved two pages:



Suppose the same process repeats. This time, pages 14, 15, and 16 are compressed into (say) two pages (2 and 3) as shown here:




The result is that pages 2 and 3 join the working set of the memory compression process, while pages 14, 15, and 16 become free:




Modified


Suppose the memory manager later decides to trim the working set of the memory compression process. In that case, such pages are moved to the modified list because they contain data not yet written to a page file. Of course, they can at any time be soft-faulted back into their original process (decompressing in the process by using free pages). The following shows pages 1 and 2 being removed from the active pages of the memory compression process and moved to the modified list:



If memory becomes tight, the memory manager may decide to write the compressed modified pages to a page file:



Finally, after such pages have been written to a page file, they move to the standby list because their content is saved, so they can be repurposed if necessary. They can also be soft-faulted (as when they are part of the modified list) by decompressing them and moving the resulting pages to the active state under the relevant process working set. When in the standby list, they are attached to the appropriate sub-list, depending on their priority (as described in the "Page priority and rebalancing" section later in this chapter):



#### **Compression architecture**

The compression engine needs a "working area" memory to store compressed pages and the data structures that manage them. In Windows 10 versions prior to 1607, the user address space of the System process was used. Starting with Windows 10 Version 1607, a new dedicated process called *Memory Compression* is used instead. One reason for creating this new process was that the System process memory consumption looked high to a casual observer, which implied the system was consuming a lot of memory. That was not the case, however, because compressed memory does not count against the commit limit. Nevertheless, sometimes perception is everything.

The Memory Compression process is a minimal process, which means it does not load any DLLs. Rather, it just provides an address space to work with. It's not running any executable image either the kernel is just using its user mode address space. (See Chapter 3, "Processes and jobs," for more information on minimal processes.)

**Note** By design, Task Manager does not show the Memory Compression process in its details view, but Process Explorer does. Using a kernel debugger, the compression process image name is MemCompression.

For each store, the Store Manager allocates memory in regions with a configurable region size. Currently, the size used is 128 KB. The allocations are done by normal VirtualAlloc calls as needed. The actual compressed pages are stored in 16 byte chunks within a region. Naturally, a compressed page (4 KB) can span many chunks. Figure 5-44 shows a store with an array of regions and some of the data structures associated with managing such a store.




FIGURE 5-44 Store data structures.

As shown in Figure 5-44, pages are managed with a B+Tree—essentially a tree where a node can have any number of children—where each page entry points to its compressed content within one of the regions. A store starts with zero regions, and regions are allocated and deallocated as needed. Regions are also associated with priorities, as described in the "Page priority and rebalancing" section later in this chapter.

Adding a page involves the following major steps:

- If there is no current region with the page's priority, allocate a new region, lock it in physical memory, and assign it the priority of the page to be added. Set the current region for that priority to the allocated region.
- 2. Compress the page and store it in the region, rounding up to the granularity unit (16 bytes). For example, if a page compresses to 687 bytes, it consumes 43 16-byte units (always rounding up). Compression is done on the current thread, with low CPU priority (7) to minimize interference. When decompression is needed, it's performed in parallel using all available processors.
- 3. Update the page and region information in the Page and Region B+Trees.

**4.** If the remaining space in the current region is not large enough to store the compressed page, a new region is allocated (with the same page priority) and set as the current region for that priority.

Removing a page from the store involves the following steps:

- 1. Find the page entry in the Page B+Tree and the region entry in the Region B+Tree.
- 2. Remove the entries and update the space used in the region.
- 3. If the region becomes empty, deallocate the region.

Regions become fragmented over time as compressed pages are added and removed. The memory for a region is not freed until the region is completely empty. This means some kind of compaction is necessary to reduce memory waste. A compaction operation is lazily scheduled with aggressiveness depending on the amount of fragmentation. Region priorities are taken into account when consolidating regions.

#### **EXPERIMENT:** Memory compression

There is very little visibility to the memory compression going on in the system. You can view the memory compression process with Process Explorer or a kernel debugger. The following figure shows the Performance tab in the properties of the Memory Compression process in Process Explorer (which must run with admin privileges):

GPU Graph	Threads	TCP/IP	Security	Environment	Strings
Image	Performance	Perf	ormance Graph	Disk an	d Network
CPU			I/O		
Priority		8	I/O Priorit	1	Normal
Kernel Tim	e 0:0	0:02.609	Reads		0
User Time	0:0	0:00.000	Read Delta	3	0
Total Time	0:0	0:02.609	Read Byte	s Delta	0
Cycles	7,214	,944,084	Writes		0
Virtual Men	nory		Write Delt	3	0
Private By	tes	136 K	Write Byte	s Delta	0
Peak Priva	te Bytes	212 K	Other		0
Virtual Size		61,952 K	Other Delt	a	0
Page Faul	ts	86,023	Other Byte	es Delta	0
Page Faul	t Delta	0	Handles		
Physical M	emory		Handles		0
Memory P		5	Peak Hand	les	0
Working S		20,116 K	GDI Handi	es .	0
WS Pr	vate	20,116 K	USER Han	dles	0
WS SH	areable	OK			
WS SH	ared	OK			
Peak Worl	ing Set 1	06,452 K			

Notice that the process has no user time (since only kernel threads "work" within this process), and its working set is private only (not shared). This is because the compressed memory is not sharable in any sense. Compare that to the Memory view in Task Manager:

ile Option			
rocesses P	erformance App his	tory Startup Users Details Services	
mMlpul	CPU 36% 2.79 GHz	Memory	2.0 GB
	Memory 1.5/2.0 GB (75%)		
ha u	Disk 0 (C:) 5%		
Ethernet S: 0 R: 0 Kbps		60 seconds Memory composition	0
		In use (Compressed) Available Slots used: 1.5 GB (19.3 MB) 513 MB Committed Cached 1.6/3.1 GB 504 MB	
		Paged pool Non-paged pool 154 MB 86.8 MB	

Here, the compressed memory in parentheses should correlate with the working set of the Memory Compression process—this screenshot was taken about a minute after the previous one—because this is the amount of space that the compressed memory is consuming.

## **Memory partitions**

Traditionally, virtual machines (VMs) are used to isolate applications so that separate VMs can run completely isolated applications (or groups of applications) at least from a security standpoint. VMs cannot interact with each other, providing strong security and resource boundaries. Although this works, VMs have a high resource cost in terms of hardware that hosts the VMs and management costs. This gave a rise to container-based technologies, such as Docker. These technologies attempt to lower the barrier for isolation and resource management by creating sandbox containers that host applications, all on the same physical or virtual machine.

Creating such containers is difficult, as it would require kernel drivers that perform some form of virtualization on top of the regular Windows. Some of these drivers are the following (a single driver can encompass all these functionalities):

- File system (mini) filter that would create an illusion of an isolated file system
- Registry virtualization driver, creating an illusion of a separate registry (CmRegisterCallbacksEx)
- Private object manager namespace, by utilizing silos (see Chapter 3 for more details)
- Process management for associating processes with the correct container by using process create/ notifications (PsSetCreateNotifyRoutineEx)

Even with these in place, some things are difficult to virtualize, specifically memory management. Each container may want to use its own PFN database, its own page file, and so on. Windows 10 (64-bit versions only) and Windows Server 2016 provide such possible memory control through Memory Partitions.

A memory partition consists of its own memory-related management structures, such as page lists (standby, modified, zero, free, etc.), commit charge, working set, page trimmer, modified page writer, zero-page thread, and so on, but isolated from other partitions. Memory partitions are represented in the system by Partition objects, which are securable, nameable objects (just like other executive objects). One partition always exists, called the *System Partition*, and it represents the system as a whole and is the ultimate parent of any explicitly created partition. The system partition's address is stored in a global variable (MiSystemPartition) and its name is KernelObjects\MemoryPartition0, visible with tools such as WinObj from Sysinternals as shown in Figure 5-45.

<ul> <li>View Help</li> <li>ArcName</li> <li>BaseNamedObjects</li> <li>Callback</li> <li>Device</li> <li>Driver</li> <li>GLOBAL77</li> <li>KenelObjects</li> <li>KnownDlis2</li> </ul>	Name T A HighPagedPoolCondition LowCommitCondition LowCommitCondition LowNermoryCondition LowNapagedPoolCondition LowPagedPoolCondition MaximumCommitCondition MaximumCommitCondition MemoryFarttion0	Type Event Event Event Event Event Event Event Event Event Event Event	SymLin ^
NINOWNOISSE NIS PC Control Security - Sessions - Windows	PhysicalMemoryChange PrefetchTracesReady Session2 Session2 SuperfetchParametersChanged SuperfetchTracesReady SuperfetchTracesReady SystemErrorPortReady	Event Event Session Event Event Event Event	

FIGURE 5-45 The System Partition in WinObj.

All partition objects are stored in global list, where the current maximum partition count is 1024 (10 bits), because the partition index must be encoded in PTEs for quick access to partition information where applicable. One of these indices is the system partition and two other values are used as special sentinels, leaving 1021 partitions available.

Memory partitions can be created from user mode or kernel mode by using the NtCreatePartition internal (and undocumented) function; user mode callers must have the SeLockMemory privilege for the call to succeed. The function can accept a parent partition, which initial pages will come from and eventually return to, when the partition is destroyed; the system partition is the default parent if none is specified. NtCreatePartition delegates the actual work to the internal memory manager MiCreatePartition.

An existing partition can be opened by name using NtOpenPartition (no special privilege required for this as the object can be protected by ACLs as usual). The actual manipulation of a partition is reserved for the NtManagePartition function. This is the function that can be used to add memory to the partition, add a paging file, copy memory from one partition to another, and generally obtain information about a partition.

#### **EXPERIMENT:** Viewing memory partitions

In this experiment, you'll use the kernel debugger to look at partition objects.

1. Start local kernel debugging and issue the !partition command. It lists all the partition objects in the system.

lkd> !partition
Partition0 fffff803eb5b2480 MemoryPartition0

2. By default, the always existing system partition is shown. The !partition command can accept the address of a partition object and show more details:

lkd> !partition fffff803eb5b2480 PartitionObject @ ffffc808f5355920 (MemoryPartitionO) \_MI\_PARTITION 0 @ fffff803eb5b2480 MemoryRuns: 0000000000000000 MemoryNodeRuns: ffffc808f521ade0 AvailablePages: 0n4198472 ( 16 Gb 16 Mb 288 Kb) ResidentAvailablePages: 0n6677702 ( 25 Gb 484 Mb 792 Kb) 0 \_MI\_NODE\_INFORMATION @ fffff10000003800 TotalPagesEntireNode: 0x7f8885 Zeroed Free 1GB 0 ( 0) 0 ( 0) 2MB 0 ( 41 ( 82 Mb) (0)64KB 3933 (245 Mb 832 Kb) 0 ( 0) 4KB 82745 ( 323 Mb 228 Kb) 0 ( 0) 
 Node Free Memory:
 ( 651 Mb 36 Kb )

 InUse Memory:
 ( 31 Gb 253 Mb 496 Kb )

 TotalNodeMemory:
 ( 31 Gb 904 Mb 532 Kb )

The output shows some of the information stored in the underlying MI\_PARTITION structure (whose address is given as well). Notice that the command shows memory information on a NUMA node basis (just one in this case). Since this is the system partition, the numbers related to used, free, and total memory should correspond to the values reported by tools such as Task Manager and Process Explorer. You can also examine the MI\_PARTITION structure with the usual dt command.

Future scenarios may leverage the memory partitioning capability for specific processes (through job objects) to be associated with a partition, such as when exclusive control over physical memory may be beneficial. One such scenario slated for the Creators Update release is game mode (more information on game mode is included in Chapter 8 in Part 2).

The memory manager uses several mechanisms in an attempt to save as much RAM as possible, such as sharing pages for images, copy-on-write for data pages, and compression. In this section, we'll take a look at yet another such mechanism called *memory combining*.

The general idea is simple: Find duplicates of pages in RAM and combine them into one, thus removing the rest of the duplicates. Clearly there are a few issues to resolve:

- What are the "best" pages to use as candidates for combining?
- When is it appropriate to initiate memory combining?
- Should combining be targeted at a particular process, a memory partition, or the entire system?
- How can the combining process be made quick so it does not adversely impact normally executing code?
- If a writeable combined page is later modified by one of its clients, how would it get a private copy?

We'll answer these questions throughout this section, starting with the last. The copy-on-write mechanism is used here: as long as a combined page is not written to, do nothing. If a process tries to write to the page, make a private copy for the writing process, and remove the copy-on-write flag for that newly allocated private page.

**Note** Page combining can be disabled by setting a DWORD value named DisablePageCombining to 1 in the HKLM\System\CurrentControlSet\Control\Session Manager\Memory Management registry key.

**Note** In this section, the terms *CRC* and *hash* are used interchangeably. They indicate a statistically unique (with high probability) 64-bit number referencing a page's contents.

The memory manager's initialization routine, MmInitSystem, creates the system partition (see the previous section on memory partitions). Within the MI\_PARTITION structure that describes a partition lies an array of 16 AVL trees that identify the duplicated pages. The array is sorted by the last 4 bits of a combined page CRC value. We'll see in a moment how this fits into the algorithm.

Two special page types are called *common pages*. One includes an all zero bytes, and the other includes an all one bits (filled with the byte 0xFF); their CRC is calculated just once and stored. Such pages can easily be identified when scanning pages' contents.

To initiate memory combining, the NtSetSystemInformation native API is called with the System-CombinePhysicalMemoryInformation system information class. The caller must have the SeProfile-SingleProcessPrivilege in its token, normally granted to the local administrators group. The argument to the API provides the following options through a combination of flags:

- Perform memory combining on the entire (system) partition or just the current process.
- Search for common pages (all zeros or all ones) to combine only, or any duplicate pages regardless of content.

The input structure also provides an optional event handle that can be passed in, and if signaled (by another thread), will abort the page combining. Currently, the Superfetch service (see the section "SuperFetch" at the end of this chapter for more information) has a special thread, running in low priority (4) that initiates memory combining for the entire system partition when the user is away, or if the user is busy, every 15 minutes.

In the Creators Update, if the amount of physical memory is higher than 3.5 GB (3584 MB), most built-in Svchost-ed services host a single service in each Svchost process. This creates dozens of processes out of the box but removes the likelihood of one service affecting another (either because of some instability or security issues). In this scenario, the Service Control Manager (SCM) uses a new option of the memory combining API, and initiates page combining in each of the Svchost processes every three minutes by utilizing a thread pool timer running with base priority of 6 (ScPerformPage-CombineOnServiceImages routine). The rationale is to try to reduce RAM consumption that may be higher than with fewer Svchost instances. Note that non-Svchost services are not page combined, nor are services running with per-user or private user accounts.

The Mi Combine Identical Pages routine is the actual entry point to the page combining process. For each NUMA node of the memory partition, it allocates and stores a list of pages with their CRC inside the page combining operation. (PCS) structure, which is the one managing all the needed information for the page combining operation. (That's the one holding the AVL trees array mentioned earlier.) The requesting thread is the one doing the work; it should run on CPUs belonging to the current NUMA node, and its affinity is modified accordingly if needed. We'll divide the memory combining algorithm into three stages to simplify the explanation: search, classification, and page sharing. The following sections assume that a complete page combining is requested (rather than for the current process) and for all pages (not just the common pages); the other cases are similar in principle, and somewhat simpler.

# The search phase

The goal of this initial stage is to calculate the CRC of all the physical pages. The algorithm analyses each physical page that belongs to the active, modified, or standby list, skipping the zeroed and free pages (since they are effectively unused).

A good page candidate for memory combining should be an active non-shared page that belongs to a working set, and that should not map a paging structure. The candidate could be even in the standby or modified state, but needs to have a reference counter of 0. Basically, the system identifies three types of pages for combining: user process, paged pool, and session space. Other types of pages are skipped.

To correctly calculate the CRC of the page, the system should map the physical page to a system address (because the process context is mostly different from the calling thread, making the page inaccessible in low user-mode addresses) using a new system PTE. The CRC of the page is then calculated with a customized algorithm (MiComputeHash64 routine), and the system PTE freed (the page is now unmapped from system address space).

#### The page hashing algorithm

The algorithm that the system uses to calculate an 8-bytes page hash (CRC) is the following: two 64-bit large prime numbers are multiplied together, and the result is used as the starting hash. The page is scanned from the end to the beginning; the algorithm hashes 64 bytes per cycle. Each read 8-byte value from the page in question is added to the starting hash, then the hash is rotated right a prime-number of bits (starting with 2, then 3, 5, 7, 11, 13, 17 and 19). 512 memory access operations (4096/8) are needed to completely hash a page.

# The classification phase

When all the hashes of the pages that belong to a NUMA node have been successfully calculated, the second part of the algorithm commences. The goal of this phase is to process each CRC/PFN entry in the list and organize them in a strategic way. The page sharing algorithm must minimize the process contexts switches, and be as fast as possible.

The MiProcessCrcList routine starts by sorting the CRC/PFN list by hash (using a quick sort algorithm). Another key data structure, *combine block*, is used to keep track of all the pages that share the same hash, and, more importantly, to store the new prototype PTE that will map the new combined page. Each CRC/PFN of the new sorted list is processed in order. The system needs to verify if the current hash is common (belongs to a zeroed or a complete-filled page) and if it's equal to the previous or next hash (remember that the list is sorted). If this is not the case, the system checks if a combine block already exists in the PCS structure. If so, it means that a combined page has been already identified in a previous execution of the algorithm or in another node of the system. Otherwise it means that the CRC is unique and the page couldn't be combined, and the algorithm continues to the next page in the list.

If the found common hash has never been seen before, the algorithm allocates a new empty combine block (used for the master PFN) and inserts it in a list used by the actual page-sharing code (next stage). Otherwise if the hash already existed (the page is not the master copy), a reference to the combine block is added in the current CRC/PFN entry.

At this point, the algorithm has prepared all the data that the page-sharing algorithm needs: a list of combine blocks used to store the master physical pages and their prototype PTEs, a list of CRC/PFN entries organized by the owning working set, and some physical memory needed to store the content of the new shared pages.

The algorithm then obtains the address of the physical page (that should exist, due to the initial check performed previously by the MiCombineIdenticalPages routine) and searches a data structure used to store all the pages that belongs to the specific working set (from now on we will call this structure *WS CRC node*). If this doesn't exist, it allocates a new one and inserts it in another AVL tree. The CRC/PFN and virtual address of the page are linked together inside the WS CRC node.

After all the identified pages have been processed, the system allocates the physical memory for the new master shared pages (using an MDL), and processes each WS CRC node; for performance reasons, the candidate pages located inside the node are sorted by their original virtual address. The system is now ready to perform the actual page combining.

# The page combining phase

The page combining phase starts with a WS CRC node structure that contains all the pages that belong to a specific working set and are all candidates for combining, and with a list of free combine blocks, used to store the prototype PTE and the actual shared page. The algorithm attaches to the target process and locks its working set (raising IRQL to dispatch level). In this way, it will be able to directly read and write each page without the need to remap it.

The algorithm processes every CRC/PFN entry in the list, but since it's running at dispatch level IRQL and execution could take some time, it checks if the processor has some DPCs or scheduled items in its queue (by calling KeShouldYieldProcessor) before analyzing the next entry. If the answer is yes, the algorithm does the right thing and takes appropriate precautions to maintain state.

The actual page sharing strategy expects three possible scenarios:


- The page is active and valid, but it contains all zeroes, so rather than combining, it replaces its PTE with a demand-zero PTE. Recall that this is the initial state of normal VirtualAlloc-like memory allocation.
- The page is active and valid, but it is not zeroed out, meaning it has to be shared. The algorithm checks if the page has to be promoted as the master: if the CRC/PFN entry has a pointer to a valid combine block, it means that it's not the master page; otherwise, the page is the master copy. The master page hash is rechecked and a new physical page assigned for the sharing. Otherwise, the already existing combine block is used (and its reference count incremented). The system is now ready to convert the private page into a shared one, and calls the MiConvert-PrivateToProto routine to perform the actual job.
- The page is in the modified or standby list. In this case, it's mapped to a system address as a valid page and its hash recalculated. The algorithm performs the same step as the previous scenario, with the only difference being that the PTE is converted from shared to prototype using the MiConvertStandbyToProto routine.

When the sharing of the current page ends, the system inserts the combine block of the master copy into the PCS structure. This is important because the combine block becomes the link between each private PTE and the combined page.

# From private to shared PTE

The goal of MiConvertPrivateToProto is to convert a PTE of an active and valid page. If the routine detects that the prototype PTE inside the combine block is zero, it means that the master page must be created (together with the master shared prototype PTE). It then maps the free physical page into a system address and copies the content of the private page into the new shared one. Before actually creating the shared PTE, the system should free any page file reservation (see the section "Page file reservation" earlier in this chapter) and fill the PFN descriptor of the shared page. The shared PFN has the prototype bit set, and the PTE frame pointer set to the PFN of the physical page that contains the Prototype PTE. Most importantly, it has the PTE pointer set to the PTE located inside the combine block, but with the 63rd bit set to zero. This signifies to the system that the PFN belongs to a page that has been combined. Next, the system needs to modify the PTE of the private page so that its target PFN is set to the shared physical page, its protection mask changed to copy-on-write, and the private page PTE is marked as valid. The prototype PTE inside the combine block is marked as a valid hardware PTE too: the content is identical to the new PTE of the private page. Finally, the page file space allocated for the private page is freed and the original PFN of the private page is marked as deleted. The TLB cache is flushed and the private process working set size is decremented by one page.

Otherwise (the prototype PTE inside the combine block is non-zero), it means that the private page should be a copy of the master one. Only the active PTE of the private page must be converted. The PFN of the shared page is mapped to a system address and the content of the two pages is compared. This is important because the CRC algorithm does not produce unique values in the general case. If the two pages don't match, the function stops processing and returns. Otherwise, it unmaps the shared page and sets the page priority of the shared PFN to the higher of the two. Figure 5-46 shows the state where only a master page exists.





The algorithm now calculates the new invalid software prototype PTE that should be inserted into the process private page table. To do that, it reads the address of the hardware PTE that maps the shared page (located in the combine block), shifts it, and sets the Prototype and Combined bits. A check is made that the share count of the private PFN is 1. If it is not, processing is aborted. The algorithm writes the new software PTE in the private page table of the process and decrements the share count of the page table of the old private PFN (keep in mind that an active PFN always has a pointer to its page table). The target process working set size is decremented by one page and the TLB is flushed. The old private page is moved into the transition state, and its PFN is marked for deletion. Figure 5-47 shows two pages, where the new page points to the prototype PTE but is not yet valid.

Finally, the system uses another trick to prevent working set trimming on the shared pages by simulating a page fault. That way the share count of the shared PFN is again incremented, and no fault would occur at a time the process will try to read the shared page. The end result is that the private PTE is again a valid hardware PTE. Figure 5-48 shows the effect of a soft page fault on the second page, making it valid and incrementing the share count.





FIGURE 5-47 Combined pages before simulated page fault.





#### **Combined pages release**


When the system needs to free a particular virtual address, it first locates the address of the PTE that maps it. The pointed PFN of a combined page has the prototype and combined bits set. The free request for a combined PFN is managed exactly like the one for a prototype PFN. The only difference is that the system (if the combined bit is set) calls MiDecrementCombinedPte after processing the prototype PFN.

MiDecrementCombinedPte is a simple function that decrements the reference count of the combine block of the Prototype PTE. (Keep in mind that at this stage the PTE is in transition because the memory manager has already dereferenced the physical page that it maps. The share count of the physical page has already dropped to zero, and so the system put the PTE in transition.) If the reference count drops to zero, the prototype PTE will be freed, the physical page put in the free list, and the combine block returned to the combine free list of the PCS structure of the memory partition.

#### **EXPERIMENT:** Memory combining

In this experiment, you will see the effects of memory combing. Follow these steps:

- 1. Start a kernel debugging session with a VM target (as described in Chapter 4, "Threads").
- Copy the MemCombine32.exe (for 32 bit targets) or MemCombine64.exe (for 64 bit targets), and MemCombineTest.exe executables from this book's downloadable resources to the target machine.
- **3.** Run MemCombineTest.exe on the target machine. You should see something like the following:



- **4.** Note the two addresses shown. These are two buffers filled with a random generated pattern of bytes, repeated so that each page has the same content.
- 5. Break into the debugger. Locate the MemCombineTest process:

```
0: kd> !process 0 0 memcombinetest.exe
PROCESS ffffe70a3cb29080
   SessionId: 2 Cid: 0728 Peb: 00d08000 ParentCid: 11c4
   DirBase: c7c95000 ObjectTable: ffff918ede582640 HandleCount: <Data Not
Accessible>
   Image: MemCombineTest.exe
```

6. Switch to the located process:

```
0: kd> .process /i /r ffffe70a3cb29080
You need to continue execution (press 'g' <enter>) for the context
to be switched. When the debugger breaks in again, you will be in
the new process context.
0: kd> g
Break instruction exception - code 80000003 (first chance)
nt!DbgBreakPointWithStatus:
fffff801'94b691c0 cc int 3
```

7. Use the !pte command to locate the PFN where the two buffers are stored:

0: kd> !pte b80000 VA 00000000b80000 PXE at FFFFA25128944000 PPE at FFFFA25128800000 PDE at FFFFA25100000028 PTE at FFFFA20000005C00 contains 00C0000025BAC867 contains 0FF00000CAA2D867 contains 00F000003B22F867 contains B9200000DEDFB867 pfn 25bac ---DA--UWEV pfn caa2d ---DA--UWEV pfn 3b22f ---DA--UWEV pfn dedfb ----DA---UW-V 0: kd> !pte b90000 VA 000000000b90000 PXE at FFFFA25128944000 PPE at FFFFA25128800000 PDE at FFFFA25100000028 PTE at FFFFA20000005C80 contains 00C0000025BAC867 contains 0FF00000CAA2D867 contains 00F000003B22F867 contains B9300000F59FD867 pfn 25bac ---DA--UWEV pfn caa2d ---DA--UWEV pfn 3b22f ---DA--UWEV pfn f59fd ---DA--UW-V

- **8.** Notice the PFN values are different, indicating that these pages are mapped to different physical addresses. Resume the target.
- 9. On the target, open an elevated command window, navigate to the directory where you copied MemCombine(32/64), and run it. The tool forces a full memory combining, which may take a few seconds.
- **10.** When it's finished, break into the debugger again. Repeat steps 6 and 7. You should see the PFNs change:

```
1: kd> !pte b80000
                                       VA 00000000b80000
PXE at FFFFA25128944000 PPE at FFFFA25128800000 PDE at
FFFFA25100000028 PTE at FFFFA20000005C00
contains 00C0000025BAC867 contains 0FF00000CAA2D867 contains
00F000003B22F867 contains B9300000EA886225
pfn 25bac ---DA--UWEV pfn caa2d ---DA--UWEV pfn 3b22f ---DA--
UWEV pfn ea886 C---A--UR-V
1: kd> !pte b90000
                                      VA 000000000b90000
PXE at FFFFA25128944000 PPE at FFFFA25128800000 PDE at
FFFFA25100000028 PTE at FFFFA20000005C80
contains 00C0000025BAC867 contains 0FF00000CAA2D867 contains
00F000003B22F867 contains BA600000EA886225
pfn 25bac ---DA--UWEV pfn caa2d ---DA--UWEV pfn 3b22f ---DA--
UWEV pfn ea886 C---A--UR-V
```

- **11.** Notice the PFN values are the same, meaning the pages are mapped to the exact same address in RAM. Also note the C flag in the PFN, indicating copy-on-write.
- **12.** Resume the target and press any key in the MemCombineTest window. This changes a single byte in the first buffer.

```
13. Break into the target again and repeat steps 6 and 7 yet again:
```

```
1: kd> !pte b80000
                                       VA 00000000b80000
PXE at FFFFA25128944000 PPE at FFFFA25128800000 PDE at
FFFFA25100000028 PTE at FFFFA20000005C00
contains 00C0000025BAC867 contains 0FF00000CAA2D867 contains
00F000003B22F867 contains B9300000813C4867
pfn 25bac ---DA--UWEV pfn caa2d ---DA--UWEV pfn 3b22f ---DA--
UWEV pfn 813c4 ---DA--UW-V
1: kd> !pte b90000
                                       VA 000000000b90000
PXE at FFFFA25128944000 PPE at FFFFA25128800000 PDE at
FFFFA25100000028 PTE at FFFFA20000005C80
contains 00C0000025BAC867 contains 0FF00000CAA2D867 contains
00F000003B22F867 contains BA600000EA886225
pfn 25bac ---DA--UWEV pfn caa2d ---DA--UWEV pfn 3b22f ---DA--
UWEV pfn ea886 C---A--UR-V
```

**14.** The PFN for the first buffer has changed, and the copy-on-write flag was removed. The page has changed and was relocated to a different address in RAM.

### **Memory enclaves**

Threads executing in a process have access to the entire process address space (as determined by page protection, which can be changed). This is desirable most of the time; however, in case malicious code manages to get itself injected into a process, it has the exact same power. It can freely read data that may contain sensitive information and even change it.

Intel has created a technology called Intel Software Guard Extensions (SGX) that allows the creation of protected memory enclaves—secure zones in a process address space where code and data are protected by the CPU from code running outside the enclave. Conversely, code running inside an enclave has full (normal) access to process address space outside the enclave. Naturally, the protection extends to access from other processes and even code running in kernel mode. A simplified diagram of memory enclaves is shown in Figure 5-49.




FIGURE 5-49 Memory enclaves.

Intel SGX is supported by sixth generation Core processors ("Skylake") and later generations. Intel has its own SDK for application developers that can be used on Windows 7 and later systems (64 bit only). Starting with Windows 10 version 1511 and Server 2016, Windows provide an abstraction using Windows API functions that removes the need to use Intel's SDK. Other CPU vendors may create similar solutions in the future, and these will also be wrapped by the same API, providing a relatively portable layer for application developers to use for creating and populating enclaves.

٢					
L	2	-	-	=	
L	Ξ	=	=	Ξ	
L	-	-	-	=	

**Note** Not all sixth generation Core processors support SGX. Also, an appropriate BIOS update must be installed on the system for SGX to work. Consult the Intel SGX documentation for more information. The Intel SGX website can be found at *https://software.intel.com/en-us/sgx*.

c	÷	÷	+	+	~
L	=	_	_	-	
L	Ξ		=		
L					J

**Note** At the time of this writing, Intel produced two versions of SGX (versions 1.0 and 2.0). Windows currently supports version 1.0 only. The differences are outside the scope of this book; consult the SGX documentation for more information.

-	÷	÷	÷	÷	<u> </u>
[				_	1
	-	_	=		
L	Ξ	=	=	Ξ.	
L	_	_	_	_	J

**Note** Current SGX versions do not support enclaves in ring 0 (kernel mode). Only ring 3 (user mode) enclaves are supported.

# **Programmatic interface**

From an application developer's perspective, creating and working with an enclave consists of the following steps. (The internal details are described in the following sections.)

- Initially the program should determine whether memory enclaves are supported by calling IsEnclaveTypeSupported, passing a value representing the enclave technology, which currently can only be ENCLAVE\_TYPE\_SGX.
- 2. A new enclave is created by calling the CreateEnclave function, which is similar in its arguments to VirtualAllocEx. For example, it's possible to create an enclave in a different process than the caller process. The complication in this function is the need to provide a vendor-specific configuration structure, which for Intel means a 4 KB data structure called *SGX Enclave Control Structure (SECS)*, which Microsoft does not define explicitly. Instead, developers are expected to create their own structure based on the particular technology used and defined in its documentation.
- 3. Once an empty enclave is created, the next step is to populate the enclave with code and data from outside of the enclave. This is accomplished by calling LoadEnclaveData where an external memory to the enclave is used to copy data to the enclave. Multiple calls to LoadEnclaveData may be used to populate the enclave.

- 4. The last step that is required to "activate" the enclave is achieved with the InitializeEnclave function. At that point, code that was configured to execute within the enclave can start executing.
- 5. Unfortunately, executing the code in the enclave is not wrapped by the API. Direct use of assembly language is required. The EENTER instruction transfers execution to the enclave and the EEXIT instruction causes return to the calling function. Abnormal termination of the enclave execution is also possible with Asynchronous Enclave Exit (AEX), such as due to a fault. The exact details are beyond the scope of this book, as they are not Windows-specific. Consult the SGX documentation to get the fine details.
- 6. Finally, to destroy the enclave, a normal VirtualFree(Ex) function can be used on the pointer to the enclave obtained in CreateEnclave.

#### Memory enclave initializations

During boot, Winload (the Windows Boot Loader) calls OslEnumerateEnclavePageRegions, which first checks if SGX is supported using the CPUID instruction. If it is, it issues instructions to enumerate Enclave Page Cache (EPC) descriptors. EPC is the protected memory provided by the processor for creating and using enclaves. For each enumerated EPC, OslEnumerateEnclavePageRegions calls BlMm-AddEnclavePageRange to add the page range information to a sorted list of memory descriptors with a type value of LoaderEnclaveMemory. This list is eventually stored in the MemoryDescriptorListHead member of the LOADER\_PARAMETER\_BLOCK structure used to pass information from the boot loader to the kernel.

During phase 1 initialization, the memory manager routine MiCreateEnclaveRegions is called to create an AVL tree for the discovered enclave regions (allowing quick lookups when needed); the tree is stored in the MiState.Hardrware.EnclaveRegions data member. The kernel adds a new enclave page list, and a special flag passed to MiInsertPageInFreeOrZeroedList enables functionality to utilize this new list. However, since the memory manager has actually run out of list identifiers (3 bits are used for a maximum of 8 values, all taken), the kernel actually identifies these pages as being "bad" pages currently suffering an in-page error. The memory manager knows never to use bad pages, so calling enclave pages "bad" keeps them from being used by normal memory management operations, and so such pages end up in the bad page list.

## **Enclave construction**

The CreateEnclave API ends up calling NtCreateEnclave in the kernel. As noted, a SECS structure must be passed in, documented by Intel SGX as shown in Table 5-24.

NtCreateEnclave first checks if memory enclaves are supported by looking at the root of the AVL tree (not by using the slower CPUID instruction). It then creates a copy of the passed-in structure (as is usual for kernel functions obtaining data from user mode) and attaches to the target process (KeStackAttachProcess) if the enclave is to be created in a different process than the caller's. Then it transfers control to MiCreateEnclave to begin the actual work.

Field	Offset (bytes)	Size (bytes)	Description
SIZE	0	8	Size of enclave in bytes; must be power of 2
BASEADDR	8	8	Enclave base linear address must be naturally aligned to size
SSAFRAMESIZE	16	4	Size of one SSA frame in pages (including XSAVE, pad, GPR, and conditionally MISC)
MRSIGNER	128	32	Measurement register extended with the public key that verified the enclave. See SIGSTRUCT for proper format
RESERVED	160	96	
ISVPRODID	256	2	Product ID of enclave
ISVSVN	258	2	Security version number (SVN) of the enclave
EID	Implementation dependent	8	Enclave identifier
PADDING	Implementation dependent	352	Padding pattern from the signature (used for key derivation strings)
RESERVED	260	3836	Includes EID, other non-zero reserved field and must-be-zero fields

#### TABLE 5-24 SECS structure layout

The first thing MiCreateEnclave does is allocate the Address Windowing Extension (AWE) information structure that AWE APIs also utilize. This is because similar to the AWE functionality, an enclave allows a user-mode application to directly have access over physical pages (that is to say, the physical pages that are EPC pages based on the detection described earlier). Anytime a user-mode application has such direct control over physical pages, AWE data structures and locks must be used. This data structure is stored in the AweInfo field of the EPROCESS structure.

Next, MiCreateEnclave calls MiAllocateEnclaveVad to allocate an enclave-type VAD describing the enclave virtual memory range. This VAD has the VadAwd flag (as all AWE VADs) but also an additional Enclave flag, to differentiate it from a true AWE VAD. Finally, as part of VAD allocation, this is where the user-mode address for the enclave memory will be chosen (if not explicitly specified in the original CreateEnclave call).

The next step in MiCreateEnclave is to acquire an enclave page regardless of the enclave size or initial commitment. This is because, as per Intel's SGX documentation, all enclaves require at least a one-page control structure to be associated with them. MiGetEnclavePage is used to obtain the required allocation. This function simply scans the enclave page list described earlier, and extracts one page as needed. The returned page is mapped using a system PTE stored as part of the enclave VAD; the MiInitializeEnclavePfn function sets up the related PFN data structure and marks it Modified and ActiveAndValid.

There are no actual bits that would help you differentiate this enclave PFN from any other active region of memory (such as non-paged pool). This is where the enclave regions AVL tree comes into play, and MI\_PFN\_IS\_ENCLAVE is a function that the kernel uses whenever it needs to check if a PFN is indeed describing an EPC region.

With the PFN initialized, the system PTE is now converted to a final global kernel PTE, and its resulting virtual address is computed. The final step in MiCreateEnclave is to call KeCreateEnclave, which will now do the low-level kernel enclave creation steps, including communication with the actual SGX hardware implementation. One job that KeCreateEnclave is responsible for is filling in the base address required by the SECS structure if the caller did not specify one, as it must be set in the SECS structure before communicating with the SGX hardware to create an enclave.

#### Loading data into an enclave

Once an enclave has been created, it's time to load information into it. The LoadEnclaveData function is exposed for that purpose. The function merely forwards the request to the underlying executive function, NtLoadEnclaveData. The function resembles a combination of a memory copy operation with some VirtualAlloc attributes (such as page protection).

If the enclave created with CreateEnclave doesn't yet have any committed enclave pages, they must first be obtained, which will result in zeroed out memory being added to the enclave, which can then be filled with non-zero memory from outside the enclave. Otherwise, if an initial pre-committed initialization size was passed in, then the enclave's pages can directly be filled in with non-zero memory from outside of the enclave.

Because enclave memory is described by a VAD, many of the traditional memory management APIs will function, at least partly, on this memory as well. For example, calling VirtualAlloc (ending up in NtAllocateVirtualMemory) on such an address with the MEM\_COMMIT flag will result in MiCommitEnclavePages being called, which will validate that the protection mask for the new pages is compatible (i.e., a combination of read, write, and/or execute, without any special caching or write combining flags), and then call MiAddPagesToEnclave, passing a pointer to the enclave VAD associated with the address range, the protection mask that was specified to VirtualAlloc, and the PTE addresses that correspond to the virtual address range being committed.

MiAddPagesToEnclave first checks if the enclave VAD has any existing EPC pages associated with it, and if there's enough of them to satisfy the commit. If not, MiReserveEnclavePages is called to obtain a sufficient amount. MiReserveEnclavePages looks at the current enclave page list and counts the total. If there aren't enough physical EPC pages provided by the processor (based on the information obtained at boot), the function fails. Otherwise, it calls MiGetEnclavePage in a loop for the required amount of pages.

For each PFN entry that is retrieved, it is linked into the PFN array in the enclave VAD. Essentially, this means that once an enclave PFN is removed from the enclave page list and put into an active state, the enclave VAD acts as the list of active enclave PFNs.

Once the required committed pages have been obtained, MiAddPagesToEnclave translates the page protection passed to LoadEnclaveData into their SGX equivalents. Next, it reserves the appropriate number of system PTEs to hold paging information for each EPC pages that will be required. With this information in hand, it will eventually call KeAddEnclavePage that calls the SGX hardware to do the actual page adding.

One special page protection attribute is PAGE\_ENCLAVE\_THREAD\_CONTROL, which indicates the memory is for a Thread Control Structure (TCS) defined by SGX. Each TCS represents a different thread that can execute independently within the enclave.

NtLoadEnclaveData validates parameters and then calls MiCopyPagesIntoEnclave to do the actual work, which may require getting committed pages as described earlier.

### Initializing an enclave

Now that the enclave has been created and data has been transferred into it, there is another last step to perform before actual code in the enclave can execute. InitializeEnclave must be called to notify SGX that the enclave is in its final state before execution can begin. InitializeEnclave requires two SGX-specific structures to be passed in (SIGSTRUCT and EINITTOKEN; see the SGX documentation for the details).

The executive function NtInitializeEnclave called by InitializeEnclave does some parameter validation and makes sure the enclave VAD obtained has the correct attributes and then passed the structures along to the SGX hardware. Note that an enclave can only be initialized once.

The final step would be to use the Intel assembly instruction EENTER to start code execution (again, see the SGX documentation for the details).

# Proactive memory management (SuperFetch)

Traditional memory management in operating systems has focused on the demand-paging model discussed thus far, with some advances in clustering and prefetching so that disk I/O can be optimized at the time of the demand-page fault. Client versions of Windows, however, include a significant improvement in the management of physical memory with the implementation of SuperFetch, a memory management scheme that enhances the least–recently accessed approach with historical file access information and proactive memory management.

The standby list management in older versions of Windows had two limitations. First, the prioritization of pages relies only on the recent past behavior of processes and does not anticipate their future memory requirements. Second, the data used for prioritization is limited to the list of pages owned by a process at any given point in time. These shortcomings can result in scenarios in which the computer is left unattended for a brief period of time, during which a memory-intensive system application runs (doing work such as an antivirus scan or a disk defragmentation) and then causes subsequent interactive application use (or launch) to be sluggish. The same thing can happen when a user purposely runs a data- and/or memory-intensive application and then returns to use other programs, which appear to be significantly less responsive.

This decline in performance occurs because the memory-intensive application forces the code and data that active applications had cached in memory to be overwritten by the memory-intensive activities—applications perform sluggishly as they have to request their data and code from disk. Client versions of Windows take a big step toward resolving these limitations with SuperFetch.

# Components

SuperFetch has several components in the system that work hand in hand to proactively manage memory and limit the impact on user activity when SuperFetch is performing its work. These components include the following:

- Tracer The tracer mechanisms are part of a kernel component (Pf) that allows SuperFetch to query detailed page-usage, session, and process information at any time. SuperFetch also uses the FileInfo mini-filter driver (%SystemRoot%\System32\Drivers\Fileinfo.sys) to track file usage.
- Trace collector and processor This collector works with the tracing components to provide a raw log based on the tracing data that has been acquired. This tracing data is kept in memory and handed off to the processor. The processor then hands the log entries in the trace to the agents, which maintain history files (described next) in memory and persist them to disk when the service stops, such as during a reboot.
- **Agents** SuperFetch keeps file page access information in history files, which keep track of virtual offsets. Agents group pages by attributes, such as the following:
  - Page access while the user was active
  - Page access by a foreground process
  - Hard fault while the user was active
  - Page access during an application launch
  - Page access upon the user returning after a long idle period
- Scenario manager This component, also called the *context agent*, manages the three Super-Fetch scenario plans: hibernation, standby, and fast-user switching. The kernel-mode part of the scenario manager provides APIs for initiating and terminating scenarios, managing the current scenario state, and associating tracing information with these scenarios.
- Rebalancer Based on the information provided by the SuperFetch agents, as well as the current state of the system (such as the state of the prioritized page lists), the rebalancer—a specialized agent in the Superfetch user-mode service—queries the PFN database and reprioritizes it based on the associated score of each page, thus building the prioritized standby lists. The rebalancer can also issue commands to the memory manager that modify the working sets of processes on the system, and it is the only agent that actually takes action on the system. Other agents merely filter information for the rebalancer to use in its decisions. In addition to reprioritization, the rebalancer initiates prefetching through the prefetcher thread, which uses FileInfo and kernel services to preload memory with useful pages.

All these components use facilities inside the memory manager that allow for the querying of detailed information about the state of each page in the PFN database, the current page counts for each page list and prioritized list, and more. Figure 5-50 shows an architectural diagram of SuperFetch's multiple components. SuperFetch components also use prioritized I/O to minimize user impact. (See Chapter 8 in Part 2 for more on I/O priority.)




FIGURE 5-50 SuperFetch architectural diagram.

# **Tracing and logging**

SuperFetch makes most of its decisions based on information that has been integrated, parsed, and post-processed from raw traces and logs, making these two components among the most critical. Tracing is like ETW in some ways because it uses certain triggers in code throughout the system to generate events, but it also works in conjunction with facilities already provided by the system, such as power-manager notification, process callbacks, and file-system filtering. The tracer also uses traditional page-aging mechanisms that exist in the memory manager, as well as newer working-set aging and access tracking implemented for SuperFetch.

SuperFetch always keeps a trace running and continuously queries trace data from the system, which tracks page usage and access through the memory manager's access bit tracking and workingset aging. To track file-related information, which is as critical as page usage because it allows prioritization of file data in the cache, SuperFetch leverages existing filtering functionality with the addition of the FileInfo driver. (See Chapter 6 for more information on filter drivers.) This driver sits on the file-system device stack and monitors access and changes to files at the stream level, which provides it with fine-grained understanding of file access. (For more information on NTFS data streams, see Chapter 13 in Part 2.) The main job of the FileInfo driver is to associate streams—identified by a unique key, currently implemented as the FsContext field of the respective file object—with file names so that the user-mode Superfetch service can identify the specific file stream and offset that a page in the standby list belonging to a memory-mapped section is associated with. It also provides the interface for prefetching file data transparently, without interfering with locked files and other file-system state. The rest of the driver ensures that the information stays consistent by tracking deletions, renaming operations, truncations, and the reuse of file keys by implementing sequence numbers.

At any time during tracing, the rebalancer might be invoked to repopulate pages differently. These decisions are made by analyzing information such as the distribution of memory within working sets, the zero page list, the modified page list and the standby page lists, the number of faults, the state of PTE access bits, the per-page usage traces, current virtual address consumption, and working set size.

A given trace can be a page-access trace, in which the tracer uses the access bit to keep track of which pages were accessed by the process (both file page and private memory). Or, it can be a name-logging trace, which monitors the file name-to-file key mapping updates to the actual file on disk. These allow SuperFetch to map a page associated with a file object.

Although a SuperFetch trace only keeps track of page accesses, the Superfetch service processes this trace in user mode and goes much deeper, adding its own richer information such as where the page was loaded from (for example, in resident memory or a hard page fault), whether this was the initial access to that page, and what the rate of page access actually is. Additional information, such as the system state, is also kept, as well as information about recent scenarios in which each traced page was last referenced. The generated trace information is kept in memory through a logger into data structures, which—in the case of page-access traces—identify traces, a virtual address-to-working set pair, or, in the case of a name-logging trace, a file-to-offset pair. SuperFetch can thus keep track of which range of virtual addresses for a given process have page-related events and which range of offsets for a given file have similar events.

#### **Scenarios**

One aspect of SuperFetch that is distinct from its primary page reprioritization and prefetching mechanisms (covered in more detail in the next section) is its support for scenarios, which are specific actions on the machine for which SuperFetch strives to improve the user experience. These scenarios are as follows:

- Hibernation The goal of hibernation is to intelligently decide which pages are saved in the hibernation file other than the existing working-set pages. The idea is to minimize the amount of time it takes for the system to become responsive after a resume.
- **Standby** The goal of standby is to completely remove hard faults after resume. Because a typical system can resume in less than 2 seconds, but can take 5 seconds to spin up the hard drive after a long sleep, a single hard fault could cause such a delay in the resume cycle. SuperFetch prioritizes pages needed after a standby to remove this chance.
- Fast user switching The goal of fast user switching is to keep an accurate priority and understanding of each user's memory. That way, switching to another user will cause the user's session to be immediately usable, and won't require a large amount of lag time to allow pages to be faulted in.

Each of these scenarios has different goals, but all are centered around the main purpose of minimizing or removing hard faults. Scenarios are hardcoded, and SuperFetch manages them through the NtSetSystemInformation and NtQuerySystemInformation APIs that control system state. For SuperFetch purposes, a special information class, SystemSuperfetchInformation, is used to control the kernel-mode components and to generate requests such as starting, ending, and querying a scenario or associating one or more traces with a scenario.

Each scenario is defined by a plan file, which contains, at minimum, a list of pages associated with the scenario. Page priority values are also assigned according to certain rules (described next). When a scenario starts, the scenario manager is responsible for responding to the event by generating the list of pages that should be brought into memory and at which priority.

## Page priority and rebalancing

You've already seen that the memory manager implements a system of page priorities to define which standby list pages will be repurposed for a given operation and in which list a given page will be inserted. This mechanism provides benefits when processes and threads have associated priorities—for example, ensuring that a defragmenter process doesn't pollute the standby page list and/or steal pages from an interactive foreground process. But its real power is unleashed through SuperFetch's page-prioritization schemes and rebalancing, which don't require manual application input or hardcoded knowledge of process importance.

SuperFetch assigns page priority based on an internal score it keeps for each page, part of which is based on frequency-based usage. This usage counts how many times a page was used in given relative time intervals, such as by hour, day, or week. The system also keeps track of time of use, recording how long it's been since a given page was accessed. Finally, data such as where this page comes from (which list) and other access patterns is used to compute this score.

The score is translated into a priority number, which can be anywhere from 1 to 6. (A priority of 7 is used for another purpose, described later.) Going down each level, the lower standby page list priorities are repurposed first, as shown in the "Viewing the prioritized standby lists" experiment. Priority 5 is typically used for normal applications, while priority 1 is meant for background applications that third-party developers can mark as such. Finally, priority 6 is used to keep a certain number of high-importance pages as far away as possible from repurposing. The other priorities are a result of the score associated with each page.

Because SuperFetch "learns" a user's system, it can start from scratch with no existing historical data and slowly build an understanding of the different page accesses associated with the user. However, this would result in a significant learning curve whenever a new application, user, or service pack was installed. Instead, by using an internal tool, Windows can pre-train SuperFetch to capture SuperFetch data and then turn it into prebuilt traces. These prebuilt traces were generated by the SuperFetch team, who traced common usages and patterns that all users will probably encounter, such as clicking the Start menu, opening Control Panel, or using the File Open/Save dialog box. This trace data was then saved to history files (which ship as resources in Sysmain.dll) and is used to prepopulate the special priority 7 list. This list is where the most critical data is placed and is rarely repurposed. Pages at priority 7 are file pages kept in memory even after the process has exited and even across reboots (by being repopulated at the next boot). Finally, pages with priority 7 are static, in that they are never reprioritized, and SuperFetch will never dynamically load pages at priority 7 other than the static pretrained set.

The prioritized list is loaded into memory (or prepopulated) by the rebalancer, but the actual act of rebalancing is handled by both SuperFetch and the memory manager. As shown, the prioritized standby page list mechanism is internal to the memory manager, and decisions as to which pages to throw out first and which to protect are innate, based on the priority number. The rebalancer does its job not by manually rebalancing memory but by reprioritizing it, which causes the memory manager to perform the needed tasks. The rebalancer is also responsible for reading the actual pages from disk, if needed, so that they are present in memory (prefetching). It then assigns the priority that is mapped by each agent to the score for each page, and the memory manager ensures that the page is treated according to its importance.

The rebalancer can take action without relying on other agents—for example, if it notices that the distribution of pages across paging lists is suboptimal or that the number of repurposed pages across different priority levels is detrimental. The rebalancer can also trigger working-set trimming, which might be required for creating an appropriate budget of pages that will be used for SuperFetch prepopulated cache data. The rebalancer will typically take low-utility pages—such as those that are already marked as low priority, that are zeroed, or that have valid content but not in any working set and have been unused—and build a more useful set of pages to bring into memory, given the budget it has allocated itself. After the rebalancer has decided which pages to bring into memory and at which priority level they need to be loaded (as well as which pages can be thrown out), it performs the required disk reads to prefetch them. It also works in conjunction with the I/O manager's prioritization schemes so that I/Os are performed with very low priority and do not interfere with the user.

The memory consumption used by prefetching is backed by standby pages. As described in the discussion of page dynamics, standby memory is available memory because it can be repurposed as free memory for another allocator at any time. In other words, if SuperFetch is prefetching the wrong data, there is no real impact on the user because that memory can be reused when needed and doesn't actually consume resources.

Finally, the rebalancer also runs periodically to ensure that pages it has marked as high priority have actually been recently used. Because these pages will rarely (sometimes never) be repurposed, it is important not to waste them on data that is rarely accessed but may have appeared to be frequently accessed during a certain period. If such a situation is detected, the rebalancer runs again to push those pages down in the priority lists.

A special agent called the *application launch agent* is involved in a different kind of prefetching mechanism, which attempts to predict application launches and builds a Markov chain model that describes the probability of certain application launches given the existence of other application launches within a time segment. These time segments are divided across four different periods of roughly 6 hours each—morning, noon, evening, and night—and by weekday or weekend. For example, if on Saturday and Sunday evening a user typically launches Outlook after having launched Word, the application launch agent will likely prefetch Outlook based on the high probability of it running after Word during weekend evenings.

Because systems today have sufficiently large amounts of memory—on average more than 2 GB (although SuperFetch works well on low-memory systems, too)—the actual real amount of memory that frequently used processes on a machine need resident for optimal performance ends up being a manageable subset of their entire memory footprint. Often, SuperFetch can fit all the pages required into RAM. When it can't, technologies such as ReadyBoost and ReadyDrive can further prevent disk usage.

## **Robust performance**

A final performance-enhancing functionality of SuperFetch is called *robustness*, or *robust performance*. This component—managed by the user-mode Superfetch service but ultimately implemented in the kernel (Pf routines)—watches for specific file I/O access that might harm system performance by populating the standby lists with unneeded data. For example, if a process were to copy a large file across the file system, the standby list would be populated with the file's contents, even though that file might never be accessed again (or not for a long period of time). This would throw out any other data within that priority—and if this was an interactive and useful program, chances are its priority would be at least 5.

SuperFetch responds to two specific kinds of I/O access patterns:

- Sequential file access With this type of I/O access pattern, the system goes through all the data in a file.
- **Sequential directory access** With this type of I/O access, the system goes through every file in a directory.

When SuperFetch detects that a certain amount of data past an internal threshold has been populated in the standby list as a result of this kind of access, it applies aggressive deprioritization (called *robustion*) to the pages being used to map this file. This occurs within the targeted process only so as not to penalize other applications. These pages, which are said to be *robusted*, essentially become reprioritized to priority 2.

Because this component of SuperFetch is reactive and not predictive, it does take some time for the robustion to kick in. SuperFetch will therefore keep track of this process for the next time it runs. Once SuperFetch has determined that it appears that this process always performs this kind of sequential access, it remembers this and robusts the file pages as soon as they're mapped instead of waiting for the reactive behavior. At this point, the entire process is now considered robusted for future file access.

Just by applying this logic, however, SuperFetch could potentially hurt many legitimate applications or user scenarios that perform sequential access in the future. For example, by using the Sysinternals Strings.exe utility, you can look for a string in all executables that are part of a directory. If there are many files, SuperFetch would likely perform robustion. Now, next time you run Strings.exe with a different search parameter, it would run just as slowly as it did the first time even though you'd expect it to run much faster. To prevent this, SuperFetch keeps a list of processes that it watches into the future, as well as an internal hard-coded list of exceptions. If a process is detected to later re-access robusted files, robustion is disabled on the process to restore the expected behavior.

The main point to remember when thinking about robustion—and SuperFetch optimizations in general—is that SuperFetch constantly monitors usage patterns and updates its understanding of the system to avoid fetching useless data. Although changes in a user's daily activities or application startup behavior might cause SuperFetch to pollute the cache with irrelevant data or to throw out data that it might think is useless, it will quickly adapt to any pattern changes. If the user's actions are erratic and random, the worst that can happen is that the system will behave in a similar state as if SuperFetch were not present at all. If SuperFetch is ever in doubt or cannot track data reliably, it quiets itself and doesn't make changes to a given process or page.

# ReadyBoost

These days, RAM is easily available and relatively cheap compared to a decade ago. Still, it doesn't beat the cost of secondary storage such as hard disk drives. Unfortunately, mechanical hard disks contain many moving parts, are fragile, and, more importantly, are relatively slow compared to RAM, especially during seeking. As a result, storing active SuperFetch data on the drive would be as bad as paging out a page and hard-faulting it inside memory.

Solid state disks and hybrid drives offset some of these disadvantages but they are still pricier and slower compared to RAM. Portable solid state media such as USB flash disk (UFD), CompactFlash cards, and Secure Digital cards, however, provide a useful compromise. They are cheaper than RAM and available in larger sizes, but also have shorter seek times than mechanical hard drives because of the lack of moving parts.

**Note** In practice, CompactFlash cards and Secure Digital cards are almost always interfaced through a USB adapter, so they all appear to the system as USB flash disks.

Random disk I/O is especially expensive because disk head seek time plus rotational latency for typical desktop hard drives total about 10 milliseconds—an eternity for today's 3 or 4 GHz processors. Flash memory, however, can service random reads up to 10 times faster than a typical hard disk. Windows therefore includes a feature called *ReadyBoost* to take advantage of flash memory storage devices by creating an intermediate caching layer on them that logically sits between memory and disks.

ReadyBoost (not to be confused with ReadyBoot) is implemented with the aid of a driver (%System-Root%\System32\Drivers\Rdyboost.sys) that is responsible for writing the cached data to the non-volatile RAM (NVRAM) device. When you insert a USB flash disk into a system, ReadyBoost looks at the device to determine its performance characteristics and stores the results of its test in HKLM\SOFTWARE\ Microsoft\Windows NT\CurrentVersion\Emdmgmt. (*Emd* is short for *external memory device*, the working name for ReadyBoost during its development.)

If the new device is between 256 MB and 32 GB in size, has a transfer rate of 2.5 MB per second or higher for random 4 KB reads, and has a transfer rate of 1.75 MB per second or higher for random 512 KB writes, then ReadyBoost will ask if you'd like to dedicate some of the space for disk caching. If you agree, ReadyBoost creates a file named *ReadyBoost.sfcache* in the root of the device, which it uses to store cached pages.

After initializing caching, ReadyBoost intercepts all reads and writes to local hard disk volumes (C:\, for example) and copies any data being read or written into the caching file that the service created. There are exceptions—for example, data that hasn't been read in a long while or data that belongs to Volume Snapshot requests. Data stored on the cached drive is compressed and typically achieves a 2:1 compression ratio, so a 4 GB cache file will usually contain 8 GB of data. Each block is encrypted as it is written using Advanced Encryption Standard (AES) encryption with a randomly generated per-boot session key to guarantee the privacy of the data in the cache if the device is removed from the system.

When ReadyBoost sees random reads that can be satisfied from the cache, it services them from there. However, because hard disks have better sequential read access than flash memory, it lets reads that are part of sequential access patterns go directly to the disk even if the data is in the cache. Likewise, when reading the cache, if large I/Os must be done, the on-disk cache will be read instead.

One disadvantage of depending on flash media is that the user can remove it at any time, which means the system can never solely store critical data on the media. (As you've seen, writes always go to the secondary storage first.) A related technology, ReadyDrive, covered in the next section, offers additional benefits and solves this problem.

#### ReadyDrive

ReadyDrive is a Windows feature that takes advantage of hybrid hard disk drives (H-HDDs). An *H-HDD* is a disk with embedded NVRAM. Typical H-HDDs include between 50 MB and 512 MB of cache.

Under ReadyDrive, the drive's flash memory does not simply act as an automatic, transparent cache, as does the RAM cache common on most hard drives. Instead, Windows uses ATA-8 commands to define the disk data to be held in the flash memory. For example, Windows saves boot data to the cache when the system shuts down, allowing for faster restarting. It also stores portions of hibernation file data in the cache when the system hibernates so that the subsequent resume is faster. Because the cache is enabled even when the disk is spun down, Windows can use the flash memory as a disk-write cache, which avoids spinning up the disk when the system is running on battery power. Keeping the disk spindle turned off can save much of the power consumed by the disk drive under normal usage.

Another consumer of ReadyDrive is SuperFetch. It offers the same advantages as ReadyBoost with some enhanced functionality, such as not requiring an external flash device and having the ability to work persistently. Because the cache is on the actual physical hard drive, which a user typically cannot remove while the computer is running, the hard drive controller typically doesn't have to worry about the data disappearing and can avoid making writes to the actual disk using solely the cache.

## **Process reflection**

There are often cases where a process exhibits problematic behavior, but because it's still providing service, suspending it to generate a full memory dump or interactively debug it is undesirable. The length of time a process is suspended to generate a dump can be minimized by taking a minidump, which captures thread registers and stacks along with pages of memory referenced by registers, but that dump type has a very limited amount of information, which many times is sufficient for diagnosing

crashes but not for troubleshooting general problems. With process reflection, the target process is suspended only long enough to generate a minidump and create a suspended cloned copy of the target, and then the larger dump that captures all of a process's valid user-mode memory can be generated from the clone while the target is allowed to continue executing.

Several Windows Diagnostic Infrastructure (WDI) components make use of process reflection to capture minimally intrusive memory dumps of processes their heuristics identify as exhibiting suspicious behavior. For example, the Memory Leak Diagnoser component of Windows Resource Exhaustion Detection and Resolution (also known as RADAR), generates a reflected memory dump of a process that appears to be leaking private virtual memory so that it can be sent to Microsoft via Windows Error Reporting (WER) for analysis. WDI's hung process detection heuristic does the same for processes that appear to be deadlocked with one another. Because these components use heuristics, they can't be certain the processes are faulty and therefore can't suspend them for long periods of time or terminate them.

The RtlCreateProcessReflection function in Ntdll.dll drives the implementation of process reflection. It works as follows:

- 1. It creates a shared memory section.
- 2. It populates the shared memory section with parameters.
- 3. It maps the shared memory section into the current and target processes.
- **4.** It creates two event objects and duplicates them into the target process so that the current process and target process can synchronize their operations.
- 5. It injects a thread into the target process via a call to RtlpCreateUserThreadEx. The thread is directed to begin execution in Ntdll's RtlpProcessReflectionStartup function. (Because Ntdll.dll is mapped at the same address (randomly generated at boot) into every process's address space, the current process can simply pass the address of the function it obtains from its own Ntdll.dll mapping.
- 6. If the caller of RtlCreateProcessReflection specified that it wants a handle to the cloned process, RtlCreateProcessReflection waits for the remote thread to terminate, otherwise it returns to the caller.
- **7.** The injected thread in the target process allocates an additional event object that it will use to synchronize with the cloned process once it's created.
- 8. The injected thread calls Rt1CloneUserProcess, passing parameters it obtains from the memory mapping it shares with the initiating process.
- 9. If the RtlCreateProcessReflection option that specifies the creation of the clone when the process is not executing in the loader, performing heap operations, modifying the process environment block (PEB), or modifying fiber-local storage is present, then RtlCreateProcess-Reflection acquires the associated locks before continuing. This can be useful for debugging because the memory dump's copy of the data structures will be in a consistent state.

10. RtlCloneUserProcess finishes by calling RtlpCreateUserProcess, the user-mode function responsible for general process creation, passing flags that indicate the new process should be a clone of the current one. RtlpCreateUserProcess in turn calls ZwCreateUserProcess to request the kernel to create the process.

When creating a cloned process, ZwCreateUserProcess executes most of the same code paths as when it creates a new process, with the exception that PspAllocateProcess, which it calls to create the process object and initial thread, calls MmInitializeProcessAddressSpace with a flag specifying that the address should be a copy-on-write copy of the target process instead of an initial process address space. The memory manager uses the same support it provides for the Services for Unix Applications fork API to efficiently clone the address space. Once the target process continues execution, any changes it makes to its address space are seen only by it, not the clone. This enables the clone's address space to represent a consistent point-in-time view of the target process.

The clone's execution begins at the point just after the return from RtlpCreateUserProcess. If the clone's creation is successful, its thread receives the STATUS\_PROCESS\_CLONED return code, whereas the cloning thread receives STATUS\_SUCCESS. The cloned process then synchronizes with the target and, as its final act, calls a function optionally passed to RtlCreateProcessReflection, which must be implemented in Ntdll.dll. RADAR, for instance, specifies RtlDetectHeapLeaks, which performs heuristic analysis of the process heaps and reports the results back to the thread that called RtlCreateProcess-Reflection. If no function was specified, the thread suspends itself or terminates, depending on the flags passed to RtlCreateProcessReflection.

When RADAR and WDI use process reflection, they call RtlCreateProcessReflection, asking for the function to return a handle to the cloned process and for the clone to suspend itself after it has initialized. Then they generate a minidump of the target process, which suspends the target for the duration of the dump generation. Next, they generate a more comprehensive dump of the cloned process. After they finish generating the dump of the clone, they terminate the clone. The target process can execute during the time window between the minidump's completion and the creation of the clone, but for most scenarios any inconsistencies do not interfere with troubleshooting. The Procdump utility from Sysinternals also follows these steps when you specify the -r switch to have it create a reflected dump of a target process.

# Conclusion

This chapter examined how the Windows memory manager implements virtual memory management. As with most modern operating systems, each process is given access to a private address space, protecting one process's memory from another's but allowing processes to share memory efficiently and securely. Advanced capabilities, such as the inclusion of mapped files and the ability to sparsely allocate memory, are also available. The Windows environment subsystem makes most of the memory manager's capabilities available to applications through the Windows API.

The next chapter covers another critical part of any operating system—the I/O system.

CHAPTER 6

# I/O system

The Windows I/O system consists of several executive components that, together, manage hardware devices and provide interfaces to hardware devices for applications and the system. This chapter lists the design goals of the I/O system, which have influenced its implementation. It then covers the components that make up the I/O system, including the I/O manager, Plug and Play (PnP) manager, and power manager. Then it examines the structure and components of the I/O system and the various types of device drivers. It discusses the key data structures that describe devices, device drivers, and I/O requests, after which it describes the steps necessary to complete I/O requests as they move through the system. Finally, it presents the way device detection, driver installation, and power management work.


#### I/O system components


The design goals for the Windows I/O system are to provide an abstraction of devices, both hardware (physical) and software (virtual or logical), to applications with the following features:

- Uniform security and naming across devices to protect shareable resources. (See Chapter 7, "Security," for a description of the Windows security model.)
- High-performance asynchronous packet-based I/O to allow for the implementation of scalable applications.
- Services that allow drivers to be written in a high-level language and easily ported between different machine architectures.
- Layering and extensibility to allow for the addition of drivers that transparently modify the behavior of other drivers or devices, without requiring any changes to the driver whose behavior or device is modified.
- Dynamic loading and unloading of device drivers so that drivers can be loaded on demand and not consume system resources when unneeded.
- Support for Plug and Play, where the system locates and installs drivers for newly detected hardware, assigns them hardware resources they require, and allows applications to discover and activate device interfaces.
- Support for power management so that the system or individual devices can enter low-power states.

- Support for multiple installable file systems, including FAT (and its variants, FAT32 and exFAT), the CD-ROM file system (CDFS), the Universal Disk Format (UDF) file system, the Resilient File System (ReFS), and the Windows file system (NTFS). (See Chapter 13, "File systems," in Part 2 of this book for more specific information on file system types and architecture.)
- Windows Management Instrumentation (WMI) support and diagnosability so that drivers can be managed and monitored through WMI applications and scripts. (WMI is described in Chapter 9, "Management mechanisms," in Part 2.)

To implement these features, the Windows I/O system consists of several executive components as well as device drivers, which are shown in Figure 6-1.





- The I/O manager is the heart of the I/O system. It connects applications and system components to virtual, logical, and physical devices, and it defines the infrastructure that supports device drivers.
- A device driver typically provides an I/O interface for a particular type of device. A *driver* is a software module that interprets high-level commands, such as read or write commands, and issues low-level, device-specific commands, such as writing to control registers. Device drivers receive commands routed to them by the I/O manager that are directed at the devices they manage, and they inform the I/O manager when those commands are complete. Device drivers often use the I/O manager to forward I/O commands to other device drivers that share in the implementation of a device's interface or control.

- The PnP manager works closely with the I/O manager and a type of device driver called *a bus driver* to guide the allocation of hardware resources as well as to detect and respond to the arrival and removal of hardware devices. The PnP manager and bus drivers are responsible for loading a device's driver when the device is detected. When a device is added to a system that doesn't have an appropriate device driver, the executive Plug and Play component calls on the device-installation services of the user-mode PnP manager.
- The power manager also works closely with the I/O manager and the PnP manager to guide the system, as well as individual device drivers, through power-state transitions.
- WMI support routines, called the Windows Driver Model (WDM) WMI provider, allow device drivers to indirectly act as providers, using the WDM WMI provider as an intermediary to communicate with the WMI service in user mode.
- The registry serves as a database that stores a description of basic hardware devices attached to the system as well as driver initialization and configuration settings. (See the section "The registry" in Chapter 9 in Part 2 for more information.)
- INF files, which are designated by the .inf extension, are driver-installation files. INF files are the link between a particular hardware device and the driver that assumes primary control of that device. They are made up of script-like instructions describing the device they correspond to, the source and target locations of driver files, required driver-installation registry modifications, and driver-dependency information. Digital signatures that Windows uses to verify that a driver file has passed testing by the Microsoft Windows Hardware Quality Labs (WHQL) are stored in .cat files. Digital signatures are also used to prevent tampering of the driver or its INF file.
- The hardware abstraction layer (HAL) insulates drivers from the specifics of the processor and interrupt controller by providing APIs that hide differences between platforms. In essence, the HAL is the bus driver for all the devices soldered onto the computer's motherboard that aren't controlled by other drivers.

# The I/O manager

The I/O manager is the core of the I/O system. It defines the orderly framework, or model, within which I/O requests are delivered to device drivers. The I/O system is packet driven. Most I/O requests are represented by an I/O request packet (IRP), which is a data structure that contains information completely describing an I/O request. The IRP travels from one I/O system component to another. (As you'll discover in the section "Fast I/O," fast I/O is the exception; it doesn't use IRPs.) The design allows an individual application thread to manage multiple I/O requests concurrently. (For more information on IRPs, see the section "I/O request packets" later in this chapter.)

The I/O manager creates an IRP in memory to represent an I/O operation, passing a pointer to the IRP to the correct driver and disposing of the packet when the I/O operation is complete. In contrast, a driver receives an IRP, performs the operation the IRP specifies, and passes the IRP back to the I/O manager, either because the requested I/O operation has been completed or because it must be passed on to another driver for further processing.

In addition to creating and disposing of IRPs, the I/O manager supplies code that is common to different drivers and that the drivers can call to carry out their I/O processing. By consolidating common tasks in the I/O manager, individual drivers become simpler and more compact. For example, the I/O manager provides a function that allows one driver to call other drivers. It also manages buffers for I/O requests, provides timeout support for drivers, and records which installable file systems are loaded into the operating system. There are about 100 different routines in the I/O manager that can be called by device drivers.

The I/O manager also provides flexible I/O services that allow environment subsystems, such as Windows and POSIX (the latter is no longer supported), to implement their respective I/O functions. These services include support for asynchronous I/O that allow developers to build scalable, high-performance server applications.

The uniform, modular interface that drivers present allows the I/O manager to call any driver without requiring any special knowledge of its structure or internal details. The operating system treats all I/O requests as if they were directed at a file; the driver converts the requests from requests made to a virtual file to hardware-specific requests. Drivers can also call each other (using the I/O manager) to achieve layered, independent processing of an I/O request.

Besides providing the normal open, close, read, and write functions, the Windows I/O system provides several advanced features, such as asynchronous, direct, buffered, and scatter/gather I/O, which are described in the "Types of I/O" section later in this chapter.

#### Typical I/O processing

Most I/O operations don't involve all the components of the I/O system. A typical I/O request starts with an application executing an I/O-related function (for example, reading data from a device) that is processed by the I/O manager, one or more device drivers, and the HAL.

As mentioned, in Windows, threads perform I/O on virtual files. A virtual file refers to any source or destination for I/O that is treated as if it were a file (such as devices, files, directories, pipes, and mailslots). A typical user mode client calls the CreateFile or CreateFile2 functions to get a handle to a virtual file. The function name is a little misleading—it's not just about files, it's anything that is known as a *symbolic link* within the object manager's directory called GLOBAL??. The suffix "File" in the CreateFile\* functions really means a virtual file object (FILE\_OBJECT) that is the entity created by the executive as a result of these functions. Figure 6-2 shows a screenshot of the WinObj Sysinternals tool for the GLOBAL?? directory.

As shown in Figure 6-2, a name such as C: is just a symbolic link to an internal name under the Device object manager directory (in this case, \Device\HarddiskVolume7). (See Chapter 8, "System mechanisms," in Part 2 for more on the object manager and the object manager namespace.) All the names in the GLOBAL?? directory are candidates for arguments to CreateFile(2). Kernel mode clients such as device drivers can use the similar ZwCreateFile to obtain a handle to a virtual file.

e Vie	ew Help				
1		Name 4	Туре	SymLink	
	ArcName	ACPI_ROOT_OBJECT	SymbolicLink	\Device\00000019	
2-	BaseNamedObjects	AcpiCtl	SymbolicLink	\Device\000002c	
	Callback	Ahcache	SymbolicLink	\Device\ahcache	
2-	Device	<b>WAUX</b>	SymbolicLink	\DosDevices\COM1	
17	FileSystem	<b>BCMBTUDN</b>	SymbolicLink	\Device\BCMBTUDN	
11	GLOBAL??	BitLocker	SymbolicLink	\Device\BitLocker	
	KernelObjects	Ridge	SymbolicLink	\Device\Bridge	
	KnownDils	[₹]C:	SymbolicLink	\Device\HarddiskVolume7	
	KnownDlls32	CdRom0	SymbolicLink	\Device\CdRom0	
1	NLS	COMPOSITEBUS#MS_IMPLAT_MP#(3164FA7A	SymbolicLink	\Device\0000066	
1-1	ObjectTypes	COMPOSITEBUS#MS_IMPLAT_MP#(3164FA7A	SymbolicLink	\Device\0000066	
1.1	RPC Control	CON	SymbolicLink	\Device\ConDrv\Console	
	Security		SymbolicLink	\Device\ConDrv\CurrentIn	
5.	Sessions	CONOUTS	SymbolicLink	\Device\ConDrv\CurrentOut	
>-1	Windows	PD:	SymbolicLink	\Device\CdRom0	
		Disk(ce77ebba-67dc-a4e0-5d0c-11e840af9148)	SymbolicLink	\Device\Harddisk1\DR1	
		Disk{ff611c3a-c68f-4ca2-87be-949bb5f1d357}	SymbolicLink	\Device\Harddisk0\DR0	
		DISPLAY#DELA017#58/21fa0be88/08/UID4353#	SymbolicLink	\Device\000005a	
		DISPLAY#DELA017#58x21fa0be8&x08xUID4353#	SymbolicLink	\Device\000005a	
		DISPLAY#LGD02DA#5&21fa0be8&0&UID4352	SymbolicLink	\Device\000007d	
		DISPLAY#LGD02DA#5&21fa0be8&0&UID4352	SymbolicLink	\Device\0000007d	
		DISPLAY#LGD02DA#58/21fa0be88/08/UID4352	SymbolicLink	\Device\000007d	
		-			>

FIGURE 6-2 The object manager's GLOBAL?? directory.

**Note** Higher-level abstractions such as the .NET Framework and the Windows Runtime have their own APIs for working with files and devices (for example, the System.IO.File class in .NET or the Windows.Storage.StorageFile class in WinRT), but these eventually call CreateFile(2) to get the actual handle they hide under the covers.

**Note** The GLOBAL?? object manager directory is sometimes called DosDevices, which is an older name. DosDevices still works because it's defined as a symbolic link to *GLOBAL*?? in the root of the object manager's namespace. In driver code, the ?? string is typically used to reference the GLOBAL?? directory.

The operating system abstracts all I/O requests as operations on a virtual file because the I/O manager has no knowledge of anything but files, therefore making it the responsibility of the driver to translate file-oriented comments (open, close, read, write) into device-specific commands. This abstraction thereby generalizes an application's interface to devices. User-mode applications call documented functions, which in turn call internal I/O system functions to read from a file, write to a file, and perform other operations. The I/O manager dynamically directs these virtual file requests to the appropriate device driver. Figure 6-3 illustrates the basic structure of a typical I/O read request flow. (Other types of I/O requests, such as write, are similar; they just use different APIs.)




FIGURE 6-3 The flow of a typical I/O request.

The following sections look at these components more closely, covering the various types of device drivers, how they are structured, how they load and initialize, and how they process I/O requests. Then we'll cover the operation and roles of the PnP manager and the power manager.

# **Interrupt Request Levels and Deferred Procedure Calls**

Before we proceed, we must introduce two very important concepts of the Windows kernel that play an important role within the I/O system: Interrupt Request Levels (IRQL) and Deferred Procedure Calls (DPC). A thorough discussion of these concepts is reserved for Chapter 8 in Part 2, but we'll provide enough information in this section to enable you to understand the mechanics of I/O processing that follow.

# **Interrupt Request Levels**

The IRQL has two somewhat distinct meanings, but they converge in certain situations:

- An IRQL is a priority assigned to an interrupt source from a hardware device This number is set by the HAL (in conjunction with the interrupt controller to which devices that require interrupt servicing are connected).
- **Each CPU has its own IRQL value** It should be considered a register of the CPU (even though current CPUs do not implement it as such).

The fundamental rule of IRQLs is that lower IRQL code cannot interfere with higher IRQL code and vice versa—code with a higher IRQL can preempt code running at a lower IRQL. You'll see examples of how this works in practice in a moment. A list of IRQLs for the Windows-supported architectures is shown in Figure 6-4. Note that IRQLs are not the same as thread priorities. In fact, thread priorities have meaning only when the IRQL is less than 2.




FIGURE 6-4 IRQLs.

**Note** IRQL is not the same as IRQ (interrupt request). IRQs are hardware lines connecting devices to an interrupt controller. See Chapter 8 in Part 2 for more on interrupts, IRQs, and IRQLs.

Normally, the IRQL of a processor is 0. This means "nothing special" is happening in that regard, and that the kernel's scheduler that schedules threads based on priorities and so on works as described in Chapter 4, "Threads." In user mode, the IRQL can only be 0. There is no way to raise IRQL from user mode. (That's why user-mode documentation never mentions the IRQL concept at all; there would be no point.)

Kernel-mode code can raise and lower the current CPU IRQL with the KeRaiseIrq1 and KeLower-Irq1 functions. However, most of the time-specific functions are called with the IRQL raised to some expected level, as you'll see shortly when we discuss a typical I/O processing by a driver.

The most important IRQLs for this I/O-related discussions are the following:

Passive(0) This is defined by the PASSIVE\_LEVEL macro in the WDK header wdm.h. It is the normal IRQL where the kernel scheduler is working normally, as described at length in Chapter 4.

- Dispatch/DPC (2) (DISPATCH\_LEVEL) This is the IRQL the kernel's scheduler works at. This means if a thread raises the current IRQL to 2 (or higher), the thread has essentially an infinite quantum and will not be preempted by another thread. Effectively, the scheduler cannot wake up on the current CPU until the IRQL drops below 2. This implies a few things:
  - With the IRQL at level 2 or above, any waiting on kernel dispatcher objects (such as mutexes, semaphores, and events) would crash the system. This is because waiting implies that the thread might enter a wait state and another should be scheduled on the same CPU. How-ever, because the scheduler is not around at this level, this cannot happen; instead, the system will bug-check (the only exception is if the wait timeout is zero, meaning no waiting is requested, just getting back the signaled state of the object).
  - No page faults can be handled. This is because a page fault would require a context switch to one of the modified page writers. However, context switches are not allowed, so the system would crash. This means code running at IRQL 2 or above can access only non-paged memory—typically memory allocated from non-paged pool, which by definition is always resident in physical memory.
- Device IRQL (3–26 on x86; 3–12 on x64 and ARM) (DIRQL) These are the levels assigned to hardware interrupts. When an interrupt arrives, the kernel's trap dispatcher calls the appropriate interrupt service routine (ISR) and raises its IRQL to that of the associated interrupt. Because this value is always higher than DISPATCH\_LEVEL (2), all rules associated with IRQL 2 apply for DIRQL as well.

Running at a particular IRQL masks interrupts with that and lower IRQLs. For example, an ISR running with IRQL of 8 would not let any code interfere (on that CPU) with IRQL of 7 or lower. Specifically, no user mode code is able to run because it always runs at IRQL 0. This implies that running in high IRQL is not desirable in the general case; there are a few specific scenarios (which we'll look at in this chapter) where this makes sense and is in fact required for normal system operation.

## **Deferred Procedure Calls**

A Deferred Procedure Call (DPC) is an object that encapsulates calling a function at IRQL DPC\_LEVEL (2). DPCs exist primarily for post-interrupt processing because running at DIRQL masks (and thus delays) other interrupts waiting to be serviced. A typical ISR would do the minimum work possible, mostly reading the state of the device and telling it to stop its interrupt signal and then deferring further processing to a lower IRQL (2) by requesting a DPC. The term *Deferred* means the DPC will not execute immediately—it can't because the current IRQL is higher than 2. However, when the ISR returns, if there are no pending interrupts waiting to be serviced, the CPU IRQL will drop to 2 and it will execute the DPCs that have accumulated (maybe just one). Figure 6-5 shows a simplified example of the sequence of events that may occur when interrupts from hardware devices (which are asynchronous in nature, meaning they can arrive at any time) occur while code executes normally at IRQL 0 on some CPU.




FIGURE 6-5 Example of interrupt and DPC processing.

Here is a rundown of the sequence of events shown in Figure 6-5:

- 1. Some user-mode or kernel-mode code is executing while the CPU is at IRQL 0, which is the case most of the time.
- 2. A hardware interrupt arrives with an IRQL of 5 (remember that Device IRQLs have a minimum value of 3). Because 5 is greater than zero (the current IRQL), the CPU state is saved, the IRQL is raised to 5, and the ISR associated with that interrupt is called. Note that there is no context switch; it's the same thread that now happens to execute the ISR code. (If the thread was in user mode, it switches to kernel mode whenever an interrupt arrives.)
- **3.** ISR 1 starts executing while the CPU IRQL is 5. At this point, any interrupt with IRQL 5 or lower cannot interrupt.
- 4. Suppose another interrupt arrives with an IRQL of 8. Assume the system decides that the same CPU should handle it. Because 8 is greater than 5, the code is interrupted again, the CPU state is saved, the IRQL is raised to 8, and the CPU jumps to ISR 2. Note again that it's the same thread. No context switch can happen because the thread scheduler cannot wake up if the IRQL is 2 or higher.
- **5.** ISR 2 is executing. Before it's done, ISR 2 would like to do some more processing at a lower IRQL so that interrupts with IRQLs less than 8 could be services as well.
- 6. As its final act, ISR 2 inserts a DPC initialized properly to point to a driver routine to do any post processing after the interrupt is dismissed by calling the KeInsertQueueDpc function. (We'll discuss what this post-processing typically includes in the next section.) Then the ISR returns, restoring the CPU state saved before entering ISR 2.
- **7.** At this point, the IRQL drops to its previous level (5) and the CPU continues execution of ISR 1 that was interrupted before.

- 8. Just before ISR 1 finishes, it queues a DPC of its own to do its required post-processing. These DPCs are collected in a DPC queue that has not been examined yet. Then ISR 1 returns, restoring the CPU state saved before ISR 1 started execution.
- 9. At this point, the IRQL would want to drop to the old value of zero before all the interrupt handling began. However, the kernel notices that there are DPCs pending and so drops the IRQL to level 2 (DPC\_LEVEL) and enters a DPC processing loop that iterates over the accumulated DPCs and calls each DPC routine in sequence. When the DPC queue is empty, DPC processing ends.
- **10.** Finally, the IRQL can drop back to zero, restore the state of the CPU again, and resume execution of the original user or kernel code that got interrupted in the first place. Again, notice that all the processing described was done by the same thread (whichever one that may be). This fact implies that ISRs and DPC routines should not rely on any particular thread (and hence part of a particular process) to execute their code. It could be any thread, the significance of which will be discussed in the next section.

The preceding description is a bit simplified. It doesn't mention DPC importance, other CPUs that may handle DPCs for quicker DPC processing, and more. These details are not important for the discussion in this chapter. However, they are described fully in Chapter 8 in Part 2.

# **Device drivers**

To integrate with the I/O manager and other I/O system components, a device driver must conform to implementation guidelines specific to the type of device it manages and the role it plays in managing the device. This section discusses the types of device drivers Windows supports as well as the internal structure of a device driver.

**Note** Most kernel-mode device drivers are written in C. Starting with the Windows Driver Kit 8.0, drivers can also be safely written in C++ due to specific support for kernel-mode C++ in the new compilers. Use of assembly language is highly discouraged because of the complexity it introduces and its effect of making a driver difficult to port between the hardware architectures supported by Windows (x86, x64, and ARM).

# Types of device drivers

Windows supports a wide range of device-driver types and programming environments. Even within a particular type of device driver, programming environments can differ depending on the specific type of device for which a driver is intended.

The broadest classification of a driver is whether it is a user-mode or kernel-mode driver. Windows supports a couple of types of user-mode drivers:

- Windows subsystem printer drivers These translate device-independent graphics requests to printer-specific commands. These commands are then typically forwarded to a kernel-mode port driver such as the universal serial bus (USB) printer port driver (Usbprint.sys).
- User-Mode Driver Framework (UMDF) drivers These are hardware device drivers that run in user mode. They communicate to the kernel-mode UMDF support library through advanced local procedure calls (ALPC). See the "User-Mode Driver Framework" section later in this chapter for more information.

In this chapter, the focus is on kernel-mode device drivers. There are many types of kernel-mode drivers, which can be divided into the following basic categories:

- **File-system drivers** These accept I/O requests to files and satisfy the requests by issuing their own more explicit requests to mass storage or network device drivers.
- Plug and Play drivers These work with hardware and integrate with the Windows power manager and PnP manager. They include drivers for mass storage devices, video adapters, input devices, and network adapters.
- Non–Plug and Play drivers These include kernel extensions, which are drivers or modules that extend the functionality of the system. They do not typically integrate with the PnP manager or power manager because they usually do not manage an actual piece of hardware. Examples include network API and protocol drivers. The Sysinternals tool Process Monitor has a driver, and is an example of a non-PnP driver.

Within the category of kernel-mode drivers are further classifications based on the driver model to which the driver adheres and its role in servicing device requests.

## WDM drivers

WDM drivers are device drivers that adhere to the Windows Driver Model (WDM). WDM includes support for Windows power management, Plug and Play, and WMI, and most Plug and Play drivers adhere to WDM. There are three types of WDM drivers:

- Bus drivers These manage a logical or physical bus. Examples of buses include PCMCIA, PCI, USB, and IEEE 1394. A bus driver is responsible for detecting and informing the PnP manager of devices attached to the bus it controls and for managing the power setting of the bus. These are typically provided by Microsoft out of the box.
- Function drivers These manage a particular type of device. Bus drivers present devices to function drivers via the PnP manager. The function driver is the driver that exports the operational interface of the device to the operating system. In general, it's the driver with the most knowledge about the operation of the device.
- Filter drivers These logically layer either above function drivers (these are called *upper filters* or *function filters*) or above the bus driver (these are called *lower filters* or *bus filters*), augmenting or changing the behavior of a device or another driver. For example, a keyboard-capture utility could be implemented with a keyboard filter driver that layers above the keyboard function driver.

Figure 6-6 shows a device node (also called a *devnode*) with a bus driver that creates a physical device object (PDO), lower filters, a function driver that creates a functional device object (FDO), and upper filters. The only required layers are the PDO and FDO. The various filters may or may not exist.




FIGURE 6-6 WDM device node (devnode).

In WDM, no one driver is responsible for controlling all aspects of a particular device. The bus driver is responsible for detecting bus membership changes (device addition or removal), assisting the PnP manager in enumerating the devices on the bus, accessing bus-specific configuration registers, and, in some cases, controlling power to devices on the bus. The function driver is generally the only driver that accesses the device's hardware. The exact manner in which these devices came to be is described in "The Plug and Play manager" section later in this chapter.

## Layered drivers


Support for an individual piece of hardware is often divided among several drivers, each providing a part of the functionality required to make the device work properly. In addition to WDM bus drivers, function drivers, and filter drivers, hardware support might be split between the following components:


- Class drivers These implement the I/O processing for a particular class of devices, such as disk, keyboard, or CD-ROM, where the hardware interfaces have been standardized so one driver can serve devices from a wide variety of manufacturers.
- Miniclass drivers These implement I/O processing that is vendor-defined for a particular class of devices. For example, although Microsoft has written a standardized battery class driver, both uninterruptible power supplies (UPS) and laptop batteries have highly specific interfaces that differ wildly between manufacturers, such that a miniclass is required from the vendor. *Miniclass drivers* are essentially kernel-mode DLLs and do not perform IRP processing directly. Instead, the class driver calls into them and they import functions from the class driver.
- Port drivers These implement the processing of an I/O request specific to a type of I/O port, such as SATA, and are implemented as kernel-mode libraries of functions rather than actual device drivers. Port drivers are almost always written by Microsoft because the interfaces are typically standardized in such a way that different vendors can still share the same port driver.

However, in certain cases, third parties may need to write their own for specialized hardware. In some cases, the concept of I/O port extends to cover logical ports as well. For example, Network Driver Interface Specification (NDIS) is the network "port" driver.

Miniport drivers These map a generic I/O request to a type of port into an adapter type, such as a specific network adapter. Miniport drivers are actual device drivers that import the functions supplied by a port driver. Miniport drivers are written by third parties, and they provide the interface for the port driver. Like miniclass drivers, they are kernel-mode DLLs and do not perform IRP processing directly.

Figure 6-7 shows a simplified example for illustrative purposes that will help demonstrate how device drivers and layering work at a high level. As you can see, a file-system driver accepts a request to write data to a certain location within a particular file. It translates the request into a request to write a certain number of bytes to the disk at a particular (that is, the logical) location. It then passes this request (via the I/O manager) to a simple disk driver. The disk driver, in turn, translates the request into a physical location on the disk and communicates with the disk to write the data.





This figure illustrates the division of labor between two layered drivers. The I/O manager receives a write request that is relative to the beginning of a particular file. The I/O manager passes the request to the file-system driver, which translates the write operation from a file-relative operation to a starting location (a sector boundary on the disk) and a number of bytes to write. The file-system driver calls the I/O manager to pass the request to the disk driver, which translates the request to a physical disk location and transfers the data.

Because all drivers—both device drivers and file-system drivers—present the same framework to the operating system, another driver can easily be inserted into the hierarchy without altering the existing drivers or the I/O system. For example, several disks can be made to seem like a very large single disk by adding a driver. This logical volume manager driver is located between the file system and the disk drivers, as shown in the conceptual simplified architectural diagram presented in Figure 6-8. (For the actual storage driver stack diagram as well as volume manager drivers, see Chapter 12, "Storage management" in Part 2.)




FIGURE 6-8 Adding a layered driver.

### **EXPERIMENT:** Viewing the loaded driver list

You can see a list of registered drivers by executing the Msinfo32.exe utility from the Run dialog box, accessible from the Start menu. Select the **System Drivers** entry under **Software Environment** to see the list of drivers configured on the system. Those that are loaded contain the text *Yes* in the Started column, as shown here:

System Information							- 0	×
ile Edit View Help	1							
System Summary	Name	Description	File	Type	Started	Start Mode	State	Stat
Hardware Resources	1394ohci	1394 OHCI Compliant Host Co	c/windows\system32\drivers\1394ohd.sys	Kernel Driver	No	Manual	Stopped	OK
Components	3ware	Bware	c/windows/system32\drivers\3ware.sys	Kernel Driver	No	Manual	Stopped	OK
Software Environment	acpi	Microsoft ACPI Driver	c\windows\system32\drivers\acpi.sys	Kernel Driver	Yes	Boot	Running	OK
System Drivers	acpidev	ACPI Devices driver	c:\windows\system32\drivers\acpidev.sys	Kernel Driver	No	Manual	Stopped	OK
- Environment Variables	acpiex	Microsoft ACPIEx Driver	c\windows\system32\drivers\acpiex.sys	Kernel Driver	Yes	Boot	Running	OK
- Print Jobs - Network Connections	acpipagr	ACPI Processor Aggregator Dr	c:\windows\system32\drivers\acpipagr.sys	Kernel Driver	No	Manual	Stopped	OK
- Running Tasks	acpipmi	ACPI Power Meter Driver	c:\windows\system32\drivers\acpipmi.sys	Kernel Driver	No	Manual	Stopped	OK
-Loaded Modules	acpitime	ACPI Wake Alarm Driver	c1\windows\system32\drivers\acpitime.sys	Kernel Driver	No	Manual	Stopped	OK
Services	adp80xx	ADPBOXX	c/windows/system32\drivers\adp60xx.sys	Kernel Driver	No	Manual	Stopped	OK
- Program Groups	afd	Ancillary Function Driver for Wi	c/windows/system32\drivers\afd.sys	Kernel Driver	Ves	System	Running	OK
Startup Programs	ahcache	Application Compatibility Cache	c\windows\system32\drivers\ahcache.sys	Kernel Driver	Yes	System	Running	ÓK.
OLE Registration	amdk8	AMD K8 Processor Driver	c/windows/system32\drivers\amdk8.sys	Kernel Driver	No	Manual	Stopped	OK
Windows Error Reporting	amdppm	AMD Processor Driver	c\windows\system32\drivers\amdppm.sys	Kernel Driver	No.	Manual	Stopped	OK
	amdsata	amdsata	c:\windows\system32\drivers\amdsata.sys	Kernel Driver	No	Manual	Stopped	OK
	amdsbs	amdsbs	c\windows\system32\drivers\amdsbs.sys	Kernel Driver	No	Manual	Stopped	OK
	amdxata	amdiata	c:\windows\system32\drivers\amdxata.sys	Kernel Driver	No	Manual	Stopped	OK
	4				10			>
Fin	d what:			Find		Close Find		

The list of drivers comes from the registry subkeys under HKLM\System\CurrentControlSet\ Services. This key is shared between drivers and services. Both can be started by the Service Control Manager (SCM). The way to distinguish between a driver and a service for each subkey is by looking at the Type value. A small value (1, 2, 4, 8) indicates a driver, while 16 (0x10) and 32 (0x20) indicate a Windows service. For more information on the Services subkey, consult Chapter 9 in Part 2.

You can also view the list of loaded kernel-mode drivers with Process Explorer. Run Process Explorer, select the **System** process, and select **DLLs** from the **Lower Pane View** menu entry in the **View** menu:

File Options View	Process Find DLL Us	ers Help				1917 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 - 1916 -	1.000		
	🗂 🤀 😁 🛪 🗛 😔								
Process		PID	CPU.	Private Bytes	Working Set	Threads Description		Company Name	Pro /
Secure System		72	Suspended	0 K	3.688 K	0			-
System Idle Proce	65	0	93.68	0 K	4K	1			_
System	-05	4	0.31	124 K	2.140 K	193			
<ul> <li>Interrupta</li> </ul>		n/a	0.61	D K	0K	0 Hardware Inter	upts and DPCs		
T STOL SOO		€.							2
None	Description		Company Name	Path			Version	Base	1
ACP1aye acplex.eys eff ays advache sys BescDapplay.ays BescPander ays BescPander ays BooTVLD all boower ays bridge ays bridge ays BTHUSE ays add all odden ays	ACPIE Driver for NT ACPIEs Driver for NT Architest The Application Compatibility Compatibility Compatibility Microsoft Bases Design Or Brandscom Blautocht Finner Brandscom Statutocht Finner Brandscom Statutocht Neue Brandscom Statutocht Neue Blautocht Minspel Driver Blautocht Minspel Univer Blautocht Minspel Univer Blautocht Minspel Univer Canonal Displer Driver Canonal Displer Driver	r WinSo, N ache N Iver N Iver N iver D Adapte, 6 N N N N N N N N N N N N N N N N N N N	Reseaft Ceparation Network Ceparation	C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING C.WING	OWS system32 / OWS system32 /	Dhreshoppies.go dhresh Jackies ays dhresh Baaic Napion DRIVERS' who ache ays dhresh Baaic Chapter a dhresh Baaic Therefore and dhresh BATTC. SY'S dhresh BATTC. SY'S dhresh BATTC. SY'S dhresh BATTC. SY'S dhresh BATTC. SY'S DRIVERS'S barnel State BATTC. SY'S DRIVERS'S barnel State DRIVERS'S barnel ays DRIVERS'S barnel ays dd ddi dhresh Cadom sys	6.1.4431.1000 6.3.4431.1000 6.3.4431.1000 6.3.1431.1000 6.3.1431.1000 6.3.1431.1000 7.2.0.1430 7.2.0.1430 6.3.2.2.256 6.3.4431.1000 6.3.1431.10000000000000000000000000000000	b.FFFF8047880000 b.FFFF8047862000 b.FFFF804786000 b.FFFF8047850000 b.FFFF8047850000 b.FFFF8047851000 b.FFFF804781000 b.FFFF804781000 b.FFFF8047810000 b.FFFF8047810000 b.FFFF8047810000 b.FFFF8047810000 b.FFFF8047810000 b.FFFF8047810000 b.FFFF8047810000 b.FFFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804782000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF804780000 b.FFF8047800000 b.FFF8047800000 b.FFF8047800000000000000000000000000000000	

Process Explorer lists the loaded drivers, their names, version information (including company and description), and load address (assuming you have configured Process Explorer to display the corresponding columns).

Finally, if you're looking at a crash dump (or live system) with the kernel debugger, you can get a similar display with the kernel debugger Im kv command:

```
kd> lm kv
start end module name
80626000 80631000 kdcom (deferred)
Image path: kdcom.dll
```

```
Image name: kdcom.dll
    Browse all global symbols functions data
   Timestamp: Sat Jul 16 04:27:27 2016 (57898D7F)
CheckSum: 0000821A
    ImageSize:
                    0000B000
    Translations: 0000.04b0 0000.04e4 0409.04b0 0409.04e4
81009000 81632000 nt
                               (pdb symbols)
                                                 e:\symbols\ntkrpamp.
pdb\A54DF85668E54895982F873F58C984591\ntkrpamp.pdb
    Loaded symbol image file: ntkrpamp.exe
    Image path: ntkrpamp.exe
    Image name: ntkrpamp.exe
    Browse all global symbols functions data
   Timestamp: Wed Sep 07 07:35:39 2016 (57CF991B)
                    005C6B08
    CheckSum:
    ImageSize:
                     00629000
    Translations: 0000.04b0 0000.04e4 0409.04b0 0409.04e4
81632000 81693000 hal
                                (deferred)
    Image path: halmacpi.dll
    Image name: halmacpi.dll
    Browse all global symbols functions data
    Timestamp: Sat Jul 16 04:27:33 2016 (57898D85)
                    00061469
    CheckSum:
    CheckSum: 00061469
ImageSize: 00061000
    Translations:
                     0000.04b0 0000.04e4 0409.04b0 0409.04e4
8a800000 8a84b000 FLTMGR (deferred)
    Image path: \SystemRoot\System32\drivers\FLTMGR.SYS
    Image name: FLTMGR.SYS
    Browse all global symbols functions data
    Timestamp: Sat Jul 16 04:27:37 2016 (57898D89)

        CheckSum:
        00053B90

        ImageSize:
        0004B000

        Translations:
        0000.04b0

                      0000.04b0 0000.04e4 0409.04b0 0409.04e4
```

## Structure of a driver

The I/O system drives the execution of device drivers. Device drivers consist of a set of routines that are called to process the various stages of an I/O request. Figure 6-9 illustrates the key driver-function routines, which are described next.




FIGURE 6-9 Primary device driver routines.

- An initialization routine The I/O manager executes a driver's initialization routine, which is set by the WDK to GSDriverEntry when it loads the driver into the operating system. GSDriverEntry initializes the compiler's protection against stack-overflow errors (called a *cookie*) and then calls DriverEntry, which is what the driver writer must implement. The routine fills in system data structures to register the rest of the driver's routines with the I/O manager and performs any necessary global driver initialization.
- An add-device routine A driver that supports Plug and Play implements an add-device routine. The PnP manager sends a notification to the driver via this routine whenever a device for which the driver is responsible is detected. In this routine, a driver typically creates a device object (described later in this chapter) to represent the device.
- A set of dispatch routines Dispatch routines are the main entry points that a device driver provides. Some examples are open, close, read, write, and Plug and Play. When called on to perform an I/O operation, the I/O manager generates an IRP and calls a driver through one of the driver's dispatch routines.
- A start I/O routine A driver can use a start I/O routine to initiate a data transfer to or from a device. This routine is defined only in drivers that rely on the I/O manager to queue their incoming I/O requests. The I/O manager serializes IRPs for a driver by ensuring that the driver processes only one IRP at a time. Drivers can process multiple IRPs concurrently, but serialization is usually required for most devices because they cannot concurrently handle multiple I/O requests.
- An interrupt service routine (ISR) When a device interrupts, the kernel's interrupt dispatcher transfers control to this routine. In the Windows I/O model, ISRs run at device interrupt request level (DIRQL), so they perform as little work as possible to avoid blocking lower IRQL interrupts (as discussed in the previous section). An ISR usually queues a DPC, which runs at a lower IRQL (DPC/dispatch level) to execute the remainder of interrupt processing. Only drivers for interrupt-driven devices have ISRs; a file-system driver, for example, doesn't have one.
- An interrupt-servicing DPC routine A DPC routine performs most of the work involved in handling a device interrupt after the ISR executes. The DPC routine executes at IRQL 2, which is a "compromise" between the high DIRQL and the low passive level (0). A typical DPC routine initiates I/O completion and starts the next queued I/O operation on a device.

Although the following routines aren't shown in Figure 6-9, they're found in many types of device drivers:

- One or more I/O completion routines A layered driver might have I/O completion routines that notify it when a lower-level driver finishes processing an IRP. For example, the I/O manager calls a file-system driver's I/O completion routine after a device driver finishes transferring data to or from a file. The completion routine notifies the file-system driver about the operation's success, failure, or cancellation, and allows the file-system driver to perform cleanup operations.
- A cancel I/O routine If an I/O operation can be canceled, a driver can define one or more cancel I/O routines. When the driver receives an IRP for an I/O request that can be canceled, it assigns a cancel routine to the IRP. As the IRP goes through various stages of processing, this

From the Library of Octavian Mustafa

routine can change or outright disappear if the current operation is not cancellable. If a thread that issues an I/O request exits before the request is completed or the operation is cancelled (for example, with the Cancello or CancelloEx Windows functions), the I/O manager executes the IRP's cancel routine if one is assigned to it. A cancel routine is responsible for performing whatever steps are necessary to release any resources acquired during the processing that has already taken place for the IRP as well as for completing the IRP with a canceled status.

- Fast-dispatch routines Drivers that make use of the cache manager, such as file-system drivers, typically provide these routines to allow the kernel to bypass typical I/O processing when accessing the driver. (See Chapter 14, "Cache manager," in Part 2, for more information on the cache manager.) For example, operations such as reading or writing can be quickly performed by accessing the cached data directly instead of taking the I/O manager's usual path that generates discrete I/O operations. Fast dispatch routines are also used as a mechanism for callbacks from the memory manager and cache manager to file-system drivers. For instance, when creating a section, the memory manager calls back into the file-system driver to acquire the file exclusively.
- An unload routine An unload routine releases any system resources a driver is using so that the I/O manager can remove the driver from memory. Any resources acquired in the initialization routine (DriverEntry) are usually released in the unload routine. A driver can be loaded and unloaded while the system is running if the driver supports it, but the unload routine will be called only after all file handles to the device are closed.
- A system shutdown notification routine This routine allows driver cleanup on system shutdown.
- Error-logging routines When unexpected errors occur (for example, when a disk block goes bad), a driver's error-logging routines note the occurrence and notify the I/O manager. The I/O manager then writes this information to an error log file.


# Driver objects and device objects

When a thread opens a handle to a file object (described in the "I/O processing" section later in this chapter), the I/O manager must determine from the file object's name which driver it should call to process the request. Furthermore, the I/O manager must be able to locate this information the next time a thread uses the same file handle. The following system objects fill this need:

- A driver object This represents an individual driver in the system (DRIVER\_OBJECT structure). The I/O manager obtains the address of each of the driver's dispatch routines (entry points) from the driver object.
- A device object This represents a physical or logical device on the system and describes its characteristics (DEVICE\_OBJECT structure), such as the alignment it requires for buffers and the location of its device queue to hold incoming IRPs. It is the target for all I/O operations because this object is what the handle communicates with.

The I/O manager creates a driver object when a driver is loaded into the system. It then calls the driver's initialization routine (DriverEntry), which fills in the object attributes with the driver's entry points.

At any time after loading, a driver creates device objects to represent logical or physical devices—or even a logical interface or endpoint to the driver—by calling IoCreateDevice or IoCreateDevice-Secure. However, most Plug and Play drivers create devices in their add-device routine when the PnP manager informs them of the presence of a device for them to manage. Non–Plug and Play drivers, on the other hand, usually create device objects when the I/O manager invokes their initialization routine. The I/O manager unloads a driver when the driver's last device object has been deleted and no references to the driver remain.



The relationship between a driver object and its device objects is shown in Figure 6-10.



A driver object holds a pointer to its first device object in the DeviceObject member. The second device object is pointed to by the NextDevice member of DEVICE\_OBJECT until the last one points to NULL. Each device object points back to its driver object with the DriverObject member. All the arrows shown in Figure 6-10 are built by the device-creation functions (IoCreateDevice or IoCreateDevice-Secure). The DeviceExtension pointer shown is a way a driver can allocate an extra piece of memory that is attached to each device object it manages.

**Note** It's important to distinguish driver objects from device objects. A driver object represents the behavior of a driver, while individual device objects represent communication endpoints. For example, on a system with four serial ports, there would be one driver object (and one driver binary) but four instances of device objects, each representing a single serial port, that can be opened individually with no effect on the other serial ports. For hardware devices, each device also represents a distinct set of hardware resources, such as I/O ports, memory-mapped I/O, and interrupt line. Windows is device-centric, rather than driver-centric.

When a driver creates a device object, the driver can optionally assign the device a name. A name places the device object in the object manager namespace. A driver can either explicitly define a name or let the I/O manager auto-generate one. By convention, device objects are placed in the \Device directory in the namespace, which is inaccessible by applications using the Windows API.

**Note** Some drivers place device objects in directories other than \Device. For example, the IDE driver creates the device objects that represent IDE ports and channels in the \Device\ Ide directory. See Chapter 12 in Part 2 for a description of storage architecture, including the way storage drivers use device objects.

If a driver needs to make it possible for applications to open the device object, it must create a symbolic link in the \GLOBAL?? directory to the device object's name in the \Device directory. (The IoCreateSymbolicLink function accomplishes this.) Non–Plug and Play and file-system drivers typically create a symbolic link with a well-known name (for example, \Device\HarddiskVolume2). Because well-known names don't work well in an environment in which hardware appears and disappears dynamically, PnP drivers expose one or more interfaces by calling the IoRegisterDeviceInterface function, specifying a globally unique identifier (GUID) that represents the type of functionality exposed. GUIDs are 128-bit values that can be generated by using tools such as unidgen and guidgen, which are included with the WDK and the Windows SDK. Given the range of values that 128 bits represents (and the formula used to generate them), it's statistically almost certain that each GUID generated will be forever and globally unique.

IoRegisterDeviceInterface generates the symbolic link associated with a device instance. However, a driver must call IoSetDeviceInterfaceState to enable the interface to the device before the I/O manager actually creates the link. Drivers usually do this when the PnP manager starts the device by sending the driver a start-device IRP—in this case, IRP\_MJ\_PNP (major function code) with IRP\_MN\_ START\_DEVICE (minor function code). IRPs are discussed in the "I/O request packets" section later in this chapter.

An application that wants to open a device object whose interfaces are represented with a GUID can call Plug and Play setup functions in user space, such as SetupDiEnumDeviceInterfaces, to enumerate the interfaces present for a particular GUID and to obtain the names of the symbolic links it can use to open the device objects. For each device reported by SetupDiEnumDeviceInterfaces, the application executes SetupDiGetDeviceInterfaceDetail to obtain additional information about the device, such as its auto-generated name. After obtaining a device's name from SetupDiGetDeviceInterface-Detail, the application can execute the Windows function CreateFile or CreateFile2 to open the device and obtain a handle.

### **EXPERIMENT:** Looking at device objects

You can use the WinObj tool from Sysinternals or the !object kernel debugger command to view the device names under \Device in the object manager namespace. The following screen-shot shows an I/O manager–assigned symbolic link that points to a device object in \Device with an auto-generated name:

File View Help				
ArcName     ArcName     BaseNamedObjects     Callback     Device     Driver     GLOBALT?     KnownDlls     KnownDlls     KnownDlls     ObjectTypes     RPC Control     Sessions     Sessions     Windows	Name         //           VDRVROOT         //           VUMLiteController         //           VUMLiteController         //           VUSBWID_0007&/PID_000875&115119=e&0.08.11#{f18a0e88-c30c-1140-8815-00a0c905be           VUSBWID_0007&/PID_000875&392d700b&0.08.11#{f18a0e88-c30c-1140-8815-00a0c905be           VUSBWID_0007         //           VUSBWID_0007         //           VUSBWID_180267&/PID_000476.3392d700b&0.08.11#{f18a0e88-c30c-1140-8815-00a0c905be           VUSBWID_1002647         //           VUSBWID_00087         //           VUSBWID_01030&/PID_3411#240A648582CC#{s2838b0e*106-6530-1142-901F-00c04Hb951ed}           VUSBWID_0C458&PID_640D_6MI_00478.34842b4608.00000#(5542777-476-4755-9555)           VUSBWID_0C458&PID_64DD6MI_00478.34842b4608.00000#(55427374-8756-4844-482b40808.0000#(55427374-8756-4845-482b40808.0000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(55427374-8756-4845-482b40808000#(5542734-8756-4845-482b40808000#(5542734-8756-4845-482b40808000#(5542734-8756-4845-482b40808000#(5542734-8756-4845-482b40808000#(5542734-8756-4845-482b40808000#(55428734-8756-4845-482b40808000#(55428734-8756-4845-482b40808000#(55428734-8756-4845-482b40808000#(55428734-8756-4845-482b40808000#(55428734-8756-4845-4845-482b40808000#(55428734-8756-4845-4845-4845-4845-4845-4845-4845-48	SymbolicLink SymbolicLink SymbolicLink SymbolicLink SymbolicLink SymbolicLink	SymLink \Device\0000008 \Device\USPDO-3 \Device\USPDO-3 \Device\USPDO-3 \Device\USPDO-7 \Device\USPDO-7 \Device\USPDO-7 \Device\USPDO-7 \Device\USPDO-7 \Device\USPDO-7 \Device\USPDO-7 \Device\USPDO-6 \Device\USPDO-6 \Device\USPDO-6 \Device\USPDO-5 \Device\USPDO-5 \Device\USPDO-5 \Device\USPDO-5 \Device\USPDO-1 \Device\USPDO-1 \Device\USPDO-1 \Device\USPDO-1 \Device\USPDO-1 \Device\USPDO-1 \Device\USPDO-1 \Device\USPDO-1	

When you run the !object kernel debugger command and specify the \Device directory, you should see output similar to the following:

1: kd> !object \device Object: 8200c530 Type: (8542b188) Directory ObjectHeader: 8200c518 (new version) HandleCount: 0 PointerCount: 231 Directory Object: 82007d20 Name: Device Hash Address Type Name \_\_\_\_\_ \_\_\_\_ \_\_\_\_ 00 d024a448 Device NisDrv SrvNet WUDFLpcDevice 959afc08 Device 958beef0 Device 854c69b8 Device FakeVid1 RdpBus 8befec98 Device 88f7c338 Device Beep Ndis ScsiPort2 KsecDD 00000025 00000019 FakeVid2 Netbios NameResTrk 89d64500 Device 8a24e250 SymbolicLink 89d6c580 Device 89c15810 Device 89c17408 Device 01 854c6898 Device 88f98a70 Device NameResT 00000026 8a48c6a8 Device NameResTrk 89c2fe88 Device FakeVid3 02 854c6778 Device 8548fee0 Device 00000034 Ip 00000027 8a214b78 SymbolicLink 89c31038 Device 03 9c205c40 Device 00000041 854c6658 Device FakeVid4 854dd9d8 Device 00000035 8d143488 Device Video0 8a541030 Device KeyboardClass0 89c323c8 Device 0000028

```
8554fb50 Device

04 958bb040 Device

97ad9fe0 SymbolicLink

854f0090 Device

854c6538 Device

8bf14e98 Device

8bf2fe20 Device

89c332a0 Device

89c05030 Device

89c3a1a8 Device
```

KMDF0 ProcessManagement MailslotRedirector 00000036 FakeVid5 Video1 KeyboardClass1 00000029 VolMgrControl VMBus

. . .

When you enter the !object command and specify an object manager directory object, the kernel debugger dumps the contents of the directory according to the way the object manager organizes it internally. For fast lookups, a directory stores objects in a hash table based on a hash of the object names, so the output shows the objects stored in each bucket of the directory's hash table.

As Figure 6-10 illustrates, a device object points back to its driver object, which is how the I/O manager knows which driver routine to call when it receives an I/O request. It uses the device object to find the driver object representing the driver that services the device. It then indexes into the driver object by using the function code supplied in the original request. Each function code corresponds to a driver entry point (called a *dispatch routine*).

A driver object often has multiple device objects associated with it. When a driver is unloaded from the system, the I/O manager uses the queue of device objects to determine which devices will be affected by the removal of the driver.

#### **EXPERIMENT:** Displaying driver and device objects

You can display driver and device objects with the !drvobj and !devobj kernel debugger commands, respectively. In the following example, the driver object for the keyboard class driver is examined, and one of its device objects viewed:

```
1: kd> !drvobj kbdclass
Driver object (8a557520) is for:
\Driver\kbdclass
Driver Extension List: (id , addr)
Device Object list:
9f509648 8bf2fe20 8a541030
1: kd> !devobj 9f509648
Device object (9f509648) is for:
KeyboardClass2 \Driver\kbdclass DriverObject 8a557520
Current Irp 00000000 RefCount 0 Type 0000000b Flags 00002044
Dacl 82090960 DevExt 9f509700 DevObjExt 9f5097f0
ExtensionFlags (0x0000c00) DOE_SESSION_DEVICE, DOE_DEFAULT_SD_PRESENT
```

Characteristics (0x0000100) FILE\_DEVICE\_SECURE\_OPEN AttachedTo (Lower) 9f509848 \Driver\terminpt Device queue is not busy.

Notice that the !devobj command also shows you the addresses and names of any device objects that the object you're viewing is layered over (the AttachedTo line). It can also show the device objects layered on top of the object specified (the AttachedDevice line), although not in this case.

The !drvobj command can accept an optional argument that indicates more information to show. Here is an example with the most information to show:

```
1: kd> !drvobj kbdclass 7
Driver object (8a557520) is for:
\Driver\kbdclass
Driver Extension List: (id , addr)
Device Object list:
9f509648 8bf2fe20 8a541030
DriverEntry:
               8c30a010
                            kbdclass!GsDriverEntry
DriverStartIo: 0000000
DriverUnload: 0000000
AddDevice:
               8c307250
                            kbdclass!KeyboardAddDevice
Dispatch routines:
[00] IRP_MJ_CREATE
                                         8c301d80
                                                         kbdclass!KeyboardClassCreate
[01] IRP_MJ_CREATE_NAMED_PIPE
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[02] IRP_MJ_CLOSE
                                         8c301c90
                                                         kbdclass!KeyboardClassClose
                                                         kbdclass!KeyboardClassRead
[03] IRP_MJ_READ
                                         8c302150
                                                         nt!IopInvalidDeviceRequest
[04] IRP_MJ_WRITE
                                         81142342
[05] IRP_MJ_QUERY_INFORMATION
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[06] IRP_MJ_SET_INFORMATION
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[07] IRP_MJ_QUERY_EA
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[08] IRP_MJ_SET_EA
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[09] IRP_MJ_FLUSH_BUFFERS
                                                         kbdclass!KeyboardClassFlush
                                         8c303678
[Oa] IRP_MJ_QUERY_VOLUME_INFORMATION
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[0b] IRP_MJ_SET_VOLUME_INFORMATION
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[Oc] IRP_MJ_DIRECTORY_CONTROL
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[Od] IRP_MJ_FILE_SYSTEM_CONTROL
                                         81142342
                                                         nt!IopInvalidDeviceRequest
[Oe] IRP_MJ_DEVICE_CONTROL
                                         8c3076d0
                                                         kbdclass!KeyboardClassDevice
Control
[Of] IRP_MJ_INTERNAL_DEVICE_CONTROL
                                         8c307ff0
                                                         kbdclass!KeyboardClassPass
Through
[10] IRP_MJ_SHUTDOWN
                                         81142342
                                                         nt!IopInvalidDeviceRequest
                                                         nt!IopInvalidDeviceRequest
[11] IRP_MJ_LOCK_CONTROL
                                         81142342
[12] IRP_MJ_CLEANUP
                                        8c302260
                                                         kbdclass!KeyboardClassCleanup
[13] IRP_MJ_CREATE_MAILSLOT
                                         81142342
                                                         nt!IopInvalidDeviceRequest
                                                         nt!IopInvalidDeviceRequest
[14] IRP_MJ_QUERY_SECURITY
                                         81142342
[15] IRP_MJ_SET_SECURITY
                                         81142342
                                                         nt!IopInvalidDeviceRequest
                                                         kbdclass!KeyboardClassPower
[16] IRP_MJ_POWER
                                         8c301440
[17] IRP_MJ_SYSTEM_CONTROL
                                         8c307f40
                                                         kbdclass!KeyboardClassSystem
Control
```

[18] IRP_MJ_DEVICE_CHANGE	81142342	nt!IopInvalidDeviceRequest
<pre>[19] IRP_MJ_QUERY_QUOTA</pre>	81142342	nt!IopInvalidDeviceRequest
[1a] IRP_MJ_SET_QUOTA	81142342	nt!IopInvalidDeviceRequest
[1b] IRP_MJ_PNP	8c301870	kbdclass!KeyboardPnP

The dispatch routines array is clearly shown, and will be discussed in the next section. Note that operations that are not supported by the driver point to an I/O manager's routine IopInvalidDeviceRequest.

The address to the !drvobj command is for a DRIVER\_OBJECT structure, and the address for the !devobj command is for a DEVICE\_OBJECT. You can view these structures directly using the debugger:

1: kd> dt nt!_driver_objec	t 8a557520
+0x000 Type	: On4
+0x002 Size	
	: 0x9f509648 _DEVICE_OBJECT
+0x008 Flags	: 0x412
+0x00c DriverStart	: 0x8c300000 Void
+0x010 DriverSize	: 0xe000
+0x014 DriverSection	: 0x8a556ba8 Void
+0x018 DriverExtension	: 0x8a5575c8 _DRIVER_EXTENSION
	: _UNICODE_STRING "\Driver\kbdclass"
+0x024 HardwareDatabase	: 0x815c2c28 _UNICODE_STRING "\REGISTRY\MACHINE\HARDWARE\
DESCRIPTION\SYSTEM"	
+0x028 FastIoDispatch	: (null)
+0x02c DriverInit	: 0x8c30a010 long +fffffff8c30a010
+0x030 DriverStartIo	: (null)
+0x034 DriverUnload	: (null)
+0x038 MajorFunction	: [28] 0x8c301d80 long +fffffff8c301d80
1: kd> dt nt!_device_objec	
+0x000 Type +0x002 Size	: On3
+0x004 ReferenceCount	
	: 0x8a557520 _DRIVER_OBJECT
	: 0x8bf2fe20 _DEVICE_OBJECT
+0x010 AttachedDevice	
+0x014 CurrentIrp	: (null)
+0x018 Timer +0x01c Flags	: (null)
+0x020 Characteristics	
+0x024 Vpb	: (null)
+0x028 DeviceExtension	: 0x9f509700 Void
+0x02c DeviceType +0x030 StackSize +0x034 Queue	: 0xb
+0x030 StackSize	: 7 ''
+0x05c AlignmentRequire	
+0x060 DeviceQueue	
+0x074 Dpc	
+0x094 ActiveThreadCoun	
+0x098 SecurityDescript	or : 0x82090930 Void
Thora are come interacting	fields in those structures, which we'll discuss in the payt section

There are some interesting fields in these structures, which we'll discuss in the next section.

Using objects to record information about drivers means that the I/O manager doesn't need to know details about individual drivers. The I/O manager merely follows a pointer to locate a driver, thereby providing a layer of portability and allowing new drivers to be loaded easily.

# **Opening devices**

A *file object* is a kernel-mode data structure that represents a handle to a device. File objects clearly fit the criteria for objects in Windows: They are system resources that two or more user-mode processes can share; they can have names; they are protected by object-based security; and they support synchronization. Shared resources in the I/O system, like those in other components of the Windows executive, are manipulated as objects. (See Chapter 8 in Part 2 for more on object management.)

File objects provide a memory-based representation of resources that conform to an I/O-centric interface, in which they can be read from or written to. Table 6-1 lists some of the file object's attributes. For specific field declarations and sizes, see the structure definition for FILE\_OBJECT in wdm.h.

Attribute	Purpose
File name	This identifies the virtual file that the file object refers to, which was passed in to the CreateFile or CreateFile2 APIs.
Current byte offset	This identifies the current location in the file (valid only for synchronous I/O).
Share modes	These indicate whether other callers can open the file for read, write, or delete operations while the current caller is using it.
Open mode flags	These indicate whether I/O will be synchronous or asynchronous, cached or non-cached, sequential or random, and so on.
Pointer to device object	This indicates the type of device the file resides on.
Pointer to the volume parameter block (VPB)	This indicates the volume, or partition, that the file resides on (in the case of file system files).
Pointer to section object pointers	This indicates a root structure that describes a mapped/cached file. This structure also contains the shared cache map, which identifies which parts of the file are cached (or rather, mapped) by the cache manager and where they reside in the cache.
Pointer to private cache map	This is used to store per-handle caching information such as the read patterns for this handle or the page priority for the process. See Chapter 5, "Memory management," for more information on page priority.
List of I/O request packets (IRPs)	If thread-agnostic I/O (described in the section "Thread-agnostic I/O" later in this chapter) is used and the file object is associated with a completion port (described in the section "I/O completion ports"), this is a list of all the I/O operations that are associated with this file object.
I/O completion context	This is context information for the current I/O completion port, if one is active.
File object extension	This stores the I/O priority (explained later in this chapter) for the file and whether share-access checks should be performed on the file object, and contains optional file object extensions that store context-specific information.

TABLE 6-1	File object	attributes
		attibutes

To maintain some level of opacity toward driver code that uses the file object, and to enable extending the file object functionality without enlarging the structure, the file object also contains an extension field, which allows for up to six different kinds of additional attributes, described in Table 6-2.

Extension	Purpose
Transaction parameters	This contains the transaction parameter block, which contains information about a transacted file operation. It's returned by IoGetTransactionParameterBlock.
Device object hint	This identifies the device object of the filter driver with which this file should be associated. It's set with IoCreateFileEx or IoCreateFileSpecifyDeviceObjectHint.
I/O status block range	This allows applications to lock a user-mode buffer into kernel-mode memory to optimize asynchronous I/Os. It's set with SetFileIoOverlappedRange.
Generic	This contains filter driver–specific information, as well as extended create parameters (ECPs) that were added by the caller. It's set with IoCreateFileEx.
Scheduled file I/O	This stores a file's bandwidth reservation information, which is used by the storage system to optimize and guarantee throughput for multimedia applications. (See the section "Bandwidth reservation (scheduled file I/O)" later in this chapter.) It's set with SetFileBandwidthReservation.
Symbolic link	This is added to the file object upon creation, when a mount point or directory junc- tion is traversed (or a filter explicitly reparses the path). It stores the caller-supplied path, including information about any intermediate junctions, so that if a relative symbolic link is hit, it can walk back through the junctions. See Chapter 13 in Part 2 for more information on NTFS symbolic links, mount points, and directory junctions.

 TABLE 6-2
 File object extensions

When a caller opens a file or a simple device, the I/O manager returns a handle to a file object. Before that happens, the driver responsible for the device in question is asked via its Create dispatch routine (IRP\_MJ\_CREATE) whether it's OK to open the device and allow the driver to perform any initialization necessary if the open request is to succeed.

**Note** File objects represent open instances of files, not files themselves. Unlike UNIX systems, which use *vnodes*, Windows does not define the representation of a file; Windows file-system drivers define their own representations.

Similar to executive objects, files are protected by a security descriptor that contains an access control list (ACL). The I/O manager consults the security subsystem to determine whether a file's ACL allows the process to access the file in the way its thread is requesting. If it does, the object manager grants the access and associates the granted access rights with the file handle that it returns. If this thread or another thread in the process needs to perform additional operations not specified in the original request, the thread must open the same file again with a different request (or duplicate the handle with the requested access) to get another handle, which prompts another security check. (See Chapter 7 for more information about object protection.)

#### **EXPERIMENT: Viewing device handles**

Any process that has an open handle to a device will have a file object in its handle table corresponding to the open instance. You can view these handles with Process Explorer by selecting a process and checking **Handles** in the **Lower Pane View** submenu of the **View** menu. Sort by the **Type** column and scroll to where you see the handles that represent file objects, which are labeled as *File*.

File Options V	iew Process Fin	d Han	dle Users H	elp							
	E) 🛄 🚳 🔤	× M	🐵 🛛 📐	×.				1 m	1		
Process		CPU	Private Bytes	Working Set	PID	Description	Company	Name			
	ENT.EXE		17,224 K	26,628 K	7092	Microsoft Office Document C.	Microsoft	Corporation			
CSISS.exe		< 0.01	1,416 K	3,876 K	608	Client Server Runtime Proces	s Microsoft	Corporation			
csrss.exe		0.03	2,152 K	6,992 K	712	Client Server Runtime Proces	s Microsoft	Corporation			
dlhost.exe			4,664 K	10,780 K	1144	COM Surrogate	Microsoft	Corporation			
dwm.exe		0.13	111,712 K	151,956 K	452	Desktop Window Manager	Microsoft	Corporation			
explorer.exe		0.07	36,528 K	82,624 K	4272	Windows Explorer	Microsoft (	Corporation			
			E4.000.1/	03.000 K	5400	Wheedering Produces	18A.	Company New York			
Handle	Туре	Name						Object	Address	Decoded Acc	ess
0x64	Directory	\Sessions	\1\BaseNamed	biects				0xFFFFE688F0	842AC0	QUERYITRA	VERSEI
0x1A0	Event	\KemelOt	jects\MaximumC	ommitCondition				0xFFFFC404B	89EF60	SYNCHRONIZ	'E
0x1C0	Event	\Sessions	1\BaseNamed	bjects\DwmCor	nposed	Event_1		0xFFFFC404B	5274080	MODIFY_STAT	TE
0x1C4	Event	Sessions	\1\BaseNamedO	bjects\DwmCor	nposed	Event 1		0xFFFFC404B	5274080	SYNCHRONIZ	'E
0x440	Event	\Sessions	\1\BaseNamedO	bjects\DWM_E	X_FUL	LSCREEN_TRANSITION_EV	/ENT	0xFFFFC404B6	534DD0	READ_CONTF	ROLIDE
0x34	File	C:\Windo	ws\System32	-	-			0xFFFFC404B6	305B00	SYNCHRONIZ	E   EXEC
0xA8	File	\Device\	CNG					0xFFFFC404B6	1ABD80	SYNCHRONIZ	E   READ
0x320	File	\Device\	DeviceApi					0xFFFFC404B	5407320	READ_CONTF	ROLISYN
0x348	File	\Device\	KsecDD					0xFFFFC404B6	406EF0	SYNCHRONIZ	EIWRIT
0x394	File	\Device\	DeviceApi					0xFFFFC404B	6411250	READ_CONTF	ROLISYN
0x398	File	\Device\	DeviceApi					0xFFFFC404B6	413EF0	READ_CONTR	ROLISYN
0x39C			DeviceApi					0xFFFFC404B		READ_CONTR	
0x420	File	C:\Windo	ws\System32\en	-US\d2d1.dll.mu	ui 👘			0xFFFFC404B6	471EF0	READ_CONTR	ROLISYN
			ws\Fonts\Static(					0xFFFFC404B6		READ_CONTF	
			STEM\ControlS					0xFFFFE688FE		QUERY_VALU	
0x80	Kev	HKI M\SY	(STEM\ControlSe	+t001\Control\N	Is\Sortir	no/Versions		0xFFFFF688FF	231AF0	READ CONTE	ROLLKEY

In this example, the Desktop Windows Manager (dwm.exe) process has a handle open to a device created by the kernel security device driver (Ksecdd.sys). You can look at the specific file object in the kernel debugger by first identifying the address of the object. The following command reports information on the highlighted handle (handle value 0x348) in the preceding screenshot, which is in the Dwm.exe process that has a process ID of 452 decimal:

```
1kd> !handle 348 f 0n452
```

```
PROCESS ffffc404b62fb780
```

SessionId: 1 Cid: 01c4 Peb: b4c3db0000 ParentCid: 0364 DirBase: 7e607000 ObjectTable: ffffe688fd1c38c0 HandleCount: <Data Not Accessible> Image: dwm.exe

Handle Error reading handle count.

```
0348: Object: ffffc404b6406ef0 GrantedAccess: 00100003 (Audit) Entry: ffffe688fd396d20
Object: ffffc404b6406ef0 Type: (ffffc404b189bf20) File
ObjectHeader: ffffc404b6406ec0 (new version)
HandleCount: 1 PointerCount: 32767
```

Because the object is a file object, you can get information about it with the ! fileobj command (notice it's also the same object address shown in Process Explorer):

lkd> !fileobj ffffc404b6406ef0

Device Object: 0xffffc404b2fa7230 \Driver\KSecDD Vpb is NULL Event signalled Flags: 0x40002 Synchronous IO Handle Created CurrentByteOffset: 0 Because a file object is a memory-based representation of a shareable resource and not the resource itself, it's different from other executive objects. A file object contains only data that is unique to an object handle, whereas the file itself contains the data or text to be shared. Each time a thread opens a file, a new file object is created with a new set of handle-specific attributes. For example, for files opened synchronously, the current byte offset attribute refers to the location in the file at which the next read or write operation using that handle will occur. Each handle to a file has a private byte offset even though the underlying file is shared. A file object is also unique to a process—except when a process duplicates a file handle to another process (by using the Windows DuplicateHandle function) or when a child process inherits a file handle from a parent process. In these situations, the two processes have separate handles that refer to the same file object.

Although a file handle is unique to a process, the underlying physical resource is not. Therefore, as with any shared resource, threads must synchronize their access to shareable resources such as files, file directories, and devices. If a thread is writing to a file, for example, it should specify exclusive write access when opening the file to prevent other threads from writing to the file at the same time. Alternatively, by using the Windows LockFile function, the thread could lock a portion of the file while writing to it when exclusive access is required.

When a file is opened, the file name includes the name of the device object on which the file resides. For example, the name \Device\HarddiskVolume1\Myfile.dat may refer to the file Myfile.dat on the C: volume. The substring \Device\HarddiskVolume1 is the name of the internal Windows device object representing that volume. When opening Myfile.dat, the I/O manager creates a file object and stores a pointer to the HarddiskVolume1 device object in the file object and then returns a file handle to the caller. Thereafter, when the caller uses the file handle, the I/O manager can find the HarddiskVolume1 device object directly.

Keep in mind that internal Windows device names can't be used in Windows applications—instead, the device name must appear in a special directory in the object manager's namespace, which is \GLOBAL??. This directory contains symbolic links to the real, internal Windows device names. As was described earlier, device drivers are responsible for creating links in this directory so that their devices will be accessible to Windows applications. You can examine or even change these links programmatically with the Windows QueryDosDevice and DefineDosDevice functions.

# I/O processing

Now that we've covered the structure and types of drivers and the data structures that support them, let's look at how I/O requests flow through the system. I/O requests pass through several predictable stages of processing. The stages vary depending on whether the request is destined for a device operated by a single-layered driver or for a device reached through a multilayered driver. Processing varies further depending on whether the caller specified synchronous or asynchronous I/O, so we'll begin our discussion of I/O types with these two and then move on to others.

# Types of I/O

Applications have several options for the I/O requests they issue. Furthermore, the I/O manager gives drivers the choice of implementing a shortcut I/O interface that can often mitigate IRP allocation for I/O processing. In this section, we'll explain these options for I/O requests.

## Synchronous and asynchronous I/O

Most I/O operations issued by applications are *synchronous* (which is the default). That is, the application thread waits while the device performs the data operation and returns a status code when the I/O is complete. The program can then continue and access the transferred data immediately. When used in their simplest form, the Windows ReadFile and WriteFile functions are executed synchronously. They complete the I/O operation before returning control to the caller.

Asynchronous I/O allows an application to issue multiple I/O requests and continue executing while the device performs the I/O operation. This type of I/O can improve an application's throughput because it allows the application thread to continue with other work while an I/O operation is in progress. To use asynchronous I/O, you must specify the FILE\_FLAG\_OVERLAPPED flag when you call the Windows CreateFile or CreateFile2 functions. Of course, after issuing an asynchronous I/O operation, the thread must be careful not to access any data from the I/O operation until the device driver has finished the data operation. The thread must synchronize its execution with the completion of the I/O request by monitoring a handle of a synchronization object (whether that's an event object, an I/O completion port, or the file object itself) that will be signaled when the I/O is complete.

Regardless of the type of I/O request, I/O operations issued to a driver on behalf of the application are performed asynchronously. That is, once an I/O request has been initiated, the device driver must return to the I/O system as soon as possible. Whether or not the I/O system returns immediately to the caller depends on whether the handle was opened for synchronous or asynchronous I/O. Figure 6-3 illustrates the flow of control when a read operation is initiated. Notice that if a wait is done, which depends on the overlapped flag in the file object, it is done in kernel mode by the NtReadFile function.

You can test the status of a pending asynchronous I/O operation with the Windows HasOverlapped-IoCompleted macro or get more details with the GetOverlappedResult(Ex) functions. If you're using I/O completion ports (described in the "I/O completion ports" section later in this chapter), you can use the GetQueuedCompletionStatus(Ex) function(s).

## Fast I/O

Fast I/O is a special mechanism that allows the I/O system to bypass the generation of an IRP and instead go directly to the driver stack to complete an I/O request. This mechanism is used for optimizing certain I/O paths, which are somewhat slower when using IRPs. (Fast I/O is described in detail in Chapter 13 and Chapter 14 in Part 2.) A driver registers its fast I/O entry points by entering them in a structure pointed to by the PFAST\_I0\_DISPATCH pointer in its driver object.

### EXPERIMENT: Looking at a driver's registered fast I/O routines

The !drvobj kernel debugger command can list the fast I/O routines that a driver registers in its driver object. Typically, however, only file-system drivers have any use for fast I/O routines— although there are exceptions, such as network protocol drivers and bus filter drivers. The following output shows the fast I/O table for the NTFS file-system driver object:

Dispatch routines:  Fast I/O routines: FastIoCheckIfPossible ffff80e565d6750 NTFS!NtfsFastIoCheckIfPossible FastIoRead ffff80e56526430 NTFS!NtfsCopyReadA FastIoWrite ffff80e5652310 NTFS!NtfsCopyWriteA FastIoQueryBasicInfo ffff80e56523140 NTFS!NtfsFastQueryBasicInfo FastIoQueryStandardInfo ffff80e56534d20 NTFS!NtfsFastQueryStdInfo FastIoLock ffff80e5651e610 NTFS!NtfsFastLock
FastIoCheckIfPossibleffff80e565d6750NTFS!NtfsFastIoCheckIfPossibleNTFS!NtfsCopyReadAFastIoReadfffff80e56523310NTFS!NtfsCopyReadAFastIoWritefffff80e56523310NTFS!NtfsCopyWriteAFastIoQueryBasicInfoffff80e56523140NTFS!NtfsFastQueryBasicInfoFastIoQueryStandardInfoffff80e56534d20NTFS!NtfsFastQueryStdInfoFastIoLockffff80e5651e610NTFS!NtfsFastLock
FastIoWriteffff80e56523310NTFS!NtfsCopyWriteAFastIoQueryBasicInfofffff80e56523140NTFS!NtfsFastQueryBasicInfofffff80e56534d20FastIoQueryStandardInfofffff80e56534d20FastIoLockfffff80e5651e610
FastIoWriteffff80e56523310NTFS!NtfsCopyWriteAFastIoQueryBasicInfofffff80e56523140NTFS!NtfsFastQueryBasicInfofffff80e56534d20FastIoQueryStandardInfofffff80e56534d20FastIoLockfffff80e5651e610
FastIoQueryBasicInfoffff80e56523140NTFS!NtfsFastQueryBasicInfoFastIoQueryStandardInfoffff80e56534d20FastIoLockfffff80e5651e610NTFS!NtfsFastLock
NTFS!NtfsFastQueryBasicInfoNTFS!NtfsFastQueryStdInfoFastIoQueryStandardInfoffff80e56534d20NTFS!NtfsFastQueryStdInfoFastIoLockfffff80e5651e610NTFS!NtfsFastLock
FastIoQueryStandardInfoffff80e56534d20NTFS!NtfsFastQueryStdInfoFastIoLockffff80e5651e610NTFS!NtfsFastLock
FastIoLock fffff80e5651e610 NTFS!NtfsFastLock
FastIoUnlockSingle fffff80e5651e3c0 NTFS!NtfsFastUnlockSingle
FastIoUnlockAll ffff80e565d59e0 NTFS!NtfsFastUnlockAll
FastIoUnlockAllByKey fffff80e565d5c50
NTFS!NtfsFastUnlockAllByKey
ReleaseFileForNtCreateSection fffff80e5644fd90 NTFS!NtfsReleaseForCreate
Section
FastIoQueryNetworkOpenInfofffff80e56537750NTFS!NtfsFastQueryNetworkOpenInfo
AcquireForModWrite fffff80e5643e0c0
NTFS!NtfsAcquireFileForModWrite
MdlRead ffff80e5651e950 NTFS!NtfsMdlReadA
MdlReadComplete ffff802dc6cd844
nt!FsRtlMdlReadCompleteDev
PrepareMdlWrite fffff80e56541a10 NTFS!NtfsPrepareMdlWriteA
MdlWriteComplete ffff802dcb76e48
nt!FsRtlMdlWriteCompleteDev
FastIoQueryOpen fffff80e5653a520
NTFS!NtfsNetworkOpenCreate
ReleaseForModWrite fffff80e5643e2c0
NTFS!NtfsReleaseFileForModWrite
AcquireForCcFlush ffff80e5644ca60
NTFS!NtfsAcquireFileForCcFlush
ReleaseForCcFlush fffff80e56450cf0 NTFS!NtfsReleaseFileForCcFlush

The output shows that NTFS has registered its NtfsCopyReadA routine as the fast I/O table's FastIoRead entry. As the name of this fast I/O entry implies, the I/O manager calls this function when issuing a read I/O request if the file is cached. If the call doesn't succeed, the standard IRP path is selected.

## Mapped-file I/O and file caching

Mapped-file I/O is an important feature of the I/O system—one that the I/O system and the memory manager produce jointly. (See Chapter 5 for details on how mapped files are implemented.) *Mapped-file I/O* refers to the ability to view a file residing on disk as part of a process's virtual memory. A program can access the file as a large array without buffering data or performing disk I/O. The program accesses memory, and the memory manager uses its paging mechanism to load the correct page from the disk file. If the application writes to its virtual address space, the memory manager writes the changes back to the file as part of normal paging.

Mapped-file I/O is available in user mode through the Windows CreateFileMapping, MapViewOf-File, and related functions. Within the operating system, mapped-file I/O is used for important operations such as file caching and image activation (loading and running executable programs). The other major consumer of mapped-file I/O is the cache manager. File systems use the cache manager to map file data in virtual memory to provide better response time for I/O-bound programs. As the caller uses the file, the memory manager brings accessed pages into memory. Whereas most caching systems allocate a fixed number of bytes for caching files in memory, the Windows cache grows or shrinks depending on how much memory is available. This size variability is possible because the cache manager relies on the memory manager to automatically expand (or shrink) the size of the cache using the normal working set mechanisms explained in Chapter 5—in this case applied to the system working set. By taking advantage of the memory manager's paging system, the cache manager avoids duplicating the work that the memory manager already performs. (The workings of the cache manager are explained in detail in Chapter 14 in Part 2.)

## Scatter/gather I/O

Windows supports a special kind of high-performance I/O called *scatter/gather*, available via the Windows ReadFileScatter and WriteFileGather functions. These functions allow an application to issue a single read or write from more than one buffer in virtual memory to a contiguous area of a file on disk instead of issuing a separate I/O request for each buffer. To use scatter/gather I/O, the file must be opened for non-cached I/O, the user buffers being used must be page-aligned, and the I/Os must be asynchronous (overlapped). Furthermore, if the I/O is directed at a mass storage device, the I/O must be aligned on a device sector boundary and have a length that is a multiple of the sector size.

# I/O request packets

An I/O request packet (IRP) is where the I/O system stores information it needs to process an I/O request. When a thread calls an I/O API, the I/O manager constructs an IRP to represent the operation as it progresses through the I/O system. If possible, the I/O manager allocates IRPs from one of three per-processor IRP non-paged look-aside lists:

- The small-IRP look-aside list This stores IRPs with one stack location. (IRP stack locations are described shortly.)
- The medium-IRP look-aside list This contains IRPs with four stack locations (which can also be used for IRPs that require only two or three stack locations).
- The large-IRP look-aside list This contains IRPs with more than four stack locations. By default, the system stores IRPs with 14 stack locations on the large-IRP look-aside list, but once per minute, the system adjusts the number of stack locations allocated and can increase it up to a maximum of 20, based on how many stack locations have been recently required.

These lists are also backed by global look-aside lists as well, allowing efficient cross-CPU IRP flow. If an IRP requires more stack locations than are contained in the IRPs on the large-IRP look-aside list, the I/O manager allocates IRPs from non-paged pool. The I/O manager allocates IRPs with the IoA11ocate-Irp function, which is also available for device-driver developers, because in some cases a driver may want to initiate an I/O request directly by creating and initializing its own IRPs. After allocating and initializing an IRP, the I/O manager stores a pointer to the caller's file object in the IRP.

**Note** If defined, the DWORD registry value LargeIrpStackLocations in the HKLM\ System\CurrentControlSet\Session Manager\I/O System key specifies how many stack locations are contained in IRPs stored on the large-IRP look-aside list. Similarly, the MediumIrpStackLocations value in the same key can be used to change the size of IRP stack locations on the medium-IRP look-aside list.

Figure 6-11 shows some of the important members of the IRP structure. It is always accompanied by one or more IO\_STACK\_LOCATION objects (described in the next section).




FIGURE 6-11 Important members of the IRP structure.

Here is a quick rundown of the members:

- IoStatus This is the status of the IRP, consisting of two members; Status, which is the actual code itself and Information, a polymorphic value that has meaning in some cases. For example, for a read or write operation, this value (set by the driver) indicates the number of bytes read or written. This same value is the one reported as an output value from the functions ReadFile and WriteFile.
- MdIAddress This is an optional pointer to a memory descriptor list (MDL). An MDL is a structure that represents information for a buffer in physical memory. We'll discuss its main usage in device drivers in the next section. If an MDL was not requested, the value is NULL.
- I/O stack locations count and current stack location These store the total number of trailing I/O stack location objects and point to the current one that this driver layer should look at, respectively. The next section discusses I/O stack locations in detail.
- **User buffer** This is the pointer to the buffer provided by the client that initiated the I/O operation. For example, it is the buffer provided to the ReadFile or WriteFile functions.
- User event This is the kernel event object that was used with an overlapped (asynchronous)
   I/O operation (if any). An event is one way to be notified when the I/O operation completes.
- **Cancel routine** This is the function to be called by the I/O manager in case the IRP is cancelled.
- AssociatedIrp This is a union of one of three fields. The SystemBuffer member is used in case the I/O manager used the buffered I/O technique for passing the user's buffer to the driver. The next section discusses buffered I/O, as well as other options for passing user mode buffers to drivers. The MasterIrp member provides a way to create a "master IRP" that splits its work into sub-IRPs, where the master is considered complete only when all its sub-IRPs have completed.

## I/O stack locations

An IRP is always followed by one or more I/O stack locations. The number of stack locations is equal to the number of layered devices in the device node the IRP is destined for. The I/O operation information is split between the IRP body (the main structure) and the current I/O stack location, where *current* means the one set up for the particular layer of devices. Figure 6-12 shows the important fields of an I/O stack location. When an IRP is created, the number of requested I/O stack locations is passed to IoAllocateIrp. The I/O manager then initializes the IRP body and the first I/O stack location only, destined for the topmost device in the device node. Each layer in the device node is responsible for initializing the next I/O stack location if it decides to pass the IRP down to the next device.

Here is a rundown of the members shown in Figure 6-12:

Major function This is the primary code that indicates the type of request (read, write, create, Plug and Play, and so on), also known as dispatch routine code. It's one of 28 constants (0 to 27) starting with IRP\_MJ\_ in wdm.h. This index is used by the I/O manager into the MajorFunction array of function pointers in the driver object to jump to the appropriate routine within a driver.

Most drivers specify dispatch routines to handle only a subset of possible major function codes, including create (open), read, write, device I/O control, power, Plug and Play, system control (for WMI commands), cleanup, and close. File-system drivers are an example of a driver type that often fills in most or all of its dispatch entry points with functions. In contrast, a driver for a simple USB device would probably fill in only the routines needed for open, close, read, write, and sending I/O control codes. The I/O manager sets any dispatch entry points that a driver doesn't fill to point to its own IopInvalidDeviceRequest, which completes the IRP with an error status indicating that the major function specified in the IRP is invalid for that device.

- Minor function This is used to augment the major function code for some functions. For example, IRP\_MJ\_READ (read) and IRP\_MJ\_WRITE (write) have no minor functions. But Plug and Play and Power IRPs always have a minor IRP code that specializes the general major code. For example, the Plug and Play IRP\_MJ\_PNP major code is too generic; the exact instruction is given by the minor IRP, such as IRP\_MN\_START\_DEVICE, IRP\_MN\_REMOVE\_DEVICE, and so on.
- Parameters This is a monstrous union of structures, each of which valid for a particular major function code or a combination of major/minor codes. For example, for a read operation (IRP\_MJ\_READ), the Parameters.Read structure holds information on the read request, such as the buffer size.
- File object and Device object These point to the associated FILE\_OBJECT and DEVICE\_ OBJECT for this I/O request.
- Completion routine This is an optional function that a driver can register with the IoSetCompletionRoutine(Ex) DDI, to be called when the IRP is completed by a lower layer driver. At that point, the driver can look at the completion status of the IRP and do any needed post-processing. It can even undo the completion (by returning the special value STATUS\_MORE\_ PROCESSING\_REQUIRED from the function) and resend the IRP (perhaps with modified parameters) to the device node—or even a different device node—again.
- Context This is an arbitrary value set with the IoSetCompletionRoutine(Ex) call that is
  passed, as is, to the completion routine.




FIGURE 6-12 Important members of the IO\_STACK\_LOCATION structure.

The split of information between the IRP body and its I/O stack location allows for the changing of I/O stack location parameters for the next device in the device stack, while keeping the original request parameters. For example, a read IRP targeted at a USB device is often changed by the function driver to a device I/O control IRP where the input buffer argument of the device control points to a USB request packet (URB) that is understood by the lower-layer USB bus driver. Also, note that completion routines can be registered by any layer (except the bottom-most one), each having its own place in an I/O stack location (the completion routine is stored in the *next* lower I/O stack location).

#### **EXPERIMENT:** Looking at driver dispatch routines

You can obtain a list of the functions a driver has defined for its dispatch routines by using bit 1 (value of 2) with the !drvobj kernel debugger command. The following output shows the major function codes supported by the NTFS driver. (This is the same experiment as with fast I/O.)

```
lkd> !drvobj \filesystem\ntfs 2
Driver object (ffffc404b2fbf810) is for:
\FileSystem\NTFS
DriverEntry: fffff80e5663a030
                                                         NTFS!GsDriverEntry
DriverStartIo: 0000000
DriverUnload: 00000000
AddDevice:
              00000000
Dispatch routines:
[00] IRP_MJ_CREATE
                                     fffff80e565278e0
                                                         NTFS!NtfsFsdCreate
[01] IRP_MJ_CREATE_NAMED_PIPE
                                     fffff802dc762c80
                                                         nt!IopInvalidDeviceRequest
                                                         NTFS!NtfsFsdClose
[02] IRP_MJ_CLOSE
                                     fffff80e565258c0
[03] IRP_MJ_READ
                                     fffff80e56436060
                                                         NTFS!NtfsFsdRead
[04] IRP_MJ_WRITE
                                     fffff80e564461d0
                                                         NTFS!NtfsFsdWrite
[05] IRP_MJ_QUERY_INFORMATION
                                     fffff80e565275f0
                                                         NTFS!NtfsFsdDispatchWait
[06] IRP_MJ_SET_INFORMATION
                                     fffff80e564edb80
                                                         NTFS!NtfsFsdSetInformation
[07] IRP_MJ_QUERY_EA
                                     fffff80e565275f0
                                                         NTFS!NtfsFsdDispatchWait
                                                         NTFS!NtfsFsdDispatchWait
[08] IRP_MJ_SET_EA
                                     fffff80e565275f0
[09] IRP_MJ_FLUSH_BUFFERS
                                     fffff80e5653c9a0
                                                         NTFS!NtfsFsdFlushBuffers
[Oa] IRP_MJ_QUERY_VOLUME_INFORMATION fffff80e56538d10
                                                         NTFS!NtfsFsdDispatch
[Ob] IRP_MJ_SET_VOLUME_INFORMATION
                                                         NTFS!NtfsFsdDispatch
                                     fffff80e56538d10
[Oc] IRP_MJ_DIRECTORY_CONTROL
                                     fffff80e564d7080
NTFS!NtfsFsdDirectoryControl
[Od] IRP_MJ_FILE_SYSTEM_CONTROL
                                     fffff80e56524b20
NTFS!NtfsFsdFileSystemControl
[Oe] IRP_MJ_DEVICE_CONTROL
                                     fffff80e564f9de0
                                                         NTFS!NtfsFsdDeviceControl
                                     fffff802dc762c80
[Of] IRP_MJ_INTERNAL_DEVICE_CONTROL
                                                         nt!IopInvalidDeviceRequest
                                                         NTFS!NtfsFsdShutdown
[10] IRP_MJ_SHUTDOWN
                                     fffff80e565efb50
[11] IRP_MJ_LOCK_CONTROL
                                     fffff80e5646c870
                                                         NTFS!NtfsFsdLockControl
                                                         NTFS!NtfsFsdCleanup
[12] IRP_MJ_CLEANUP
                                     fffff80e56525580
[13] IRP_MJ_CREATE_MAILSLOT
                                     fffff802dc762c80
                                                         nt!IopInvalidDeviceRequest
[14] IRP_MJ_QUERY_SECURITY
                                     fffff80e56538d10
                                                         NTFS!NtfsFsdDispatch
[15] IRP_MJ_SET_SECURITY
                                       fffff80e56538d10 NTFS!NtfsFsdDispatch
[16] IRP_MJ_POWER
                                       fffff802dc762c80 nt!IopInvalidDeviceRequest
                                       fffff802dc762c80 nt!IopInvalidDeviceRequest
[17] IRP_MJ_SYSTEM_CONTROL
[18] IRP_MJ_DEVICE_CHANGE
                                       fffff802dc762c80 nt!IopInvalidDeviceRequest
```

```
[19] IRP_MJ_QUERY_QUOTA
[1a] IRP_MJ_SET_QUOTA
[1b] IRP_MJ_PNP
Fast I/O routines:
. . .
```

fffff80e56566230 NTFS!NtfsFsdPnp

fffff80e565275f0 NTFS!NtfsFsdDispatchWait fffff80e565275f0 NTFS!NtfsFsdDispatchWait

While active, each IRP is usually queued in an IRP list associated with the thread that requested the I/O. (Otherwise, it is stored in the file object when performing thread-agnostic I/O, which is described in the "Thread agnostic I/O" section, later in this chapter.) This allows the I/O system to find and cancel any outstanding IRPs if a thread terminates with I/O requests that have not been completed. Additionally, paging I/O IRPs are also associated with the faulting thread (although they are not cancellable). This allows Windows to use the thread-agnostic I/O optimization—when an asynchronous procedure call (APC) is not used to complete I/O if the current thread is the initiating thread. This means page faults occur inline instead of requiring APC delivery.

### EXPERIMENT: Looking at a thread's outstanding IRPs

The ! thread command prints any IRPs associated with the thread. The ! process command does this as well, if requested. Run the kernel debugger with local or live debugging and list the threads of an explorer process:

```
lkd> !process 0 7 explorer.exe
PROCESS ffffc404b673c780
   SessionId: 1 Cid: 10b0 Peb: 00cbb000 ParentCid: 1038
   DirBase: 8895f000 ObjectTable: ffffe689011b71c0 HandleCount: <Data Not
Accessible>
   Image: explorer.exe
   VadRoot ffffc404b672b980 Vads 569 Clone 0 Private 7260. Modified 366527. Locked 784.
   DeviceMap ffffe688fd7a5d30
   Token
                                     ffffe68900024920
   ElapsedTime
                                    18:48:28.375
   UserTime
                                     00:00:17.500
   KernelTime
                                   00:00:13.484
   . . .
   MemoryPriority
                                   BACKGROUND
   BasePriority
                                    8
   CommitCharge
                                    10789
   Job
                                     ffffc404b6075060
       THREAD ffffc404b673a080 Cid 10b0.10b4 Teb: 000000000cbc000 Win32Thread:
ffffc404b66e7090 WAIT: (WrUserRequest) UserMode Non-Alertable
           ffffc404b6760740 SynchronizationEvent
       Not impersonating
. . .
       THREAD ffffc404b613c7c0 Cid 153c.15a8 Teb: 000000006a3000 Win32Thread:
```


```
ffffc404b58d0d60 SynchronizationEvent
ffffc404b566f310 SynchronizationEvent
IRP List:
ffffc404b69ad920: (0006,02c8) Flags: 00060800 Mdl: 00000000
```

You should see many threads, with most of them having IRPs reported in the IRP List section of the thread information (note that the debugger will show only the first 17 IRPs for a thread that has more than 17 outstanding I/O requests). Choose an IRP and examine it with the ! i rp command:

The IRP has two stack locations and is targeted at a device owned by the Named Pipe File System (NPFS) driver. (NPFS is described in Chapter 10, "Networking," in Part 2.)

### **IRP flow**

IRPs are typically created by the I/O manager, and then sent to the first device on the target device node. Figure 6-13 shows a typical IRP flow for hardware-based device drivers.



The I/O manager is not the only entity that creates IRPs. The Plug and Play manager and the Power manager are also responsible for creating IRPs with major function code IRP\_MJ\_PNP and IRP\_MJ\_ POWER, respectively.

Figure 6-13 shows an example device node with six layered device objects: two upper filters, the FDO, two lower filters, and the PDO. This means an IRP targeted at this devnode is created with six I/O stack locations—one for each layer. An IRP is always delivered to the highest layered device, even if a handle was opened to a named device that is lower in the device stack.

A driver that receives an IRP can do one of the following:

- It can complete the IRP then and there by calling IoCompleteRequest. This could be because the IRP has some invalid parameters (for example, insufficient buffer size or bad I/O control code), or because the operation requested is quick and can be accomplished immediately, such as getting some status from the device or reading a value from the registry. The driver calls IoGetCurrentIrpStackLocation to get a pointer to the stack location that it should refer to.
- The driver can forward the IRP to the next layer after optionally doing some processing. For example, an upper filter can do some logging of the operation and send the IRP down to be executed normally. Before sending the request down, the driver must prepare the next I/O stack location that would be looked at by the next driver in line. It can use the IoSkipCurrentIrp-StackLocation macro if it does not wish to make changes, or it can make a copy with IoCopy-IrpStackLocationToNext and make changes to the copied stack location by getting a pointer with IoGetNextIrpStackLocation and making appropriate changes. Once the next I/O stack location is prepared, the driver calls IoCallDriver to do the actual IRP forwarding.
- As an extension of the previous point, the driver can also register for a completion routine by calling IoSetCompletionRoutine(Ex) before passing down the IRP. Any layer except the bottom-most one can register a completion routine (there is no point in registering for the bottom-most layer since that driver must complete the IRP, so no callback is needed). After IoCompleteRequest is called by a lower-layer driver, the IRP travels up (refer to Figure 6-13), calling any completion routines on the way up in reverse order of registration. In fact, the IRP originator (I/O manager, PnP manager, or power manager) use this mechanism to do any post-IRP processing and finally free the IRP.

**Note** Because the number of devices on a given stack is known in advance, the I/O manager allocates one stack location per device driver on the stack. However, there are situations in which an IRP might be directed into a new driver stack. This can happen in scenarios involving the filter manager, which allows one filter to redirect an IRP to another filter (for example, going from a local file system to a network file system). The I/O manager exposes an API, IoAdjustStackSizeForRedirection, that enables this functionality by adding the required stack locations because of devices present on the redirected stack.

### **EXPERIMENT:** Viewing a device stack

The !devstack kernel debugger command shows you the device stack of layered device objects associated with a specified device object. This example shows the device stack associated with a device object, \device\keyboardclass0, which is owned by the keyboard class driver:

```
1kd> !devstack keyboardclass0
 !DevObj !DrvObj !DevExt ObjectName
> ffff9c80c0424440 \Driver\kbdclass ffff9c80c0424590 KeyboardClass0
 ffff9c80c04247c0 \Driver\kbdhid ffff9c80c0424910
 ffff9c80c0414060 \Driver\mshidkmdf ffff9c80c04141b0 000003f
!DevNode ffff9c80c0414d30 :
 DeviceInst is "HID\MSHW0029&Col01\5&1599b1c7&0&0000"
 ServiceName is "kbdhid"
```

The output highlights the entry associated with KeyboardClass0 with the > character in the first column. The entries above that line are drivers layered above the keyboard class driver, and those below are layered beneath it.

### **EXPERIMENT: Examining IRPs**

In this experiment, you'll find an uncompleted IRP on the system, and will determine the IRP type, the device at which it's directed, the driver that manages the device, the thread that issued the IRP, and what process the thread belongs to. This experiment is best performed on a 32-bit system with non-local kernel debugging. It will work with local kernel debugging as well, but IRPs may complete during the period between when commands are issued, so some instability of data should be expected.

At any point in time, there are at least a few uncompleted IRPs on a system. This occurs because there are many devices to which applications can issue IRPs that a driver will complete only when a particular event occurs, such as data becoming available. One example is a blocking read from a network endpoint. You can see the outstanding IRPs on a system with the !irpfind kernel debugger command (this may take some time; you can stop after some IRPs appear):

```
kd> !irpfind
Scanning large pool allocation table for tag 0x3f707249 (Irp?) (a5000000 : a5200000)
Irp [ Thread ] irpStack: (Mj,Mn) DevObj [Driver] MDL Process
9515ad68 [aa0c04c0] irpStack: (e, 5) 8bcb2ca0 [ \Driver\AFD] 0xaala3540
8bd5c548 [91deeb80] irpStack: (e,20) 8bcb2ca0 [ \Driver\AFD] 0x91da5c40
Searching nonpaged pool (80000000 : ffc00000) for tag 0x3f707249 (Irp?)
86264a20 [86262040] irpStack: (e, 0) 8a7b4ef0 [ \Driver\vmbus]
86278720 [91d96b80] irpStack: (e,20) 8bcb2ca0 [ \Driver\AFD] 0x86270040
86279e48 [91d96b80] irpStack: (e,20) 8bcb2ca0 [ \Driver\AFD] 0x86270040
862a1868 [862978c0] irpStack: (d, 0) 8bca4030 [ \FileSystem\Npfs]
```

```
862a24c0 [86297040] irpStack: (d, 0) 8bca4030 [ \FileSystem\Npfs]
862c3218 [9c25f740] irpStack: ( c, 2) 8b127018 [ \FileSystem\NTFS]
862c4988 [a14bf800] irpStack: ( e, 5) 8bcb2ca0 [ \Driver\AFD] 0xaa1a3540
862c57d8 [a8ef84c0] irpStack: ( d, 0) 8b127018 [ \FileSystem\NTFS] 0xa8e6f040
862c91c0 [99ac9040] irpStack: (3, 0) 8a7ace48 [ \Driver\vmbus] 0x9517ac40
862d2d98 [9fd456c0] irpStack: ( e, 5) 8bcb2ca0 [ \Driver\AFD] 0x9fc11780
862d6528 [9aded800] irpStack: ( c, 2) 8b127018 [ \FileSystem\NTFS]
862e3230 [00000000] Irp is complete (CurrentLocation 2 > StackCount 1)
862ec248 [862e2040] irpStack: ( d, 0) 8bca4030 [ \FileSystem\Npfs]
862f7d70 [91dd0800] irpStack: ( d, 0) 8bca4030 [ \FileSystem\Npfs]
863011f8 [00000000] Irp is complete (CurrentLocation 2 > StackCount 1)
86327008 [00000000] Irp is complete (CurrentLocation 43 > StackCount 42)
86328008 [00000000] Irp is complete (CurrentLocation 43 > StackCount 42)
86328960 [00000000] Irp is complete (CurrentLocation 43 > StackCount 42)
86329008 [00000000] Irp is complete (CurrentLocation 43 > StackCount 42)
863296d8 [00000000] Irp is complete (CurrentLocation 2 > StackCount 1)
86329960 [00000000] Irp is complete (CurrentLocation 43 > StackCount 42)
89feeae0 [00000000] irpStack: ( e, 0) 8a765030 [ \Driver\ACPI]
8a6d85d8 [99aa1040] irpStack: ( d, 0) 8b127018 [ \FileSystem\NTFS] 0x0000000
8a6dc828 [8bc758c0] irpStack: (4, 0) 8b127018 [ \FileSystem\NTFS] 0x0000000
8a6f42d8 [8bc728c0] irpStack: (4,34) 8b0b8030 [ \Driver\disk] 0x0000000
8a6f4d28 [8632e6c0] irpStack: ( 4,34) 8b0b8030 [ \Driver\disk] 0x0000000
8a767d98 [00000000] Irp is complete (CurrentLocation 6 > StackCount 5)
8a788d98 [00000000] irpStack: (f, 0) 00000000 [00000000: Could not read device
object or _DEVICE_OBJECT not found
1
8a7911a8 [9fdb4040] irpStack: ( e, 0) 86325768 [ \Driver\DeviceApi]
8b03c3f8 [00000000] Irp is complete (CurrentLocation 2 > StackCount 1)
8b0b8bc8 [863d6040] irpStack: ( e, 0) 8a78f030 [ \Driver\vmbus]
8b0c48c0 [91da8040] irpStack: ( e, 5) 8bcb2ca0 [ \Driver\AFD] 0xaa1a3540
8b118d98 [00000000] Irp is complete (CurrentLocation 9 > StackCount 8)
8b1263b8 [00000000] Irp is complete (CurrentLocation 8 > StackCount 7)
8b174008 [aa0aab80] irpStack: ( 4, 0) 8b127018 [ \FileSystem\NTFS] 0xa15e1c40
8b194008 [aa0aab80] irpStack: ( 4, 0) 8b127018 [ \FileSystem\NTFS] 0xa15e1c40
8b196370 [8b131880] irpStack: ( e,31) 8bcb2ca0 [ \Driver\AFD]
8b1a8470 [00000000] Irp is complete (CurrentLocation 2 > StackCount 1)
8b1b3510 [9fcd1040] irpStack: ( e, 0) 86325768 [ \Driver\DeviceApi]
8b1b35b0 [a4009b80] irpStack: ( e, 0) 86325768 [ \Driver\DeviceApi]
8b1cd188 [9c3be040] irpStack: ( e, 0) 8bc73648 [ \Driver\Beep]
```

...

Some IRPs are complete, and may be de-allocated very soon, or they have been de-allocated, but because the allocation from lookaside lists, the IRP has not yet been replaced with a new one.

For each IRP, its address is given, followed by the thread that issued the request. Next, the major and minor function codes for the current stack location are shown in parentheses. You can examine any IRP with the ! i rp command:

```
kd> !irp 8a6f4d28
Irp is active with 15 stacks 6 is current (= 0x8a6f4e4c)
Mdl=8b14b250: No System Buffer: Thread 8632e6c0: Irp stack trace.
    cmd flg cl Device File Completion-Context
```

[N/A(0), N/A(0)]0 0 0000000 0000000 0000000-0000000 Args: 0000000 0000000 0000000 0000000 [N/A(0), N/A(0)]0 0 0000000 0000000 0000000-0000000 Args: 0000000 0000000 0000000 0000000 [N/A(0), N/A(0)]0 0 0000000 0000000 0000000-0000000 Args: 0000000 0000000 0000000 0000000 [N/A(0), N/A(0)]0 0 0000000 0000000 0000000-0000000 Args: 0000000 0000000 0000000 0000000 [N/A(0), N/A(0)]0 0 0000000 0000000 0000000-0000000 Args: 0000000 0000000 0000000 0000000 >[IRP\_MJ\_WRITE(4), N/A(34)] 14 e0 8b0b8030 00000000 876c2ef0-00000000 Success Error Cancel \Driver\disk partmgr!PmIoCompletion Args: 0004b000 0000000 4b3a0000 0000002  $[IRP_MJ_WRITE(4), N/A(3)]$ 14 e0 8b0fc058 0000000 876c36a0-00000000 Success Error Cancel \Driver\partmgr partmgr!PartitionIoCompletion Args: 4b49ace4 00000000 4b3a0000 0000002 [IRP\_MJ\_WRITE(4), N/A(0)] 14 e0 8b121498 00000000 87531110-8b121a30 Success Error Cancel \Driver\partmgr volmgr!VmpReadWriteCompletionRoutine Args: 0004b000 00000000 2bea0000 0000002 [IRP\_MJ\_WRITE(4), N/A(0)] 4 e0 8b121978 00000000 82d103e0-8b1220d9 Success Error Cancel \Driver\volmgr fvevol!FvePassThroughCompletionRdpLevel2 Args: 0004b000 0000000 4b49acdf 0000000  $[IRP_MJ_WRITE(4), N/A(0)]$ 4 e0 8b122020 00000000 82801a40-00000000 Success Error Cancel \Driver\fvevol rdyboost!SmdReadWriteCompletion Args: 0004b000 00000000 2bea0000 0000002 [IRP\_MJ\_WRITE(4), N/A(0)] 4 e1 8b118538 00000000 828637d0-00000000 Success Error Cancel pending \Driver\rdyboost iorate!IoRateReadWriteCompletion Args: 0004b000 3fffffff 2bea0000 0000002 [IRP\_MJ\_WRITE(4), N/A(0)] 4 e0 8b11ab80 00000000 82da1610-8b1240d8 Success Error Cancel \Driver\iorate volsnap!VspRefCountCompletionRoutine Args: 0004b000 00000000 2bea0000 0000002  $[IRP_MJ_WRITE(4), N/A(0)]$ 4 e1 8b124020 00000000 87886ada-89aec208 Success Error Cancel pending \Driver\volsnap NTFS!NtfsMasterIrpSyncCompletionRoutine Args: 0004b000 00000000 2bea0000 0000002

Irp Extension present at 0x8a6f4fb4:

This is a monstrous IRP with 15 stack locations (6 is current, shown in bold above, and is also specified by the debugger with the > character). The major and minor functions are shown for each stack location along with information on the device object and completion routines addresses.

The next step is to see what device object the IRP is targeting by executing the !devobj command on the device object address in the active stack location:

```
kd> !devobj 8b0b8030
Device object (8b0b8030) is for:
   DR0 \Driver\disk DriverObject 8b0a7e30
Current Irp 00000000 RefCount 1 Type 00000007 Flags 01000050
Vpb 8b0fc420 SecurityDescriptor 87da1b58 DevExt 8b0b80e8 DevObjExt 8b0b8578 Dope
8b0fc3d0
ExtensionFlags (0x00000800) DOE_DEFAULT_SD_PRESENT
Characteristics (0x00000100) FILE_DEVICE_SECURE_OPEN
AttachedDevice (Upper) 8b0fc058 \Driver\partmgr
AttachedTo (Lower) 8b0a4d10 \Driver\storflt
Device queue is not busy.
```

Finally, you can see details about the thread and process that issued the IRP by using the !thread command:

```
kd> !thread 8632e6c0
THREAD 8632e6c0 Cid 0004.0058 Teb: 00000000 Win32Thread: 00000000 WAIT:
(Executive) KernelMode Non-Alertable
     89aec20c NotificationEvent
IRP List:
     8a6f4d28: (0006,02d4) Flags: 00060043 Mdl: 8b14b250
Not impersonating
DeviceMap87c025b0Owning Process86264280Image:SysAttached ProcessN/AImage:N/AWait Start TickCount8083Ticks: 1 (0:00:00:Context Switch Count2223IdealProcessor: 0UserTime00:00:00000
                                                                System
                                                                  N/A
                                               Ticks: 1 (0:00:00:00.015)
                            00:00:00.000
UserTime
                             00:00:00.046
KernelTime
Win32 Start Address nt!ExpWorkerThread (0x81e68710)
Stack Init 89aecca0 Current 89aebeb4 Base 89aed000 Limit 89aea000 Call 00000000
Priority 13 BasePriority 13 PriorityDecrement 0 IoPriority 2 PagePriority 5
```

# I/O request to a single-layered hardware-based driver

This section traces I/O requests to a single-layered kernel-mode device driver. Figure 6-14 shows a typical IRP processing scenario for such a driver.




FIGURE 6-14 Typical single layer I/O request processing for hardware drivers.

Before we dig into the various steps outlined in Figure 6-14, some general comments are in order:

- There are two types of horizontal divider lines. The first (solid line) is the usual user-mode/ kernel-mode divider. The second (dotted line) separates code that runs in the requesting thread context versus the arbitrary thread context. These contexts are defined as follows:
  - The requesting thread context region indicates that the executing thread is the original one that requested the I/O operation. This is important because if the thread is the one that made the original call, it means the process context is the original process, and so the user-mode address space that contains the user's buffer supplied to the I/O operation is directly accessible.
  - The arbitrary thread context region indicates that the thread running those functions can be any thread. More specifically, it's most likely *not* the requesting thread, and so the user-mode process address space visible is not likely to be the original one. In this context, accessing the user's buffer with a user-mode address can be disastrous. You'll see in the next section how this issue is handled.

ſ	1	'	'	٦
L	Ē			T
L	Ξ			T
U				J

**Note** The explanations for the steps outlined in Figure 6-14 will prove why the divider lines reside where they are.

- The large rectangle consisting of the four blocks (labeled Dispatch Routine, Start I/O Routine, ISR, and DPC Routine) represents the driver-provided code. All other blocks are provided by the system.
- The figure assumes the hardware device can handle one operation at a time, which is true of many types of devices. Even if the device can handle multiple requests, the basic flow of operations is still the same.

Here is the sequence of events as outlined in Figure 6-14:

- A client application calls a Windows API such as ReadFile. ReadFile calls the native NtReadFile (in Ntdll.dll), which makes the thread transition to kernel mode to the executive NtReadFile (these steps have already been discussed earlier in this chapter).
- 2. The I/O manager, in its NtReadFile implementation, performs some sanity checks on the request, such as whether the buffer provided by the client is accessible with the right page protection. Next, the I/O manager locates the associated driver (using the file handle provided), allocates and initializes an IRP, and calls the driver into the appropriate dispatch routine (in this case, corresponding to the IRP\_MJ\_READ index) using IoCallDriver with the IRP.
- 3. This is the first time the driver sees the IRP. This call is usually invoked using the requesting thread; the only way for that not to happen is if an upper filter held on to the IRP and called IoCallDriver later from a different thread. For the sake of this discussion, we'll assume this is not the case (and in most cases involving hardware devices, this does not happen; even if there are upper filters, they do some processing and call the lower driver immediately from the same thread). The dispatch read callback in the driver has two tasks on its hand: first, it should perform more checking that the I/O manager can't do because it has no idea what the request really means. For example, the driver could check if the buffer provided to a read or write operation is large enough; or for a DeviceIoControl operation, the driver would check whether the I/O control code provided is a supported one. If any such check fails, the driver completes the IRP (IoCompleteRequest) with the failed status and returns immediately. If the checks turn up OK, the driver calls its Start I/O routine to initiate the operation. However, if the hardware device is currently busy (handling a previous IRP), then the IRP should be inserted into a queue managed by the driver and a STATUS\_PENDING is returned without completing the IRP. The I/O manager caters for such a scenario with the IoStartPacket function, that checks a busy bit in the device object and, if the device is busy, inserts the IRP into a queue (also part of the device object structure). If the device is not busy, it sets the device bit as busy and calls the registered Start I/O routine (recall that there is such a member in the driver object that would have been initialized in DriverEntry). Even if a driver chooses not to use IoStartPacket, it would still follow similar logic.
- 4. If the device is not busy, the Start I/O routine is called from the dispatch routine directly meaning it's still the requesting thread that is making the call. Figure 6-14, however, shows that the Start I/O routine is called in an arbitrary thread context; this will be proven to be true in the general case when we look at the DPC routine in step 8. The purpose of the Start I/O routine is to take the IRP relevant parameters and use them to program the hardware device (for example,

by writing to its ports or registers using HAL hardware access routines such as WRITE\_PORT\_UCHAR, WRITE\_REGISTER\_ULONG, etc.). After the Start I/O completes, the call returns, and no particular code is running in the driver, the hardware is working and "does its thing." While the hardware device is working, more requests can come in to the device by the same thread (if using asynchronous operations) or other threads that also opened handles to the device. In this case the dispatch routine would realize the device is busy and insert the IRP into the IRP queue (as mentioned, one way to achieve this is with a call to IoStartPacket).

- 5. When the device is done with the current operation, it raises an interrupt. The kernel trap handler saves the CPU context for whatever thread was running on the CPU that was selected to handle the interrupt, raises the IRQL of that CPU to the IRQL associated with the interrupt (DIRQL) and jumps to the registered ISR for the device.
- 6. The ISR, running at Device IRQL (above 2) does as little work as possible, telling the device to stop the interrupt signal and getting the status or other required information from the hardware device. As its last act, the ISR queues a DPC for further processing at a lower IRQL. The advantage of using a DPC to perform most of the device servicing is that any blocked interrupt whose IRQL lies between the Device IRQL and the DPC/dispatch IRQL (2) is allowed to occur before the lower-priority DPC processing occurs. Intermediate-level interrupts are thus serviced more promptly than they otherwise would be, and this reduces latency on the system.
- **7.** After the interrupt is dismissed, the kernel notices that the DPC queue is not empty and so uses a software interrupt at IRQL DPC\_LEVEL (2) to jump to the DPC processing loop.
- 8. Eventually, the DPC is de-queued and executes at IRQL 2, typically performing two main operations:
  - It gets the next IRP in the queue (if any) and starts the new operation for the device. This is done first to prevent the device from being idle for too long. If the dispatch routine used IoStart-Packet, then the DPC routine would call its counterpart, IoStartNextPacket, which does just that. If an IRP is available, the Start I/O routine is called from the DPC. This is why in the general case, the Start I/O routine is called in an arbitrary thread context. If there are no IRPs in the queue, the device is marked not busy—that is, ready for the next request that comes in.
  - It completes the IRP, whose operation has just finished by the driver by calling IoComplete-Request. From that point, the driver is no longer responsible for the IRP and it shouldn't be touched, as it can be freed at any moment after the call. IoCompleteRequest calls any completion routines that have been registered. Finally, the I/O manager frees the IRP (it's actually using a completion routine of its own to do that).
- 9. The original requesting thread needs to be notified of the completion. Because the current thread executing the DPC is arbitrary, it's not the original thread with its original process address space. To execute code in the context of the requesting thread, a special kernel APC is issued to the thread. An APC is a function that is forced to execute in the context of a particular thread. When the requesting thread gets CPU time, the special kernel APC executes first (at IRQL APC\_LEVEL=1). It does what's needed, such as releasing the thread from waiting, signaling an event that was registered in an asynchronous operation, and so on. (For more on APCs, see Chapter 8 in Part 2.)

A final note about I/O completion: the asynchronous I/O functions ReadFileEx and WriteFileEx allow a caller to supply a callback function as a parameter. If the caller does so, the I/O manager queues a user mode APC to the caller's thread APC queue as the last step of I/O completion. This feature allows a caller to specify a subroutine to be called when an I/O request is completed or canceled. User-mode APC completion routines execute in the context of the requesting thread and are delivered only when the thread enters an alertable wait state (by calling functions such as SleepEx, WaitForSingleObjectEx, or WaitForMultipleObjectsEx).

#### User address space buffer access

As shown in Figure 6-14, there are four main driver functions involved in processing an IRP. Some or all of these routines may need to access the buffer in user space provided by the client application. When an application or a device driver indirectly creates an IRP by using the NtReadFile, NtWriteFile, or NtDeviceIoControlFile system services (or the Windows API functions corresponding to these services, which are ReadFile, WriteFile, and DeviceIoControl), the pointer to the user's buffer is provided in the UserBuffer member of the IRP body. However, accessing this buffer directly can be done only in the requesting thread context (the client's process address space is visible) and in IRQL 0 (paging can be handled normally).

As discussed in the previous section, only the dispatch routine meets the criteria of running in the requesting thread context and in IRQL 0. And even this is not always the case—it's possible for an upper filter to hold on to the IRP and not pass it down immediately, possibly passing it down later on using a different thread, and could even be done when the CPU IRQL is 2 or higher.

The other three functions (Start I/O, ISR, DPC) clearly run on an arbitrary thread (could be any thread), and with IRQL 2 (DIRQL for the ISR). Accessing the user's buffer directly from any of these routine is mostly fatal. Here's why:

- Because the IRQL is 2 or higher, paging is not allowed. Since the user's buffer (or part of it) may be paged out, accessing the non-resident memory would crash the system.
- Because the thread executing these functions could be any thread, and thus a random process address space would be visible, the original user's address has no meaning and would likely lead to an access violation, or worse—accessing data from some random process (the parent process of whatever thread was running at the time).

Clearly, there must be a safe way to access the user's buffer in any of these routines. The I/O manager provides two options, for which it does the heavy lifting. These are known as Buffered I/O and Direct I/O. A third option, which is not really an option, is called Neither I/O, in which the I/O manager does nothing special and lets the driver handle the problem on its own.

A driver selects the method in the following way:

For read and write requests (IRP\_MJ\_READ and IRP\_MJ\_WRITE), it sets the Flags member (with an OR boolean operation so as not to disturb other flags) of the device object (DEVICE\_OBJECT) to D0\_BUFFERED\_IO (for buffered I/O) or D0\_DIRECT\_IO (for direct I/O). If neither flag is set, neither I/O is implied. (D0 is short for *device object*.) For device I/O control requests (IRP\_MJ\_DEVICE\_CONTROL), each control code is constructed using the CTL\_CODE macro, where some of the bits indicate the buffering method. This means the buffering method can be set on a control code-by-control code basis, which is very useful.

The following sections describe each buffering method in detail.

**Buffered I/O** With buffered I/O, the I/O manager allocates a mirror buffer that is the same size as the user's buffer in non-paged pool and stores the pointer to the new buffer in the AssociatedIrp. SystemBuffer member of the IRP body. Figure 6-15 shows the main stages in buffered I/O for a read operation (write is similar).




FIGURE 6-15 Buffered I/O.

The driver can access the system buffer (address q in Figure 6-15) from any thread and any IRQL:


- The address is in system space, meaning it's valid in any process context.
- The buffer is allocated from non-paged pool, so a page fault will not happen.

For write operations, the I/O manager copies the caller's buffer data into the allocated buffer when creating the IRP. For read operations, the I/O manager copies data from the allocated buffer to the user's buffer when the IRP completes (using a special kernel APC) and then frees the allocated buffer.

Buffered I/O clearly is very simple to use because the I/O manager does practically everything. Its main downside is that it always requires copying, which is inefficient for large buffers. Buffered I/O is commonly used when the buffer size is no larger than one page (4 KB) and when the device does not

support direct memory access (DMA), because DMA is used to transfer data from a device to RAM or vice versa without CPU intervention—but with buffered I/O, there is always copying done with the CPU, which makes DMA pointless.

**Direct I/O** Direct I/O provides a way for a driver to access the user's buffer directly without any need for copying. Figure 6-16 shows the main stages in direct I/O for a read or write operation.





When the I/O manager creates the IRP, it locks the user's buffer into memory (that is, makes it nonpageable) by calling the MmProbeAndLockPages function (documented in the WDK). The I/O manager stores a description of the memory in the form of a memory descriptor list (MDL), which is a structure that describes the physical memory occupied by a buffer. Its address is stored in the Md1Address member of the IRP body. Devices that perform DMA require only physical descriptions of buffers, so an MDL is sufficient for the operation of such devices. If a driver must access the contents of a buffer, however, it can map the buffer into the system's address space using the MmGetSystemAddressForMd1Safe function, passing in the provided MDL. The resulting pointer (*q* in Figure 6-16) is safe to use in any thread context (it's a system address) and in any IRQL (the buffer cannot be paged out). The user's buffer is effectively double-mapped, where the user's direct address (*p* in Figure 6-16) is usable only from the original process context, but the second mapping into system space is usable in any context. Once the IRP is complete, the I/O manager unlocks the buffer (making it pageable again) by calling MmUn1ock-Pages (documented in the WDK).

Direct I/O is useful for large buffers (more than one page) because no copying is done, especially for DMA transfers (for the same reason).

**Neither I/O** With neither I/O, the I/O manager doesn't perform any buffer management. Instead, buffer management is left to the discretion of the device driver, which can choose to manually perform the steps the I/O manager performs with the other buffer-management types. In some cases, accessing the buffer in the dispatch routine is sufficient, so the driver may get away with neither I/O. The main advantage of neither I/O is its zero overhead.

Drivers that use neither I/O to access buffers that might be located in user space must take special care to ensure that buffer addresses are valid and do not reference kernel-mode memory. Scalar values, however, are perfectly safe to pass, although very few drivers have only a scalar value to pass around. Failure to do so could result in crashes or in security vulnerabilities, where applications have access to kernel-mode memory or can inject code into the kernel. The ProbeForRead and ProbeForWrite functions that the kernel makes available to drivers verify that a buffer resides entirely in the user-mode portion of the address space. To avoid a crash from referencing an invalid user-mode address, drivers can access user-mode buffers protected with structured exception handling (SEH), expressed with \_\_\_try/\_\_except blocks in C/C++, that catch any invalid memory faults and translate them into error codes to return to the application. (See Chapter 8 in Part 2 for more information on SEH.) Additionally, drivers should also capture all input data into a kernel buffer instead of relying on user-mode addresses because the caller could always modify the data behind the driver's back, even if the memory address itself is still valid.

#### Synchronization

Drivers must synchronize their access to global driver data and hardware registers for two reasons:

- The execution of a driver can be preempted by higher-priority threads and time-slice (or quantum) expiration or can be interrupted by higher IRQL interrupts.
- On multiprocessor systems (the norm), Windows can run driver code simultaneously on more than one processor.

Without synchronization, corruption could occur—for example, device-driver code running at passive IRQL (0) (say, a dispatch routine) when a caller initiates an I/O operation can be interrupted by a device interrupt, causing the device driver's ISR to execute while its own device driver is already running. If the device driver was modifying data that its ISR also modifies—such as device registers, heap storage, or static data—the data can become corrupted when the ISR executes.

To avoid this situation, a device driver written for Windows must synchronize its access to any data that can be accessed at more than one IRQL. Before attempting to update shared data, the device driver must lock out all other threads (or, in the case of a multiprocessor system, CPUs) to prevent them from updating the same data structure.

On a single-CPU system, synchronizing between two or more functions that run at different IRQLs is easy enough. Such function just needs to raise the IRQL (KeRaiseIrq1) to the highest IRQL these functions execute in. For example, to synchronize between a dispatch routine (IRQL 0) and a DPC routine (IRQL 2), the dispatch routine needs to raise IRQL to 2 before accessing the shared data. If synchronization between a DPC and ISR is required, the DPC would raise IRQL to the Device IRQL (this information is provided to the driver when the PnP manager informs the driver of the hardware resources a device is connected to.) On multiprocessing systems, raising IRQL is not enough because the other routine for example, ISR—could be serviced on another CPU (remember that IRQL is a CPU attribute, and not a global system attribute).

To allow high IRQL synchronization across CPUs, the kernel provides a specialized synchronization object: the spinlock. Here, we'll take a brief look at spinlocks as they apply to driver synchronization. (A full treatment of spinlocks is reserved for Chapter 8 in Part 2.) In principle, a spinlock resembles a mutex (also discussed in detail in Chapter 8 in Part 2) in the sense that it allows one piece of code to access shared data, but it works and is used quite differently. Table 6-3 summarizes the differences between mutexes and spinlocks.

	Mutex	Spinlock	
Synchronization nature	One thread out of any number of threads that is allowed enters a critical region and accesses shared data.	One CPU out of any number of CPUs that is allowed enters a critical region and accesses shared data.	
Usable at IRQL	< DISPATCH_LEVEL (2)	>= DISPATCH_LEVEL (2)	
Wait kind	Normal. That is, it does not waste CPU cycles while waiting.	Busy. That is, the CPU is constantly testing spinlock bit until it's free.	
Ownership	The owner thread is tracked, and recursive acquisition is allowed.	The CPU owner is not tracked, and recursive acquisition will cause a deadlock.	

TABLE 6-3	Mutexes	versus	spinlocks
-----------	---------	--------	-----------


A spinlock is just a bit in memory that is accessed by an atomic test and modify operation. A spinlock may be owned by a CPU or free (unowned). As shown in Table 6-3, spinlocks are necessary when synchronization is needed in high IRQLs (>=2), because a mutex can't be used in these cases as a scheduler is needed, but as we've seen the scheduler cannot wake up on a CPU whose IRQL is 2 or higher. This is why waiting for a spinlock is a busy wait operation: The thread cannot go to a normal wait state because that implies the scheduler waking up and switching to another thread on that CPU.

Acquiring a spinlock by a CPU is always a two-step operation. First, the IRQL is raised to the associated IRQL on which synchronization is to occur—that is, the highest IRQL on which the function that needs to synchronize executes. For example, synchronizing between a dispatch routine (IRQL 0) and a DPC (2) would need to raise IRQL to 2; synchronizing between DPC (2) and ISR (DIRQL) would need to raise IRQL to DIRQL (the IRQL for that particular interrupt). Second, the spinlock is attempted acquisition by atomically testing and setting the spinlock bit.

**Note** The steps outlined for spinlock acquisition are simplified and omit some details that are not important for this discussion. The complete spinlock story is described in Chapter 8 in Part 2.

The functions that acquire spinlocks determine the IRQL on which to synchronize, as we shall see in a moment.

Figure 6-17 shows a simplified view of the two-step process of acquiring a spinlock.





When synchronizing at IRQL 2—for example, between a dispatch routine and a DPC or between a DPC and another DPC (running on another CPU, of course)—the kernel provides the KeAcquireSpinLock and KeReleaseSpinLock functions (there are other variations that are discussed in Chapter 8 in Part 2). These functions perform the steps in Figure 6-17 where the "associated IRQL" is 2. The driver in this case must allocate a spinlock (KSPIN\_LOCK, which is just 4 bytes on 32-bit systems and 8 bytes on 64-bit systems), typically in the device extension (where driver-managed data for the device is kept) and initialize it with KeInitializeSpinLock.

For synchronizing between any function (such as DPC or a dispatch routine) and the ISR, different functions must be used. Every interrupt object (KINTERRUPT) holds inside it a spinlock, which is acquired before the ISR executes (this implies that the same ISR cannot run concurrently on other CPUs). Synchronization in this case would be with that particular spinlock (no need to allocate another one), which can be acquired indirectly with the KeAcquireInterruptSpinLock function and released with KeReleaseInterruptSpinLock. Another option is to use the KeSynchronizeExecution function, which accepts a callback function the driver provides that is called between the acquisition and release of the interrupt spinlock.

By now, you should realize that although ISRs require special attention, any data that a device driver uses is subject to being accessed by the same device driver (one of its functions) running on another processor. Therefore, it's critical for device-driver code to synchronize its use of any global or shared data or any accesses to the physical device itself.

## I/O requests to layered drivers

The "IRP flow" section showed the general options drivers have for dealing with IRPs, with a focus on a standard WDM device node. The preceding section showed how an I/O request to a simple device controlled by a single device driver is handled. I/O processing for file-based devices or for requests to other layered drivers happens in much the same way, but it's worthwhile to take a closer look at a request targeted at file-system drivers. Figure 6-18 shows a very simplified illustrative example of how an asynchronous I/O request might travel through layered drivers for non-hardware based devices as primary targets. It uses as an example a disk controlled by a file system.




FIGURE 6-18 Queuing an asynchronous request to layered drivers.

Once again, the I/O manager receives the request and creates an IRP to represent it. This time, however, it delivers the packet to a file-system driver. The file-system driver exercises great control over the I/O operation at that point. Depending on the type of request the caller made, the file system can send the same IRP to the disk driver or it can generate additional IRPs and send them separately to the disk driver.

The file system is most likely to reuse an IRP if the request it receives translates into a single straightforward request to a device. For example, if an application issues a read request for the first 512 bytes in a file stored on a volume, the NTFS file system would simply call the volume manager driver, asking it to read one sector from the volume, beginning at the file's starting location.

After the disk controller's DMA adapter finishes a data transfer, the disk controller interrupts the host, causing the ISR for the disk controller to run, which requests a DPC callback completing the IRP, as shown in Figure 6-19.

As an alternative to reusing a single IRP, a file system can establish a group of associated IRPs that work in parallel on a single I/O request. For example, if the data to be read from a file is dispersed across the disk, the file-system driver might create several IRPs, each of which reads some portion of the request from a different sector. This queuing is illustrated in Figure 6-20.






FIGURE 6-19 Completing a layered I/O request.



**FIGURE 6-20** Queuing associated IRPs.

The file-system driver delivers the associated IRPs to the volume manager, which in turn sends them to the disk-device driver, which queues them to the disk device. They are processed one at a time, and the file-system driver keeps track of the returned data. When all the associated IRPs complete, the I/O system completes the original IRP and returns to the caller, as shown in Figure 6-21.





**Note** All Windows file-system drivers that manage disk-based file systems are part of a stack of drivers that is at least three layers deep. The file-system driver sits at the top, a volume manager in the middle, and a disk driver at the bottom. In addition, any number of filter drivers can be interspersed above and below these drivers. For clarity, the preceding example of layered I/O requests includes only a file-system driver and the volume-manager driver. See Chapter 12 in Part 2 for more information.

## Thread-agnostic I/O

In the I/O models described thus far, IRPs are queued to the thread that initiated the I/O and are completed by the I/O manager issuing an APC to that thread so that process-specific and thread-specific context are accessible by completion processing. Thread-specific I/O processing is usually sufficient for the performance and scalability needs of most applications, but Windows also includes support for *thread-agnostic I/O* via two mechanisms:

- I/O completion ports, which are described at length in the section "I/O completion ports" later in this chapter
- Locking the user buffer into memory and mapping it into the system address space

With I/O completion ports, the application decides when it wants to check for the completion of I/O. Therefore, the thread that happens to have issued an I/O request is not necessarily relevant because any other thread can perform the completion request. As such, instead of completing the IRP inside the specific thread's context, it can be completed in the context of any thread that has access to the completion port.

Likewise, with a locked and kernel-mapped version of the user buffer, there's no need to be in the same memory address space as the issuing thread because the kernel can access the memory from arbitrary contexts. Applications can enable this mechanism by using SetFileIoOverlappedRange as long as they have the SeLockMemoryPrivilege.

With both completion port I/O and I/O on file buffers set by SetFileIoOverlappedRange, the I/O manager associates the IRPs with the file object to which they have been issued instead of with the issuing thread. The !fileobj extension in WinDbg shows an IRP list for file objects that are used with these mechanisms.

In the next sections, you'll see how thread-agnostic I/O increases the reliability and performance of applications in Windows.

# I/O cancellation

While there are many ways in which IRP processing occurs and various methods to complete an I/O request, a great many I/O processing operations actually end in cancellation rather than completion. For example, a device may require removal while IRPs are still active, or the user might cancel a long-running operation to a device—for example, a network operation. Another situation that requires I/O cancellation support is thread and process termination. When a thread exits, the I/Os associated with the thread must be cancelled. This is because the I/O operations are no longer relevant and the thread cannot be deleted until the outstanding I/Os have completed.


The Windows I/O manager, working with drivers, must deal with these requests efficiently and reliably to provide a smooth user experience. Drivers manage this need by registering a cancel routine, by calling IoSetCancelRoutine, for their cancellable I/O operations (typically, those operations that are still enqueued and not yet in progress), which is invoked by the I/O manager to cancel an I/O operation. When drivers fail to play their role in these scenarios, users may experience unkillable processes, which have disappeared visually but linger and still appear in Task Manager or Process Explorer.

### User-initiated I/O cancellation


Most software uses one thread to handle user interface (UI) input and one or more threads to perform work, including I/O. In some cases, when a user wants to abort an operation that was initiated in the UI, an application might need to cancel outstanding I/O operations. Operations that complete quickly might not require cancellation, but for operations that take arbitrary amounts of time—like large data transfers or network operations. Windows provides support for cancelling both synchronous and asynchronous operations.

- Cancelling synchronous I/Os A thread can call CancelSynchronousIo. This enables even create (open) operations to be cancelled when supported by a device driver. Several drivers in Windows support this functionality. These include drivers that manage network file systems (for example, MUP, DFS, and SMB), which can cancel open operations to network paths.
- Cancelling asynchronous I/Os A thread can cancel its own outstanding asynchronous I/Os by calling Cancello. It can cancel all asynchronous I/Os issued to a specific file handle, regardless of which thread initiated them, in the same process with CancelloEx. CancelloEx also works on operations associated with I/O completion ports through the aforementioned thread-agnostic support in Windows. This is because the I/O system keeps track of a completion port's outstanding I/Os by linking them with the completion port.

Figure 6-22 and Figure 6-23 show synchronous and asynchronous I/O cancellation. (To a driver, all cancel processing looks the same.)









### I/O cancellation for thread termination

The other scenario in which I/Os must be cancelled is when a thread exits, either directly or as a result of its process terminating (which causes the threads of the process to terminate). Because every thread has a list of IRPs associated with it, the I/O manager can walk this list, look for cancellable IRPs, and cancel them. Unlike CancelloEx, which does not wait for an IRP to be cancelled before returning, the process manager will not allow thread termination to proceed until all I/Os have been cancelled. As a result, if a driver fails to cancel an IRP, the process and thread object will remain allocated until the system shuts down.

**Note** Only IRPs for which a driver sets a cancel routine are cancellable. The process manager waits until all I/Os associated with a thread are either cancelled or completed before deleting the thread.

#### **EXPERIMENT:** Debugging an unkillable process

In this experiment, we'll use Notmyfault from Sysinternals to force an unkillable process by causing the Myfault.sys driver, which Notmyfault.exe uses, to indefinitely hold an IRP without having registered a cancel routine for it. (Notmyfault is covered in detail in the "Crash dump analysis" section of Chapter 15, "Crash dump analysis," in Part 2.) Follow these steps:

- 1. Run Notmyfault.exe.
- 2. The Not My Fault dialog box appears. Click the **Hang** tab and choose **Hang with IRP**, as shown in the following screenshot. Then click the **Hang** button.

ot My	Tepit				- 1
Crash	Hang	Leak			
		2002-2016 M by Daniel Pe	ark Russinovic arson	th .	
Op	tions				
Sek	ecting eit	her the Han		ne system to hang. Deadlock option will	
۲	Hang wit	h IRP			
0	Hang wit	h DPC			
0	Deadlock				
				Hang	
				(1) (1) (1)	172

3. You shouldn't see anything happen, and you should be able to click the Cancel button to quit the application. However, you should still see the Notmyfault process in Task Manager or Process Explorer. Attempts to terminate the process will fail because Windows will wait forever for the IRP to complete given that the Myfault driver doesn't register a cancel routine.

4. To debug an issue such as this, you can use WinDbg to look at what the thread is currently doing. Open a local kernel debugger session and start by listing the information about the Notmyfault.exe process with the !process command (notmyfault64 is the 64-bit version):

```
lkd> !process 0 7 notmyfault64.exe
PROCESS ffff8c0b88c823c0
   SessionId: 1 Cid: 2b04 Peb: 4e5c9f4000 ParentCid: 0d40
   DirBase: 3edfa000 ObjectTable: ffffdf08dd140900 HandleCount: <Data Not
Accessible>
   Image: notmyfault64.exe
   VadRoot ffff8c0b863ed190 Vads 81 Clone 0 Private 493. Modified 8. Locked
0....
      THREAD ffff8c0b85377300 Cid 2b04.2714 Teb: 0000004e5c808000
Win32Thread: 00000000000000 WAIT: (UserRequest) UserMode Non-Alertable
         fffff80a4c944018 SynchronizationEvent
      IRP List:
         ffff8c0b84f1d130: (0006,0118) Flags: 00060000 Mdl: 00000000
      Not impersonating
      DeviceMap
                         ffffdf08cf4d7d20
      Owning Process
                        ffff8c0b88c823c0
                                            Image:
notmyfault64.exe
. . .
      Child-SP RetAddr
                                 : Args to Child
: Call Site
      ffffb881'3ecf74a0 fffff802'cfc38a1c : 00000000'00000100
nt!KiSwapContext+0x76
      ffffb881'3ecf75e0 fffff802'cfc384bf : 00000000'0000000
nt!KiSwapThread+0x17c
      ffffb881'3ecf7690 fffff802'cfc3a287 : 00000000'00000000
nt!KiCommitThreadWait+0x14f
      ffffb881'3ecf7730 fffff80a'4c941fce : fffff80a'4c944018
nt!KeWaitForSingleObject+0x377
      ffffb881'3ecf77e0 fffff802'd0067430 : ffff8c0b'88d2b550
ffffb881'3ecf7820 fffff802'd0066314 : ffff8c0b'0000000
ffff8c0b'88d2b504 00000000'00000000 ffffb881'3ecf7b80 : nt!IopSynchronousSer
viceTail+0x1a0
      ffffb881'3ecf78e0 fffff802'd0065c96 : 00000000'0000000
nt!IopXxxControlFile+0x674
      ffffb881'3ecf7a20 fffff802'cfd57f93 : ffff8c0b'85377300
fffff802'cfcb9640 00000000'00000000 fffff802'd005b32f :
nt!NtDeviceIoControlFile+0x56
      ffffb881'3ecf7a90 00007ffd'c1564f34 : 00000000'00000000
nt!KiSystemServiceCopyEnd+0x13 (TrapFrame @ ffffb881'3ecf7b00)
```

5. From the stack trace, you can see that the thread that initiated the I/O is now waiting for cancellation or completion. The next step is to use the same debugger extension command used in the previous experiments, ! i rp, and attempt to analyze the problem. Copy the IRP pointer, and examine it with ! i rp:

6. From this output, it is obvious who the culprit driver is: \Driver\MYFAULT, or Myfault.sys. The name of the driver highlights the fact that the only way this situation can occur is through a driver problem—not a buggy application. Unfortunately, although you now know which driver caused the problem, there isn't much you can do about it apart from rebooting the system. This is necessary because Windows can never safely assume it is OK to ignore the fact that cancellation hasn't yet occurred. The IRP could return at any time and cause corruption of system memory.

**Tip** If you encounter this situation in practice, you should check for a newer version of the driver, which might include a fix for the bug.

# I/O completion ports

Writing a high-performance server application requires implementing an efficient threading model. Having either too few or too many server threads to process client requests can lead to performance problems. For example, if a server creates a single thread to handle all requests, clients can become starved because the server will be tied up processing one request at a time. A single thread could simultaneously process multiple requests, switching from one to another as I/O operations are started. However, this architecture introduces significant complexity and can't take advantage of systems with more than one logical processor. At the other extreme, a server could create a big pool of threads so that virtually every client request is processed by a dedicated thread. This scenario usually leads to thread-thrashing, in which lots of threads wake up, perform some CPU processing, block while waiting for I/O, and then, after request processing is completed, block again waiting for a new request. If nothing else, having too many threads results in excessive context switching, caused by the scheduler having to divide processor time among multiple active threads; such a scheme will not scale.

The goal of a server is to incur as few context switches as possible by having its threads avoid unnecessary blocking, while at the same time maximizing parallelism by using multiple threads. The ideal is for there to be a thread actively servicing a client request on every processor and for those threads not to block when they complete a request if additional requests are waiting. For this optimal process to work correctly, however, the application must have a way to activate another thread when a thread processing a client request blocks I/O (such as when it reads from a file as part of the processing).

#### The IoCompletion object

Applications use the IoCompletion executive object, which is exported to the Windows API as a completion port, as the focal point for the completion of I/O associated with multiple file handles. Once a file is associated with a completion port, any asynchronous I/O operations that complete on the file result in a completion packet being queued to the completion port. A thread can wait for any outstanding I/Os to complete on multiple files simply by waiting for a completion packet to be queued to the completion port. The Windows API provides similar functionality with the WaitForMultipleObjects API function, but completion ports have one important advantage: concurrency. *Concurrency* refers to the number of threads that an application has actively servicing client requests, which is controlled with the aid of the system.

When an application creates a completion port, it specifies a concurrency value. This value indicates the maximum number of threads associated with the port that should be running at any given time. As stated earlier, the ideal is to have one thread active at any given time for every processor in the system. Windows uses the concurrency value associated with a port to control how many threads an application has active. If the number of active threads associated with a port equals the concurrency value, a thread that is waiting on the completion port won't be allowed to run. Instead, an active thread will finish processing its current request, after which it will check whether another packet is waiting at the port. If one is, the thread simply grabs the packet and goes off to process it. When this happens, there is no context switch, and the CPUs are utilized nearly to their full capacity.

## Using completion ports

Figure 6-24 shows a high-level illustration of completion-port operation. A completion port is created with a call to the CreateIoCompletionPort Windows API function. Threads that block on a completion port become associated with the port and are awakened in last in, first out (LIFO) order so that the thread that blocked most recently is the one that is given the next packet. Threads that block for long periods of time can have their stacks swapped out to disk, so if there are more threads associated with a port than there is work to process, the in-memory footprints of threads blocked the longest are minimized.

A server application will usually receive client requests via network endpoints that are identified by file handles. Examples include Windows Sockets 2 (Winsock2) sockets or named pipes. As the server creates its communications endpoints, it associates them with a completion port and its threads wait for incoming requests by calling GetQueuedCompletionStatus(Ex) on the port. When a thread is given a packet from the completion port, it will go off and start processing the request, becoming an active thread. A thread will block many times during its processing, such as when it needs to read or write data to a file on disk or when it synchronizes with other threads. Windows detects this activity and recognizes that the completion port has one less active thread. Therefore, when a thread becomes inactive because it blocks, a thread waiting on the completion port will be awakened if there is a packet in the queue.




FIGURE 6-24 I/O completion-port operation.

Microsoft's guidelines are to set the concurrency value roughly equal to the number of processors in a system. Keep in mind that it's possible for the number of active threads for a completion port to exceed the concurrency limit. Consider a case in which the limit is specified as 1:

- 1. A client request comes in and a thread is dispatched to process the request, becoming active.
- **2.** A second request arrives, but a second thread waiting on the port isn't allowed to proceed because the concurrency limit has been reached.
- 3. The first thread blocks, waiting for a file I/O, so it becomes inactive.
- 4. The second thread is released.
- 5. While the second thread is still active, the first thread's file I/O is completed, making it active again. At that point—and until one of the threads blocks—the concurrency value is 2, which is higher than the limit of 1. Most of the time, the count of active threads will remain at or just above the concurrency limit.

The completion port API also makes it possible for a server application to queue privately defined completion packets to a completion port by using the PostQueuedCompletionStatus function. A server typically uses this function to inform its threads of external events, such as the need to shut down gracefully.

Applications can use thread-agnostic I/O, described earlier, with I/O completion ports to avoid associating threads with their own I/Os and associating them with a completion port object instead. In addition to the other scalability benefits of I/O completion ports, their use can minimize context switches. Standard I/O completions must be executed by the thread that initiated the I/O, but when an I/O associated with an I/O completion port completes, the I/O manager uses any waiting thread to perform the completion operation.

### I/O completion port operation

Windows applications create completion ports by calling the CreateIoCompletionPort Windows API and specifying a NULL completion port handle. This results in the execution of the NtCreateIoCompletion system service. The executive's IoCompletion object contains a kernel synchronization object called a *kernel queue*. Thus, the system service creates a completion port object and initializes a queue object in the port's allocated memory. (A pointer to the port also points to the queue object because the queue is the first member of the completion port.) A kernel queue object has a concurrency value that is specified when a thread initializes it, and in this case the value that is used is the one that was passed to CreateIoCompletionPort. KeInitializeQueue is the function that NtCreateIoCompletion calls to initialize a port's queue object.

When an application calls CreateIoCompletionPort to associate a file handle with a port, the NtSetInformationFile system service is executed with the file handle as the primary parameter. The information class that is set is FileCompletionInformation, and the completion port's handle and the CompletionKey parameter from CreateIoCompletionPort are the data values. NtSetInformationFile dereferences the file handle to obtain the file object and allocates a completion context data structure.

Finally, NtSetInformationFile sets the CompletionContext field in the file object to point at the context structure. When an asynchronous I/O operation completes on a file object, the I/O manager checks whether the CompletionContext field in the file object is non-NULL. If it is, the I/O manager allocates a completion packet and queues it to the completion port by calling KeInsertQueue with the port as the queue on which to insert the packet (this works because the completion port object and queue object have the same address).

When a server thread invokes GetQueuedCompletionStatus, the NtRemoveIoCompletion system service is executed. After validating parameters and translating the completion port handle to a pointer to the port, NtRemoveIoCompletion calls IoRemoveIoCompletion, which eventually calls KeRemoveQueueEx. For high-performance scenarios, it's possible that multiple I/Os may have been completed, and although the thread will not block, it will still call into the kernel each time to get one item. The GetQueuedCompletionStatus or GetQueuedCompletionStatusEx API allows applications to retrieve more than one I/O completion status at the same time, reducing the number of user-to-kernel roundtrips and maintaining peak efficiency. Internally, this is implemented through the NtRemoveIo-CompletionEx function. This calls IoRemoveIoCompletion with a count of queued items, which is passed on to KeRemoveQueueEx.

As you can see, KeRemoveQueueEx and KeInsertQueue are the engine behind completion ports. They are the functions that determine whether a thread waiting for an I/O completion packet should be activated. Internally, a queue object maintains a count of the current number of active threads and the maximum number of active threads. If the current number equals or exceeds the maximum when a thread calls KeRemoveQueueEx, the thread will be put (in LIFO order) onto a list of threads waiting for a turn to process a completion packet. The list of threads hangs off the queue object. A thread's control block data structure (KTHREAD) has a pointer in it that references the queue object of a queue that it's associated with; if the pointer is NULL, the thread isn't associated with a queue. Windows keeps track of threads that become inactive because they block on something other than the completion port by relying on the queue pointer in a thread's control block. The scheduler routines that possibly result in a thread blocking (such as KeWaitForSingleObject, KeDelayExecutionThread, and so on) check the thread's queue pointer. If the pointer isn't NULL, the functions call KiActivate-WaiterQueue, a queue-related function that decrements the count of active threads associated with the queue. If the resulting number is less than the maximum and at least one completion packet is in the queue, the thread at the front of the queue's thread list is awakened and given the oldest packet. Conversely, whenever a thread that is associated with a queue wakes up after blocking, the scheduler executes the KiUnwaitThread function, which increments the queue's active count.

The PostQueuedCompletionStatus Windows API function results in the execution of the NtSet-IoCompletion system service. This function simply inserts the specified packet onto the completion port's queue by using KeInsertQueue.

Figure 6-25 shows an example of a completion port object in operation. Even though two threads are ready to process completion packets, the concurrency value of 1 allows only one thread associated with the completion port to be active, and so the two threads are blocked on the completion port.




FIGURE 6-25 I/O completion port object in operation.

 TABLE 6-4
 I/O completion port notification modes

You can fine-tune the exact notification model of the I/O completion port through the SetFile-CompletionNotificationModes API, which allows application developers to take advantage of additional, specific improvements that usually require code changes but can offer even more throughput. Three notification-mode optimizations are supported, which are listed in Table 6-4. Note that these modes are per file handle and cannot be changed after being set.

· · · ·	
Notification Mode	Meaning

Notification Mode	Meaning
Skip completion port on success (FILE_SKIP_ COMPLETION_PORT_ON_SUCCESS=1)	If the following three conditions are true, the I/O manager does not queue a completion entry to the port when it would ordinarily do so. First, a completion port must be associated with the file handle. Second, the file must be opened for asynchronous I/O. Third, the request must return success immediately without returning ERROR_ PENDING.

Continues...

 TABLE 6-4
 I/O completion port notification modes (continued)

Notification Mode	Meaning
Skip set event on handle (FILE_SKIP_SET_ EVENT_ON_HANDLE=2)	The I/O manager does not set the event for the file object if a request returns with a success code or the error returned is ERROR_PENDING and the function that is called is not a synchronous function. If an explicit event is provided for the request, it is still signaled.
Skip set user event on fast I/O (FILE_SKIP_SET_ USER_EVENT_ON_FAST_IO=4)	The I/O manager does not set the explicit event provided for the request if a request takes the fast I/O path and returns with a success code or the error returned is ERROR_PENDING and the function that is called is not a synchronous function.

## I/O prioritization

Without I/O priority, background activities like search indexing, virus scanning, and disk defragmenting can severely impact the responsiveness of foreground operations. For example, a user who launches an application or opens a document while another process is performing disk I/O will experience delays as the foreground task waits for disk access. The same interference also affects the streaming playback of multimedia content like music from a disk.

Windows includes two types of I/O prioritization to help foreground I/O operations get preference: priority on individual I/O operations and I/O bandwidth reservations.

#### I/O priorities

The Windows I/O manager internally includes support for five I/O priorities, as shown in Table 6-5, but only three of the priorities are used. (Future versions of Windows may support High and Low.)

I/O Priority	Usage
Critical	Memory manager
High	Not used
Normal	Normal application I/O
Low	Not used
Very Low	Scheduled tasks, SuperFetch, defragmenting, content indexing, background activities

TABLE 6-5 I/O priorities

I/O has a default priority of Normal, and the memory manager uses Critical when it wants to write dirty memory data out to disk under low-memory situations to make room in RAM for other data and code. The Windows Task Scheduler sets the I/O priority for tasks that have the default task priority to Very Low. The priority specified by applications that perform background processing is Very Low. All the Windows background operations, including Windows Defender scanning and desktop search indexing, use Very Low I/O priority.

## **Prioritization strategies**

Internally, the five I/O priorities are divided into two I/O prioritization modes, called *strategies*. These are the hierarchy prioritization and the idle prioritization strategies. Hierarchy prioritization deals with all the I/O priorities except Very Low. It implements the following strategy:


- All critical-priority I/O must be processed before any high-priority I/O.
- All high-priority I/O must be processed before any normal-priority I/O.
- All normal-priority I/O must be processed before any low-priority I/O.
- All low-priority I/O is processed after any higher-priority I/O.

As each application generates I/Os, IRPs are put on different I/O queues based on their priority, and the hierarchy strategy decides the ordering of the operations.

The idle prioritization strategy, on the other hand, uses a separate queue for non-idle priority I/O. Because the system processes all hierarchy prioritized I/O before idle I/O, it's possible for the I/Os in this queue to be starved, as long as there's even a single non-idle I/O on the system in the hierarchy priority strategy queue.

To avoid this situation, as well as to control back-off (the sending rate of I/O transfers), the idle strategy uses a timer to monitor the queue and guarantee that at least one I/O is processed per unit of time (typically, half a second). Data written using non-idle I/O priority also causes the cache manager to write modifications to disk immediately instead of doing it later and to bypass its read-ahead logic for read operations that would otherwise preemptively read from the file being accessed. The prioritization strategy also waits for 50 milliseconds after the completion of the last non-idle I/O in order to issue the next idle I/O. Otherwise, idle I/Os would occur in the middle of non-idle streams, causing costly seeks.

Combining these strategies into a virtual global I/O queue for demonstration purposes, a snapshot of this queue might look similar to Figure 6-26. Note that within each queue, the ordering is first-in, first-out (FIFO). The order in the figure is shown only as an example.





User-mode applications can set I/O priority on three different objects. The functions SetPriority-Class (with the PROCESS\_MODE\_BACKGROUND\_BEGIN value) and SetThreadPriority (with the THREAD\_ MODE\_BACKGROUND\_BEGIN value), set the priority for all the I/Os that are generated by either the entire process or specific threads (the priority is stored in the IRP of each request). These functions work only on the current process or thread and lower the I/O priority to Very Low. In addition, these also lower the scheduling priority to 4 and the memory priority to 1. The function SetFileInformationByHandle can set the priority for a specific file object (the priority is stored in the file object). Drivers can also set I/O priority directly on an IRP by using the IoSetIoPriorityHint API. **Note** The I/O priority field in the IRP and/or file object is a *hint*. There is no guarantee that the I/O priority will be respected or even supported by the different drivers that are part of the storage stack.


The two prioritization strategies are implemented by two different types of drivers. The hierarchy strategy is implemented by the storage *port* drivers, which are responsible for all I/Os on a specific port, such as ATA, SCSI, or USB. Only the ATA port driver (Ataport.sys) and USB port driver (Usbstor.sys) implement this strategy, while the SCSI and storage port drivers (Scsiport.sys and Storport.sys) do not.

**Note** All port drivers check specifically for Critical priority I/Os and move them ahead of their queues, even if they do not support the full hierarchy mechanism. This mechanism is in place to support critical memory manager paging I/Os to ensure system reliability.

This means that consumer mass storage devices such as IDE or SATA hard drives and USB flash disks will take advantage of I/O prioritization, while devices based on SCSI, Fibre Channel, and iSCSI will not.

On the other hand, it is the system storage class device driver (Classpnp.sys) that enforces the idle strategy, so it automatically applies to I/Os directed at all storage devices, including SCSI drives. This separation ensures that idle I/Os will be subject to back-off algorithms to ensure a reliable system during operation under high idle I/O usage and so that applications that use them can make forward progress. Placing support for this strategy in the Microsoft-provided class driver avoids performance problems that would have been caused by lack of support for it in legacy third-party port drivers.

Figure 6-27 displays a simplified view of the storage stack that shows where each strategy is implemented. See Chapter 12 in Part 2 for more information on the storage stack.





## I/O priority inversion avoidance

To avoid I/O priority inversion, in which a high I/O priority thread is starved by a low I/O priority thread, the executive resource (ERESOURCE) locking functionality uses several strategies. The ERESOURCE was picked for the implementation of I/O priority inheritance specifically because of its heavy use in file system and storage drivers, where most I/O priority inversion issues can appear. (See Chapter 8 in Part 2 for more on executive resources.)

If an ERESOURCE is being acquired by a thread with low I/O priority, and there are currently waiters on the ERESOURCE with normal or higher priority, the current thread is temporarily boosted to normal I/O priority by using the PsBoostThreadIo API, which increments the IoBoostCount in the ETHREAD structure. It also notifies Autoboost if the thread I/O priority was boosted or the boost was removed. (Refer to Chapter 4 for more on Autoboost.)

It then calls the IoBoostThreadIoPriority API, which enumerates all the IRPs queued to the target thread (recall that each thread has a list of pending IRPs) and checks which ones have a lower priority than the target priority (normal in this case), thus identifying pending idle I/O priority IRPs. In turn, the device object responsible for each of those IRPs is identified, and the I/O manager checks whether a priority callback has been registered, which driver developers can do through the IoRegisterPriority-Callback API and by setting the DO\_PRIORITY\_CALLBACK\_ENABLED flag on their device object. Depending on whether the IRP was a paging I/O, this mechanism is called *threaded boost* or *paging boost*. Finally, if no matching IRPs were found, but the thread has at least some pending IRPs, all are boosted regardless of device object or priority, which is called *blanket boosting*.

## I/O priority boosts and bumps

Windows uses a few other subtle modifications to normal I/O paths to avoid starvation, inversion, or otherwise unwanted scenarios when I/O priority is being used. Typically, these modifications are done by boosting I/O priority when needed. The following scenarios exhibit this behavior:

- When a driver is being called with an IRP targeted to a particular file object, Windows makes sure that if the request comes from kernel mode, the IRP uses normal priority even if the file object has a lower I/O priority hint. This is called a *kernel bump*.
- When reads or writes to the paging file are occurring (through IoPageRead and IoPageWrite), Windows checks whether the request comes from kernel mode and is not being performed on behalf of Superfetch (which always uses idle I/O). In this case, the IRP uses normal priority even if the current thread has a lower I/O priority. This is called a *paging bump*.

The following experiment will show you an example of Very Low I/O priority and how you can use Process Monitor to look at I/O priorities on different requests.

### EXPERIMENT: Very low versus normal I/O throughput

You can use the IO Priority sample application (included in this book's utilities) to look at the throughput difference between two threads with different I/O priorities. Follow these steps:

- 1. Launch loPriority.exe.
- 2. In the dialog box, under Thread 1, check the Low Priority check box.
- **3.** Click the **Start I/O** button. You should notice a significant difference in speed between the two threads, as shown in the following screenshot:

lo Priority		-		×
Thread 1			Start	1/0
Low Priority	I/O Speed: 624 bytes/sec		Cance	9/1/0
Thread 2				
Low Priority	I/O Speed: 1910161 bytes/sec			



**Note** If both threads run at low priority and the system is relatively idle, their throughput will be roughly equal to the throughput of a single normal I/O priority in the example. This is because low-priority I/Os are not artificially throttled or otherwise hindered if there isn't any competition from higher-priority I/O.

4. Open the process in Process Explorer and look at the low I/O priority thread to see the priorities:

Image	Perform	ance	Perf	ormance	Graph	Disk i	and Net	work	GPU Gr	aph
Threads	TO	P/IP	Sec	urity	Enviro	onment		Job	Strie	ngs
Count: 6										
TID	CPU	Cycles	Deta	Start Ad	dress					
9880				ntdl.dl!T	ppWorker	Thread				
10372					ppWorker					
9012 8164	4.71	466.54			ppWorker exelwWin		TOut	20		
11048	9.73	963.72			exe CloPr					_
4464	< 0.01	15	4,972	Io Priority	.exe IClo Pr	ionty Lig	ao me	ad		>
\$	< 0.01		4.972	Io Priority	exelCloff	ionty Lig			2444	
	< 0.01	4464		05-Oct-10			Stac		Module	
< Thread ID:	< 0.01	4464	)7 PM (	05-Oct-16					Module	
< Thread ID: Start Time;		4464 04:42:0	)7 PM (	05-Oct-10	5	ity:			Module	
< Thread ID: Start Time: State:		4464 04;42:0 WaitED	)7 PM ( kecutive	05-Oct-10	5 Base Prior	ity: riority:	Stac 4	k [	Module	
< Thread ID: Start Time: State: Kernel Time:		4464 04:42:0 Wait:E0 0:00:00	)7 PM ( kecutive	05-Oct-14	5 Base Prior Dynamic P	ity: riority: y:	Stac 4 6	k [	Module	
< Ihread ID: Start Time: State: State: Sernel Time: Jser Time:		4464 04:42:0 Wait:E0 0:00:00 0:00:00	07 PM ( recutive 0.000	05-Oct-10	5 Base Prior Dynamic P	ity: riority: y: riority:	Stac 4 6 Very	k [	Module	

5. You can also use Process Monitor to trace IO Priority's I/Os and look at their I/O priority hint. To do so, launch Process Monitor, configure a filter for IoPriority.exe, and repeat the experiment. In this application, each thread reads from a file named *\_File\_* concatenated with the thread ID.

6. Scroll down until you see a write to File\_1. You should see output similar to the following:

ile Edit Event Filter Tools	Options Help				
🚅 🖬   💸 🕅 🖾   🗧	🛆 🌚   🗉   🏘	) 📕 🕴 🎎 🔂 🍇 🗸 🔳			
Relative Time Process Name	PID Operation	Path	Result	Detail	
0:00:02.3156375 🔏 lo Priority.exe	12912 🛃 CreateFile	C:\Dev\loPriority\_File_7920	SUCCESS	Desired Access: Generic Read/Write, Delete, Disposition: Create,	Optior
00:00:02.3160181 🔏 lo Priority.exe	12912 🛃 WriteFile	C:\Dev\loPriority\_File_7920	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
10:00:02.3174006 🔏 lo Priority.exe	12912 🛃 WriteFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
0:00:02.3177795 🖉 lo Priority.exe	12912 🔜 ReadFile	C:\Dev\loPriority\_File_7920	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Very Low	
0:00:02.3181271 🔏 lo Priority.exe	12912 🛃 ReadFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
0:00:02.3183190 🔏 lo Priority.exe	12912 🛃 ReadFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
10:00:02.3185555 🖓 lo Priority.exe	12912 🛃 ReadFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
10:00:02.3187344 🚜 lo Priority.exe	12912 🔜 ReadFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
0:00:02.3189125 🖓 lo Priority.exe	12912 🛃 ReadFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
0:00:02.3191022 🚜 lo Priority.exe	12912 🔜 ReadFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
0:00:02.3192820 🖓 lo Priority.exe	12912 🛃 ReadFile	C:\Dev\loPriority\_File_13636	SUCCESS	Offset: 0, Length: 1,024, I/O Flags: Non-cached, Priority: Normal	
					)

7. Notice that I/Os directed at \_File\_7920 in the screenshot have a priority of very low. Looking at the Time of Day and Relative Time columns, you'll also notice that the I/Os are spaced half a second from each other, which is another sign of the idle strategy in action.

### EXPERIMENT: Performance analysis of I/O priority boosting/bumping

The kernel exposes several internal variables that can be queried through the undocumented SystemLowPriorityIoInformation system class available in NtQuerySystemInformation. However, even without writing or relying on such an application, you can use the local kernel debugger to view these numbers on your system. The following variables are available:


- IoLowPriorityReadOperationCount and IoLowPriorityWriteOperationCount
- IoKernellssuedIoBoostedCount
- IoPagingReadLowPriorityCount and IoPagingWriteLowPriorityCount
- IoPagingReadLowPriorityBumpedCount and IoPagingWriteLowPriorityBumpedCount
- IoBoostedThreadedIrpCount and IoBoostedPagingIrpCount
- IoBlanketBoostCount


You can use the dd memory-dumping command in the kernel debugger to see the values of these variables (all are 32-bit values).

#### Bandwidth reservation (scheduled file I/O)

Windows I/O bandwidth-reservation support is useful for applications that desire consistent I/O throughput. For example, using the SetFileBandwidthReservation call, a media player application can ask the I/O system to guarantee it the ability to read data from a device at a specified rate. If the device can deliver data at the requested rate and existing reservations allow it, the I/O system gives the application guidance as to how fast it should issue I/Os and how large the I/Os should be.

The I/O system won't service other I/Os unless it can satisfy the requirements of applications that have made reservations on the target storage device. Figure 6-28 shows a conceptual timeline of I/Os issued on the same file. The shaded regions are the only ones that will be available to other applications. If I/O bandwidth is already taken, new I/Os will have to wait until the next cycle.





Like the hierarchy prioritization strategy, bandwidth reservation is implemented at the port driver level, which means it is available only for IDE, SATA, or USB-based mass-storage devices.

## **Container notifications**

Container notifications are specific classes of events that drivers can register for through an asynchronous callback mechanism by using the IoRegisterContainerNotification API and selecting the notification class that interests them. Thus far, one such class is implemented in Windows: IoSession-StateNotification. This class allows drivers to have their registered callback invoked whenever a change in the state of a given session is registered. The following changes are supported:

- A session is created or terminated.
- A user connects to or disconnects from a session.
- A user logs on to or logs off from a session.

By specifying a device object that belongs to a specific session, the driver callback will be active only for that session. In contrast, by specifying a global device object (or no device object at all), the driver will receive notifications for all events on a system. This feature is particularly useful for devices that participate in the Plug and Play device redirection functionality that is provided through Terminal Services, which allows a remote device to be visible on the connecting host's Plug and Play manager bus as well (such as audio or printer device redirection). Once the user disconnects from a session with audio playback, for example, the device driver needs a notification in order to stop redirecting the source audio stream.

## **Driver Verifier**

Driver Verifier is a mechanism that can be used to help find and isolate common bugs in device drivers or other kernel-mode system code. Microsoft uses Driver Verifier to check its own device drivers as well as all device drivers that vendors submit for WHQL testing. Doing so ensures that the drivers submitted are compatible with Windows and free from common driver errors. (Although not described in this book, there is also a corresponding Application Verifier tool that has resulted in quality improvements for user-mode code in Windows.) **Note** Although Driver Verifier serves primarily as a tool to help device driver developers discover bugs in their code, it is also a powerful tool for system administrators experiencing crashes. Chapter 15 in Part 2 describes its role in crash analysis troubleshooting.

Driver Verifier consists of support in several system components: the memory manager, I/O manager, and HAL all have driver verification options that can be enabled. These options are configured using the Driver Verifier Manager (%SystemRoot%\System32\Verifier.exe). When you run Driver Verifier with no command-line arguments, it presents a wizard-style interface, as shown in Figure 6-29. (You can also enable and disable Driver Verifier, as well as display current settings, by using its commandline interface. From a command prompt, type **verifier /?** to see the switches.)

Select a task	
Create glandard settings	
Create gustom settings (for code developers)	
○ Relete existing settings	
Display existing settings	
O Display information about the currently verified drivers	
Click Next to create standard settings.	
You will then be asked to select the drivers to verify.	

FIGURE 6-29 Driver Verifier Manager.

Driver Verifier Manager distinguishes between two sets of settings: standard and additional. This is somewhat arbitrary, but the standard settings represent the more common options that should be probably selected for every driver being tested, while the additional settings represent those settings that are less common or specific to some types of drivers. Selecting **Create Custom Settings** from the main wizard's page shows all options with a column indicating which is standard and which is additional, as shown in Figure 6-30.

Regardless of which options are selected, Driver Verifier always monitors drivers selected for verification, looking for a number of illegal and boundary operations, including calling kernel-memory pool functions at invalid IRQL, double-freeing memory, releasing spinlocks inappropriately, not freeing timers, referencing a freed object, delaying shutdown for longer than 20 minutes, and requesting a zero-size memory allocation.




FIGURE 6-30 Driver Verifier settings.

Driver Verifier settings are stored in the registry under the HKLM\SYSTEM\CurrentControlSet\ Control\Session Manager\Memory Management key. The VerifyDriverLevel value contains a bitmask that represents the verification options that are enabled. The VerifyDrivers value contains the names of the drivers to monitor. (These values won't exist in the registry until you select drivers to verify in the Driver Verifier Manager.) If you choose to verify all drivers (which you should never do, since this will cause considerable system slowdown), VerifyDrivers is set to an asterisk (\*) character. Depending on the settings you have made, you might need to reboot the system for the selected verification to occur.

Early in the boot process, the memory manager reads the Driver Verifier registry values to determine which drivers to verify and which Driver Verifier options you enabled. (Note that if you boot in safe mode, any Driver Verifier settings are ignored.) Subsequently, if you've selected at least one driver for verification, the kernel checks the name of every device driver it loads into memory against the list of drivers you've selected for verification. For every device driver that appears in both places, the kernel invokes the VfLoadDriver function, which calls other internal Vf\* functions to replace the driver's references to a number of kernel functions with references to Driver Verifier–equivalent versions of those functions. For example, ExAllocatePool is replaced with a call to VerifierAllocatePool. The windowing system driver (Win32k.sys) also makes similar changes to use Driver Verifier–equivalent functions.

## I/O-related verification options

The various I/O-related verification options are as follows:

 I/O Verification When this option is selected, the I/O manager allocates IRPs for verified drivers from a special pool and their usage is tracked. In addition, the Driver Verifier crashes the system when an IRP is completed that contains an invalid status or when an invalid device object is passed to the I/O manager. This option also monitors all IRPs to ensure that drivers mark them correctly when completing them asynchronously, that they manage device-stack locations correctly, and that they delete device objects only once. In addition, the Verifier randomly stresses drivers by sending them fake power management and WMI IRPs, changing the order in which devices are enumerated, and adjusting the status of PnP and power IRPs when they complete to test for drivers that return incorrect status from their dispatch routines. Finally, the Verifier also detects incorrect re-initialization of remove locks while they are still being held due to pending device removal.

- DMA Checking DMA is a hardware-supported mechanism that allows devices to transfer data to or from physical memory without involving the CPU. The I/O manager provides several functions that drivers use to initiate and control DMA operations, and this option enables checks for the correct use of the functions and buffers that the I/O manager supplies for DMA operations.
- Force Pending I/O Requests For many devices, asynchronous I/Os complete immediately, so drivers may not be coded to properly handle the occasional asynchronous I/O. When this option is enabled, the I/O manager randomly returns STATUS\_PENDING in response to a driver's calls to IoCallDriver, which simulates the asynchronous completion of an I/O.
- IRP Logging This option monitors a driver's use of IRPs and makes a record of IRP usage, which is stored as WMI information. You can then use the Dc2wmiparser.exe utility in the WDK to convert these WMI records to a text file. Note that only 20 IRPs for each device will be recorded—each subsequent IRP will overwrite the least recently added entry. After a reboot, this information is discarded, so Dc2wmiparser.exe should be run if the contents of the trace are to be analyzed later.


## Memory-related verification options


The following are memory-related verification options supported by Driver Verifier. (Some are also related to I/O operations.)

## **Special Pool**

Selecting the Special Pool option causes the pool allocation routines to bracket pool allocations with an invalid page so that references before or after the allocation will result in a kernel-mode access violation, thus crashing the system with the finger pointed at the buggy driver. Special pool also causes some additional validation checks to be performed when a driver allocates or frees memory. With special pool enabled, the pool allocation routines allocate a region of kernel memory for Driver Verifier to use. Driver Verifier redirects memory allocation requests that drivers under verification make to the special pool area rather than to the standard kernel-mode memory pools. When a device driver allocates memory from special pool, Driver Verifier rounds up the allocation to an even-page boundary. Because Driver Verifier brackets the allocated page with invalid pages, if a device driver attempts to read or write past the end of the buffer, the driver will access an invalid page, and the memory manager will raise a kernel-mode access violation.

Figure 6-31 shows an example of the special pool buffer that Driver Verifier allocates to a device driver when Driver Verifier checks for overrun errors.





By default, Driver Verifier performs overrun detection. It does this by placing the buffer that the device driver uses at the end of the allocated page and filling the beginning of the page with a random pattern. Although the Driver Verifier Manager doesn't let you specify underrun detection, you can set this type of detection manually by adding the DWORD registry value PoolTagOverruns to the HKLM\ SYSTEM\CurrentControlSet\Control\Session Manager\Memory Management key and setting it to 0 (or by running the Gflags.exe utility and selecting the **Verify Start** option in the Kernel Special Pool Tag section instead of the default option, Verify End). When Windows enforces underrun detection, Driver Verifier allocates the driver's buffer at the beginning of the page rather than at the end.

The overrun-detection configuration includes some measure of underrun detection as well. When the driver frees its buffer to return the memory to Driver Verifier, Driver Verifier ensures that the pattern preceding the buffer hasn't changed. If the pattern is modified, the device driver has underrun the buffer and written to memory outside the buffer.

Special pool allocations also check to ensure that the processor IRQL at the time of an allocation and deallocation is legal. This check catches an error that some device drivers make: allocating pageable memory from an IRQL at DPC/dispatch level or above.

You can also configure special pool manually by adding the DWORD registry value PoolTag in the HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Memory Management key, which represents the allocation tags the system uses for special pool. Thus, even if Driver Verifier isn't configured to verify a particular device driver, if the tag the driver associates with the memory it allocates matches what is specified in the PoolTag registry value, the pool allocation routines will allocate the memory from special pool. If you set the value of PoolTag to 0x2a or to the wildcard (\*), all memory that drivers allocate will be from special pool, provided there's enough virtual and physical memory (drivers will revert to allocating from regular pool if there aren't enough free pages).

#### **Pool tracking**

If pool tracking is enabled, the memory manager checks at driver unload time whether the driver freed all the memory allocations it made. If it didn't, it crashes the system, indicating the buggy driver. Driver Verifier also shows general pool statistics on the Driver Verifier Manager's Pool Tracking tab (accessible from the main wizard UI by selecting **Display Information About the Currently Verified Drivers**  and selecting **Next** twice). You can also use the !verifier kernel debugger command. This command shows more information than Driver Verifier and is useful to driver writers.

Pool tracking and special pool cover not only explicit allocation calls, such as ExAllocatePoolWith-Tag, but also calls to other kernel APIs that implicitly allocate memory from pools: IoAllocateMdl, IoAllocateIrp, and other IRP allocation calls; various Rtl string APIs; and IoSetCompletionRoutineEx.

Another driver verified function enabled by the Pool Tracking option pertains to pool quota charges. The call to ExAllocatePoolWithQuotaTag charges the current process's pool quota for the number of bytes allocated. If such a call is made from a DPC routine, the process that is charged is unpredictable because DPC routines may execute in the context of any process. The Pool Tracking option checks for calls to this routine from the DPC routine context.

Driver Verifier can also perform locked memory page tracking, which additionally checks for pages that have been left locked after an I/O operation completes and generates a DRIVER\_LEFT\_LOCKED\_ PAGES\_IN\_PROCESS crash code instead of PROCESS\_HAS\_LOCKED\_PAGES—the former indicates the driver responsible for the error as well as the function responsible for the locking of the pages.

## Force IRQL Checking

One of the most common device driver bugs occurs when a driver accesses pageable data or code when the processor on which the device driver is executing is at an elevated IRQL. The memory manager can't service a page fault when the IRQL is DPC/dispatch level or above. The system often doesn't detect instances of a device driver accessing pageable data when the processor is executing at a high IRQL level because the pageable data being accessed happens to be physically resident at the time. At other times, however, the data might be paged out, which results in a system crash with the stop code IRQL\_NOT\_LESS\_OR\_EQUAL (that is, the IRQL wasn't less than or equal to the level required for the operation attempted—in this case, accessing pageable memory).

Although testing device drivers for this kind of bug is usually difficult, Driver Verifier makes it easy. If you select the Force IRQL Checking option, Driver Verifier forces all kernel-mode pageable code and data out of the system working set whenever a device driver under verification raises the IRQL. The internal function that does this is MiTrimAllSystemPagableMemory. With this setting enabled, whenever a device driver under verification accesses pageable memory when the IRQL is elevated, the system instantly detects the violation, and the resulting system crash identifies the faulty driver.

Another common driver crash that results from incorrect IRQL usage occurs when synchronization objects are part of data structures that are paged and then waited on. Synchronization objects should never be paged because the dispatcher needs to access them at an elevated IRQL, which would cause a crash. Driver Verifier checks whether any of the following structures are present in pageable memory: KTIMER, KMUTEX, KSPIN\_LOCK, KEVENT, KSEMAPHORE, ERESOURCE, and FAST\_MUTEX.

### Low Resources Simulation

Enabling Low Resources Simulation causes Driver Verifier to randomly fail memory allocations that verified device drivers perform. In the past, developers wrote many device drivers under the assumption that kernel memory would always be available, and that if memory ran out, the device driver

didn't have to worry about it because the system would crash anyway. However, because low-memory conditions can occur temporarily, and today's mobile devices are not as powerful as larger machines, it's important that device drivers properly handle allocation failures that indicate kernel memory is exhausted.

The driver calls that will be injected with random failures include the functions ExAllocatePool\*, MmProbeAndLockPages, MmMapLockedPagesSpecifyCache, MmMapIoSpace, MmAllocateContiguous-Memory, MmAllocatePagesForMdl, IoAllocateIrp, IoAllocateMdl, IoAllocateWorkItem, IoAllocateErrorLogEntry, IOSetCompletionRoutineEx, and various Rtl string APIs that allocate from the pool. Driver Verifier also fails some allocations made by kernel GDI functions (see the WDK documentation for a complete list). Additionally, you can specify the following:

- The probability that allocation will fail This is 6 percent by default.
- Which applications should be subject to the simulation All are by default.
- Which pool tags should be affected All are by default.
- What delay should be used before fault injection starts The default is 7 minutes after the system boots, which is enough time to get past the critical initialization period in which a low-memory condition might prevent a device driver from loading.

You can change these customizations with command line options to verifier.exe.

After the delay period, Driver Verifier starts randomly failing allocation calls for device drivers it is verifying. If a driver doesn't correctly handle allocation failures, this will likely show up as a system crash.

### Systematic Low Resources Simulation

Similar to the Low Resources Simulation option, this option fails certain calls to the kernel and *Ndis.Sys* (for network drivers), but does so in a systematic way, by examining the call stack at the point of failure injection. If the driver handles the failure correctly, that call stack will not be failure injected again. This allows the driver writer to see issues in a systematic way, fix a reported issue, and then move on to the next. Examining call stacks is a relatively expensive operation, therefore verifying more than a single driver at a time with this setting is not recommended.

### **Miscellaneous checks**

Some of the checks that Driver Verifier calls *miscellaneous* allow it to detect the freeing of certain system structures in the pool that are still active. For example, Driver Verifier will check for:

- Active work items in freed memory A driver calls ExFreePool to free a pool block in which one or more work items queued with IoQueueWorkItem are present.
- Active resources in freed memory A driver calls ExFreePool before calling ExDelete-Resource to destroy an ERESOURCE object.
- Active look-aside lists in freed memory A driver calls ExFreePool before calling ExDelete-NPagedLookasideList or ExDeletePagedLookasideList to delete the look-aside list.

Finally, when verification is enabled, Driver Verifier performs certain automatic checks that cannot be individually enabled or disabled. These include the following:

- Calling MmProbeAndLockPages or MmProbeAndLockProcessPages on an MDL having incorrect flags. For example, it is incorrect to call MmProbeAndLockPages for an MDL that was set up by calling MmBuildMdlForNonPagedPool.
- Calling MmMapLockedPages on an MDL having incorrect flags. For example, it is incorrect to call MmMapLockedPages for an MDL that is already mapped to a system address. Another example of incorrect driver behavior is calling MmMapLockedPages for an MDL that was not locked.
- Calling MmUnlockPages or MmUnmapLockedPages on a partial MDL (created by using IoBuild-PartialMdl).
- Calling MmUnmapLockedPages on an MDL that is not mapped to a system address.
- Allocating synchronization objects such as events or mutexes from NonPagedPoolSession memory.

Driver Verifier is a valuable addition to the arsenal of verification and debugging tools available to device driver writers. Many device drivers that first ran with Driver Verifier had bugs that Driver Verifier was able to expose. Thus, Driver Verifier has resulted in an overall improvement in the quality of all kernel-mode code running in Windows.

# The Plug and Play manager

The PnP manager is the primary component involved in supporting the ability of Windows to recognize and adapt to changing hardware configurations. A user doesn't need to understand the intricacies of hardware or manual configuration to install and remove devices. For example, it's the PnP manager that enables a running Windows laptop that is placed on a docking station to automatically detect additional devices located in the docking station and make them available to the user.

Plug and Play support requires cooperation at the hardware, device driver, and operating system levels. Industry standards for the enumeration and identification of devices attached to buses are the foundation of Windows Plug and Play support. For example, the USB standard defines the way that devices on a USB bus identify themselves. With this foundation in place, Windows Plug and Play support provides the following capabilities:

- The PnP manager automatically recognizes installed devices, a process that includes enumerating devices attached to the system during a boot and detecting the addition and removal of devices as the system executes.
- Hardware resource allocation is a role the PnP manager fills by gathering the hardware resource requirements (interrupts, I/O memory, I/O registers, or bus-specific resources) of the devices attached to a system and, in a process called *resource arbitration*, optimally assigning resources so that each device meets the requirements necessary for its operation. Because hardware devices can be added to the system after boot-time resource assignment, the PnP manager must also be able to reassign resources to accommodate the needs of dynamically added devices.

- Loading appropriate drivers is another responsibility of the PnP manager. The PnP manager determines, based on the identification of a device, whether a driver capable of managing the device is installed on the system, and if one is, it instructs the I/O manager to load it. If a suitable driver isn't installed, the kernel-mode PnP manager communicates with the user-mode PnP manager to install the device, possibly requesting the user's assistance in locating a suitable driver.
- The PnP manager also implements application and driver mechanisms for the detection of hardware configuration changes. Applications or drivers sometimes require a specific hardware device to function, so Windows includes a means for them to request notification of the presence, addition, or removal of devices.
- It provides a place for storing device state, and it participates in system setup, upgrade, migration, and offline image management.
- It supports network connected devices, such as network projectors and printers, by allowing specialized bus drivers to detect the network as a bus and create device nodes for the devices running on it.

# Level of Plug and Play support

Windows aims to provide full support for Plug and Play, but the level of support possible depends on the attached devices and installed drivers. If a single device or driver doesn't support Plug and Play, the extent of Plug and Play support for the system can be compromised. In addition, a driver that doesn't support Plug and Play might prevent other devices from being usable by the system. Table 6-6 shows the outcome of various combinations of devices and drivers that can and can't support Plug and Play.

Type of Device	Plug-and-Play Driver	Non-Plug and Play Driver
Plug and play	Full plug and play	No plug and play
Non–plug and play	Possible partial plug and play	No plug and play

A device that isn't Plug and Play–compatible is one that doesn't support automatic detection, such as a legacy ISA sound card. Because the operating system doesn't know where the hardware physically lies, certain operations—such as laptop undocking, sleep, and hibernation—are disallowed. However, if a Plug and Play driver is manually installed for the device, the driver can at least implement PnP manager–directed resource assignment for the device.

Drivers that aren't Plug and Play–compatible include legacy drivers, such as those that ran on Windows NT 4. Although these drivers might continue to function on later versions of Windows, the PnP manager can't reconfigure the resources assigned to such devices in the event that resource reallocation is necessary to accommodate the needs of a dynamically added device. For example, a device might be able to use I/O memory ranges A and B, and during the boot, the PnP manager assigns it range A. If a device that can use only A is attached to the system later, the PnP manager can't direct the first device's driver to reconfigure itself to use range B. This prevents the second device from obtaining required resources, which results in the device being unavailable for use by the system. Legacy drivers also impair a machine's ability to sleep or hibernate. (See the section "The power manager" later in this chapter for more details.)

### **Device enumeration**

Device enumeration occurs when the system boots, resumes from hibernation, or is explicitly instructed to do so (for example, by clicking Scan for Hardware Changes in the Device Manager UI). The PnP manager builds a device tree (described momentarily) and compares it to its known stored tree from a previous enumeration, if any. For a boot or resume from hibernation, the stored device tree is empty. Newly discovered devices and removed devices require special treatment, such as loading appropriate drivers (for a newly discovered device) and notifying drivers of a removed device.

The PnP manager begins device enumeration with a virtual bus driver called *Root*, which represents the entire computer system and acts as the bus driver for non–Plug and Play drivers and the HAL. The HAL acts as a bus driver that enumerates devices directly attached to the motherboard as well as system components such as batteries. Instead of actually enumerating, however, the HAL relies on the hardware description the Setup process recorded in the registry to detect the primary bus (in most cases, a PCI bus) and devices such as batteries and fans.

The primary bus driver enumerates the devices on its bus, possibly finding other buses, for which the PnP manager initializes drivers. Those drivers in turn can detect other devices, including other subsidiary buses. This recursive process of enumeration, driver loading (if the driver isn't already loaded), and further enumeration proceeds until all the devices on the system have been detected and configured.

As the bus drivers report detected devices to the PnP manager, the PnP manager creates an internal tree called a *device tree* that represents the relationships between devices. Nodes in the tree are called *device nodes*, or *devnodes*. A devnode contains information about the device objects that represent the device as well as other Plug and Play–related information stored in the devnode by the PnP manager. Figure 6-32 shows an example of a simplified device tree. A PCI bus serves as the system's primary bus, which USB, ISA, and SCSI buses are connected to.




FIGURE 6-32 An example of a device tree.

The Device Manager utility, which is accessible from the Computer Management snap-in in the Programs/Administrative Tools folder of the Start menu (and also from the Device Manager link of the System utility in Control Panel), shows a simple list of devices present on a system in its default configuration. You can also select the Devices by Connection option from the Device Manager's View menu to see the devices as they relate to the device tree. Figure 6-33 shows an example of the Device Manager's Devices by connection view.




FIGURE 6-33 Device Manager, with the device tree shown.

#### **EXPERIMENT:** Dumping the device tree

A more detailed way to view the device tree than using Device Manager is to use the !devnode kernel debugger command. Specifying 0 1 as command options dumps the internal device tree devnode structures, indenting entries to show their hierarchical relationships, as shown here:

```
lkd> !devnode 0 1
Dumping IopRootDeviceNode (= 0x85161a98)
DevNode 0x85161a98 for PD0 0x84d10390
InstancePath is "HTREE\ROOT\0"
State = DeviceNodeStarted (0x308)
Previous State = DeviceNodeEnumerateCompletion (0x30d)
DevNode 0x8515bea8 for PD0 0x8515b030
DevNode 0x8515c698 for PD0 0x8515c820
InstancePath is "Root\ACPI_HAL\0000"
State = DeviceNodeStarted (0x308)
```


```
Previous State = DeviceNodeEnumerateCompletion (0x30d)
DevNode 0x84d1c5b0 for PDO 0x84d1c738
  InstancePath is "ACPI_HAL\PNP0C08\0"
  ServiceName is "ACPI"
  State = DeviceNodeStarted (0x308)
  Previous State = DeviceNodeEnumerateCompletion (0x30d)
  DevNode 0x85ebf1b0 for PDO 0x85ec0210
    InstancePath is "ACPI\GenuineIntel_-_x86_Family_6_Model_15\_0"
    ServiceName is "intelppm"
    State = DeviceNodeStarted (0x308)
    Previous State = DeviceNodeEnumerateCompletion (0x30d)
  DevNode 0x85ed6970 for PDO 0x8515e618
    InstancePath is "ACPI\GenuineIntel_-_x86_Family_6_Model_15\_1"
    ServiceName is "intelppm"
    State = DeviceNodeStarted (0x308)
    Previous State = DeviceNodeEnumerateCompletion (0x30d)
  DevNode 0x85ed75c8 for PDO 0x85ed79e8
    InstancePath is "ACPI\ThermalZone\THM_"
    State = DeviceNodeStarted (0x308)
    Previous State = DeviceNodeEnumerateCompletion (0x30d)
  DevNode 0x85ed6cd8 for PDO 0x85ed6858
    InstancePath is "ACPI\pnp0c14\0"
    ServiceName is "WmiAcpi"
    State = DeviceNodeStarted (0x308)
    Previous State = DeviceNodeEnumerateCompletion (0x30d)
  DevNode 0x85ed7008 for PD0 0x85ed6730
    InstancePath is "ACPI\ACPI0003\2&daba3ff&2"
    ServiceName is "CmBatt"
    State = DeviceNodeStarted (0x308)
    Previous State = DeviceNodeEnumerateCompletion (0x30d)
  DevNode 0x85ed7e60 for PDO 0x84d2e030
    InstancePath is "ACPI\PNP0C0A\1"
    ServiceName is "CmBatt"
```


...

Information shown for each devnode includes the InstancePath, which is the name of the device's enumeration registry key stored under HKLM\SYSTEM\CurrentControlSet\Enum, and the ServiceName, which corresponds to the device's driver registry key under HKLM\SYSTEM\ CurrentControlSet\Services. To see the resources assigned to each devnode, such as interrupts, ports, and memory, specify 0 3 as the command options for the !devnode command.

### **Device stacks**

As devnodes are created by the PnP manager, driver objects and device objects are created to manage and logically represent the linkage between the devices that make up the devnode. This linkage is called a *device stack* (briefly discussed in the "IRP flow" section earlier in this chapter). You can think of the device stack as an ordered list of device object/driver pairs. Each device stack is built from the bottom to the top. Figure 6-34 shows an example of a devnode (a reprint of Figure 6-6), with seven device objects (all managing the same physical device). Each devnode contains at least two devices (PDO and FDO), but can contain more device objects. A device stack consists of the following:





- A physical device object (PDO) that the PnP manager instructs a bus driver to create when the bus driver reports the presence of a device on its bus during enumeration. The PDO represents the physical interface to the device and is always at the bottom of the device stack.
- One or more optional filter device objects (FiDOs) that layer between the PDO and the functional device object (FDO; described in the next bullet), called *lower filters* (the term "lower" is always considered in relation to the FDO). These may be used for intercepting IRPs coming out of the FDO and towards the bus driver (which may be of interest to bus filters).
- One (and only one) functional device object (FDO) that is created by the driver, which is called a *function driver*, that the PnP manager loads to manage a detected device. An FDO represents the logical interface to a device, having the most "intimate" knowledge of the functionality provided by the device. A function driver can also act as a bus driver if devices are attached to the device represented by the FDO. The function driver often creates an interface (essentially a name) to the FDO's corresponding PDO so that applications and other drivers can open the device and interact with it. Sometimes function drivers are divided into a separate class/port driver and miniport driver that work together to manage I/O for the FDO.
- One or more optional FiDOs that layer above the FDO, called upper filters. These get first crack at an IRP header for the FDO.

**Note** The various device objects have different names in Figure 6-34 to make them easier to describe. However, they are all instances of DEVICE\_OBJECT structures.

Device stacks are built from the bottom up and rely on the I/O manager's layering functionality, so IRPs flow from the top of a device stack toward the bottom. However, any level in the device stack can choose to complete an IRP, as described in the "IRP flow" section earlier in this chapter.

### Device-stack driver loading

How does the PnP manager find the correct drivers as part of building the device stack? The registry has this information scattered in three important keys (and their subkeys), shown in Table 6-7. (Note that CCS is short for CurrentControlSet.)

Registry Key	Short Name	Description
HKLM\System\CCS\Enum	Hardware key	Settings for known hardware devices
HKLM\System\CCS\Control\Class	Class key	Settings for device types
HKLM\System\CCS\Services	Software key	Settings for drivers

 TABLE 6-7
 Important registry keys for plug-and-play driver loading

When a bus driver performs device enumeration and discovers a new device, it first creates a PDO to represent the existence of the physical device that has been detected. Next, it informs the PnP manager by calling IoInvalidateDeviceRelations (documented in the WDK) with the BusRelations enumeration value and the PDO, indicating to the PnP manager that a change on its bus has been detected. In response, the PnP manager asks the bus driver (through an IRP) for the device identifier.

The identifiers are bus-specific; for example, a USB device identifier consists of a vendor ID (VID) for the hardware vendor that made the device and a product ID (PID) that the vendor assigned to the device. For a PCI device, a similar vendor ID is required, along with a device ID, to uniquely identify the device within a vendor (plus some optional components; see the WDK for more information on device ID formats). Together, these IDs form what Plug and Play calls a *device ID*. The PnP manager also queries the bus driver for an instance ID to help it distinguish different instances of the same hardware. The instance ID can describe either a bus-relative location (for example, the USB port) or a globally unique descriptor (for example, a serial number).

The device ID and instance ID are combined to form a device instance ID (DIID), which the PnP manager uses to locate the device's key under the Hardware key shown in Table 6-7. The subkeys under that key have the form <Enumerator>\<Device ID>\<Instance ID>, where the enumerator is a bus driver, the device ID is a unique identifier for a type of device, and the instance ID uniquely identifies different instances of the same hardware.

Figure 6-35 presents an example of an enumeration subkey of an Intel display card. The device's key contains descriptive data and includes values named Service and ClassGUID (which are obtained from a driver's INF file upon installation) that help the PnP manager locate the device's drivers as follows:

- The Service value is looked up in the Software key, and there the path to the driver (SYS file) is stored in the ImagePath value. Figure 6-36 shows the Software subkey named *igfx* (from Figure 6-35) where the Intel display driver can be located. The PnP manager will load that driver (if it's not already loaded), call its add-device routine, and there the driver will create the FDO.
- If a value named LowerFilters is present, it contains a multiple string list of drivers to load as lower filters, which can be located in the Software subkey. The PnP manager loads these drivers before loading the driver associated with the Service value above.

	SAM		^	Name	Туре	Data
	SECL	12.1	T-0	ab (Default)	REG_SZ	(value not set)
	SOFT		RE	200 Capabilities	REG DWORD	0x00000000 (0)
	SYST			ab ClassGUID	REG SZ	{4d36e968-e325-11ce-bfc1-08002be10318
-	_		ationBroker	ab CompatibleIDs	REG MULTI SZ	PCI/VEN 8086&DEV 0A26&REV 09 PCI/V
1	-		rolSet001	ConfigFlags	REG DWORD	0x00000000 (0)
	0	_	entControlSet	ab ContainerID	REG SZ	{0000000-0000-ffff-fffffffffffff
	2 -		ontrol	ab DeviceDesc	REG SZ	
	Y .	Er	num		-	@oem79.inf,%ihswgt3ut%;Intel(R) HD G
			(30ebfbf8-df5f-4d4d-9fc5-a26c7fd1df4a)	ab Driver	REG_SZ	{4d36e968-e325-11ce-bfc1-08002be1031
	13	-	{4E781CFC-87EE-459B-A319-9B0531EB7485}	ab HardwarelD	REG_MULTI_SZ	PCI\VEN_8086&DEV_0A26&SUBSYS_0005
	1.3		{5d624f94-8850-40c3-a3fa-a4fd2080baf3}	ab LocationInformation	REG_SZ	@System32\drivers\pci.sys,#65536;PCI b
			{5E9A8CDC-14AB-4609-A017-68BCE594AB68}	ab Mfg	REG_SZ	@oem79.inf,%intel%Intel Corporation
		-	(8e7bd593-6e6c-4c52-86a6-77175494dd8e)	ab ParentldPrefix	REG_SZ	48:17a0b3558:0
			ACPI	ab Service	REG_SZ	igfx
		-	ACPI_HAL			
			BTH			
			BTHENUM			
			COMPOSITEBUS			
			DISPLAY			
			HDAUDIO			
			HID			
		-	HTREE			
			PCI			
		2	VEN_11AB&DEV_2B38&SUBSYS_045E0001&REV_00			
		2	VEN_8086&DEV_0A04&SUBSYS_0A041414&REV_09			
		>	VEN_8086&DEV_0A0C&SUBSYS_0A0C8086&REV_0			
	1	Y	VEN_8086&DEV_0A26&SUBSYS_00051414&REV_09 3&11583659&0&10			
		3	VEN_8086&DEV_9C03&SUBSYS_9C031414&REV_04			

FIGURE 6-35 Example of a Hardware subkey.

>-	iaLPSSi_GPIO	^	Name	Туре	Data
> -	iaLPSSi_I2C		ab (Default)	REG SZ	(value not set)
3-	iaStorAV		110 ErrorControl	REG DWORD	0x00000000 (0)
3-	iaStorV		ab Group	REG_SZ	Video
2 -	ibbus				
3-	icssvc		ab ImagePath	REG_EXPAND_SZ	\SystemRoot\system32\DRIVERS\igdkmd64.sys
54	igfx		(ab) Owners	REG_MULTI_SZ	oem79.inf
3-	igfxCUIService2.0.0.0		86 Start	REG_DWORD	0x0000003 (3)
3-	IKEEXT		100 Tag	REG_DWORD	0x00000004 (4)
-	IndirectKmd		<b>111</b> Туре	REG_DWORD	0x00000001 (1)
3-	inetaccs				

FIGURE 6-36 Example of a Software subkey.

- If a value named UpperFilters is present, it indicates a list of driver names (under the Software key, similar to LowerFilters) which the PnP manager will load in much the same way after it loads the driver pointed to by the Service value.
- The ClassGUID value represents the general type of device (display, keyboard, disk, etc.), and points to a subkey under the Class key (from Table 6-7). The key represents settings applicable to all drivers for that type of device. In particular, if the values LowerFilters and/or UpperFilters are present, they are treated just like the same values in the Hardware key of the particular device. This allows, for example, the loading of an upper filter for keyboard devices, regardless of the particular keyboard or the vendor. Figure 6-37 shows the class key for keyboard devices. Notice the friendly name (Keyboard), although the GUID is what matters (the decision on the particular class is provided as part of the installation INF file). An UpperFilters value exists, listing the system provided keyboard class driver that always loads as part of any keyboard deviced deviced. (You can also see the IconPath value that is used as the icon for the keyboard type in the Device Manager's UI.)

4d36e967-e325-11ce-bfc1-08002be ^	Name	Туре	Data
{4d36e968-e325-11ce-bfc1-08002be	ab (Default)	REG_SZ	(value not set)
4d36e969-e325-11ce-bfc1-08002be	ab Class	REG_SZ	Keyboard
{4d36e96a-e325-11ce-bfc1-08002be	ab ClassDesc	REG SZ	@%SystemRoot%\System32\SysClass.Dll3002
{4d36e96b-e325-11ce-bfc1-08002be	ab IconPath	REG MULTI SZ	%SystemRoot%\System32\setupapi.dll3
4d36e96c-e325-11ce-bfc1-08002be	ab NoInstallClass	REG SZ	1
{4d36e96d-e325-11ce-bfc1-08002be	ab UpperFilters	REG MULTI SZ	kbdclass
{4d36e96e-e325-11ce-bfc1-08002be	opperniters	NEO_MOLTI_SZ	KDOCIASS

FIGURE 6-37 The keyboard class key.

To summarize, the order of driver loading for a devnode is as follows:

- 1. The bus driver is loaded, creating the PDO.
- **2.** Any lower filters listed in the Hardware instance key are loaded, in the order listed (multi string), creating their filter device objects (FiDOs in Figure 6-34).
- **3.** Any lower filters listed in the corresponding Class key are loaded in the order listed, creating their FiDOs.
- 4. The driver listed in the Service value is loaded, creating the FDO.
- **5.** Any upper filters listed in the Hardware instance key are loaded, in the order listed, creating their FiDOs.
- **6.** Any upper filters listed in the corresponding Class key are loaded in the order listed creating their FiDOs.

To deal with multifunction devices (such as all-in-one printers or cell phones with integrated camera and music player functionalities), Windows also supports a container ID property that can be associated with a devnode. The container ID is a GUID that is unique to a single instance of a physical device and shared between all the function devnodes that belong to it, as shown in Figure 6-38.



• Fax

FIGURE 6-38 All-in-one printer with a unique ID as seen by the PnP manager.

The container ID is a property that, similar to the instance ID, is reported back by the bus driver of the corresponding hardware. Then, when the device is being enumerated, all devnodes associated with the same PDO share the container ID. Because Windows already supports many buses out of the box—such as PnP-X, Bluetooth, and USB—most device drivers can simply return the bus-specific ID, from which Windows will generate the corresponding container ID. For other kinds of devices or buses, the driver can generate its own unique ID through software.

Finally, when device drivers do not supply a container ID, Windows can make educated guesses by querying the topology for the bus, when that's available, through mechanisms such as ACPI. By understanding whether a certain device is a child of another, and whether it is removable, hot-pluggable, or user-reachable (as opposed to an internal motherboard component), Windows is able to assign container IDs to device nodes that reflect multifunction devices correctly.

The final end-user benefit of grouping devices by container IDs is visible in the Devices and Printers UI. This feature is able to display the scanner, printer, and faxing components of an all-in-one printer as a single graphical element instead of three distinct devices. For example, in Figure 6-39, the HP 6830 printer/fax/scanner is identified as a single device.





FIGURE 6-39 The Devices and Printers Control Panel applet.

### EXPERIMENT: Viewing detailed devnode information in Device Manager

The Device Manager applet shows detailed information about a device node on its Details tab. The tab allows you to view an assortment of fields, including the devnode's device instance ID, hardware ID, service name, filters, and power capabilities.

The following screen shows the selection combo box of the Details tab expanded to reveal some of the types of information you can access:



# Driver support for Plug and Play

To support Plug and Play, a driver must implement a Plug and Play dispatch routine (IRP\_MJ\_PNP), a power-management dispatch routine (IRP\_MJ\_POWER, described in the section "The power manager" later in this chapter), and an add-device routine. Bus drivers must support Plug and Play requests that are different than the ones that function or filter drivers support, however. For example, when the PnP manager guides device enumeration during the system boot, it asks bus drivers for a description of the devices that they find on their respective buses through PnP IRPs.

Function and filter drivers prepare to manage their devices in their add-device routines, but they don't actually communicate with the device hardware. Instead, they wait for the PnP manager to send a start-device command (IRP\_MN\_START\_DEVICE minor PnP IRP code) for the device to their Plug and Play dispatch routine. Before sending the start-device command, the PnP manager performs resource arbitration to decide what resources to assign the device. The start-device command includes the resource assignment that the PnP manager determines during resource arbitration. When a driver receives a start-device command, it can configure its device to use the specified resources. If an application tries to open a device that hasn't finished starting, it receives an error indicating that the device does not exist.

After a device has started, the PnP manager can send the driver additional Plug and Play commands, including ones related to the device's removal from the system or to resource reassignment. For example, when the user invokes the remove/eject device utility, shown in Figure 6-40 (accessible by clicking the USB connector icon in the taskbar notification area), to tell Windows to eject a USB flash drive, the PnP manager sends a query-remove notification to any applications that have registered for Plug and Play notifications for the device. Applications typically register for notifications on their handles, which they close during a query-remove notification. If no applications veto the query-remove request, the PnP manager sends a query-remove command to the driver that owns the device being ejected (IRP\_MN\_QUERY\_REMOVE\_DEVICE). At that point, the driver has a chance to deny the removal or to ensure that any pending I/O operations involving the device have completed, and to begin rejecting further I/O requests aimed at the device. If the driver agrees to the remove request and no open handles to the device remain, the PnP manager next sends a remove command to the driver (IRP\_MN\_REMOVE\_DEVICE) to request that the driver stop accessing the device and release any resources the driver has allocated on behalf of the device.

	Open Devices and Printers	
-	Eject USB 2.0 FD	
	- (G:)	

FIGURE 6-40 The remove/eject device utility.

When the PnP manager needs to reassign a device's resources, it first asks the driver whether it can temporarily suspend further activity on the device by sending the driver a query-stop command (IRP\_MN\_QUERY\_STOP\_DEVICE). The driver either agrees to the request (if doing so won't cause data loss or corruption) or denies the request. As with a query-remove command, if the driver agrees to the request, the driver completes pending I/O operations and won't initiate further I/O requests for the device that can't be aborted and subsequently restarted. The driver typically queues new I/O requests so that the resource reshuffling is transparent to applications currently accessing the device. The PnP manager then sends the driver a stop command (IRP\_MN\_STOP\_DEVICE). At that point, the PnP manager can direct the driver to assign different resources to the device and once again send the driver a start-device command for the device.

The various Plug and Play commands essentially guide a device through an operational state machine, forming a well-defined state-transition table, which is shown in Figure 6-41. (The state diagram reflects the state machine implemented by function drivers. Bus drivers implement a more complex state machine.) Each transition in Figure 6-41 is marked by its minor IRP constant name without the IRP\_MN\_ prefix. One state that we haven't discussed is the one that results from the PnP manager's command (IRP\_MN\_SURPRISE\_REMOVAL). This command results when either a user removes a device without warning, as when the user ejects a PCMCIA card without using the remove/eject utility, or the device fails. The command tells the driver to immediately cease all interaction with the device because the device is no longer attached to the system and to cancel any pending I/O requests. Device detected, driver loaded, DriverEntry called, AddDevice called





FIGURE 6-41 Device plug-and-play state transitions.

### Plug-and-play driver installation

If the PnP manager encounters a device for which no driver is installed, it relies on the user-mode PnP manager to guide the installation process. If the device is detected during the system boot, a devnode is defined for the device, but the loading process is postponed until the user-mode PnP manager starts. (The user-mode PnP manager service is implemented in Umpnpmgr.dll hosted in a standard Svchost. exe instance.)

The components involved in a driver's installation are shown in Figure 6-42. Dark-shaded objects in the figure correspond to components generally supplied by the system, whereas lighter-shaded objects are those included in a driver's installation files. First, a bus driver informs the PnP manager of a device it enumerates using a Device ID (1). The PnP manager checks the registry for the presence of a corresponding function driver, and when it doesn't find one, it informs the user-mode PnP manager (2) of the new device by its Device ID. The user-mode PnP manager first tries to perform an automatic install without user intervention. If the installation process involves the posting of dialog boxes that require user interaction and the currently logged-on user has administrator privileges, the user-mode PnP manager launches the Rundll32.exe application (the same application that hosts classic .cpl Control Panel utilities) to execute the Hardware Installation Wizard (3) (%SystemRoot%\System32\Newdev. dll). If the currently logged-on user doesn't have administrator privileges (or if no user is logged on) and the installation of the device requires user interaction, the user-mode PnP manager defers the installation until a privileged user logs on. The Hardware Installation Wizard uses Setupapi.dll and CfgMgr32.dll (configuration manager) API functions to locate INF files that correspond to drivers that are compatible with the detected device. This process might involve having the user insert installation media containing a vendor's INF files, or the wizard might locate a suitable INF file in the driver store (%SystemRoot%\System32\DriverStore) that contains drivers that ship with Windows or others that are downloaded through Windows Update. Installation is performed in two steps. In the first, the thirdparty driver developer imports the driver package into the driver store, and in the second, the system performs the actual installation, which is always done through the %SystemRoot%\System32\Drvinst. exe process.





To find drivers for the new device, the installation process gets a list of hardware IDs (discussed earlier) and compatible IDs from the bus driver. Compatible IDs are more generic—for example a USB mouse from a specific vendor might have a special button that does something unique, but a compatible ID for a generic mouse can utilize a more generic driver that ships with Windows if the specific driver is not available and at least provide the basic, common functionality of a mouse.

These IDs describe all the various ways the hardware might be identified in a driver installation file (INF). The lists are ordered so that the most specific description of the hardware is listed first. If matches are found in multiple INFs, the following points apply:

- More-precise matches are preferred over less-precise matches.
- Digitally signed INFs are preferred over unsigned ones.
- Newer signed INFs are preferred over older signed ones.

**Note** If a match is found based on a compatible ID, the Hardware Installation wizard can prompt for media in case a more up-to-date driver came with the hardware.

The INF file locates the function driver's files and contains instructions that fill in the driver's enumeration and class keys in the registry, copy required files, and the INF file might direct the Hardware Installation Wizard to (4) launch class or device co-installer DLLs that perform class-specific or devicespecific installation steps, such as displaying configuration dialog boxes that let the user specify settings for a device. Finally, when the drivers that make up a devnode load, the device/driver stack is built (5).

### **EXPERIMENT:** Looking at a driver's INF file

When a driver or other software that has an INF file is installed, the system copies its INF file to the %SystemRoot%\Inf directory. One file that will always be there is Keyboard.inf because it's the INF file for the keyboard class driver. View its contents by opening it in Notepad and you should see something like this (anything after a semicolon is a comment):

```
KEYBOARD.INF -- This file contains descriptions of Keyboard class devices
Copyright (c) Microsoft Corporation. All rights reserved.
[Version]
Signature ="$Windows NT$"
Class = Keyboard
ClassGUID ={4D36E96B-E325-11CE-BFC1-08002BE10318}
Provider =$MSFT%
DriverVer=06/21/2006,10.0.10586.0
[SourceDisksNames]
3426=windows cd
[SourceDisksFiles]
i8042prt.sys = 3426
kbdclass.sys = 3426
kbdhid.sys = 3426
...
```

An INF has the classic INI format, with sections in square brackets and underneath are key/ value pairs separated by an equal sign. An INF is not "executed" from start to end sequentially; instead, it's built more like a tree, where certain values point to sections with the value name where execution continues. (Consult the WDK for the details.)

If you search the file for .*sys*, you'll come across sections that direct the user-mode PnP manager to install the i8042prt.sys and kbdclass.sys drivers:

```
[i8042prt_CopyFiles]
i8042prt.sys,,,0x100
[KbdClass.CopyFiles]
kbdclass.sys,,,0x100
...
```

Before installing a driver, the user-mode PnP manager checks the system's driver-signing policy. If the settings specify that the system should block or warn of the installation of unsigned drivers, the user-mode PnP manager checks the driver's INF file for an entry that locates a catalog (a file that ends with the .cat extension) containing the driver's digital signature.

Microsoft's WHQL tests the drivers included with Windows and those submitted by hardware vendors. When a driver passes the WHQL tests, it is "signed" by Microsoft. This means that WHQL obtains a *hash*, or unique value representing the driver's files, including its image file, and then cryptographically signs it with Microsoft's private driver-signing key. The signed hash is stored in a catalog file and included on the Windows installation media or returned to the vendor that submitted the driver for inclusion with its driver.

#### **EXPERIMENT: Viewing catalog files**

When you install a component such as a driver that includes a catalog file, Windows copies the catalog file to a directory under %SystemRoot%\System32\Catroot. Navigate to that directory in Explorer, and you'll find a subdirectory that contains .cat files. For example, Nt5.cat and Nt5ph. cat store the signatures and page hashes for Windows system files.

If you open one of the catalog files, a dialog box appears with two pages. The page labeled "General" shows information about the signature on the catalog file, and the Security Catalog page has the hashes of the components that are signed with the catalog file. This screenshot of a catalog file for an Intel audio driver shows the hash for the audio driver SYS file. Other hashes in the catalog are associated with the various support DLLs that ship with the driver.

Catalog entries:		
Tag		
	F785E8620F9F7AFAC7897E110223E	1597DCEA
	3A12C4EA63C89D85638B8324D 340E9016D15648C80EB51EF3A	
	340E9016D15648CB0EB51EF3A D42685799B314A1DE5481000F9100	940770CE
CONTRACTOR SHOULD SHO	0120037330311A IDC 310 10001 3100	ADAUT TOLELL
Entry details		
P. Construction		
Field	Value	^
DRMLevel	1300	100
File	intedaud.sys	
()SAttr	2:6.2.2:6.3.2:10.0	
1272		
Value:		
intcdaud.sys		

As it installs a driver, the user-mode PnP manager extracts the driver's signature from its catalog file, decrypts the signature using the public half of Microsoft's driver-signing private/public key pair, and compares the resulting hash with a hash of the driver file it's about to install. If the hashes match, the driver is verified as having passed WHQL testing. If a driver fails the signature verification, the user-mode PnP manager acts according to the settings of the system driver-signing policy, either failing the installation attempt, warning the user that the driver is unsigned, or silently installing the driver.

**Note** Drivers installed using setup programs that manually configure the registry and copy driver files to a system and driver files that are dynamically loaded by applications aren't checked for signatures by the PnP manager's signing policy. Instead, they are checked by the kernel-mode code-signing policy described in Chapter 8 in Part 2. Only drivers installed using INF files are validated against the PnP manager's driver-signing policy.

-					_
$^{-}$	-	T	T	-	٦.
	-	_	_	-	
	-	_	_	=	
	-	-	-	-	
	-	_	_	_	
	-			_	
ι.					

**Note** The user-mode PnP manager also checks whether the driver it's about to install is on the *protected driver list* maintained by Windows Update and, if so, blocks the installation with a warning to the user. Drivers that are known to have incompatibilities or bugs are added to the list and blocked from installation.

# General driver loading and installation

The preceding section showed how drivers for hardware devices are discovered and loaded by the PnP manager. These drivers mostly load "on demand," meaning such a driver is not loaded unless needed— a device that the driver is responsible for enters the system; conversely, if all devices managed by a driver are removed, the driver will be unloaded.

More generally, the Software key in the registry holds settings for drivers (as well as Windows Services). Although services are managed within the same registry key, they are user-mode programs and have no connection to kernel drivers (although the Service Control Manager can be used to load both services and device drivers). This section focuses on drivers; for a complete treatment of services, see Chapter 9 in Part 2.

# **Driver loading**

Each subkey under the Software key (HKLM\System\CurrentControlSet\Services) holds a set of values that control some static aspects of a driver (or service). One such value, ImagePath, was encountered already when we discussed the loading process of PnP drivers. Figure 6-36 shows an example of a driver key and Table 6-8 summarizes the most important values in a driver's Software key (see Chapter 9 in Part 2 for a complete list).

The Start value indicates the phase in which a driver (or service) is loaded. There are two main differences between device drivers and services in this regard:

- Only device drivers can specify Start values of boot-start (0) or system-start (1). This is because at these phases, no user mode exists yet, so services cannot be loaded.
- Device drivers can use the Group and Tag values (not shown in Table 6-8) to control the order of loading within a phase of the boot, but unlike services, they can't specify DependOnGroup or DependOnService values (see Chapter 9 in Part 2 for more details).

TABLE 6-8	Important values in a driver's registry key
-----------	---

Value Name	Description
ImagePath	This is the path to the driver's image file (SYS).
Туре	This indicates whether this key represents a service or a driver. A value of 1 means a driver and a value of 2 means a file system (or filter) driver. Values of 16 (0x10) and 32 (0x20) mean a service. See Chapter 9 in Part 2 for more information.
Start	<ul> <li>This indicates when the driver should load. The options are as follows:</li> <li>0 (SERVICE_BOOT_START) The driver is loaded by the boot loader.</li> <li>1 (SERVICE_SYSTEM_START) The driver is loaded after the executive is initialized.</li> <li>2 (SERVICE_AUTO_START) The driver is loaded by the service control manager.</li> <li>3 (SERVICE_DEMAND_START) The driver is loaded on demand.</li> <li>4 (SERVICE_DISABLED) The driver is not loaded.</li> </ul>

Chapter 11, "Startup and shutdown, in Part 2 describes the phases of the boot process and explains that a driver Start value of 0 means that the operating system loader loads the driver. A Start value of 1 means that the I/O manager loads the driver after the executive subsystems have finished initializing. The I/O manager calls driver initialization routines in the order that the drivers load within a boot phase. Like Windows services, drivers use the Group value in their registry key to specify which group they belong to; the registry value HKLM\SYSTEM\CurrentControlSet\Control\ServiceGroupOrder\List determines the order that groups are loaded within a boot phase.

A driver can further refine its load order by including a Tag value to control its order within a group. The I/O manager sorts the drivers within each group according to the Tag values defined in the drivers' registry keys. Drivers without a tag go to the end of the list in their group. You might assume that the I/O manager initializes drivers with lower-number tags before it initializes drivers with higher-number tags, but such isn't necessarily the case. The registry key HKLM\SYSTEM\CurrentControlSet\Control\GroupOrderList defines tag precedence within a group; with this key, Microsoft and device-driver developers can take liberties with redefining the integer number system.

**Note** The use of Group and Tag is reminiscent from the early Windows NT days. These tags are rarely used in practice. Most drivers should not have dependencies on other drivers (only on kernel libraries linked to the driver, such as NDIS.sys).

Here are the guidelines by which drivers set their Start value:

- Non-Plug and Play drivers set their Start value to reflect the boot phase they want to load in.
- Drivers, including both Plug and Play and non-Plug and Play drivers, that must be loaded by the boot loader during the system boot specify a Start value of boot-start (0). Examples include system bus drivers and the boot file-system driver.
- A driver that isn't required for booting the system and that detects a device that a system bus driver can't enumerate specifies a Start value of system-start (1). An example is the serial port driver, which informs the PnP manager of the presence of standard PC serial ports that were detected by Setup and recorded in the registry.

- A non-Plug and Play driver or file-system driver that doesn't have to be present when the system boots specifies a Start value of auto-start (2). An example is the Multiple Universal Naming Convention (UNC) Provider (MUP) driver, which provides support for UNC-based path names to remote resources (for example, \\RemoteComputerName\SomeShare).
- Plug and Play drivers that aren't required to boot the system specify a Start value of demandstart (3). Examples include network adapter drivers.

The only purpose that the Start values for Plug and Play drivers and drivers for enumerable devices have is to ensure that the operating system loader loads the driver—if the driver is required for the system to boot successfully. Beyond that, the PnP manager's device enumeration process determines the load order for Plug and Play drivers.

## **Driver installation**

As we've seen, Plug and Play drivers require an INF file for installation. The INF includes the hardware device IDs this driver can handle and the instructions for copying files and setting registry values. Other type of drivers (such as file system drivers, file system filters and network filters) require an INF as well, which includes a unique set of values for the particular type of driver.

Software-only drivers (such as the one Process Explorer uses) can use an INF for installation, but don't have to. These can be installed by a call to the CreateService API (or use a tool such as sc.exe that wraps it), as Process Explorer does after extracting its driver from a resource within the executable (if running with elevated permissions). As the API name suggests, it's used to install services as well as drivers. The arguments to CreateService indicate whether it's installing a driver or a service, the Start value and other parameters (see the Windows SDK documentation for the details). Once installed, a call to StartService loads the driver (or service), calling DriverEntry (for a driver) as usual.

A software-only driver typically creates a device object with a name its clients know. For example, Process Explorer creates a device named PROCEXP152 that is then used by Process Explorer in a Create-File call, followed by calls such as DeviceIoControl to send requests to the driver (turned into IRPs by the I/O manager). Figure 6-43 shows the Process Explorer object symbolic link (using the WinObj Sysinternals tool) in the \GLOBAL?? directory (recall that the names in this directory are accessible to user mode clients) that's created by Process Explorer the first time it's running with elevated privileges. Notice that it points to the real device object under the \Device directory and it has the same name (which is not a requirement).

le View Help				
•- <mark></mark> \	Name /	Туре	SymLink	1
ArcName	PIPE	SymbolicLink	\Device\NamedPipe	
> - BaseNamedObjects	PRN	SymbolicLink	\DosDevices\LPT1	
- Callback	ProcessManagement	SymbolicLink	\Device\ProcessManage	
> - Device	ROCEXP152	SymbolicLink	\Device\PROCEXP152	
FileSystem	Psched	SymbolicLink	\Device\Psched	
GLOBAL??	RdpDrDvMgr	SymbolicLink	\Device\RdpDrDvMgr	
KernelObjects	RESOURCE_HUB	SymbolicLink	\Device\RESOURCE_HUB	
KnownDils	ROOT#BasicDisplay#0000#{5b45201d-f	SymbolicLink	\Device\0000003	
KnownDlls32	ROOT#BasicRender#0000#(1ca05180-a	SymbolicLink	\Device\000000d	- 14
NLS	ROOT#spaceport#0000#(53f5630e-b6bf	SymbolicLink	\Device\0000008	

FIGURE 6-43 Process Explorer's symbolic link and device name.

# **The Windows Driver Foundation**

The Windows Driver Foundation (WDF) is a framework for developing drivers that simplifies common tasks such as handing Plug and Play and Power IRPs correctly. WDF includes the Kernel-Mode Driver Framework (KMDF) and the User-Mode Driver Framework (UMDF). WDF is now open source and can be found at *https://github.com/Microsoft/Windows-Driver-Frameworks*. Table 6-9 shows the Windows version support (for Windows 7 and later) for KMDF. Table 6-10 shows the same for UMDF.

KMDF Version	Release Method	Included in Windows	Drivers Using It Run On
1.9	Windows 7 WDK	Windows 7	Windows XP and later
1.11	Windows 8 WDK	Windows 8	Windows Vista and later
1.13	Windows 8.1 WDK	Windows 8.1	Windows 8.1 and later
1.15	Windows 10 WDK	Windows 10	Windows 10, Windows Server 2016
1.17	Windows 10 version 1511 WDK	Windows 10 version 1511	Windows 10 version 1511 and later, Windows Server 2016
1.19	Windows 10 version 1607 WDK	Windows 10 version 1607	Windows 10 version 1607 and later, Windows Server 2016

TABLE 6-9 KMDF versions

TABLE 6-10	UMDF versions
------------	---------------

UMDF Version	Release Method	Included in Windows	Drivers Using It Run On
1.9	Windows 7 WDK	Windows 7	Windows XP and later
1.11	Windows 8 WDK	Windows 8	Windows Vista and later
2.0	Windows 8.1 WDK	Windows 8.1	Windows 8.1 and later
2.15	Windows 10 WDK	Windows 10	Windows 10 and later, Windows Server 2016
2.17	Windows 10 version 1511 WDK	Windows 10 version 1511	Windows 10 version 1511 and later, Windows Server 2016
2.19	Windows 10 version 1607 WDK	Windows 10 version 1607	Windows 10 version 1607, Windows Server 2016

Windows 10 introduced the concept of Universal Drivers, briefly described in Chapter 2, "System architecture." These drivers use a common set of DDIs implemented in multiple editions of Windows 10 from IoT Core, to Mobile, to desktops. Universal drivers can be built with KMDF, UMDF 2.x, or WDM. Building such drivers is relatively easy with the aid of Visual Studio, where the Target Platform setting is set to Universal. Any DDI that is outside the boundaries of Universal will be flagged by the compiler.

UMDF versions 1.x used a COM based model for programming drivers, which is a very different programming model than KMDF, which is using object-based C. UMDF 2 has been aligned with KMDF and provides an almost identical API, reducing overall cost associated with WDF driver development; in fact, UMDF 2.x drivers can be converted to KMDF if the need arises with little work. UMDF 1.x will not be discussed in this book; consult the WDK for more information.

The following sections discuss KMDF and UMDF, which essentially behave in a consistent manner, no matter the exact OS they're running on.

## Kernel-Mode Driver Framework

We've already discussed some details about the Windows Driver Foundation (WDF) in Chapter 2. In this section, we'll take a deeper look at the components and functionality provided by the kernelmode part of the framework, KMDF. Note that this section will only briefly touch on some of the core architecture of KMDF. For a much more complete overview on the subject, please refer to the Windows Driver Kit documentation.

r	+	+	+	+	٦
L	Ξ			=	
L	Ξ				
L					J

**Note** Most of the details presented in this section are the same for UMDF 2.x, with the exceptions discussed in the next section.

### Structure and operation of a KMDF driver

First, let's look at which kinds of drivers or devices are supported by KMDF. In general, any WDM-conformant driver should be supported by KMDF, as long as it performs standard I/O processing and IRP manipulation. KMDF is not suitable for drivers that don't use the Windows kernel API directly but instead perform library calls into existing port and class drivers. These types of drivers cannot use KMDF because they only provide callbacks for the actual WDM drivers that do the I/O processing. Additionally, if a driver provides its own dispatch functions instead of relying on a port or class driver, IEEE 1394, ISA, PCI, PCMCIA, and SD Client (for Secure Digital storage devices) drivers can also use KMDF.

Although KMDF provides an abstraction on top of WDM, the basic driver structure shown earlier also generally applies to KMDF drivers. At their core, KMDF drivers must have the following functions:

- An initialization routine Like any other driver, a KMDF driver has a DriverEntry function that initializes the driver. KMDF drivers initiate the framework at this point and perform any configuration and initialization steps that are part of the driver or part of describing the driver to the framework. For non–Plug and Play drivers, this is where the first device object should be created.
- An add-device routine KMDF driver operation is based on events and callbacks (described shortly), and the EvtDriverDeviceAdd callback is the single most important one for PnP devices because it receives notifications when the PnP manager in the kernel enumerates one of the driver's devices.
- One or more EvtIo\* routines Similar to a WDM driver's dispatch routines, these callback routines handle specific types of I/O requests from a particular device queue. A driver typically creates one or more queues in which KMDF places I/O requests for the driver's devices. These queues can be configured by request type and dispatching type.

The simplest KMDF driver might need to have only an initialization and add-device routine because the framework will provide the default, generic functionality that's required for most types of I/O processing, including power and Plug and Play events. In the KMDF model, *events* refer to run-time states to which a driver can respond or during which a driver can participate. These events are not related to the synchronization primitives (synchronization is discussed in Chapter 8 in Part 2), but are internal to the framework.

For events that are critical to a driver's operation, or that need specialized processing, the driver registers a given callback routine to handle this event. In other cases, a driver can allow KMDF to perform a default, generic action instead. For example, during an eject event (EvtDeviceEject), a driver can choose to support ejection and supply a callback or to fall back to the default KMDF code that will tell the user that the device does not support ejection. Not all events have a default behavior, however, and callbacks must be provided by the driver. One notable example is the EvtDriverDeviceAdd event just described that is at the core of any Plug and Play driver.

#### **EXPERIMENT: Displaying KMDF and UMDF 2 drivers**

The Wdfkd.dll extension that ships with the Debugging Tools for Windows package provides many commands that can be used to debug and analyze KMDF drivers and devices (instead of using the built-in WDM-style debugging extension, which may not offer the same kind of WDF-specific information). You can display installed KMDF drivers with the <code>!wdfkd.wdfldr</code> debugger command. In the following example, the output from a Windows 10 32-bit Hyper-V virtual machine is shown, displaying the built-in drivers that are installed.

```
lkd> !wdfkd.wdfldr
_____
KMDF Drivers
_____
LoadedModuleList 0x870991ec
_____
LIBRARY_MODULE 0x8626aad8
 Version v1.19
 Service \Registry\Machine\System\CurrentControlSet\Services\Wdf01000
ImageName Wdf01000.sys
 ImageAddress 0x87000000
 ImageSize 0x8f000
 Associated Clients: 25
 ImageName
                            Ver
                                 WdfGlobals FxGlobals ImageAddress ImageSize
 umpass.sys
                            v1.15 0xa1ae53f8 0xa1ae52f8 0x9e5f0000
                                                                0x00008000
                            v1.7 0x95e798d8 0x95e797d8 0x9e400000
                                                                0x000ba000
 peauth.sys
                           v1.15 0x9aed1b50 0x9aed1a50 0x8e300000
                                                                0x00014000
 mslldp.sys
 vmgid.sys
                           v1.15 0x97d0fd08 0x97d0fc08 0x8e260000
                                                                0x00008000
 monitor.sys
                           v1.15 0x97cf7e18 0x97cf7d18 0x8e250000
                                                                0x0000c000
                      v1.15 0x8d0fc2b0 0x8d0fc1b0 0x87a90000
v1.15 0x8d0fcfd0 0x8d0fc1b0 0x87a90000
 tsusbhub.sys
                                                                0x0001b000
                                                                0x00009000
 NdisVirtualBus.sys
 vmgencounter.sys
                                                                0x00008000
 intelppm.sys
                            v1.15 0x8d0f4cf0 0x8d0f4bf0 0x87a50000
                                                                0x00021000
```

	vms3cap.sys	v1.15	0x8d0f5218	0x8d0f5118	0x87a40000	0x00008000
	netvsc.sys	v1.15	0x8d11ded0	0x8d11ddd0	0x87a20000	0x00019000
	hyperkbd.sys	v1.15	0x8d114488	0x8d114388	0x87a00000	0x00008000
	dmvsc.sys	v1.15	0x8d0ddb28	0x8d0dda28	0x879a0000	0x0000c000
	umbus.sys	v1.15	0x8b86ffd0	0x8b86fed0	0x874f0000	0x00011000
	CompositeBus.sys	v1.15	0x8b869910	0x8b869810	0x87df0000	0x0000d000
	cdrom.sys	v1.15	0x8b863320	0x8b863220	0x87f40000	0x00024000
	vmstorfl.sys	v1.15	0x8b2b9108	0x8b2b9008	0x87c70000	0x0000c000
	EhStorClass.sys	v1.15	0x8a9dacf8	0x8a9dabf8	0x878d0000	0x00015000
	vmbus.sys	v1.15	0x8a9887c0	0x8a9886c0	0x82870000	0x00018000
	vdrvroot.sys	v1.15	0x8a970728	0x8a970628	0x82800000	0x0000f000
	msisadrv.sys	v1.15	0x8a964998	0x8a964898	0x873c0000	0x00008000
	WindowsTrustedRTProxy.sys	v1.15	0x8a1f4c10	0x8a1f4b10	0x87240000	0x00008000
	WindowsTrustedRT.sys	v1.15	0x8a1f1fd0	0x8a1f1ed0	0x87220000	0x00017000
	intelpep.sys	v1.15	0x8a1ef690	0x8a1ef590	0x87210000	0x0000d000
	acpiex.sys	v1.15	0x86287fd0	0x86287ed0	0x870a0000	0x00019000
12						

Total: 1 library loaded

If UMDF 2.x1 drivers were loaded, they would have been shown as well. This is one of the benefits of the UMDF 2.x1 library (see the UMDF section later in this chapter for more on this subject).

Notice that the KMDF library is implemented in Wdf01000.sys, which is the current version 1.x of KMDF. Future versions of KMDF may have a major version of 2 and will be implemented in another kernel module, Wdf02000.sys. This future module can live side by side with the version 1.x module, each loaded with the drivers that compiled against it. This ensures isolation and independence between drivers built against different KMDF major version libraries.

#### KMDF object model

The KMDF object model is object-based, with properties, methods and events, implemented in C, much like the model for the kernel, but it does not make use of the object manager. Instead, KMDF manages its own objects internally, exposing them as handles to drivers and keeping the actual data structures opaque. For each object type, the framework provides routines to perform operations on the object (called *methods*), such as WdfDeviceCreate, which creates a device. Additionally, objects can have specific data fields or members that can be accessed by Get/Set (used for modifications that should never fail) or Assign/Retrieve APIs (used for modifications that can fail), which are called *properties*. For example, the WdfInterruptGetInfo function returns information on a given interrupt object (WDFINTERRUPT).


Also unlike the implementation of kernel objects, which all refer to distinct and isolated object types, KMDF objects are all part of a hierarchy—most object types are bound to a parent. The root object is the WDFDRIVER structure, which describes the actual driver. The structure and meaning is analogous to the DRIVER\_OBJECT structure provided by the I/O manager, and all other KMDF structures are children of it. The next most important object is WDFDEVICE, which refers to a given instance of a detected device on the system, which must have been created with WdfDeviceCreate. Again, this is analogous to the DEVICE\_OBJECT structure that's used in the WDM model and by the I/O manager. Table 6-11 lists the object types supported by KMDF.

#### TABLE 6-11 KMDF object types

Object	Туре	Description
Child list	WDFCHILDLIST	This is a list of child WDFDEVICE objects associated with the device. It is used only by bus drivers.
Collection	WDFCOLLECTION	This is a list of objects of a similar type, such as a group of WDFDEVICE objects being filtered.
Deferred Procedure Call	WDFDPC	This is an instance of a DPC object.
Device	WDFDEVICE	This is an instance of a device.
DMA common buffer	WDFCOMMONBUFFER	This is a region of memory that a device and driver can access for DMA.
DMA enabler	WDFDMAENABLER	This enables DMA on a given channel for a driver.
DMA transaction	WDFDMATRANSACTION	This is an instance of a DMA transaction.
Driver	WDFDRIVER	This is an object for the driver. It represents the driver, its param- eters, and its callbacks, among other items.
File	WDFFILEOBJECT	This is an instance of a file object that can be used as a channel for communication between an application and the driver.
Generic object	WDFOBJECT	This allows driver-defined custom data to be wrapped inside the framework's object data model as an object.
Interrupt	WDFINTERRUPT	This is an instance of an interrupt that the driver must handle.
I/O queue	WDFQUEUE	This represents a given I/O queue.
I/O request	WDFREQUEST	This represents a given request on a WDFQUEUE.
I/O target	WDFIOTARGET	This represents the device stack being targeted by a given WDFREQUEST.
Look-aside list	WDFLOOKASIDE	This describes an executive look-aside list. (See Chapter 5.)
Memory	WDFMEMORY	This describes a region of paged or nonpaged pool.
Registry key	WDFKEY	This describes a registry key.
Resource list	WDFCMRESLIST	This identifies the hardware resources assigned to a WDFDEVICE.
Resource range list	WDFIORESLIST	This identifies a given possible hardware resource range for a WDFDEVICE.
Resource requirements list	WDFIORESREQLIST	This contains an array of WDFIORESLIST objects describing all possible resource ranges for a WDFDEVICE.
Spinlock	WDFSPINLOCK	This describes a spinlock.
String	WDFSTRING	This describes a Unicode string structure.
Timer	WDFTIMER	This describes an executive timer. (See Chapter 8 in Part 2 for more information.)
USB device	WDFUSBDEVICE	This identifies the one instance of a USB device.
USB interface	WDFUSBINTERFACE	This identifies one interface on the given WDFUSBDEVICE.
USB pipe	WDFUSBPIPE	This identifies a pipe to an endpoint on a given WDFUSBINTERFACE.
Wait lock	WDFWAITLOCK	This represents a kernel dispatcher event object.

Object	Туре	Description
WMI instance	WDFWMIINSTANCE	This represents a WMI data block for a given WDFWMIPROVIDER.
WMI provider	WDFWMIPROVIDER	This describes the WMI schema for all the WDFWMIINSTANCE objects supported by the driver.
Work item	WDFWORKITEM	This describes an executive work item.

For each of these objects, other KMDF objects can be attached as children. Some objects have only one or two valid parents, while others can be attached to any parent. For example, a WDFINTERRUPT object must be associated with a given WDFDEVICE, but a WDFSPINLOCK or WDFSTRING object can have any object as a parent. This allows for fine-grained control over their validity and usage and the reduction of global state variables. Figure 6-44 shows the entire KMDF object hierarchy.





The associations mentioned earlier and shown in Figure 6-44 are not necessarily immediate. The parent must simply be on the *hierarchy chain*, meaning one of the ancestor nodes must be of this type. This relationship is useful to implement because object hierarchies affect not only an object's locality but also its lifetime. Each time a child object is created, a reference count is added to it by its link to its parent. Therefore, when a parent object is destroyed, all the child objects are also destroyed, which is why associating objects such as WDFSTRING or WDFMEMORY with a given object instead of the default WDFDRIVER object can automatically free up memory and state information when the parent object is destroyed.

Closely related to the concept of hierarchy is KMDF's notion of object context. Because KMDF objects are opaque (as discussed) and are associated with a parent object for locality, it becomes important to allow drivers to attach their own data to an object in order to track certain specific information outside the framework's capabilities or support. Object contexts allow all KMDF objects to contain such information. They also allow multiple object context areas, which permit multiple layers of code inside the same driver to interact with the same object in different ways. In WDM, the device extension custom data structure allows such information to be associated with a given device, but with KMDF even a spinlock or string can contain context areas. This extensibility enables each library or layer of code responsible for processing an I/O request to interact independently of other code, based on the context area that it works with.

Finally, KMDF objects are also associated with a set of attributes, shown in Table 6-12. These attributes are usually configured to their defaults, but the values can be overridden by the driver when creating the object by specifying a WDF\_OBJECT\_ATTRIBUTES structure (similar to the object manager's OBJECT\_ATTRIBUTES structure that's used when creating a kernel object).

Attribute	Description
ContextSizeOverride	This is the size of the object context area.
ContextTypeInfo	This is the type of the object context area.
EvtCleanupCallback	This is the callback to notify the driver of the object's cleanup before deletion. (References may still exist.)
EvtDestroyCallback	This is the callback to notify the driver of the object's imminent deletion. (The reference count will be 0.)
ExecutionLevel	This describes the maximum IRQL at which the callbacks may be invoked by KMDF.
ParentObject	This identifies the parent of the object.
SynchronizationScope	Specifies whether callbacks should be synchronized with the parent, a queue, a device, or nothing.

TABLE 6-12	KMDF object attributes
------------	------------------------

### KMDF I/O model

The KMDF I/O model follows the WDM mechanisms discussed earlier in this chapter. In fact, you can even think of the framework itself as a WDM driver, since it uses kernel APIs and WDM behavior to abstract KMDF and make it functional. Under KMDF, the framework driver sets its own WDM-style IRP dispatch routines and takes control of all IRPs sent to the driver. After being handled by one of three KMDF I/O handlers (described shortly), it then packages these requests in the appropriate KMDF objects, inserts them in the appropriate queues (if required), and performs driver callback if the driver is interested in those events. Figure 6-45 describes the flow of I/O in the framework.




FIGURE 6-45 KMDF I/O flow and IRP processing.

Based on the IRP processing discussed previously for WDM drivers, KMDF performs one of the following three actions:

- It sends the IRP to the I/O handler, which processes standard device operations.
- It sends the IRP to the PnP and power handler that processes these kinds of events and notifies other drivers if the state has changed.
- It sends the IRP to the WMI handler, which handles tracing and logging.

These components then notify the driver of any events it registered for, potentially forward the request to another handler for further processing, and then complete the request based on an internal handler action or as the result of a driver call. If KMDF has finished processing the IRP but the request itself has still not been fully processed, KMDF will take one of the following actions:

- For bus drivers and function drivers, it completes the IRP with STATUS\_INVALID\_DEVICE\_REQUEST.
- For filter drivers, it forwards the request to the next lower driver.

I/O processing by KMDF is based on the mechanism of queues (WDFQUEUE, not the KQUEUE object discussed earlier in this chapter). KMDF queues are highly scalable containers of I/O requests (pack-aged as WDFREQUEST objects) and provide a rich feature set beyond merely sorting the pending I/Os for a given device. For example, queues track currently active requests and support I/O cancellation, I/O concurrency (the ability to perform and complete more than one I/O request at a time), and I/O synchronization (as noted in the list of object attributes in Table 6-12). A typical KMDF driver creates at least one queue (if not more) and associates one or more events with each queue, as well as some of the following options:

- The callbacks registered with the events associated with this queue.
- The power management state for the queue. KMDF supports both power-managed and non-power managed queues. For the former, the I/O handler wakes up the device when required (and when possible), arms the idle timer when the device has no I/Os queued up, and calls the driver's I/O cancellation routines when the system is switching away from a working state.
- The dispatch method for the queue. KMDF can deliver I/Os from a queue in sequential, parallel, or manual mode. Sequential I/Os are delivered one at a time (KMDF waits for the driver to complete the previous request), while parallel I/Os are delivered to the driver as soon as possible. In manual mode, the driver must manually retrieve I/Os from the queue.
- Whether the queue can accept zero-length buffers, such as incoming requests that don't actually contain any data.

**Note** The dispatch method only affects the number of requests that can be active inside a driver's queue at one time. It does not determine whether the event callbacks themselves will be called concurrently or serially. That behavior is determined through the synchronization scope object attribute described earlier. Therefore, it is possible for a parallel queue to have concurrency disabled but still have multiple incoming requests.

Based on the mechanism of queues, the KMDF I/O handler can perform various tasks upon receiving a create, close, cleanup, write, read, or device control (IOCTL) request:

- For create requests, the driver can request to be immediately notified through the EvtDevice-FileCreate callback event, or it can create a non-manual queue to receive create requests. It must then register an EvtIoDefault callback to receive the notifications. Finally, if none of these methods are used, KMDF will simply complete the request with a success code, meaning that by default, applications will be able to open handles to KMDF drivers that don't supply their own code.
- For cleanup and close requests, the driver will be immediately notified through EvtFileCleanup and EvtFileClose callbacks, if registered. Otherwise, the framework will simply complete with a success code.
- For write, read, and IOCTL requests, the flow shown in Figure 6-46 applies.




FIGURE 6-46 Handling read, write, and IOCTL I/O requests by KMDF.

## **User-Mode Driver Framework**

Windows includes a growing number of drivers that run in user mode, using the User-Mode Driver Framework (UMDF), which is part of the WDF. UMDF version 2 is aligned with KMDF in terms of object model, programming model and I/O model. The frameworks are not identical, however, because of some of the inherent differences between user mode and kernel mode. For example, some KMDF objects listed in Table 6-12 don't exist in UMDF, including WDFCHILDLIST, DMA-related objects, WDFLO0KASIDELIST (look-aside lists can be allocated only in kernel mode), WDFIORESLIST, WDFIORES-REQLIST, WDFDPC, and WMI objects. Still, most KMDF objects and concepts apply equally to UMDF 2.x.

UMDF provides several advantages over KMDF:

- UMDF drivers execute in user mode, so any unhandled exception crashes the UMDF host process, but not the entire system.
- The UMDF host process runs with the Local Service account, which has very limited privileges on the local machine and only anonymous access in network connections. This reduces the security attack surface.
- Running in user mode means the IRQL is always 0 (PASSIVE\_LEVEL). Thus, the driver can always take page faults and use kernel dispatcher objects for synchronization (events, mutexes, and so on).
- Debugging UMDF drivers is easier than debugging KMDF drivers because the debugging setup does not require two separate machines (virtual or physical).

The main drawback to UMDF is increased latency because of the kernel/user transitions and communication required (as described shortly). Also, some types of drivers, such as drivers for high-speed PCI devices, are simply not meant to execute in user mode and thus cannot be written with UMDF.

UMDF is designed specifically to support protocol device classes, which refers to devices that all use the same standardized, generic protocol and offer specialized functionality on top of it. These protocols currently include IEEE 1394 (FireWire), USB, Bluetooth, human interface devices (HIDs) and TCP/IP. Any device running on top of these buses (or connected to a network) is a potential candidate for UMDF. Examples include portable music players, input devices, cell phones, cameras and webcams, and so on. Two other users of UMDF are SideShow-compatible devices (auxiliary displays) and the Windows Portable Device (WPD) Framework, which supports USB-removable storage (USB bulk transfer devices). Finally, as with KMDF, it's possible to implement software-only drivers, such as for a virtual device, in UMDF.

Unlike KMDF drivers, which run as driver objects representing a SYS image file, UMDF drivers run in a driver host process (running the image %SystemRoot%\System32\WUDFHost.exe), similar to a service-hosting process. The host process contains the driver itself, the User-Mode Driver Framework (implemented as a DLL), and a run-time environment (responsible for I/O dispatching, driver loading, device-stack management, communication with the kernel, and a thread pool).

As in the kernel, each UMDF driver runs as part of a stack. This can contain multiple drivers that are responsible for managing a device. Naturally, because user-mode code can't access the kernel address space, UMDF also includes components that allow this access to occur through a specialized interface to the kernel. This is implemented by a kernel-mode side of UMDF that uses ALPC—essentially an efficient inter-process communication mechanism to talk to the run-time environment in the user-mode driver host processes. (See Chapter 8 in Part 2 for more information on ALPC.) Figure 6-47 shows the architecture of the UMDF driver model.




FIGURE 6-47 UMDF architecture.

Figure 6-47 shows two different device stacks that manage two different hardware devices, each with a UMDF driver running inside its own driver host process. From the diagram, you can see that the following components comprise the architecture:

- Applications These are the clients of the drivers. They are standard Windows applications that use the same APIs to perform I/Os as they would with a KMDF-managed or WDM-managed device. Applications don't know (nor care) that they're talking to a UMDF-based device, and the calls are still sent to the kernel's I/O manager.
- Windows kernel (I/O manager) Based on the application I/O APIs, the I/O manager builds the IRPs for the operations, just like for any other standard device.
- Reflector The reflector is what makes UMDF "tick." It is a standard WDM filter driver (%SystemRoot%\System32\Drivers\WUDFRd.Sys) that sits at the top of the device stack of each device that is being managed by a UMDF driver. The reflector is responsible for managing the communication between the kernel and the user-mode driver host process. IRPs related to power management, Plug and Play, and standard I/O are redirected to the host process through ALPC. This enables the UMDF driver to respond to the I/Os and perform work, as well as be involved in the Plug and Play model, by providing enumeration, installation, and management of its devices. Finally, the reflector is responsible for keeping an eye on the driver host processes by making sure they remain responsive to requests within an adequate time to prevent drivers and applications from hanging.
- Driver manager The driver manager is responsible for starting and quitting the driver host processes, based on which UMDF-managed devices are present, and also for managing information on them. It is also responsible for responding to messages coming from the reflector and applying them to the appropriate host process (such as reacting to device installation). The driver manager runs as a standard Windows service implemented in %SystemRoot%\System32\WUDFsvc.dll (hosted in a standard Svchost.exe), and is configured for automatic startup as soon as the first UMDF driver for a device is installed. Only one instance of the driver manager runs for all driver host processes (as is always the case with services), and it must always be running to allow UMDF drivers to work.
- Host process The host process provides the address space and run-time environment for the actual driver (WUDFHost.exe). Although it runs in the local service account, it is not actually a Windows service and is not managed by the SCM—only by the driver manager. The host process is also responsible for providing the user-mode device stack for the actual hardware, which is visible to all applications on the system. Currently, each device instance has its own device stack, which runs in a separate host process. In the future, multiple instances may share the same host process. Host processes are child processes of the driver manager.
- Kernel-mode drivers If specific kernel support for a device that is managed by a UMDF driver is needed, it is also possible to write a companion kernel-mode driver that fills that role. In this way, it is possible for a device to be managed both by a UMDF and a KMDF (or WDM) driver.

You can easily see UMDF in action on your system by inserting a USB flash drive with some content on it. Run Process Explorer, and you should see a WUDFHost.exe process that corresponds to a driver host process. Switch to DLL view and scroll down until you see DLLs like the ones shown in Figure 6-48.

🛃 📵 🔳 🖻 🗂 🍪 😁	× # @			
Process	CPU Private Bytes	Working Set PID Descriptio	n Company Name	
background Task Host	Susp 4,704 K 8,484 K	14,936 K 15148 Backgroun 14,656 K 12064 SmartScre		
svchost.exe	0.03 7.680 K		es for Windows S., Microsoft Corporation	
e svchost.exe	17,232 K	23,960 K 1192 Host Proce	es for Windows S Microsoft Corporation	
WUDFHost.exe	0.02 2,652 K	8,656 K 1496 Windows I	Driver Foundation Microsoft Corporation	
WUDFHost.exe	1,840 K		viver Foundation Microsoft Corporation	
Total Line ave	A 244C A	10.0XD K 1954 Deulas As	noistion Francus Manaatt Composition	-
Name Desc	cription	Company Name	Path	
setupapi dl Wind SHCore dl SHCo ahlwapi dl Shell segnapi dl SQM sepici dl Secu	one v2 Utilities DLL lows Setup API DRE Light-weight Utility Library Citent thy Support Provider Interfa- soft® C Runtime Library User Windows USER API ( 2n	Microsoft Corporation Microsoft Corporation Microsoft Corporation Microsoft Corporation Microsoft Corporation Microsoft Corporation Microsoft Corporation	2: Windows (System 22: Sensors Ubits? all 2: Windows (System 22: eshaps) all 3: Window	

FIGURE 6-48 DLL in UMDF host process.

You can identify three main components, which match the architectural overview described earlier:

- WUDFHost.exe This is the UMDF host executable.
- WUDFx02000.dll This is the UMDF 2.x framework DLL.
- WUDFPlatform.dll This is the run-time environment.

### The power manager

Just as Windows Plug and Play features require support from a system's hardware, its power-management capabilities require hardware that complies with the Advanced Configuration and Power Interface (ACPI) specification, which is now part of the Unified Extensible Firmware Interface (UEFI). (The ACPI spec is available at *http://www.uefi.org/specifications*.)

The ACPI standard defines various power levels for a system and for devices. The six system power states are described in Table 6-13. They are referred to as S0 (fully on or working) through S5 (fully off). Each state has the following characteristics:

- **Power consumption** This is the amount of power the system consumes.
- **Software resumption** This is the software state from which the system resumes when moving to a "more on" state.
- Hardware latency This is the length of time it takes to return the system to the fully on state.

<b>TABLE 6-13</b>	System	power-state	definitions
-------------------	--------	-------------	-------------

State	Power Consumption	Software Resumption	Hardware Latency
S0 (fully on)	Maximum	Not applicable	None
S1 (sleeping)	Less than S0, more than S2	System resumes where it left off (returns to S0)	Less than 2 seconds
S2 (sleeping)	Less than S1, more than S3	System resumes where it left off (returns to S0)	2 or more seconds
S3 (sleeping)	Less than S2; processor is off	System resumes where it left off (returns to S0)	Same as S2
S4 (hibernating)	Trickle current to power button and wake circuitry	System restarts from saved hibernation file and resumes where it left off before hibernation (returns to S0)	Long and undefined
S5 (fully off)	Trickle current to power button	System boot	Long and undefined

As noted in Table 6-13, states S1 through S4 are sleeping states, in which the system appears to be off because of reduced power consumption. However, in these sleeping states, the system retains enough information—either in memory or on disk—to move to S0. For states S1 through S3, enough power is required to preserve the contents of the computer's memory so that when the transition is made to S0 (when the user or a device wakes up the computer), the power manager continues executing where it left off before the suspend.

When the system moves to S4, the power manager saves the compressed contents of memory to a hibernation file named Hiberfil.sys, which is large enough to hold the uncompressed contents of memory, in the root directory of the system volume (hidden file). (Compression is used to minimize disk I/O and to improve hibernation and resume-from-hibernation performance.) After it finishes saving memory, the power manager shuts off the computer. When a user subsequently turns on the computer, a normal boot process occurs, except that the boot manager checks for and detects a valid memory image stored in the hibernation file. If the hibernation file contains the saved system state, the boot manager launches %SystemRoot%\System32\Winresume.exe, which reads the contents of the file into memory, and then resumes execution at the point in memory that is recorded in the hibernation file.

On systems with hybrid sleep enabled, a user request to put the computer to sleep will actually be a combination of both the S3 state and the S4 state. While the computer is put to sleep, an emergency hibernation file will also be written to disk. Unlike typical hibernation files, which contain almost all active memory, the emergency hibernation file includes only data that could not be paged in at a later time, making the suspend operation faster than a typical hibernation (because less data is written to disk). Drivers will then be notified that an S4 transition is occurring, allowing them to configure themselves and save state just as if an actual hibernation request had been initiated. After this point, the system is put in the normal sleep state just like during a standard sleep transition. However, if the power goes out, the system is now essentially in an S4 state—the user can power on the machine, and Windows will resume from the emergency hibernation file.

**Note** You can disable hibernation completely and gain some disk space by running power-cfg /h off from an elevated command prompt.

The computer never directly transitions between states S1 and S4 (because that requires code execution, but the CPU is off in these states); instead, it must move to state S0 first. As illustrated in Figure 6-49, when the system is moving from any of states S1 through S5 to state S0, it's said to be *waking*, and when it's transitioning from state S0 to any of states S1 through S5, it's said to be *sleeping*.




FIGURE 6-49 System power-state transitions.

#### **Experiment: System power states**

To view the supported power states, open an elevated command window and type in the command **powercfg /a**. You'll see output similar to the following:

```
C:\WINDOWS\system32>powercfg /a
The following sleep states are available on this system:
    Standby (S3)
    Hibernate
    Fast Startup
The following sleep states are not available on this system:
    Standby (S1)
        The system firmware does not support this standby state.
    Standby (S2)
        The system firmware does not support this standby state.
    Standby (SO Low Power Idle)
        The system firmware does not support this standby state.
   Hybrid Sleep
        The hypervisor does not support this standby state.
  Notice that the standby state is S3 and hibernation is available. Let's turn off hibernation and
re-execute the command:
C:\WINDOWS\system32>powercfg /h off
C:\WINDOWS\system32>powercfg /a
```

```
The following sleep states are available on this system:
    Standby (S3)
The following sleep states are not available on this system:
    Standby (S1)
        The system firmware does not support this standby state.
    Standby (S2)
        The system firmware does not support this standby state.
    Hibernate
        Hibernation has not been enabled.
    Standby (SO Low Power Idle)
        The system firmware does not support this standby state.
    Hybrid Sleep
        Hibernation is not available.
        The hypervisor does not support this standby state.
    Fast Startup
        Hibernation is not available.
```

For devices, ACPI defines four power states, from D0 through D3. State D0 is fully on, while state D3 is fully off. The ACPI standard leaves it to individual drivers and devices to define the meanings of states D1 and D2, except that state D1 must consume an amount of power less than or equal to that consumed in state D0, and when the device is in state D2, it must consume power less than or equal to that that consumed in D1.

Windows 8 (and later) splits the D3 state into two sub-states, D3-hot and D3-cold. In D3-hot state, the device is mostly turned off, but is not disconnected from its main power source, and its parent bus controller can detect the presence of the device on the bus. In D3-cold, the main power source is removed from the device, and the bus controller cannot detect the device. This state provides another opportunity for saving power. Figure 6-50 shows the device states and the possible state transitions.




Figure 6-50 shows the device states and the possible state transitions.

FIGURE 6-50 Device power-state transitions.

Before Windows 8, devices could only reach D3-hot state while the system is fully on (S0). The transition to D3-cold was implicit when the system went into a sleep state. Starting with Windows 8, a device's power state can be set to D3-cold while the system is fully on. The driver that controls the device cannot put the device into D3-cold state directly; instead, it can put the device into D3-hot state, and then, depending on other devices on the same bus entering D3-hot states, the bus driver and firmware may decide to move all the devices to D3-cold. The decision whether to move the devices to D3-cold states depends on two factors: first, the actual ability of the bus driver and firmware, and second on the driver that must enable the transition to D3-cold either by specifying that in the installation INF file or by calling the SetD3DColdSupport function dynamically.

Microsoft, in conjunction with the major hardware OEMs, has defined a series of power management reference specifications that specify the device power states that are required for all devices in a particular class (for the major device classes: display, network, SCSI, and so on). For some devices, there's no intermediate power state between fully on and fully off, which results in these states being undefined.

### **Connected Standby and Modern Standby**

You may have noticed in the experiment above another system state called Standby (S0 Low Power Idle). Although not an official ACPI state, it is a variant of S0 known as *Connected Standby* on Windows 8.x and later enhanced in Windows 10 (desktop and mobile editions) and called *Modern Standby*. The "normal" standby state (S3 above) is sometimes referred to as *Legacy Standby*.

The main problem with Legacy Standby is that the system is not working, and therefore, for example, the user receives an email, the system can't pick that up without waking to S0, which may or may not happen, depending on configuration and device capabilities. Even if the system wakes up to get that email, it won't go immediately to sleep again. Modern Standby solves both issues.

Systems that support Modern Standby normally go into this state when the system is instructed to go to Standby. The system is technically still at S0, meaning the CPU is active and code can execute. However, desktop processes (non-UWP apps) are suspended, as well as UWP apps (most are not in the foreground and suspended anyway), but background tasks created by UWP apps are allowed to execute. For example, an email client would have a background task that periodically polls for new messages.

Being in Modern Standby also means that the system is able to wake to full S0 very quickly, sometimes referred to as *Instant On*. Note that not all systems support Modern Standby, as it depends on the chipset and other platform components (as can be seen in the last experiment, the system on which the experiment ran does not support Modern Standby and thus supports Legacy Standby).

For more information on Modern Standby, consult the Windows Hardware documentation at https://msdn.microsoft.com/en-us/library/windows/hardware/mt282515(v=vs.85).aspx.

## Power manager operation

Windows power-management policy is split between the power manager and the individual device drivers. The power manager is the owner of the system power policy. This ownership means the power manager decides which system power state is appropriate at any given point, and when a sleep, hiber-nation, or shutdown is required, the power manager instructs the power-capable devices in the system to perform appropriate system power-state transitions.

The power manager decides when a system power-state transition is necessary by considering several factors:

- System activity level
- System battery level
- Shutdown, hibernate, or sleep requests from applications
- User actions, such as pressing the power button
- Control Panel power settings

When the PnP manager performs device enumeration, part of the information it receives about a device is its power-management capabilities. A driver reports whether its devices support device states D1 and D2 and, optionally, the latencies, or times required, to move from states D1 through D3 to D0. To help the power manager determine when to make system power-state transitions, bus drivers also return a table that implements a mapping between each of the system power states (S0 through S5) and the device power states that a device supports.

The table lists the lowest possible device power state for each system state and directly reflects the state of various power planes when the machine sleeps or hibernates. For example, a bus that supports all four device power states might return the mapping table shown in Table 6-14. Most device drivers turn their devices completely off (D3) when leaving S0 to minimize power consumption when the machine isn't in use. Some devices, however, such as network adapter cards, support the ability to wake up the system from a sleeping state. This ability, along with the lowest device power state in which the capability is present, is also reported during device enumeration.

System Power State	Device Power State	
S0 (fully on)	D0 (fully on)	
S1 (sleeping)	D1	
S2 (sleeping)	D2	
S3 (sleeping)	D2	
S4 (hibernating)	D3 (fully off)	
S5 (fully off)	D3 (fully off)	

<b>TABLE 6-14</b>	An example of sy	stem-to-device	power mappings
-------------------	------------------	----------------	----------------

# Driver power operation

When the power manager decides to make a transition between system power states, it sends power commands to a driver's power dispatch routine (IRP\_MJ\_POWER). More than one driver can be responsible for managing a device, but only one of the drivers is designated as the device power-policy owner. This is typically the driver that manages the FDO. This driver determines, based on the system state, a device's power state. For example, if the system transitions between state S0 and S3, a driver might decide to move a device's power state from D0 to D1.

Instead of directly informing the other drivers that share the management of the device of its decision, the device power-policy owner asks the power manager, via the PoRequestPowerIrp function, to tell the other drivers by issuing a device power command to their power dispatch routines. This behavior enables the power manager to control the number of power commands that are active on a system at any given time. For example, some devices in the system might require a significant amount of current to power up. The power manager ensures that such devices aren't powered up simultaneously.

#### **EXPERIMENT:** Viewing a driver's power mappings

You can use Device Manager to see a driver's system power state-to-driver power state mappings. To do so, open the Properties dialog box for a device, click the **Details** tab, click the **Property** drop-down list, and choose **Power Data**. The Properties dialog box also displays the current power state of the device, the device-specific power capabilities that it provides, and the power states from which it can wake the system:

General	Policies	Volumes	Driver	Details	Events		
-		AV256MBI	-1AN15/	ABHA			
Property							
	UDLO						
Value		7755					_
	r capabiliti	es:					^
00000		-					
		PPORTE					
PDCA	P_D3_SU	PPORTED					
Powe	r state ma	ppings:					
S0 ->	DO						
\$1->	Unspecifie	be					
\$2->	Unspecifie	ed					
\$3->	D3						
S4 ->	D3						
S5->	D3						Y
					OK	Cance	el

Many power commands have corresponding query commands. For example, when the system is moving to a sleep state, the power manager will first ask the devices on the system whether the transition is acceptable. A device that is busy performing time-critical operations or interacting with device hardware might reject the command, which results in the system maintaining its current system power-state setting.


## EXPERIMENT: Viewing the system power capabilities and policy

You can view a computer's system power capabilities by using the !pocaps kernel debugger command. Here's the output of the command when run on an x64 Windows 10 laptop:

<pre>lkd&gt; !pocaps PopCapabilities @ 0xfffff80 Misc Supported Features: VideoDim</pre>	35a98ce60 PwrButton SlpButton Lid S3 S4 S5 HiberFile FullWake
Processor Features:	Thermal
Disk Features:	
Battery Features:	BatteriesPresent
Battery 0 - Capacity:	0 Granularity: 0
Battery 1 - Capacity:	0 Granularity: 0
Battery 2 - Capacity:	0 Granularity: 0
Wake Caps	
Ac OnLine Wake:	Sx
Soft Lid Wake:	Sx
RTC Wake:	S4
Min Device Wake:	Sx
Default Wake:	Sx

The Misc Supported Features line reports that, in addition to S0 (fully on), the system supports system power states of S3, S4 and S5 (it doesn't implement S1 or S2) and has a valid hibernation file to which it can save system memory when it hibernates (state S4).

The Power Options page, which you open by selecting **Power Options** in the Control Panel, lets you configure various aspects of the system's power policy. The exact properties you can configure depend on the system's power capabilities.



Notice that OEMs can add power schemes. These schemes can be listed by typing the **power**cfg /list command as shown here:

```
C:\WINDOWS\system32>powercfg /list
```

By changing any of the preconfigured plan settings, you can set the idle detection timeouts that control when the system turns off the monitor, spins down hard disks, goes to standby mode (moves to system power state S3 in the previous experiment), and hibernates (moves the system to power state S4). In addition, selecting the **Change Plan Settings** link lets you specify the power-related behavior of the system when you press the power or sleep buttons or close a laptop's lid.

🔋 Control	I Panel\All Control Panel Items\Power Op	tions\Edit Plan Settings					
$\leftarrow \rightarrow$	<ul> <li></li></ul>	an Settings		ٽ ~	Search Con	trol Panel	P
	Change settings for the Choose the sleep and display set						
		On battery		Plugg	jed in		
	Turn off the display:	5 minutes	~	10 minutes	v		
	Put the computer to sleep:	15 minutes	~	Never	~		
	🔆 Adjust plan brightness:	•	*	0	<b>V</b> 🖗		
	Change advanced power settings						
	Restore default settings for this p	lan					
				Save	changes	Cancel	

The Change Advanced Power Settings link directly affects values in the system's power policy, which you can display with the !popolicy debugger command. Here's the output of the command on the same system:

```
lkd> !popolicy
SYSTEM_POWER_POLICY (R.1) @ 0xfffff8035a98cc64
PowerButton: Sleep Flags: 00000000 Event: 00000000
SleepButton: Sleep Flags: 00000000 Event: 00000000
LidClose: None Flags: 00000000 Event: 00000000
Idle: Sleep Flags: 00000000 Event: 00000000
```

OverThrottled:	None	Flags: 00000000	Event: 00000000
IdleTimeout:	0	IdleSensitivity:	90%
MinSleep:	S3	MaxSleep:	S3
LidOpenWake:	S0	FastSleep:	S3
WinLogonFlags:	1	S4Timeout:	0
VideoTimeout:	600	VideoDim:	0
SpinTimeout:	4b0	OptForPower:	0
FanTolerance:	0%	ForcedThrottle:	0%
MinThrottle:	0%	DyanmicThrottle:	None (0)

The first lines of the display correspond to the button behaviors specified in the Power Options Advanced Settings window. On this system, both the power and the sleep buttons put the computer in a sleep state. Closing the lid, however, does nothing. The timeout values shown near the end of the output are expressed in seconds and displayed in hexadecimal notation. The values reported here directly correspond to the settings configured in the Power Options window. For example, the video timeout is 600, meaning the monitor turns off after 600 seconds (because of a bug in the debugging tools used here, it's displayed in decimal), or 10 minutes. Similarly, the hard disk spin-down timeout is 0x4b0, which corresponds to 1200 seconds, or 20 minutes.

## Driver and application control of device power

In addition to responding to power manager commands related to system power-state transitions, a driver can unilaterally control the device power state of its devices. In some cases, a driver might want to reduce the power consumption of a device it controls if the device is left inactive for a period of time. Examples include monitors that support a dimmed mode and disks that support spin-down. A driver can either detect an idle device itself or use facilities provided by the power manager. If the device uses the power manager, it registers the device with the power manager by calling the PoRegisterDevice-ForIdleDetection function.

This function informs the power manager of the timeout values to use to detect whether a device is idle and, if so, the device power state that the power manager should apply. The driver specifies two timeouts: one to use when the user has configured the computer to conserve energy and the other to use when the user has configured the computer for optimum performance. After calling PoRegisterDeviceForIdleDetection, the driver must inform the power manager, by calling the PoSetDeviceBusy or PoSetDeviceBusyEx functions, whenever the device is active, and then register for idle detection again to disable and re-enable it as needed. The PoStartDeviceBusy and PoEndDeviceBusy APIs are available as well, which simplify the programming logic required to achieve the behavior just described.

Although a device has control over its own power state, it does not have the ability to manipulate the system power state or to prevent system power transitions from occurring. For example, if a badly designed driver doesn't support any low-power states, it can choose to remain on or turn itself completely off without hindering the system's overall ability to enter a low-power state—this is because the power manager only *notifies* the driver of a transition and doesn't ask for *consent*. Drivers do receive a power query IRP (IRP\_MN\_QUERY\_POWER) when the system is about to transition to a lower power state.

The driver may veto the request, but the power manager does not have to comply; it may delay transition if possible (e.g., the device is running on a battery that is not critically low); transition to hibernation, however, can never fail.

Although drivers and the kernel are chiefly responsible for power management, applications are also allowed to provide their input. User-mode processes can register for a variety of power notifications, such as when the battery is low or critically low, when the machine has switched from DC (battery) to AC (adapter/charger) power, or when the system is initiating a power transition. Applications can never veto these operations, and they can have up to two seconds to clean up any state necessary before a sleep transition.

## Power management framework

Starting with Windows 8, the kernel provides a framework for managing power states of individual components (sometimes called *functions*) within a device. For example, suppose an audio device has playback and recording components, but if the playback component is active and the recording component is not, it would be beneficial to put the recording component into a lower power state. The power management framework (PoFx) provides an API that drivers can use to indicate their components' power states and requirements. All components must support the fully-on state, identified as F0. Higher-number F-states indicate lower power states that a component may be in, where each higher F-state represents a lower power consumption and higher transition time to F0. Note that F-state management has meaning only when the device is in power state D0, because it's not working at all in higher D-states.

The power policy owner of the device (typically the FDO) must register with PoFx by calling the PoFxRegisterDevice function. The driver passes along the following information in the call:

- The number of components within the device.
- A set of callbacks the driver can implement to be notified by PoFx when various events occur, such as switching to active or idle state, switching the device to D0 state and sending power control codes (see the WDK for more information).
- For each component, the number of F-states it supports.
- For each component, the deepest F-state from which the component can wake.
- For each component, for each F-state, the time required to return from this state to F0, the minimum amount of time the component can be in this F-state to make the transition worthwhile, and the nominal power the component consumes in this F-state. Or, it can be set to indicate that the power consumption is negligible and is not worth considering when PoFx decides to wake several components simultaneously.

PoFx uses this information—combined with information from other devices and system-wide power state information, such as the current power profile—to make intelligent decisions for which power F-state a particular component should be in. The challenge is to reconcile two conflicting objectives: first, ensuring that an idle component consumes as little power as possible, and second, making sure a component can transition to the F0 state quickly enough so that the component is perceived as always on and always connected.

The driver must notify PoFx when a component needs to be active (F0 state) by calling PoFxActivate-Component. Sometime after this call, the corresponding callback is invoked by PoFx, indicating to the driver that the component is now at F0. Conversely, when the driver determines the component is not currently needed, it calls PoFxIdleComponent to tell PoFx, which responds by transitioning the component to a lower-power F-state and notifies the driver once it does.

#### Performance state management

The mechanisms just described allow a component in an idle condition (non-F0 states) to consume less power than in F0. But some components can consume less power even in state F0, related to the actual work a device is doing. For example, a graphic card may be able to use less power when showing a mostly static display, whereas it would need higher power when rendering 3D content in 60 frames per second.

In Windows 8.*x*, such drivers would have to implement a propriety performance state selection algorithm and notify an OS service called platform extension plug-in (PEP). PEP is specific to a particular line of processors or system on a chip (SoC). This makes the driver code tightly coupled to the PEP.

Windows 10 extends the PoFx API for performance state management, prompting the driver code to use standard APIs and not worry about the particular PEP on the platform. For each component, PoFx provides the following types of performance states:

- A discrete number of states in the frequency (Hz), bandwidth (bits per second), or an opaque number meaningful to the driver.
- A continuous distribution of states between a minimum and maximum (frequency, bandwidth, or custom).

An example of this is for a graphic card to define a discrete set of frequencies in which it can operate, thus indirectly affecting its power consumption. Similar performance sets could be defined for its bandwidth usage, if appropriate.

To register with PoFx for performance state management, a driver must first register the device with PoFx (PoFxRegisterDevice) as described in the previous section. Then, the driver calls PoFxRegister-ComponentPerfStates, passing performance details (discrete or range-based, frequency, bandwidth, or custom) and a callback when state changes actually occur.

When a driver decides that a component should change performance state, it calls PoFxIssue-PerfStateChange or PoFxIssuePerfStateChangeMultiple. These calls request the PEP to place the component in the specified state (based on the provided index or value, depending on whether the set is for a discrete state or range-based). The driver may also specify that the call should be synchronous, asynchronous or "don't care," in which case the PEP decides. Either way, PoFx will eventually call into the driver-registered callback with the performance state, which may be the requested one, but it can also be denied by the PEP. If accepted, the driver should make the appropriate calls to its hardware to make the actual change. If the PEP denies the request, the driver may try again with a new call to one of the aforementioned functions. Only a single call can be made before the driver's callback is invoked.

# Power availability requests

Applications and drivers cannot veto sleep transitions that are already initiated. However, certain scenarios demand a mechanism for disabling the ability to initiate sleep transitions when a user is interacting with the system in certain ways. For example, if the user is currently watching a movie and the machine would normally go idle (based on a lack of mouse or keyboard input after 15 minutes), the media player application should have the capability to temporarily disable idle transitions as long as the movie is playing. You can probably imagine other power-saving measures that the system would normally undertake, such as turning off or even just dimming the screen, that would also limit your enjoyment of visual media. In legacy versions of Windows, SetThreadExecutionState was a user-mode API capable of controlling system and display idle transitions by informing the power manager that a user was still present on the machine. However, this API did not provide any sort of diagnostic capabilities, nor did it allow sufficient granularity for defining the availability request. Also, drivers could not issue their own requests, and even user applications had to correctly manage their threading model, because these requests were at the thread level, not at the process or system level.

Windows now supports power request objects, which are implemented by the kernel and are bonafide object manager-defined objects. You can use the WinObj utility from Sysinternals (more details on this tool are in Chapter 8 in Part 2) and see the PowerRequest object type in the \ObjectTypes directory, or use the !object kernel debugger command on the \ObjectTypes\PowerRequest object type, to validate this.

Power availability requests are generated by user-mode applications through the PowerCreate-Request API and then enabled or disabled with the PowerSetRequest and PowerClearRequest APIs, respectively. In the kernel, drivers use PoCreatePowerRequest, PoSetPowerRequest, and PoClear-PowerRequest. Because no handles are used, PoDeletePowerRequest is needed to remove the reference on the object (while user mode can simply use CloseHandle).

There are four kinds of requests that can be used through the Power Request API:

- **System request** This type request asks that the system not automatically go to sleep due to the idle timer (although the user can still close the lid to enter sleep, for example).
- **Display request** This type of request does the same as a system request, but for the display.
- **Away-mode request** This is a modification to the normal sleep (S3 state) behavior of Windows, which is used to keep the computer in full powered-on mode but with the display and sound card turned off, making it appear to the user as though the machine is really sleeping. This behavior is normally used only by specialized set-top boxes or media center devices when media delivery must continue even though the user has pressed a physical sleep button, for example.
- Execution required request This type of request (available starting with Windows 8 and Server 2012) requests a UWP app process continue execution even if normally the Process Lifecycle Manager (PLM) would have terminated it (for whatever reason); the extended length of time depends on factors such as the power policy settings. This request type is only supported for systems that support Modern Standby, otherwise this request is interpreted as a system request.

## **EXPERIMENT:** Viewing power availability requests

Unfortunately, the power request kernel object that's created with a call such as PowerCreate-Request is unavailable in the public symbols. However, the Powercfg utility provides a way to list power requests without any need for a kernel debugger. Here's the output of the utility while playing a video and a stream audio from the web on a Windows 10 laptop:

```
C:\WINDOWS\system32>powercfg /requests
DISPLAY:
[PROCESS] \Device\HarddiskVolume4\Program Files\WindowsApps\Microsoft.
ZuneVideo_10.16092.10311.0_x64__8wekyb3d8bbwe\Video.UI.exe
Windows Runtime Package: Microsoft.ZuneVideo_8wekyb3d8bbwe
SYSTEM:
[DRIVER] Conexant ISST Audio (INTELAUDIO\FUNC_01&VEN_14F1&DEV_50F4&SUBSYS_103C80D3&R
EV_1001\4&1a010da&0&0001)
An audio stream is currently in use.
[PROCESS] \Device\HarddiskVolume4\Program Files\WindowsApps\Microsoft.
ZuneVideo_10.16092.10311.0_x64__8wekyb3d8bbwe\Video.UI.exe
Windows Runtime Package: Microsoft.ZuneVideo_8wekyb3d8bbwe
```

EXECUTION: None.

PERFBOOST: None.

ACTIVELOCKSCREEN: None.

The output shows six request types (as opposed to the four described previously). The last two—perfboost and active lockscreen—are declared as part of an internal power request type in a kernel header, but are otherwise currently unused.

# Conclusion

The I/O system defines the model of I/O processing on Windows and performs functions that are common to or required by more than one driver. Its chief responsibilities are to create IRPs representing I/O requests and to shepherd the packets through various drivers, returning results to the caller when an I/O is complete. The I/O manager locates various drivers and devices by using I/O system objects, including driver and device objects. Internally, the Windows I/O system operates asynchronously to achieve high performance and provides both synchronous and asynchronous I/O capabilities to usermode applications. Device drivers include not only traditional hardware device drivers but also file-system, network, and layered filter drivers. All drivers have a common structure and communicate with each other and the I/O manager by using common mechanisms. The I/O system interfaces allow drivers to be written in a high-level language to lessen development time and to enhance their portability. Because drivers present a common structure to the operating system, they can be layered one on top of another to achieve modularity and reduce duplication between drivers. By using the Universal DDI baseline, drivers can target multiple devices and form factors with no code changes.

Finally, the role of the PnP manager is to work with device drivers to dynamically detect hardware devices and to build an internal device tree that guides hardware device enumeration and driver installation. The power manager works with device drivers to move devices into low-power states when applicable to conserve energy and prolong battery life.

The next chapter touches on one of the most important aspects of today's computer systems: security.

#### CHAPTER 7

# Security

Preventing unauthorized access to sensitive data is essential in any environment in which multiple users have access to the same physical or network resources. An operating system, as well as individual users, must be able to protect files, memory, and configuration settings from unwanted viewing and modification. Operating system security includes obvious mechanisms such as accounts, passwords, and file protection. It also includes less obvious mechanisms, such as protecting the operating system from corruption, preventing less privileged users from performing actions (rebooting the computer, for example), and not allowing user programs to adversely affect the programs of other users or the operating system.

In this chapter, we explain how every aspect of the design and implementation of Microsoft Windows was influenced in some way by the stringent requirements of providing robust security.

## Security ratings

Having software, including operating systems, rated against well-defined standards helps the government, corporations, and home users protect proprietary and personal data stored in computer systems. The current security rating standard used by the United States and many other countries is the Common Criteria (CC). To understand the security capabilities designed into Windows, however, it's useful to know the history of the security ratings system that influenced the design of Windows: the Trusted Computer System Evaluation Criteria (TCSEC).

## **Trusted Computer System Evaluation Criteria**

The National Computer Security Center (NCSC) was established in 1981 as part of the U.S. Department of Defense's (DoD) National Security Agency (NSA). One goal of the NCSC was to create a range of security ratings, listed in Table 7-1, to indicate the degree of protection commercial operating systems, network components, and trusted applications offer. These security ratings, which can be found at *http://csrc.nist.gov/publications/history/dod85.pdf*, were defined in 1983 and are commonly referred to as the *Orange Book*.

#### TABLE 7-1 TCSEC rating levels

Rating	Description
A1	Verified design
B3	Security domains
B2	Structured protection
B1	Labeled security protection
C2	Controlled access protection
C1	Discretionary access protection (obsolete)
D	Minimal protection

The TCSEC standard consists of levels-of-trust ratings, where higher levels build on lower levels by adding more rigorous protection and validation requirements. No operating system meets the A1 (verified design) rating. Although a few operating systems have earned one of the B-level ratings, C2 is considered sufficient and the highest rating practical for a general-purpose operating system.

The following were the key requirements for a C2 security rating, and they are still considered the core requirements for any secure operating system:

- A secure logon facility This requires that users be able to be uniquely identified and that they must be granted access to the computer only after they have been authenticated in some way.
- Discretionary access control This allows the owner of a resource (such as a file) to determine who can access the resource and what they can do with it. The owner grants rights that permit various kinds of access to a user or to a group of users.
- Security auditing This affords the ability to detect and record security-related events or any attempts to create, access, or delete system resources. Logon identifiers record the identities of all users, making it easy to trace anyone who performs an unauthorized action.
- Object reuse protection This prevents users from seeing data that another user has deleted or from accessing memory that another user previously used and then released. For example, in some operating systems, it's possible to create a new file of a certain length and then examine the contents of the file to see data that happens to have occupied the location on the disk where the file is allocated. This data might be sensitive information that was stored in another user's file but had been deleted. Object reuse protection prevents this potential security hole by initializing all objects, including files and memory, before they are allocated to a user.

Windows also meets two requirements of B-level security:

Trusted path functionality This prevents Trojan horse programs from being able to intercept users' names and passwords as they try to log on. The trusted path functionality in Windows comes in the form of its Ctrl+Alt+Delete logon-attention sequence, which cannot be intercepted by nonprivileged applications. This sequence of keystrokes, which is also known

as the secure attention sequence (SAS), always displays a system-controlled Windows security screen (if a user is already logged on) or the logon screen so that would-be Trojan horses can easily be recognized. (The SAS can also be sent programmatically via the SendSAS API if Group Policy and other restrictions allow it.) A Trojan horse presenting a fake logon dialog box will be bypassed when the SAS is entered.

Trusted facility management This requires support for separate account roles for administrative functions. For example, separate accounts are provided for administration (Administrators), user accounts charged with backing up the computer, and standard users.

Windows meets all these requirements through its security subsystem and related components.

# The Common Criteria

In January 1996, the United States, United Kingdom, Germany, France, Canada, and the Netherlands released the jointly developed Common Criteria for Information Technology Security Evaluation (CCITSE) specification. CCITSE, usually referred to as the Common Criteria (CC), is the recognized multinational standard for product security evaluation. The CC home page is at *http://www.niap-ccevs.org/cc-scheme*.

The CC is more flexible than the TCSEC trust ratings and has a structure closer to the ITSEC standard than to the TCSEC standard. The CC includes the concept of a Protection Profile (PP), used to collect security requirements into easily specified and compared sets, and the concept of a Security Target (ST), which contains a set of security requirements that can be made by reference to a PP. The CC also defines a range of seven Evaluation Assurance Levels (EALs), which indicate a level of confidence in the certification. In this way, the CC (like the ITSEC standard before it) removes the link between functionality and assurance level that was present in TCSEC and earlier certification schemes.

Windows 2000, Windows XP, Windows Server 2003, and Windows Vista Enterprise all achieved Common Criteria certification under the Controlled Access Protection Profile (CAPP). This is roughly equivalent to a TCSEC C2 rating. All received a rating of EAL 4+, the "plus" denoting "flaw remediation." EAL 4 is the highest level recognized across national boundaries.

In March 2011, Windows 7 and Windows Server 2008 R2 were evaluated as meeting the requirements of the US Government Protection Profile for General-Purpose Operating Systems in a Networked Environment, version 1.0 (GPOSPP) (*http://www.commoncriteriaportal.org/files/ppfiles/pp\_gpospp\_v1.0.pdf*). The certification includes the Hyper-V hypervisor. Again, Windows achieved Evaluation Assurance Level 4 with flaw remediation (EAL 4+). The validation report can be found at *http://www.commoncriteriaportal.org/files/epfiles/st\_vid10390-vr.pdf*, and the description of the security target, giving details of the requirements satisfied, can be found at *http://www.commoncriteriaportal.org/files/epfiles/st\_vid10390-st.pdf*. Similar certifications were achieved by Windows 10 and Windows Server 2012 R2 in June 2016. The report can be found at *http://www.commoncriteriaportal.org/files/epfiles/cr\_windows10.pdf*.

# Security system components

These are the core components and databases that implement Windows security. (All files mentioned are in the %SystemRoot%\System32 directory unless otherwise specified.)

- Security reference monitor (SRM) This component in the Windows executive (Ntoskrnl.exe) is responsible for defining the access token data structure to represent a security context, performing security access checks on objects, manipulating privileges (user rights), and generating any resulting security audit messages.
- Local Security Authority Subsystem Service (Lsass) This user-mode process runs the image Lsass.exe that is responsible for the local system security policy (such as which users are allowed to log on to the machine, password policies, privileges granted to users and groups, and the system security auditing settings), user authentication, and sending security audit messages to the event log. The Local Security Authority service (Lsasrv.dll), a library that Lsass loads, implements most of this functionality.
- LSAlso.exe This is used by Lsass (if so configured on supported Windows 10 and Server 2016 systems), also known as Credential Guard (see the upcoming "Credential Guard" section for more on Credential Guard), to store users' token hashes instead of keeping them in Lsass's memory. Because Lsaiso.exe is a Trustlet (Isolated User Mode process) running in VTL 1, no normal process—not even the normal kernel—can access the address space of this process. Lsass itself stores an encrypted blob of the password hash needed when it communicates with Lsaiso (via ALPC).
- Lsass policy database This database contains the local system security policy settings. It is stored in the registry in an ACL-protected area under HKLM\SECURITY. It includes such information as what domains are entrusted to authenticate logon attempts, who has permission to access the system and how (interactive, network, and service logons), who is assigned which privileges, and what kind of security auditing is to be performed. The Lsass policy database also stores "secrets" that include logon information used for cached domain logons and Windows service user-account logons. (See Chapter 9, "Management mechanisms," in *Windows Internals Part 2* for more information on Windows services.)
- Security Accounts Manager (SAM) This service is responsible for managing the database that contains the user names and groups defined on the local machine. The SAM service, which is implemented in Samsrv.dll, is loaded into the Lsass process.
- SAM database This database contains the defined local users and groups along with their passwords and other attributes. On domain controllers, the SAM does not store the domain-defined users, but stores the system's administrator recovery account definition and password. This database is stored in the registry under HKLM\SAM.

- Active Directory This is a directory service that contains a database that stores information about objects in a domain. A *domain* is a collection of computers and their associated security groups that are managed as a single entity. Active Directory stores information about the objects in the domain, including users, groups, and computers. Password information and privileges for domain users and groups are stored in Active Directory, which is replicated across the computers that are designated as domain controllers of the domain. The Active Directory server, implemented as Ntdsa.dll, runs in the Lsass process. For more information on Active Directory, see Chapter 10, "Networking," in Part 2.
- Authentication packages These include dynamic link libraries (DLLs) that run in the context of both Lsass process and client processes and implement Windows authentication policy. An authentication DLL is responsible for authenticating a user by checking whether a given user name and password match (or whatever mechanism was used to provide credentials), and if so, returning to Lsass information detailing the user's security identity, which Lsass uses to generate a token.
- Interactive logon manager (Winlogon) This is a user-mode process running Winlogon. exe that is responsible for responding to the SAS and for managing interactive logon sessions. Winlogon creates a user's first process when the user logs on, for example.
- Logon user interface (LogonUI) This is a user-mode process running the image LogonUI. exe that presents users with the user interface they can use to authenticate themselves on the system. LogonUI uses credential providers to query user credentials through various methods.
- Credential providers (CPs) These are in-process COM objects that run in the LogonUI process (started on demand by Winlogon when the SAS is performed) and used to obtain a user's name and password, smartcard PIN, biometric data (such as a fingerprint), or other identification mechanism. The standard CPs are authui.dll, SmartcardCredentialProvider.dll, BioCredProv. Dll, and FaceCredentialProvider.dll, a face-detection provider added in Windows 10.
- Network logon service (Netlogon) This is a Windows service (Netlogon.dll, hosted in a standard SvcHost) that sets up the secure channel to a domain controller, over which security requests—such as an interactive logon (if the domain controller is running Windows NT 4) or LAN Manager and NT LAN Manager (v1 and v2) authentication validation—are sent. Netlogon is also used for Active Directory logons.
- Kernel Security Device Driver (KSecDD) This is a kernel-mode library (%SystemRoot% System32\Drivers\Ksecdd.sys) of functions that implement the advanced local procedure call (ALPC) interfaces that other kernel mode security components, including the Encrypting File System (EFS), use to communicate with Lsass in user mode.
- AppLocker This mechanism allows administrators to specify which executable files, DLLs, and scripts can be used by specified users and groups. AppLocker consists of a driver (%SystemRoot%\ System32\Drivers\AppId.sys) and a service (AppIdSvc.dll) running in a standard SvcHost process.

Figure 7-1 shows the relationships among some of these components and the databases they manage.




FIGURE 7-1 Windows security components.

## EXPERIMENT: Looking inside HKLM\SAM and HKLM\Security

The security descriptors associated with the SAM and Security keys in the registry prevent access by any account other than the local system account. One way to gain access to these keys for exploration is to reset their security, but that can weaken the system's security. Another way is to execute Regedit.exe while running as the local system account. This can be done using the PsExec tool from Sysinternals with the -s option, as shown here:

C:\>psexec -s -i -d c:\windows\regedit.exe

The -i switch instructs PsExec to run the target executable under the interactive window station. Without it, the process would run in a non-interactive window station, on an invisible desktop. The -d switch just indicates PsExec should not wait until the target process exits.

le Edit View Favorites Help			
Computer     Computer	Name d)(Default) ∰F ∰V	Type REG_SZ REG_BINARY REG_BINARY	Data (value not set) 02 00 01 00 00 00 00 00 20 17 8a 47 14 23 d2 01 00 00 00 00 bc 00 00 00 02 00 01 00 bc 00 00 00

The SRM, which runs in kernel mode, and Lsass, which runs in user mode, communicate using the ALPC facility described in Chapter 8, "System mechanisms," in Part 2. During system initialization, the SRM creates a port, named SeRmCommandPort, to which Lsass connects. When the Lsass process starts, it creates an ALPC port named SeLsaCommandPort. The SRM connects to this port, resulting in the creation of private communication ports. The SRM creates a shared memory section for messages longer than 256 bytes, passing a handle in the connect call. Once the SRM and Lsass connect to each other during system initialization, they no longer listen on their respective connect ports. Therefore, a later user process has no way to connect successfully to either of these ports for malicious purposes. The connect request will never complete.

## Virtualization-based security

It is common to refer to the kernel as *trusted*, due to its inherently higher level of privilege and isolation from user-mode applications. Yet, countless third-party drivers are written each month—Microsoft has stated that a million unique driver hashes are seen through telemetry, monthly! Each of these can contain any number of vulnerabilities, not to mention purposefully malicious kernel-mode code. In such a reality, the idea that the kernel is a small, protected component, and that user-mode applications are "safe" from attack, is clearly an unrealized ideal. This state of affairs leads to an inability to fully trust the kernel, and leaves key user-mode applications, which may contain highly private user data, open to compromise from other malicious user-mode applications (which exploit buggy kernel-mode components) or malicious kernel-mode programs.

As discussed in Chapter 2, "System architecture," Windows 10 and Server 2016 include a virtualizationbased security (VBS) architecture that enables an additional orthogonal level of trust: the virtual trust level (VTL). In this section, you will see how Credential Guard and Device Guard leverage VTLs to protect user data and provide an additional hardware-trust-based layer of security for digital code-signing purposes. At the end of this chapter, you will also see how Kernel Patch Protection (KPP) is provided through the PatchGuard component and enhanced by the VBS-powered HyperGuard technology.

As a reminder, normal user-mode and kernel code runs in VTL 0 and is unaware of the existence of VTL 1. This means anything placed at VTL 1 is hidden and inaccessible to VTL 0 code. If malware is able to penetrate the normal kernel, it still cannot gain access to anything stored in VTL 1, including even user-mode code running in VTL 1 (which is called Isolated User Mode). Figure 7-2 shows the main VBS components we'll be looking at in this section:

- Hypervisor-Based Code Integrity (HVCI) and Kernel-Mode Code Integrity (KMCI), which power Device Guard
- LSA (Lsass.exe) and isolated LSA (Lsalso.exe), which power Credential Guard

Additionally, recall that the implementation of Trustlets, which run in IUM, was shown in Chapter 3, "Process and jobs."




FIGURE 7-2 VBS components.

Of course, like any trusted component, VTL 1 also makes certain assumptions that the components it depends on can also be trusted. As such, VTL 1 requires Secure Boot (and thus, firmware) to function correctly, the hypervisor to not have been compromised, and hardware elements such as the IOMMU and Intel Management Engine to be free of VTL 0–accessible vulnerabilities. For more information on the hardware chain of trust and boot-related security technologies, see Chapter 11, "Startup and shutdown," in Part 2.

# **Credential Guard**

To understand the security boundary and protection that Credential Guard provides, it is important to understand the various components that provide access to a user's resources and data or login capabilities on a networked environment:

- Password This is the primary credential used by interactive users to identify themselves on the machine. This credential is used for authentication and to derive the other components of the credential model. It is the most highly sought after piece of a user's identity.
- NT one-way function (NT OWF) This is a hash used by legacy components to identify the user (after a successful password logon) using the NT LAN Manager (NTLM) protocol. While modern networked systems no longer use NTLM to authenticate the user, many local components still do, as do some types of legacy network components (such as NTLM-based authenticating proxies). Because NTOWF is an MD4 hash, its algorithmic complexity in the face of today's hardware, and its lack of anti-repeatability protection, means that intercepting the hash leads to instant compromise and even possible recovery of the password.
- Ticket-granting ticket (TGT) This is the equivalent of the NTOWF when a much more modern remote authentication mechanism is used: Kerberos. This is the default on Windows Active Directory–based domains and is enforced on Server 2016. The TGT and a corresponding key are provided to the local machine after a successful logon (just like the NTOWF on NTLM), and intercepting both components will result in instant compromise of the user's credentials, although reuse and password recovery will not be possible.

Without Credential Guard enabled, some or all of these components of a user's authentication credentials are present in the memory of Lsass.

-	-			 -
r -				
	-	_	_	
	-	_	_	

Note To enable Credential Guard on Windows 10 Enterprise and Server 2016 editions, open the Group Policy editor (**gpedit.msc**), choose **Computer Configuration**, select **Administrative Templates**, choose **System**, choose **Device Guard**, and select **Turn on Virtualization Based Security**. In the top-left part of the dialog box that appears, select **Enabled**. Finally, select one of the **Enabled** options in the Credential Guard Configuration combo box.

## Protecting the password

The password, encrypted with a local symmetric key, is stored to provide single sign-on (SSO) capabilities over protocols such as digest authentication (WDigest, used for HTTP-based authentication since Windows XP) or Terminal Services/RDP. As these protocols use plaintext authentication, the password must be kept in memory, which is then accessible through code injection, debugger, or other exploit techniques, and decrypted. Credential Guard cannot change the nature of these inherently unsafe protocols. Therefore, the only possible solution, which Credential Guard employs, is to disable SSO functionality for such protocols. This causes a loss of compatibility and forces the user to re-authenticate.

Obviously, a preferable solution is to remove the usage of a password completely, which Windows Hello, described in the "Windows Hello" section later in this chapter, allows. Authenticating with biometric credentials such as a user's face or fingerprint removes the need to ever type a password, securing the interactive credential against hardware key loggers, kernel sniffing/hooking tools, and user mode–based spoofing applications. If the user never has a password to type, there is no password to steal. Another similar secure credential is the combination of a smart card and associated PIN. While a PIN may be stolen as its typed in, the smart card is a physical element whose key cannot be intercepted without a complex hardware-based attack. This is a type of two-factor authentication (TFA), of which many other implementations exist.

## Protecting the NTOWF/TGT key

Even with protected interactive credentials, a successful login results in a domain controller's key distribution center (KDC) returning the TGT and its key, as well as the NTOWF for legacy applications. Later, the user simply uses the NTOWF for accessing legacy resources and uses the TGT and its key to generate a service ticket. This can then be used to access remote resources (such as files on a share), as shown in Figure 7-3.



FIGURE 7-3 Accessing remote resources.

Thus, with either the NTOWF or the TGT and its key (stored in Lsass) in the attacker's hands, access to resources is possible even without the smart card, PIN, or user's face or fingerprint. Protecting Lsass from access by an attacker is thus one option that can be used, and which is possible using the Protected Process Light (PPL) architecture described in Chapter 3.

Lsass can be configured to run protected by setting the DWORD value RunAsPPL in the HKLM\ System\CurrentControlSet\Consol\Lsa registry key to 1. (This is not a default option, as legitimate thirdparty authentication providers [DLLs] load and execute in the context of Lsass, which would not be possible if Lsass would run protected.) Unfortunately, while this protection does guard the NTOWF and TGT key from user-mode attackers, it does not protect against kernel attackers or user-mode attackers that leverage vulnerabilities in any of the millions of drivers that are produced monthly. Credential Guard solves this problem by using another process, Lsaiso.exe, which runs as a Trustlet in VTL 1. This process therefore stores the user's s secrets in its memory, not in Lsass.

#### Secure communication

As shown in Chapter 2, VTL 1 has a minimal attack surface, as it does not have the full regular "NT" kernel, nor does it have any drivers or access to I/O of hardware of any kind. As such, isolated LSA, which is a VTL 1 Trustlet, cannot directly communicate with the KDC. This is still the responsibility of the Lsass process, which serves as a proxy and protocol implementer, communicating with the KDC to authenticate the user and to receive the TGT and the key and NTOWF, as well as communicating with the file server by using service ticket. This seemingly results in a problem: the TGT and its key/NTOWF transiently pass through Lsass during authentication, and the TGT and its key are somehow available to Lsass for the generation of service tickets. This leads to two questions: How does Lsass send and receive the secrets from isolated ISA, and how can we prevent an attacker from doing the same?

To answer the first question, recall that Chapter 3, "Processes and jobs," described which services are available to Trustlets. One was the Advanced Local Procedure Call (ALPC), which the Secure Kernel supports by proxying the NtA1pc\* calls to the Normal Kernel. Then, the Isolated User Mode environment implements support for the RPC runtime library (Rpcrt4.dll) over the ALPC protocol, which allows a VTL 0 and VTL 1 application to communicate using local RPC just like any other application and service. In Figure 7-4, which shows Process Explorer, you can see the Lsalso.exe process, which has a handle to the LSA\_ISO\_RPC\_SERVER ALPC port. This is used to communicate with the Lsass.exe process. (See Chapter 8 in Part 2 for more information on ALPC.)

To answer the second question, some understanding of cryptographic protocols and challenge/ response models is required. If you're already familiar with some of the basic concepts of SSL/TLS technology and its use in Internet communications to prevent man-in-the-middle (MitM) attacks, you can think of the KDC and isolated LSA protocol in a similar way. Although Lsass sits in the middle as a proxy would, it only sees encrypted traffic between the KDC and isolated LSA, without the ability to understand its contents. Because isolated LSA establishes a local "session key," which only lives in VTL 1, and then uses a secure protocol to send this session key encrypted with yet another key, which only the KDC has, the KDC can then respond with the TGT and its key after encrypting it with the isolated LSA session key. Therefore, Lsass sees an encrypted message to the KDC (which it can't decrypt) and an encrypted message from the KDC (which it can't decrypt).

	🖻 🖹 📄 🔛 🛣 メ (	4 💮	march			-
Process	^	CPU	Private Bytes	Working Set	PID Description	Compar
🖃 🎥 explorer	exe	0.07	22,144 K	68,772 K	3104 Windows Explorer	Microsoft
inetinfo.	50(8)	112-161-3	6,480 K	14,888 K	2572 Internet Information Services	Microsoft
Interrupt	9	13.88	0 K	0 K	n/a Hardware Interrupts and DPCs	1
IpOverU	lsb Svc.exe		7,680 K	12,132 K	1776 Windows IP Over USB PC S	Microsoft
Internet .	exe		1,928 K	5,408 K	2584 Windows NT Intersite Messa	. Microsoft
LogonU	l.exe		11,364 K	47,088 K	432 Windows Logon User Interfa	Microsoft
Laalso.e	008	-	1,444 K	3.628 K	720	
I loads.co		0.02	48,612 K	58,960 K	728	
Media St	reamingProvider.exe		33,860 K	43,136 K	6816 Windows Server Essentials	Microsoft
Microsol	t Active Directory. Web Services	<	20.010.10	10 700 10	0.55 0.5 m Fr 1 186	" ,"
Туре	Name					
ALPC Port	VRPC Control/LSA_ISO_RE	C_SERV	ER			
vent	\LSA_ISO_SHUTDOWN	1.0				
ile	C:\Windows					
hread	Lsalso.exe(720): 724					
Thread	Lsalso.exe(720): 760					
hread	Lsalso.exe(720): 772					
Thread	Lsalso.exe(720): 776 Lsalso.exe(720): 5512					
Thread	Lsalso.exe(720): 5516					
TRODU	Esdiso.exe(720). 53 To					

FIGURE 7-4 Lsalso.exe and its ALPC port.

This model can even be used to protect legacy NTLM authentication, which is based on a challenge/ response model. For example, when a user logs in with a plaintext credential, LSA sends it to isolated LSA, which then encrypts it with its session key and returns the encrypted credential to Lsass. Later, when an NTLM challenge/response is required, Lsass sends the NTLM challenge and the previously encrypted credentials to isolated LSA. At this point, only isolated LSA has the encryption key, so it decrypts the credentials and generates an NTLM response based on the challenge.

Note, however, that four possible attacks exist in this model:

- If the machine is already physically compromised, the plaintext password can be intercepted either as it is inputted or as it is sent to isolated LSA (if Lsass is already compromised). Using Windows Hello can mitigate against this.
- As mentioned, NTLM does not have anti-replay properties. Therefore, if the NTLM response is captured, it can be replayed for the same challenge. Alternatively, if the attacker can compromise Lsass after logon, it can capture the encrypted credential and force isolated LSA to generate new NTLM responses for arbitrary NTLM challenges. This attack, however, only works until reboot, because isolated LSA generates a new session key at that point.
- In the case of Kerberos logon, the NTOWF (which is not encrypted) can be intercepted and then reused, just like in a standard pass-the-hash attack. Again, however, this requires an already compromised machine (or physical network interception).
- The user, with physical access, may be able to disable Credential Guard. In this situation, the legacy authentication model is used (a so-called "downgrade attack"), and older attack models can now be employed.

## **UEFI** lock

Because disabling Credential Guard (which is ultimately nothing more than a registry setting) is trivial for an attacker, Secure Boot and UEFI can be leveraged to prevent a non-physically present administrator (such as malware with admin rights) from disabling Credential Guard. This is done by enabling Credential Guard with UEFI Lock. In this mode, an EFI runtime variable is written to firmware memory and a reboot is required. At the reboot, the Windows boot loader, which still operates in EFI Boot Services mode, will write an EFI boot variable (which has the property of not being readable or writeable once EFI Boot Services mode is exited) to record the fact that Credential Guard is enabled. Additionally, a Boot Configuration Database (BCD) option will be recorded.

When the kernel boots, it will automatically rewrite the required Credential Guard registry key in the presence of the BCD option and/or UEFI runtime variable. If the BCD option is deleted by an attacker, BitLocker (if enabled) and TPM-based remote attestation (if enabled) will detect the change and require physical input of the admin's recovery key before booting, which will then restore the BCD option based on the UEFI runtime variable. If the UEFI runtime variable is deleted, the Windows boot loader will restore it based on the UEFI boot variable. As such, without special code to delete the UEFI boot variable—which can only be done in EFI Boot Services mode—there is no way to disable Credential Guard in UEFI lock mode.

The only such code that exists is in a special Microsoft binary called SecComp.efi. This must be downloaded by the administrator, who must then either boot the computer from an alternate EFI-based device and manually execute it (which will require the BitLocker recovery key as well as physical access) or modify the BCD (which will require the BitLocker recovery key). At the reboot, SecComp.efi will require user confirmation while in UEFI mode (which can only be done by a physical user).

#### Authentication policies and armored Kerberos

Using a security model of "secure, unless already compromised before logon or by a physical administrator" is definitely an improvement over the traditional non-Credential Guard–based security model. However, some enterprises and organizations may want an even stronger security guarantee: that even a compromised machine cannot be used to fake or replay a user's credentials, and that if a user's credentials *have* been compromised, they cannot be used outside of specific systems. By leveraging a Server 2016 feature called Authentication Policies, and armored Kerberos, Credential Guard can operate in this heightened security mode.

In this mode, the VTL 1 Secure Kernel will collect, using the TPM (a file on disk can also be used, but makes the security moot), a special machine ID key. This key is then used to generate a machine TGT key during the initial domain join operation as the machine is provisioned (obviously, it is important to ensure the machine is in a trusted state during provisioning), and this TGT key is sent to the KDC. Once configured, when the user logs in with his or her credential, it is combined with the machine's credential (which only isolated LSA has access to), which forms a proof-of-origin key. The KDC will then reply with the NTOWF and user TGT and its key after encrypting it with the proof-of-origin key. In this mode, two security guarantees are provided:

The user is authenticating from a known machine If the user, or an attacker, has the original credentials, and attempts to use them on a different machine, its TPM-based machine credential will be different.

The NTLM response/user ticket is coming from isolated LSA and has not been manually generated from Lsass This guarantees that Credential Guard is enabled on the machine, even if the physical user can disable it in some way.

Unfortunately, once again, if the machine is compromised in such a way that the proof-of-originencrypted KDC response that contains the user TGT and its key is intercepted, it can be stored and used to request session key–encrypted service tickets from isolated LSA. This can then be sent to a file server (for example) to access it until a reboot is issued to wipe the session key. As such, on a system with Credential Guard, it is recommended to reboot each time a user logs off. Otherwise, an attacker may be able to issue valid tickets even after the user is no longer present.

#### **Future improvements**

As discussed in Chapter 2 and Chapter 3, the Secure Kernel in VTL 1 is currently undergoing improvements to add support for specialized classes of PCI and USB hardware, which can exclusively be communicated with only through the hypervisor and VTL 1 code using the Secure Device Framework (SDF). Combined with Biolso.exe and FsIso.exe, which are new Trustlets to securely obtain biometric data and video frames (from a webcam), a VTL 0 kernel mode–based component cannot intercept the contents of a Windows Hello authentication attempt (which we've classified as safe compared to a user's plaintext password, but still technically capturable through custom driver-based interception). Once released, Windows Hello credentials will be guaranteed at the hardware level to not ever be available to VTL 0. In this mode, Lsass will not need to be involved in a Windows Hello authentication. Isolated LSA will obtain the credentials directly from the isolated biometrics or isolated frame service.

**Note** The Secure Driver Framework (SDF) is the WDF-equivalent for VTL 1 drivers. This framework is not currently public, but is shared with Microsoft partners only for creating VTL 1 drivers.

# **Device Guard**

While Credential Guard is concerned with safeguarding the user's credentials, Device Guard has a completely different goal: protecting the user's machine itself from different kinds of software- and hardware-based attacks. Device Guard leverages the Windows Code Integrity services, such as Kernel-Mode Code Signing (KMCS) and User-Mode Code Integrity (UMCI), and strengthens them through HyperVisor Code Integrity (HVCI). (See Chapter 8 in Part 2 for more information on Code Integrity.)

Additionally, Device Guard is fully configurable, thanks to Custom Code Integrity (CCI) and signing policies that are protected by Secure Boot and defined by the enterprise administrator. These policies, which are explained in Chapter 8, allow the enforcement of inclusion/exclusion lists that are based on cryptographically sound information (such as certificate signers or SHA-2 hashes) instead of file paths or file names as with AppLocker's policies. (See the section "AppLocker" later in this chapter for more on AppLocker.)

Therefore, while we won't describe here the different ways in which Code Integrity policies can be defined and customized, we will show how Device Guard enforces whatever these policies may be set to, through the following guarantees:

- If kernel-mode code signing is enforced, only signed code can load, regardless of the kernel itself being compromised This is because the kernel-loading process will notify the Secure Kernel in VTL 1 whenever it loads a driver, and only successfully load it once HVCI has validated its signature.
- If kernel-mode code signing is enforced, signed code cannot be modified once loaded, even by the kernel itself This is because the executable code pages will be marked as readonly through the hypervisor's Second Level Address Translation (SLAT) mechanism, which is further explained in Chapter 8 in Part 2.
- If kernel-mode code signing is enforced, dynamically allocated code is prohibited (a tautology of the first two bullets) This is because the kernel does not have the ability to allocate executable entries in the SLAT page table entries, even though the kernel's page tables themselves may mark such code as executable.
- If kernel-mode code signing is enforced, UEFI runtime code cannot be modified, even by other UEFI runtime code or by the kernel itself Additionally, Secure Boot should already have validated that this code was signed at the time it was loaded. (Device Guard relies on this assumption.) Furthermore, UEFI runtime data cannot be made executable. This is done by reading all the UEFI runtime code and data, enforcing the correct permissions, and duplicating them in the SLAT page table entries, which are protected in VTL 1.
- If kernel-mode code signing is enforced, only kernel-mode (ring 0) signed code can execute This may once again sound like a tautology of the first three bullets, but consider signed ring 3 code. Such code is valid from UMCI's perspective and has been authorized as executable code in the SLAT page table entries. The Secure Kernel relies on the Mode-Based Execution Control (MBEC) feature, if present in hardware, which enhances the SLAT with a user/ kernel executable bit, or the hypervisor's software emulation of this feature, called Restricted User Mode (RUM).
- If user-mode code signing is enforced, only signed user-mode images can be loaded This means all executable processes must be signed (.exe) files as well as the libraries they load (.dll).
- If user-mode code signing is enforced, the kernel does not allow user-mode applications to make existing executable code pages writable Obviously, it is impossible for user-mode code to allocate executable memory or to modify existing memory without asking the kernel permission. As such, the kernel can apply its usual enforcement rules. But even in the case of a compromised kernel, the SLAT ensures that no user-mode pages will be executable without the Secure Kernel's knowledge and approval, and that such executable pages can never be writeable.
- If user-mode code signing is enforced, and hard code guarantees are requested by the signing policy, dynamically allocated code is prohibited This is an important distinction from the kernel scenarios. By default, signed user-mode code is allowed to allocate additional

executable memory to support JIT scenarios unless a special enhanced key usage (EKU) is present in the application's certificate, which serves as a dynamic code generation entitlement. At present, NGEN.EXE (.NET Native Image Generation) has this EKU, which allows IL-only .NET executables to function even in this mode.

If user-mode PowerShell constrained language mode is enforced, all PowerShell scripts that use dynamic types, reflection, or other language features that allow the execution or arbitrary code and/or marshalling to Windows/.NET API functions must also be signed This prevents possibly malicious PowerShell scripts from escaping constrained mode.

SLAT page table entries are protected in VTL 1 and contain the "ground truth" for what permissions a given page of memory can have. By withholding the executable bit as needed, and/or withholding the writable bit from existing executable pages (a security model known as W^X, pronounced *double-you xor ex*), Device Guard moves all code-signing enforcement into VTL 1 (in a library called SKCI.DLL, or Secure Kernel Code Integrity).

Additionally, even if not configured explicitly on the machine, Device Guard operates in a third mode if Credential Guard is enabled by enforcing that all Trustlets have a specific Microsoft signature with a certificate that includes the Isolated User Mode EKU. Otherwise, an attacker with ring 0 privileges could attack the regular KMCS mechanism and load a malicious Trustlet to attack the isolated LSA component. Furthermore, all user-mode code-signing enforcements are active for the Trustlet, which executes in hard code guarantees mode.

Finally, as a performance optimization, it is important to understand that the HVCI mechanism will not reauthenticate every single page when the system resumes from hibernation (S4 sleep state). In some cases, the certificate data may not even be available. Even if this were the case, the SLAT data must be reconstructed, which means that the SLAT page table entries are stored in the hibernation file itself. As such, the hypervisor needs to trust the hibernation file has not been modified in any way. This is done by encrypting the hibernation file with a local machine key that is stored in the TPM. Unfortunately, without a TPM present, this key must be stored in a UEFI runtime variable, which allows a local attacker to decrypt the hibernation file, modify it, and re-encrypt it.

## **Protecting objects**

Object protection and access logging are the essence of discretionary access control and auditing. The objects that can be protected on Windows include files, devices, mailslots, pipes (named and anonymous), jobs, processes, threads, events, keyed events, event pairs, mutexes, semaphores, shared memory sections, I/O completion ports, LPC ports, waitable timers, access tokens, volumes, window stations, desktops, network shares, services, registry keys, printers, Active Directory objects, and so on—theoretically, anything managed by the executive object manager. In practice, objects that are not exposed to user mode (such as driver objects) are usually not protected. Kernel-mode code is trusted and usually uses interfaces to the object manager that do not perform access checking. Because system resources that are exported to user mode (and hence require security validation) are implemented as objects in kernel mode, the Windows object manager plays a key role in enforcing object security.

You can view object protection with the WinObj Sysinternals tool (for named objects), shown in Figure 7-5. Figure 7-6 shows the Security property page of a section object in the user's session. Although files are the resources most commonly associated with object protection, Windows uses the same security model and mechanism for executive objects as it does for files in the file system. As far as access controls are concerned, executive objects differ from files only in the access methods supported by each type of object.

Vie	w Help			
1		Name /	Туре	
	ArcName	A HKEY_LOCAL_MACHINE_SOFTWARE_Microsoft_Speech_Voices_Tokens	Event	
2	BaseNamedObjects	HKEY_LOCAL_MACHINE_SOFTWARE_Microsoft_Speech_Voices_Tokens	Mutant	
<u>_</u>	Callback Device	A HKEY_LOCAL_MACHINE_SOFTWARE_Microsoft_Speech_Voices_Tokens	Event	
2-	Driver	HKEY_LOCAL_MACHINE_SOFTWARE_Microsoft_Speech_Voices_Tokens	Mutant	
-	FileSystem	A HomePageEvent	Event	
Y - 1	Filters	HPNOTIFICATIONS	Mutant	
	GLOBAL??	HWNDInterface:100d62	Section	
	KernelObjects	HWNDInterface:10126	Section	
	KnownDils	HWNDInterface: 10168	Section	
	KnownDils32	HWNDInterface:1017a	Section	
	NLS	HWNDInterface:10180	Section	
	ObjectTypes	HWNDInterface:101834	Section	
	RPC Control	HWNDInterface:101b2	Section	
	Security	HWNDInterface:1036c	Section	
1-	Sessions	HWNDInterface:10372	Section	
5		HWNDInterface:10378	Section	
~	. 1	HWNDInterface: 103e4	Section	
11	> AppContainerNamedObjects	HWNDInterface:103ec	Section	
11	> BaseNamedObjects	HWNDInterface:103f4	Section	
11	- DosDevices	HWNDInterface:103f6	Section	
1	> Windows	HWNDInterface: 10400	Section	
	BNOLINKS	HWNDInterface: 10404	Section	
¢-	Windows	HWNDInterface: 10408	Section	
-		HWNDInterface: 1048e	Section	
		HWNDInterface:1049e	Section	
			4 1	>

FIGURE 7-5 WinObj with a section object selected.

Group or user names:		
SYSTEM Pavel Yosifovich (zodiacon@ LogonSessionId_0_1484282		
	Add	Remove
Permissions for SYSTEM	Allow	Deny
Read		^
Write		
Delete		
Execute		
Contractor		v
Synchronize	ed settings, click	Advanced

FIGURE 7-6 An executive object and its security descriptor, viewed by WinObj.

What is shown in Figure 7-6 is actually the object's discretionary access control list (DACL). We will describe DACLs in detail in the section "Security descriptors and access control."

You can use Process Explorer to view the security properties of objects by double-clicking a handle in the lower pane view (when configured to show handles). This has the added benefit of displaying objects that are unnamed. The Property page shown is the same in both tools, as the page itself is provided by Windows.

To control who can manipulate an object, the security system must first be sure of each user's identity. This need to guarantee the user's identity is the reason that Windows requires authenticated logon before accessing any system resources. When a process requests a handle to an object, the object manager and the security system use the caller's security identification and the object's security descriptor to determine whether the caller should be assigned a handle that grants the process access to the object it desires.

As discussed later in this chapter, a thread can assume a different security context than that of its process. This mechanism is called *impersonation*. When a thread is impersonating, security validation mechanisms use the thread's security context instead of that of the thread's process. When a thread isn't impersonating, security validation falls back on using the security context of the thread's owning process. It's important to keep in mind that all the threads in a process share the same handle table, so when a thread opens an object—even if it's impersonating—all the threads of the process have access to the object.

Sometimes, validating the identity of a user isn't enough for the system to grant access to a resource that should be accessible by the account. Logically, one can think of a clear distinction between a service running under the Alice account and an unknown application that Alice downloaded while browsing the Internet. Windows achieves this kind of intra-user isolation with the Windows integrity mechanism, which implements integrity levels. The Windows integrity mechanism is used by User Account Control (UAC) elevations, User Interface Privilege Isolation (UIPI) and AppContainers, all described later in this chapter.

## Access checks

The Windows security model requires that a thread specify up front, at the time that it opens an object, what types of actions it wants to perform on the object. The object manager calls the SRM to perform access checks based on a thread's desired access. If the access is granted, a handle is assigned to the thread's process with which the thread (or other threads in the process) can perform further operations on the object.

One event that causes the object manager to perform security access validation is when a thread opens an existing object using a name. When an object is opened by name, the object manager performs a lookup of the specified object in the object manager namespace. If the object isn't located in a secondary namespace, such as the configuration manager's registry namespace or a file system driver's file system namespace, the object manager calls the internal function ObpCreateHandle once it locates the object. As its name implies, ObpCreateHandle creates an entry in the process handle table that becomes associated with the object. ObpCreateHandle first calls ObpGrantAccess to see if the thread has

permission to access the object. If so, ObpCreateHandle calls the executive function ExCreateHandle to create the entry in the process handle table. ObpGrantAccess calls ObCheckObjectAccess to initiate the security access check.

ObpGrantAccess passes to ObCheckObjectAccess the security credentials of the thread opening the object, the types of access to the object that the thread is requesting (read, write, delete, and so forth, including object-specific operations), and a pointer to the object. ObCheckObjectAccess first locks the object's security descriptor and the security context of the thread. The object security lock prevents another thread in the system from changing the object's security while the access check is in progress. The lock on the thread's security context prevents another thread (from that process or a different process) from altering the security identity of the thread while security validation is in progress. ObCheckObjectAccess then calls the object's security method to obtain the security settings of the object. (See Chapter 8 in Part 2 for a description of object methods.) The call to the security method might invoke a function in a different executive component. However, many executive objects rely on the system's default security management support.

When an executive component defining an object doesn't want to override the SRM's default security policy, it marks the object type as having default security. Whenever the SRM calls an object's security method, it first checks to see whether the object has default security. An object with default security stores its security information in its header, and its security method is SeDefaultObjectMethod. An object that doesn't rely on default security must manage its own security information and supply a specific security method. Objects that rely on default security include mutexes, events, and semaphores. A file object is an example of an object that overrides default security. The I/O manager, which defines the file object type, has the file system driver on which a file resides manage (or choose not to implement) the security for its files. Thus, when the system queries the security on a file object that represents a file on an NTFS volume, the I/O manager file object security method retrieves the file's security using the NTFS file system driver. Note, however, that ObCheckObjectAccess isn't executed when files are opened because they reside in secondary namespaces. The system invokes a file object's security method only when a thread explicitly queries or sets the security on a file (with the Windows SetFileSecurity or GetFileSecurity functions, for example).

After obtaining an object's security information, ObCheckObjectAccess invokes the SRM function SeAccessCheck. SeAccessCheck is one of the functions at the heart of the Windows security model. Among the input parameters SeAccessCheck accepts are the object's security information, the security identity of the thread as captured by ObCheckObjectAccess, and the access that the thread is requesting. SeAccessCheck returns true or false, depending on whether the thread is granted the access it requested to the object.

Here is an example: Suppose a thread wants to know when a specific process exits (or terminates in some way). It needs to get a handle to the target process by calling the OpenProcess API, passing in two important arguments: the unique process ID (let's assume it's known or has been obtained in some way) and an access mask indicating the operations that the thread wants to perform using the returned handle. Lazy developers may just pass PROCESS\_ALL\_ACCESS for the access mask, specifying they want all possible access rights for the process. One of the following two results would occur:

- If the calling thread can be granted all the permissions, it would get back a valid handle and then could call WaitForSingleObject to wait for the process to exit. However, another thread in the process, perhaps with fewer privileges, can use the same handle to do other operations with the process, such as terminate it prematurely with TerminateProcess, because the handle allows all possible operations on the process.
- The call can fail if the calling thread does not have sufficient privileges to be granted all possible access and the result is an invalid handle, meaning no access to the process. This is unfortunate, because the thread just needed to ask for the SYNCHRONIZE access mask. That has a much better chance of succeeding than asking for PROCESS\_ALL\_ACCESS.

The simple conclusion here is that a thread should request the exact access it requires—no more, no less.

Another event that causes the object manager to execute access validation is when a process references an object using an existing handle. Such references often occur indirectly, as when a process calls on a Windows API to manipulate an object and passes an object handle. For example, a thread opening a file can request read permission to the file. If the thread has permission to access the object in this way, as dictated by its security context and the security settings of the file, the object manager creates a handle representing the file—in the handle table of the thread's process. The types of accesses the threads in the process are granted through the handle are stored with the handle by the object manager.

Subsequently, the thread could attempt to write to the file using the WriteFile Windows function, passing the file's handle as a parameter. The system service NtWriteFile, which WriteFile calls via Ntdll.dll, uses the object manager function ObReferenceObjectByHandle (documented in the WDK) to obtain a pointer to the file object from the handle. ObReferenceObjectByHandle accepts the access that the caller wants from the object as a parameter. After finding the handle entry in the process handle table, ObReferenceObjectByHandle compares the access being requested with the access granted at the time the file was opened. In this example, ObReferenceObjectByHandle will indicate that the write operation should fail because the caller didn't obtain write access when the file was opened.

The Windows security functions also enable Windows applications to define their own private objects and to call on the services of the SRM (through the AuthZ user-mode APIs, described later) to enforce the Windows security model on those objects. Many kernel-mode functions that the object manager and other executive components use to protect their own objects are exported as Windows user-mode APIs. The user-mode equivalent of SeAccessCheck is the AuthZ API AccessCheck. Windows applications can therefore leverage the flexibility of the security model and transparently integrate with the authentication and administrative interfaces that are present in Windows.

The essence of the SRM's security model is an equation that takes three inputs: the security identity of a thread, the access that the thread wants to an object, and the security settings of the object. The output is either yes or no and indicates whether the security model grants the thread the access it desires. The following sections describe the inputs in more detail and then document the model's access-validation algorithm.

## **EXPERIMENT:** Viewing handle access masks

Process Explorer can show the access mask associated with open handles. Follow these steps:

- 1. Open Process Explorer.
- 2. Open the View menu, choose Lower Pane View, and select Handles to configure the lower pane to show handles.
- **3.** Right-click the column headers of the lower pane and choose **Select Columns** to open the dialog box shown here:



- 4. Select the Access Mask and Decoded Access Mask check boxes (the latter is available in version 16.10 and later) and click OK.
- 5. Select Explorer.exe from the process list and look at the lower pane handles. Each handle has an access mask, indicating the access granted using this handle. To help with interpreting the bits of the access mask, the decoded access mask column shows a textual representation of the access masks for many types of objects:

H H B B B B B B A A O	Uses Help			1	
Voces C devenues devenues D devenues D Dhyort.exe D Dyburd.exe D D D D D D D D D D D D D D D D D D D	PID CPU 7696 0.65 11496 0.05 13252 8980 9092 5884 3820	Private Bytes 611.044 K 361.668 K 4,756 K 26,520 K 924 K 2,360 K 30.824 K	Weeking Skil Description 705/328 K Microsoft Vasal Studio 2015 435/321 K Microsoft Vasal Studio 2015 12,528 K COM Samogate 41,476 K DigitalPersona Local Agent 4,292 K DigitalPersona Card Ingien 42,448 K DigitalPersona Card Ingien 42,448 K DigitalPersona Card Ingien 42,448 K DigitalPersona Card Ingien	Company Name Microsoft Corporation Microsoft Corporation Digital/Prisona, Inc Digital/Prisona, Inc Digital/Prisona, Inc Digital/Prisona, Inc.	
0x3D0 ALPC Part 0x3D4 EtwRegistration 0x3D8 EtwRegistration			Dx001F0001 READ_CONTROL   DELETE   5) 0x00000004 <unknown+ 0x00000004 <unknown+< th=""><th>LACHINGUISE   MIDIE THY:   MIDIE OV</th><th>AMER   <u< th=""></u<></th></unknown+<></unknown+ 	LACHINGUISE   MIDIE THY:   MIDIE OV	AMER   <u< th=""></u<>
Ox3DC EtwRegistration Ox3E0 EtwRegistration Ox3E4 Event Ox3E8 ALPC Point			0x0000000 «Unknown» 0x00000004 «Unknown» 0x00000004 «Unknown» 0x001F0003 READ_CONTROL   DELETE   51 0x001F0001 READ_CONTROL   DELETE   51		

CPU Usage: 32.28% Commit Charge: 41.97% Processes: 174 Physical Usage: 38.45%

Notice there are generic access rights (for example, READ\_CONTROL and SYNCHRONIZE) and specific ones (for example, KEY\_READ and MODIFY\_STATE). Most of the specific ones are shortened versions of the actual defines in the windows headers (for example, MODIFY\_STATE instead of EVENT\_MODIFY\_STATE, TERMINATE instead of PROCESS\_TERMINATE).

# Security identifiers

Instead of using names (which might or might not be unique) to identify entities that perform actions in a system, Windows uses security identifiers (SIDs). Users have SIDs, as do local and domain groups, local computers, domains, domain members, and services. A SID is a variable-length numeric value that consists of a SID structure revision number, a 48-bit identifier authority value, and a variable number of 32-bit subauthority or relative identifier (RID) values. The authority value identifies the agent that issued the SID, and this agent is typically a Windows local system or a domain. Subauthority values identify trustees relative to the issuing authority, and RIDs are simply a way for Windows to create unique SIDs based on a common base SID. Because SIDs are long and Windows takes care to generate truly random values within each SID, it is virtually impossible for Windows to issue the same SID twice on machines or domains anywhere in the world.

When displayed textually, each SID carries an S prefix, and its various components are separated with hyphens like so:

#### S-1-5-21-1463437245-1224812800-863842198-1128

In this SID, the revision number is 1, the identifier authority value is 5 (the Windows security authority), and four subauthority values plus one RID (1128) make up the remainder of the SID. This SID is a domain SID, but a local computer on the domain would have a SID with the same revision number, identifier authority value, and number of subauthority values.

When you install Windows, the Windows Setup program issues the computer a machine SID. Windows assigns SIDs to local accounts on the computer. Each local-account SID is based on the source computer's SID and has a RID at the end. RIDs for user accounts and groups start at 1000 and increase in increments of 1 for each new user or group. Similarly, Domain Controller Promote (Dcpromo.exe), the utility used to create a new Windows domain, reuses the computer SID of the computer being promoted to domain controller as the domain SID and re-creates a new SID for the computer if it is ever demoted. Windows issues to new domain accounts SIDs that are based on the domain SID and have an appended RID (again starting at 1000 and increasing in increments of 1 for each new user or group). A RID of 1028 indicates that the SID is the twenty-ninth SID the domain issued.

Windows issues SIDs that consist of a computer or domain SID with a predefined RID to many predefined accounts and groups. For example, the RID for the Administrator account is 500, and the RID for the guest account is 501. A computer's local Administrator account, for example, has the computer SID as its base with the RID of 500 appended to it:

#### S-1-5-21-13124455-12541255-61235125-500

Windows also defines a number of built-in local and domain SIDs to represent well-known groups. For example, a SID that identifies any and all accounts (except anonymous users) is the Everyone SID: S-1-1-0. Another example of a group that a SID can represent is the Network group, which is the group that represents users who have logged on to a machine from the network. The Network group SID is S-1-5-2. Table 7-2, reproduced here from the Windows SDK documentation, shows some basic wellknown SIDs, their numeric values, and their use. Unlike users' SIDs, these SIDs are predefined constants, and have the same values on every Windows system and domain in the world. Thus, a file that is accessible by members of the Everyone group on the system where it was created is also accessible to Everyone on any other system or domain to which the hard drive where it resides happens to be moved. Users on those systems must, of course, authenticate to an account on those systems before becoming members of the Everyone group.

SID	Name	Use
S-1-0-0	Nobody	Used when the SID is unknown
S-1-1-0	Everyone	A group that includes all users except anonymous users
S-1-2-0	Local	Users who log on to terminals locally (physically) connected to the system
S-1-3-0	Creator Owner ID	A security identifier to be replaced by the security identifier of the user who created a new object (used in inheritable ACEs)
S-1-3-1	Creator Group ID	Identifies a security identifier to be replaced by the Primary group SID of the user who created a new object (used in inheritable ACEs)
S-1-5-18	Local System account	Used by services
S-1-5-19	Local Service account	Used by services
S-1-5-20	Network Service account	Used by services

**Note** See Microsoft Knowledge Base article 243330 for a list of defined SIDs at *http://support.microsoft.com/kb/243330*.

Finally, Winlogon creates a unique logon SID for each interactive logon session. A typical use of a logon SID is in an access control entry (ACE) that allows access for the duration of a client's logon session. For example, a Windows service can use the LogonUser function to start a new logon session. The LogonUser function returns an access token from which the service can extract the logon SID. The service can then use the SID in an ACE (described in the section "Security descriptors and access control" later in this chapter) that allows the client's logon session to access the interactive window station and desktop. The SID for a logon session is S-1-5-5-X-Y, where the X and Y are randomly generated.

## **EXPERIMENT: Using PsGetSid and Process Explorer to view SIDs**

You can easily see the SID representation for any account you're using by running the PsGetSid utility from Sysinternals. PsGetSid's options allow you to translate machine and user account names to their corresponding SIDs and vice versa.

If you run PsGetSid with no options, it prints the SID assigned to the local computer. Because the Administrator account always has a RID of 500, you can determine the name assigned to the account (in cases where a system administrator has renamed the account for security reasons) simply by passing the machine SID appended with -500 as PsGetSid's command-line argument. To obtain the SID of a domain account, enter the user name with the domain as a prefix:

#### c:\>psgetsid redmond\johndoe

You can determine the SID of a domain by specifying the domain's name as the argument to PsGetSid:


#### c:\>psgetsid Redmond

Finally, by examining the RID of your own account, you know at least a number of security accounts (equal to the number resulting from subtracting 999 from your RID) have been created in your domain or on your local machine (depending on whether you are using a domain or local machine account). You can determine what accounts have been assigned RIDs by passing a SID with the RID you want to query to PsGetSid. If PsGetSid reports that no mapping between the SID and an account name was possible and the RID is lower than that of your account, you know that the account assigned the RID has been deleted.

For example, to find out the name of the account assigned the 28th RID, pass the domain SID appended with -1027 to PsGetSid:

```
c:\>psgetsid S-1-5-21-1787744166-3910675280-2727264193-1027
Account for S-1-5-21-1787744166-3910675280-2727264193-1027:
User: redmond\johndoe
```

Process Explorer can also show you information on account and group SIDs on your system through its Security tab. This tab shows you information such as who owns this process and which groups the account is a member of. To view this information, simply double-click any process (for example, Explorer.exe) in the Process list and then click the **Security** tab. You should see something similar to the following:



The information displayed in the User field contains the friendly name of the account owning this process, while the SID field contains the actual SID value. The Group list includes information on all the groups that this account is a member of (groups are described later in this chapter).

## **Integrity levels**

As mentioned, integrity levels can override discretionary access to differentiate a process and objects running as and owned by the same user, offering the ability to isolate code and data within a user account. The mechanism of Mandatory Integrity Control (MIC) allows the SRM to have more detailed information about the nature of the caller by associating it with an integrity level. It also provides information on the trust required to access the object by defining an integrity level for it.

The integrity level of a token can be obtained with the GetTokenInformation API with the Token-IntegrityLevel enumeration value. These integrity levels are specified by a SID. Although integrity levels can be arbitrary values, the system uses six primary levels to separate privilege levels, as described in Table 7-3.

SID	Name (Level)	Use
S-1-16-0x0	Untrusted (0)	Used by processes started by the Anonymous group. It blocks most write access.
S-1-16-0x1000	Low (1)	Used by AppContainer processes (UWP) and Protected Mode Internet Explorer. It blocks write access to most objects (such as files and registry keys) on the system.
S-1-16-0x2000	Medium (2)	Used by normal applications being launched while UAC is enabled.
S-1-16-0x3000	High (3)	Used by administrative applications launched through elevation when UAC is enabled, or normal applications if UAC is disabled and the user is an administrator.
S-1-16-0x4000	System (4)	Used by services and other system-level processes (such as Wininit, Winlogon, Smss, and so on).
S-1-16-0x5000	Protected (5)	Currently unused by default. Can be set by kernel-mode caller only.

TABLE 7-3 Integrity level SIDs

Another, seemingly additional, integrity level is called *AppContainer*, used by UWP apps. Although seemingly another level, it's in fact equal to Low. UWP process tokens have another attribute that indicates they are running inside an AppContainer (described in the "AppContainers" section). This information is available with the GetTokenInformation API with the TokenIsAppContainer enumeration value.

## **EXPERIMENT:** Looking at the integrity level of processes

You can use Process Explorer to quickly display the integrity level for the processes on your system. The following steps demonstrate this functionality.

- 1. Launch Microsoft Edge browser and Calc.exe (Windows 10).
- 2. Open an elevated command prompt window.
- 3. Open Notepad normally (without elevating it).
- **4.** Open an elevated Process Explorer, right-click any column header in the Process list, and then click **Select Columns**.

5. Select the **Process Image** tab and select the **Integrity Level** check box. The dialog box should look similar to the one shown here:

Process Network	Pr	ocess Disk	Pro	cess Me	mory
Process GPU I	landle	DLL	NET	State	us Ba
Process Image Process		ess Perform	ance	Proces	is I/O
Select the columns Process Explorer.	that will	appear on th	e Proces	s view of	
Process Name		W	Indow Titl	le	
PID (Process Id	W	Window Status			
User Name		S	ession		
Description		Command Line			
Company Name			mment		
Verified Signer			utostart L	ocation	
Version		UN.	rusTotal		
Image Path			EP Statu	s	
Image Type (64	vs 32-bit	) 🗹 in	tegrity Le	low	
Package Name		UV.	rtualized		
DPI Awareness			SLR Ena	bied	
Protection		UI Access			
Control Flow Gu	ard				
				-	
			OK.	Ca	incel

6. Process Explorer shows you the integrity level of the processes on your system. You should see the Notepad process at medium, the Edge (MicrosoftEdge.exe) process at AppContainer, and the elevated command prompt at High. Also note that the services and system processes are running at an even higher integrity level, System.

Process Explorer - Sysinternals: www.sysin File Options View Process Find Users H		com [200blactessoro]		- 🗆 X
H A S C B C A A O	eip			
Process	PID	CPU Integrity	Private Bytes	Working Set Description
Isass.exe	496	< 0.01 System	9.164 K	20.884 K Local Sec
(5) lync.exe	13928	0.04 Medium	183,248 K	142,044 K Skype for
T macmnsvc.exe	3808	0.05 System	15.116 K	25.572 K McAfee A
macompatsvc.exe	7216	0.01 System	6.920 K	19,348 K MA Come
- U masvc.exe	3784	0.04 System	5.444 K	18.604 K McAfee A
moshield exe		< 0.01 System	167.116 K	188.288 K McAfee C
U mctray.exe	14372	0.11 Medium	8,556 K	1,356 K McTray Ar
mDNSResponder.exe		System	2.048 K	7,168 K Bonjour S
Memory Compression		System	156 K	18,224 K
mfeann.exe		< 0.01 System	4.336 K	3.152 K VSCore A
W MfeEpeHosLexe		0.02 System	29.884 K	32.904 K McAfee E
mfemms.exe		System	3,360 K	8,716 K McAfee N
mfevtps.exe	3824	System	1.644 K	6,596 K McAfee P
mfevtps.exe	6372	System	5,368 K	11,048 K McAfee P
Microsoft Alm Shared Remoting Remo	11868	Medium	26,360 K	39,900 K Microsoft
Microsoft VsHub Server HttpHost.exe	12120	0.01 Medium	202,704 K	202,616 K Microsoft
MicrosoftEdge.exe	17216	< 0.01 AppContainer	36,900 K	73,772 K Microsoft
C MicrosoftEdgeCP.exe	16836	0.01 AppContainer	66.864 K	96,636 K Microsoft
mgsvc.exe	4208	System	5.696 K	13,492 K Message
-Inotepad.exe	1184	< 0.01 Medium	2.372 K	14,228 K Notepad
NvBackend.exe	10724	< 0.01 Medium	2,452 K	10,032 K NVIDIA B
- Envtray.exe	10640	Medium	3.572 K	13,716 K NVIDIA S
- M nvvsvc.exe	1952	System	2,492 K	10,136 K NVIDIA D
- Envwmi64.exe	1960	System	1,444 K	6.836 K NVIDIA W
nvwmi64.exe	3756	< 0.01 System	5,428 K	15,232 K NVIDIA W
- Renveration and the second s	1900	< 0.01 System	10.836 K	26,724 K NVIDIA U
OfficeClickToRun.exe	3560	< 0.01 System	40,148 K	56,256 K Microsoft
ConeDrive.exe	13888	0.06 Medium	219,172 K	242,160 K Microsoft
OUTLOOKEXE	14236	0.03 Medium	167,308 K	212,160 K Microsoft
PerfWatson2.exe	15180	0.01 Medium	59,984 K	74,372 K PerfWatsc
PerfWatson2.exe	14836	0.01 High	41,044 K	55,548 K PerfWatsc
PresentationFontCache.exe	1540	System	23.980 K	24,220 K Presentati
PrivacylconClient.exe	<			>

Every process has an integrity level that is represented in its token and propagated according to the following rules:

- A process normally inherits the integrity level of its parent (which means an elevated command prompt will spawn other elevated processes).
- If the file object for the executable image to which the child process belongs has an integrity level and the parent process's integrity level is medium or higher, the child process will inherit the lower of the two.
- A parent process can create a child process with an explicit integrity level lower than its own. To do this, it uses DuplicateTokenEx to duplicate its own access token, it uses SetToken-Information to change the integrity level in the new token to the desired level, and then it calls CreateProcessAsUser with that new token.

Table 7-3 lists the integrity level associated with processes, but what about objects? Objects also have an integrity level stored as part of their security descriptor, in a structure that is called the *mandatory label*.

To support migrating from previous versions of Windows (whose registry keys and files would not include integrity-level information), and to make it simpler for application developers, all objects have an implicit integrity level to avoid having to manually specify one. This implicit integrity level is medium, meaning that the mandatory policy (described shortly) on the object will be performed on tokens accessing this object with an integrity level lower than medium.

When a process creates an object without specifying an integrity level, the system checks the integrity level in the token. For tokens with a level of medium or higher, the implicit integrity level of the object remains medium. However, when a token contains an integrity level lower than medium, the object is created with an explicit integrity level that matches the level in the token.

Objects that are created by high- or system-integrity-level processes have a medium integrity level themselves so that users can disable and enable UAC. If object integrity levels always inherited their creator's integrity level, the applications of an administrator who disables UAC and subsequently reenables it could fail because the administrator would not be able to modify any registry settings or files created when running at the high integrity level. Objects can also have an explicit integrity level that is set by the system or by the creator of the object. For example, processes, threads, tokens, and jobs are given an explicit integrity level by the kernel when it creates them. The reason for assigning an integrity level to these objects is to prevent a process for the same user, but one running at a lower integrity level, from accessing these objects and modifying their content or behavior (for example, DLL injection or code modification).

Apart from an integrity level, objects also have a mandatory policy, which defines the actual level of protection that's applied based on the integrity-level check. Three types are possible, shown in Table 7-4. The integrity level and the mandatory policy are stored together in the same ACE.

TABLE 7-4 Object mandatory policies

Policy	Present on, by Default	Description		
No-Write-Up	Implicit on all objects	Used to restrict write access coming from a lower integrity level pro- cess to the object.		
No-Read-Up	Only on process objects	Used to restrict read access coming from a lower integrity level proce to the object. Specific use on process objects protects against informa- tion leakage by blocking address space reads from an external proces		
No-Execute-Up Only on binaries imple- menting COM classes		Used to restrict execute access coming from a lower integrity level process to the object. Specific use on COM classes is to restrict launch-activation permissions on a COM class.		

## **EXPERIMENT:** Looking at the integrity level of objects

You can use the AccessChk tool from Sysinternals to display the integrity level of objects on the system, such as files, processes, and registry keys. Here's an experiment showing the purpose of the LocalLow directory in Windows:

- 1. Browse to C:\Users\<UserName>\ in a command prompt window, where <username> is your user name.
- 2. Try running AccessChk on the AppData folder, as follows:

C:\Users\UserName> accesschk -v appdata

**3.** Note the differences between the Local and LocalLow subfolders in your output, similar to that shown here:

```
C:\Users\UserName\AppData\Local
Medium Mandatory Level (Default) [No-Write-Up]
[...]
C:\Users\UserName\AppData\LocalLow
Low Mandatory Level [No-Write-Up]
[...]
C:\Users\UserName\AppData\Roaming
Medium Mandatory Level (Default) [No-Write-Up]
[...]
```

- **4.** Notice that the LocalLow directory has an integrity level set to Low, while the Local and Roaming directories have integrity levels of Medium (default). The default means the system is using an implicit integrity level.
- Pass the –e flag to AccessChk so it displays only explicit integrity levels. If you run the tool on the AppData folder again, you'll notice only the LocalLow information is displayed.

The -o (object), -k (registry key), and -p (process) flags allow you to specify something other than a file or directory.

### Tokens

The SRM uses an object called a *token* (or *access token*) to identify the security context of a process or thread. A security context consists of information that describes the account, groups, and privileges associated with the process or thread. Tokens also include information such as the session ID, the integrity level, and the UAC virtualization state. (We'll describe both privileges and UAC's virtualization mechanism later in this chapter.)

During the logon process (described later in this chapter), Lsass creates an initial token to represent the user logging on. It then determines whether the user logging on is a member of a powerful group or possesses a powerful privilege. The groups checked for in this step are as follows:

- Built-In Administrators
- Certificate Administrators
- Domain Administrators
- Enterprise Administrators
- Policy Administrators
- Schema Administrators
- Domain Controllers
- Enterprise Read-Only Domain Controllers
- Read-Only Domain Controllers
- Account Operators
- Backup Operators
- Cryptographic Operators
- Network Configuration Operators
- Print Operators
- System Operators
- RAS Servers
- Power Users
- Pre-Windows 2000 Compatible Access

Many of the groups listed are used only on domain-joined systems and don't give users local administrative rights directly. Instead, they allow users to modify domain-wide settings.

The privileges checked for are as follows:

- SeBackupPrivilege
- SeCreateTokenPrivilege
- SeDebugPrivilege
- SeImpersonatePrivilege

- SeLabelPrivilege
- SeLoadDriverPrivilege
- SeRestorePrivilege
- SeTakeOwnershipPrivilege
- SeTcbPrivilege

These privileges are described in detail in the section "Privileges," later in this chapter.

If one or more of these groups or privileges are present, Lsass creates a restricted token for the user (also called a *filtered admin token*) and creates a logon session for both. The standard user token is attached to the initial process or processes that Winlogon starts (by default, Userinit.exe).

**Note** If UAC has been disabled, administrators run with a token that includes their administrator group memberships and privileges.

Because child processes inherit a copy of the token of their creators by default, all processes in the user's session run under the same token. You can also generate a token by using the Windows LogonUser function. You can then use this token to create a process that runs within the security context of the user logged on through the LogonUser function by passing the token to the Windows CreateProcessAsUser function. The CreateProcessWithLogonW function combines these into a single call, which is how the Runas command launches processes under alternative tokens.

Tokens vary in size because different user accounts have different sets of privileges and associated group accounts. However, all tokens contain the same types of information. The most important contents of a token are represented in Figure 7-7.




FIGURE 7-7 Access tokens.

The security mechanisms in Windows use two components to determine what objects can be accessed and what secure operations can be performed. One component comprises the token's user account SID and group SID fields. The SRM uses SIDs to determine whether a process or thread can obtain requested access to a securable object, such as an NTFS file.

The group SIDs in a token indicate which groups a user's account is a member of. For example, a server application can disable specific groups to restrict a token's credentials when the server application is performing actions requested by a client. Disabling a group produces nearly the same effect as if the group wasn't present in the token. (It results in a deny-only group, described in the section "Restricted tokens." Disabled SIDs are used as part of security access checks, described in the section "Determining access" later in the chapter.) Group SIDs can also include a special SID that contains the integrity level of the process or thread. The SRM uses another field in the token, which describes the mandatory integrity policy, to perform the mandatory integrity check described later in the chapter.

The second component in a token that determines what the token's thread or process can do is the privilege array. A token's privilege array is a list of rights associated with the token. An example of a privilege is the right of the process or thread associated with the token to shut down the computer. Privileges are described in more detail later in this chapter.

A token's default primary group field and default discretionary access control list (DACL) field are security attributes that Windows applies to objects that a process or thread creates when it uses the token. By including security information in tokens, Windows makes it convenient for a process or thread to create objects with standard security attributes because the process or thread doesn't need to request discrete security information for every object it creates.

Each token's type distinguishes a primary token (a token that identifies the security context of a process) from an impersonation token (a type of token that threads use to temporarily adopt a different security context, usually of another user). Impersonation tokens carry an impersonation level that signifies what type of impersonation is active in the token. (Impersonation is described later in this chapter.)

A token also includes the mandatory policy for the process or thread, which defines how MIC will behave when processing this token. There are two policies:

- TOKEN\_MANDATORY\_NO\_WRITE\_UP Enabled by default, this sets the No-Write-Up policy on this token, specifying that the process or thread will not be able to access objects with a higher integrity level for write access.
- TOKEN\_MANDATORY\_NEW\_PROCESS\_MIN Also enabled by default, this specifies that the SRM should look at the integrity level of the executable image when launching a child process and compute the minimum integrity level of the parent process and the file object's integrity level as the child's integrity level.

Token flags include parameters that determine the behavior of certain UAC and UIPI mechanisms, such as virtualization and user interface access. Those mechanisms will be described later in this chapter.

Each token can also contain attributes that are assigned by the Application Identification service (part of AppLocker) when AppLocker rules have been defined. AppLocker and its use of attributes in the access token are described later in this chapter.

A token for a UWP process includes information on the AppContainer hosting the process. First, it stores a package SID, identifying the UWP package the process originated from. The significance of this SID will be described in the "AppContainers" section later in this chapter. Second, UWP processes need to request capabilities for operations that require the user's consent. Examples of capabilities include network access, using the phone capabilities of the device (if any), accessing the camera on the device, and more. Each such capability is represented with a SID, stored as part of the token. (Capabilities will be discussed further in the "AppContainers" section.)

The remaining fields in a token serve informational purposes. The token source field contains a short textual description of the entity that created the token. Programs that want to know where a token originated use the token source to distinguish among sources such as the Windows Session Manager, a network file server, or the remote procedure call (RPC) server. The token identifier is a locally unique identifier (LUID) that the SRM assigns to the token when it creates the token. The Windows executive maintains the executive LUID, a monotonically increasing counter it uses to assign a unique numeric identifier to each token. A LUID is guaranteed to be unique only until the system is shut down.

The token authentication ID is another kind of LUID. A token's creator assigns the token's authentication ID when calling the LsaLogonUser function. If the creator doesn't specify a LUID, Lsass obtains the LUID from the executive LUID. Lsass copies the authentication ID for all tokens descended from an initial logon token. A program can obtain a token's authentication ID to see whether the token belongs to the same logon session as other tokens the program has examined.

The executive LUID refreshes the modified ID every time a token's characteristics are modified. An application can test the modified ID to discover changes in a security context since the context's last use.

Tokens contain an expiration time field that can be used by applications performing their own security to reject a token after a specified amount of time. However, Windows itself does not enforce the expiration time of tokens.

**Note** To guarantee system security, the fields in a token are immutable (because they are located in kernel memory). Except for fields that can be modified through a specific system call designed to modify certain token attributes (assuming the caller has the appropriate access rights to the token object), data such as privileges and SIDs in a token can never be modified from user mode.

#### **EXPERIMENT: Viewing access tokens**

The kernel debugger dt \_TOKEN command displays the format of an internal token object. Although this structure differs from the user-mode token structure returned by Windows API security functions, the fields are similar. For further information on tokens, see the description in the Windows SDK documentation. Here's a token structure on Windows 10:

```
lkd> dt nt!_token
   +0x000 TokenSource : _TOKEN_SOURCE
+0x010 TokenId : _LUID
                             : _LUID
   +0x018 AuthenticationId : _LUID
   +0x020 ParentTokenId : _LUID
   +0x028 ExpirationTime : _LARGE_INTEGER
   +0x030 TokenLock : Ptr64 _ERESOURCE
+0x038 ModifiedId : _LUID
   +0x040 Privileges : _SEP_TOKEN_PRIVILEGES
+0x058 AuditPolicy : _SEP_AUDIT_POLICY
+0x078 SessionId : Uint4B
   +0x07c UserAndGroupCount : Uint4B
   +0x080 RestrictedSidCount : Uint4B
   +0x084 VariableLength : Uint4B
   +0x088 DynamicCharged : Uint4B
   +0x08c DynamicAvailable : Uint4B
   +0x090 DefaultOwnerIndex : Uint4B
   +0x098 UserAndGroups : Ptr64 _SID_AND_ATTRIBUTES
   +0x0a0 RestrictedSids : Ptr64 _SID_AND_ATTRIBUTES
   +0x0a8 PrimaryGroup: Ptr64 Void+0x0b0 DynamicPart: Ptr64 Uint4B+0x0b8 DefaultDac1: Ptr64 _ACL+0x0c0 TokenType: _TOKEN_TYPE
   +0x0c4 ImpersonationLevel : _SECURITY_IMPERSONATION_LEVEL
   +0x0c8 TokenFlags : Uint4B
+0x0cc TokenInUse : UChar
   +0x0d0 IntegrityLevelIndex : Uint4B
   +0x0d4 MandatoryPolicy : Uint4B
   +0x0d8 LogonSession : Ptr64 _SEP_LOGON_SESSION_REFERENCES
   +0x0e0 OriginatingLogonSession : _LUID
   +0x0e8 SidHash : _SID_AND_ATTRIBUTES_HASH
   +0x1f8 RestrictedSidHash : _SID_AND_ATTRIBUTES_HASH
   +0x308 pSecurityAttributes : Ptr64 _AUTHZBASEP_SECURITY_ATTRIBUTES_INFORMATION
   +0x310 Package : Ptr64 Void
+0x318 Capabilities : Ptr64 _SID_AND_ATTRIBUTES
   +0x320 CapabilityCount : Uint4B
   +0x328 CapabilitiesHash : _SID_AND_ATTRIBUTES_HASH
   +0x438 LowboxNumberEntry : Ptr64 _SEP_LOWBOX_NUMBER_ENTRY
   +0x440 LowboxHandlesEntry : Ptr64 _SEP_LOWBOX_HANDLES_ENTRY
   +0x448 pClaimAttributes : Ptr64 _AUTHZBASEP_CLAIM_ATTRIBUTES_COLLECTION
   +0x450 TrustLevelSid : Ptr64 Void
   +0x458 TrustLinkedToken : Ptr64 _TOKEN
   +0x460 IntegrityLevelSidValue : Ptr64 Void
   +0x468 TokenSidValues : Ptr64 _SEP_SID_VALUES_BLOCK
   +0x470 IndexEntry : Ptr64 _SEP_LUID_TO_INDEX_MAP_ENTRY
   +0x478 DiagnosticInfo : Ptr64 _SEP_TOKEN_DIAG_TRACK_ENTRY
   +0x480 SessionObject : Ptr64 Void
+0x488 VariablePart : Uint8B
```

You can examine the token for a process with the ! token command. You'll find the address of the token in the output of the !process command. Here's an example for an explorer.exe process: lkd> !process 0 1 explorer.exe PROCESS ffffe18304dfd780 SessionId: 1 Cid: 23e4 Peb: 00c2a000 ParentCid: 2264 DirBase: 2aa0f6000 ObjectTable: ffffcd82c72fcd80 HandleCount: <Data Not Accessible> Image: explorer.exe VadRoot ffffe18303655840 Vads 705 Clone 0 Private 12264. Modified 376410. Locked 18. DeviceMap ffffcd82c39bc0d0 Token ffffcd82c72fc060 . . . PROCESS ffffe1830670a080 SessionId: 1 Cid: 27b8 Peb: 00950000 ParentCid: 035c DirBase: 2cba97000 ObjectTable: ffffcd82c7ccc500 HandleCount: <Data Not Accessible> Image: explorer.exe VadRoot ffffe183064e9f60 Vads 1991 Clone 0 Private 19576. Modified 87095. Locked 0. DeviceMap ffffcd82c39bc0d0 Token ffffcd82c7cd9060 lkd> !token ffffcd82c72fc060 \_TOKEN 0xffffcd82c72fc060 TS Session ID: 0x1 User: S-1-5-21-3537846094-3055369412-2967912182-1001 User Groups: 00 S-1-16-8192 Attributes - GroupIntegrity GroupIntegrityEnabled 01 S-1-1-0 Attributes - Mandatory Default Enabled 02 S-1-5-114 Attributes - DenyOnly 03 S-1-5-21-3537846094-3055369412-2967912182-1004 Attributes - Mandatory Default Enabled 04 S-1-5-32-544 Attributes - DenyOnly 05 S-1-5-32-578 Attributes - Mandatory Default Enabled 06 S-1-5-32-559 Attributes - Mandatory Default Enabled 07 S-1-5-32-545 Attributes - Mandatory Default Enabled 08 S-1-5-4 Attributes - Mandatory Default Enabled 09 S-1-2-1 Attributes - Mandatory Default Enabled 10 S-1-5-11 Attributes - Mandatory Default Enabled

```
11 S-1-5-15
    Attributes - Mandatory Default Enabled
 12 S-1-11-96-3623454863-58364-18864-2661722203-1597581903-1225312835-2511459453-
1556397606-2735945305-1404291241
    Attributes - Mandatory Default Enabled
 13 S-1-5-113
    Attributes - Mandatory Default Enabled
 14 S-1-5-5-0-1745560
    Attributes - Mandatory Default Enabled LogonId
 15 S-1-2-0
    Attributes - Mandatory Default Enabled
 16 S-1-5-64-36
    Attributes - Mandatory Default Enabled
Primary Group: S-1-5-21-3537846094-3055369412-2967912182-1001
Privs:
19 0x00000013 SeShutdownPrivilege
                                                Attributes -

    23 0x000000017 SeChangeNotifyPrivilege
    Attributes - Enabled Default

 25 0x00000019 SeUndockPrivilege
                                                Attributes -
 33 0x000000021 SeIncreaseWorkingSetPrivilege Attributes -
 34 0x00000022 SeTimeZonePrivilege
                                                 Attributes -
Authentication ID:
                          (0,1aa448)
Impersonation Level:
                        Anonymous
                         Primary
TokenType:
Source: User32
                          TokenFlags: 0x2a00 ( Token in use )
Token ID: 1be803
                        ParentToken ID: 1aa44b
Modified ID:
                          (0, 43d9289)
RestrictedSidCount: 0 RestrictedSids: 0x0000000000000000
OriginatingLogonSession: 3e7
PackageSid: (null)
CapabilityCount: 0
                        Capabilities: 0x0000000000000000
LowboxNumberEntry: 0x000000000000000
Security Attributes:
Unable to get the offset of nt!_AUTHZBASEP_SECURITY_ATTRIBUTE.ListLink
Process Token TrustLevelSid: (null)
   Notice that there is no package SID for Explorer, since it's not running inside an AppContainer.
   Run calc.exe under Windows 10, which spawns calculator.exe (now a UWP app), and examine
its token:
lkd> !process 0 1 calculator.exe
PROCESS ffffe18309e874c0
    SessionId: 1 Cid: 3c18 Peb: cd0182c000 ParentCid: 035c
    DirBase: 7a15e4000 ObjectTable: ffffcd82ec9a37c0 HandleCount: <Data Not
Accessible>
    Image: Calculator.exe
    VadRoot ffffe1831cf197c0 Vads 181 Clone 0 Private 3800. Modified 3746. Locked 503.
    DeviceMap ffffcd82c39bc0d0
    Token
                                      ffffcd82e26168f0
. . .
1kd> !token ffffcd82e26168f0
TOKEN 0xffffcd82e26168f0
```

```
TS Session ID: 0x1
User: S-1-5-21-3537846094-3055369412-2967912182-1001
User Groups:
00 S-1-16-4096
   Attributes - GroupIntegrity GroupIntegrityEnabled
01 S-1-1-0
   Attributes - Mandatory Default Enabled
02 S-1-5-114
   Attributes - DenyOnly
03 S-1-5-21-3537846094-3055369412-2967912182-1004
   Attributes - Mandatory Default Enabled
04 S-1-5-32-544
   Attributes - DenyOnly
05 S-1-5-32-578
   Attributes - Mandatory Default Enabled
06 S-1-5-32-559
   Attributes - Mandatory Default Enabled
07 S-1-5-32-545
   Attributes - Mandatory Default Enabled
08 S-1-5-4
   Attributes - Mandatory Default Enabled
09 S-1-2-1
   Attributes - Mandatory Default Enabled
10 S-1-5-11
   Attributes - Mandatory Default Enabled
11 S-1-5-15
   Attributes - Mandatory Default Enabled
12 S-1-11-96-3623454863-58364-18864-2661722203-1597581903-1225312835-2511459453-
1556397606-2735945305-1404291241
   Attributes - Mandatory Default Enabled
13 S-1-5-113
   Attributes - Mandatory Default Enabled
14 S-1-5-5-0-1745560
   Attributes - Mandatory Default Enabled LogonId
15 S-1-2-0
   Attributes - Mandatory Default Enabled
16 S-1-5-64-36
   Attributes - Mandatory Default Enabled
Primary Group: S-1-5-21-3537846094-3055369412-2967912182-1001
Privs:
19 0x000000013 SeShutdownPrivilege
                                                Attributes -
23 0x00000017 SeChangeNotifyPrivilege
                                               Attributes - Enabled Default
25 0x00000019 SeUndockPrivilege
                                                Attributes -
33 0x00000021 SeIncreaseWorkingSetPrivilege Attributes -
 34 0x00000022 SeTimeZonePrivilege
                                                 Attributes -
Authentication ID:
                        (0,1aa448)
Impersonation Level:
                        Anonymous
TokenType:
                         Primary
Source: User32
                         TokenFlags: 0x4a00 ( Token in use )
                       ParentToken ID: 1aa44b
Token ID: 4ddb8c0
Modified ID:
                          (0, 4ddb8b2)
```

```
RestrictedSidCount: 0
                           RestrictedSids: 0x000000000000000
OriginatingLogonSession: 3e7
PackageSid: S-1-15-2-466767348-3739614953-2700836392-1801644223-4227750657-
1087833535-2488631167
CapabilityCount: 1
                        Capabilities: 0xffffcd82e1bfccd0
Capabilities:
00 S-1-15-3-466767348-3739614953-2700836392-1801644223-4227750657-1087833535-
2488631167
   Attributes - Enabled
LowboxNumberEntry: 0xffffcd82fa2c1670
LowboxNumber: 5
Security Attributes:
Unable to get the offset of nt!_AUTHZBASEP_SECURITY_ATTRIBUTE.ListLink
Process Token TrustLevelSid: (null)
```

You can see there is one capability required by Calculator (which is in fact equal to its AppContainer SID RID, as described in the section "AppContainers" later in this chapter). Looking at the token of the Cortana process (searchui.exe) shows the following capabilities:

```
lkd> !process 0 1 searchui.exe
PROCESS ffffe1831307d080
   SessionId: 1 Cid: 29d8 Peb: fb407ec000 ParentCid: 035c
DeepFreeze
   DirBase: 38b635000 ObjectTable: ffffcd830059e580 HandleCount: <Data Not
Accessible>
   Image: SearchUI.exe
   VadRoot ffffe1831fe89130 Vads 420 Clone 0 Private 11029. Modified 2031. Locked 0.
   DeviceMap ffffcd82c39bc0d0
                                   ffffcd82d97d18f0
   Token
    . . .
1kd> !token ffffcd82d97d18f0
TOKEN 0xffffcd82d97d18f0
TS Session ID: 0x1
User: S-1-5-21-3537846094-3055369412-2967912182-1001
User Groups:
Primary Group: S-1-5-21-3537846094-3055369412-2967912182-1001
Privs:
19 0x00000013 SeShutdownPrivilege
                                              Attributes -
23 0x00000017 SeChangeNotifyPrivilege
                                              Attributes - Enabled Default
25 0x00000019 SeUndockPrivilege
                                             Attributes -
33 0x000000021 SeIncreaseWorkingSetPrivilege Attributes -
 34 0x00000022 SeTimeZonePrivilege
                                              Attributes -
Authentication ID:
                        (0,1aa448)
Impersonation Level:
                        Anonymous
TokenType:
                       Primary
Source: User32
                        TokenFlags: 0x4a00 ( Token in use )
Token ID: 4483430
                       ParentToken ID: 1aa44b
Modified ID:
                         (0, 4481b11)
OriginatingLogonSession: 3e7
```

```
PackageSid: S-1-15-2-1861897761-1695161497-2927542615-642690995-327840285-
2659745135-2630312742
CapabilityCount: 32
                        Capabilities: 0xffffcd82f78149b0
Capabilities:
00 S-1-15-3-1024-1216833578-114521899-3977640588-1343180512-2505059295-473916851-
3379430393-3088591068
    Attributes - Enabled
01 S-1-15-3-1024-3299255270-1847605585-2201808924-710406709-3613095291-873286183-
3101090833-2655911836
   Attributes - Enabled
02 S-1-15-3-1024-34359262-2669769421-2130994847-3068338639-3284271446-2009814230-
2411358368-814686995
   Attributes - Enabled
03 S-1-15-3-1
   Attributes - Enabled
 29 S-1-15-3-3633849274-1266774400-1199443125-2736873758
   Attributes - Enabled
 30 S-1-15-3-2569730672-1095266119-53537203-1209375796
   Attributes - Enabled
 31 S-1-15-3-2452736844-1257488215-2818397580-3305426111
    Attributes - Enabled
LowboxNumberEntry: 0xffffcd82c7539110
LowboxNumber: 2
Security Attributes:
Unable to get the offset of nt!_AUTHZBASEP_SECURITY_ATTRIBUTE.ListLink
Process Token TrustLevelSid: (null)
```

There are 32 capabilities required by Cortana. This simply indicates the process is richer in features that need to be accepted by end users and validated by the system.

You can indirectly view token contents with Process Explorer's Security tab in the process Properties dialog box. The dialog box shows the groups and privileges included in the token of the process you examine.

#### EXPERIMENT: Launching a program at low integrity level


When you elevate a program, either by using the Run as Administrator option or because the program is requesting it, the program is explicitly launched at high integrity level. However, it is also possible to launch a program at low integrity level by using PsExec from Sysinternals:

1. Launch Notepad at low integrity level by using the following command:

c:\psexec -1 notepad.exe

- 2. Try opening a file (such as one of the XML files) in the %SystemRoot%\System32 directory. Notice that you can browse the directory and open any file contained within it.
- 3. In Notepad, open the File menu and choose New.

**4.** Enter some text in the window and try saving it in the %SystemRoot%\System32 directory. Notepad displays a dialog box indicating a lack of permissions and suggests saving the file in the Documents folder.



- **5.** Accept Notepad's suggestion. You will get the same message box again, and repeatedly for each attempt.
- **6.** Now try saving the file in the LocalLow directory of your user profile, shown in an experiment earlier in the chapter.

In the previous experiment, saving a file in the LocalLow directory worked because Notepad was running with low integrity level, and only the LocalLow directory also had low integrity level. All the other directories where you tried to save the file had an implicit medium integrity level. (You can verify this with AccessChk.) However, reading from the %SystemRoot%\System32 directory, as well as opening files within it, did work, even though the directory and its file also have an implicit medium integrity level.

#### Impersonation

Impersonation is a powerful feature Windows uses frequently in its security model. Windows also uses impersonation in its client/server programming model. For example, a server application can provide access to resources such as files, printers, and databases. Clients wanting to access a resource send a request to the server. When the server receives the request, it must ensure that the client has permission to perform the desired operations on the resource. For example, if a user on a remote machine tries to delete a file on an NTFS share, the server exporting the share must determine whether the user is allowed to delete the file. The obvious way to determine whether a user has permission is for the server to query the user's account and group SIDs and scan the security attributes on the file. This approach is tedious to program, prone to errors, and wouldn't permit new security features to be supported transparently. Thus, Windows provides impersonation services to simplify the server's job.

Impersonation lets a server notify the SRM that the server is temporarily adopting the security profile of a client making a resource request. The server can then access resources on behalf of the client, and the SRM carries out the access validation, but it does so based on the impersonated client security context. Usually, a server has access to more resources than a client does and loses some of its security credentials during impersonation. However, the reverse can be true: The server can gain security credentials during impersonation.

A server impersonates a client only within the thread that makes the impersonation request. Thread-control data structures contain an optional entry for an impersonation token. However, a thread's primary token, which represents the thread's real security credentials, is always accessible in the process's control structure.

Windows makes impersonation available through several mechanisms. For example, if a server communicates with a client through a named pipe, the server can use the ImpersonateNamedPipeClient Windows API function to tell the SRM that it wants to impersonate the user on the other end of the pipe. If the server is communicating with the client through Dynamic Data Exchange (DDE) or RPC, it can make similar impersonation requests using DdeImpersonateClient and RpcImpersonateClient. A thread can create an impersonation token that's simply a copy of its process token with the ImpersonateSelf function. The thread can then alter its impersonation token, perhaps to disable SIDs or privileges. A Security Support Provider Interface (SSPI) package can impersonate its clients with ImpersonateSecurityContext. SSPIs implement a network authentication protocol such as LAN Manager version 2 or Kerberos. Other interfaces such as COM expose impersonation through APIs of their own, such as CoImpersonateClient.

After the server thread finishes its task, it reverts to its primary security context. These forms of impersonation are convenient for carrying out specific actions at the request of a client and for ensuring that object accesses are audited correctly. (For example, the audit that is generated gives the identity of the impersonated client rather than that of the server process.) The disadvantage to these forms of impersonation is that they can't execute an entire program in the context of a client. In addition, an impersonation token can't access files or printers on network shares unless it is a delegation-level impersonation (described shortly) and has sufficient credentials to authenticate to the remote machine, or the file or printer share supports null sessions. (A null session is one that results from an anonymous logon.)

If an entire application must execute in a client's security context or must access network resources without using impersonation, the client must be logged on to the system. The LogonUser Windows API function enables this action. LogonUser takes an account name, a password, a domain or computer name, a logon type (such as interactive, batch, or service), and a logon provider as input, and it returns a primary token. A server thread can adopt the token as an impersonation token, or the server can start a program that has the client's credentials as its primary token. From a security standpoint, a process created using the token returned from an interactive logon via LogonUser, such as with the CreateProcessAsUser API, looks like a program a user starts by logging on to the machine interactively. The disadvantage to this approach is that a server must obtain the user's account name and password. If the server transmits this information across the network, the server must encrypt it securely so that a malicious user snooping network traffic can't capture it.

To prevent the misuse of impersonation, Windows doesn't let servers perform impersonation without a client's consent. A client process can limit the level of impersonation that a server process can perform by specifying a security quality of service (SQOS) when connecting to the server. For instance, when opening a named pipe, a process can specify SECURITY\_ANONYMOUS, SECURITY\_IDENTIFICATION, SECURITY\_IMPERSONATION, or SECURITY\_DELEGATION as flags for the Windows CreateFile function. These same options apply to other impersonation-related functions listed earlier. Each level lets a server perform different types of operations with respect to the client's security context:

SecurityAnonymous This is the most restrictive level of impersonation. The server can't impersonate or identify the client.

- SecurityIdentification This lets the server obtain the identity (the SIDs) of the client and the client's privileges, but the server can't impersonate the client.
- SecurityImpersonation This lets the server identify and impersonate the client on the local system.
- SecurityDelegation This is the most permissive level of impersonation. It lets the server impersonate the client on local and remote systems.

Other interfaces such as RPC use different constants with similar meanings (for example, RPC\_C\_ IMP\_LEVEL\_IMPERSONATE).

If the client doesn't set an impersonation level, Windows chooses the SecurityImpersonation level by default. The CreateFile function also accepts SECURITY\_EFFECTIVE\_ONLY and SECURITY\_CONTEXT\_TRACKING as modifiers for the impersonation setting:

- SECURITY\_EFFECTIVE\_ONLY This prevents a server from enabling or disabling a client's privileges or groups while the server is impersonating.
- SECURITY\_CONTEXT\_TRACKING This specifies that any changes a client makes to its security context are reflected in a server that is impersonating it. If this option isn't specified, the server adopts the context of the client at the time of the impersonation and doesn't receive any changes. This option is honored only when the client and server processes are on the same system.

To prevent spoofing scenarios in which a low-integrity process could create a user interface that captured user credentials and then used LogonUser to obtain that user's token, a special integrity policy applies to impersonation scenarios: a thread cannot impersonate a token of higher integrity than its own. For example, a low-integrity application cannot spoof a dialog box that queries administrative credentials and then attempt to launch a process at a higher privilege level. The integrity-mechanism policy for impersonation access tokens is that the integrity level of the access token that is returned by LsaLogonUser must be no higher than the integrity level of the calling process.

#### **Restricted tokens**

A restricted token is created from a primary or impersonation token using the CreateRestrictedToken function. The restricted token is a copy of the token it's derived from, with the following possible modifications:

- Privileges can be removed from the token's privilege array.
- SIDs in the token can be marked as deny-only. These SIDs remove access to any resources for which the SID's access is denied by using a matching access-denied ACE that would otherwise be overridden by an ACE granting access to a group containing the SID earlier in the security descriptor.
- SIDs in the token can be marked as restricted. These SIDs are subject to a second pass of the access-check algorithm, which will parse only the restricted SIDs in the token. The results of both the first pass and the second pass must grant access to the resource or no access is granted to the object.

Restricted tokens are useful when an application wants to impersonate a client at a reduced security level, primarily for safety reasons when running untrusted code. For example, the restricted token can have the shutdown-system privilege removed from it to prevent code executed in the restricted token's security context from rebooting the system.

#### Filtered admin token


As you saw earlier, restricted tokens are also used by UAC to create the filtered admin token that all user applications will inherit. A filtered admin token has the following characteristics:

- The integrity level is set to medium.
- The administrator and administrator-like SIDs mentioned previously are marked as deny-only to prevent a security hole if the group were to be removed altogether. For example, if a file had an access control list (ACL) that denied the Administrators group all access but granted some access to another group the user belongs to, the user would be granted access if the Administrators group was absent from the token, which would give the standard user version of the user's identity more access than the user's administrator identity.
- All privileges are stripped except Change Notify, Shutdown, Undock, Increase Working Set, and Time Zone.

#### **EXPERIMENT:** Looking at filtered admin tokens

You can make Explorer launch a process with either the standard user token or the administrator token by following these steps on a machine with UAC enabled:

- **1.** Log on to an account that's a member of the Administrators group.
- 2. Open the **Start** menu, type **command**, right-click the **Command Prompt** option that appears, and choose **Run as Administrator** to run an elevated command prompt.
- 3. Run a new instance of cmd.exe, but this time do it normally (that is, not elevated).
- 4. Run Process Explorer elevated, open the Properties dialog boxes for the two command prompt processes, and click the Security tabs. Note that the standard user token contains a deny-only SID and a medium mandatory label, and that it has only a couple of privileges. The properties on the right in the following screenshot are from a command prompt running with an administrator token, and the properties on the left are from one running with the filtered administrator token:



## Virtual service accounts

Windows provides a specialized type of account known as a *virtual service account* (or simply *virtual account*) to improve the security isolation and access control of Windows services with minimal administrative effort. (See Chapter 9 in Part 2 for more information on Windows services.) Without this mechanism, Windows services must run under one of the accounts defined by Windows for its built-in services (such as Local Service or Network Service) or under a regular domain account. The accounts such as Local Service are shared by many existing services and so offer limited granularity for privilege and access control; furthermore, they cannot be managed across the domain. Domain accounts require periodic password changes for security, and the availability of services during a password-change cycle might be affected. Furthermore, for best isolation, each service should run under its own account, but with ordinary accounts this multiplies the management effort.

With virtual service accounts, each service runs under its own account with its own security ID. The name of the account is always NT SERVICE\ followed by the internal name of the service. Virtual service accounts can appear in access control lists and can be associated with privileges via Group Policy like any other account name. They cannot, however, be created or deleted through the usual account-management tools, nor assigned to groups.

Windows automatically sets and periodically changes the password of the virtual service account. Similar to the Local System and Other Service Accounts, there is a password, but the password is unknown to the system administrators.

#### **EXPERIMENT: Using virtual service accounts**

You can create a service that runs under a virtual service account by using the Service Control (Sc.exe) tool. Follow these steps:


 In an Administrator command prompt, type the create command in the Sc.exe commandline tool to create a service and a virtual account in which it will run. This example uses the srvany service from the Windows 2003 resource kit, which you can download here: https://www.microsoft.com/en-us/download/details.aspx?id=17657.

C:\Windows\system32>sc create srvany obj= "NT SERVICE\srvany" binPath= "c:\temp\srvany.exe" [SC] CreateService SUCCESS

2. The previous command created the service (in the registry and in the service controller manager's internal list) and created the virtual service account. Now run the Services MMC snap-in (services.msc), select the new service, and open its Properties dialog box.

Q. Services							10 C	
File Action View								
* * 🖬 🗐 🖉	🔒 🛛 📰 🕨 🗰 🖬 🕩							
Services (Local)	Services (Local)							
	stvany	Name	Description	Status	Startup Type	Log On As		
	Stat the service	Shell Hardware Detection     Shell Andware Detection     Shell Charlow Control Contro Control Control Control Control Con	Provides notificat Enables the detec Manages access t Creates ioftware Allows the syste Receives trap mes Enables the down Verifies potential f	Running	Automatic Automatic Disabled Manual (Trigger St., Manual Automatic (Delay., Manual (Trigger St.,	Local System Local System Local Service Local System Local System Local Service Network Service Local System		
		SQL Server VSS Writer	Provides the inter	Running	Automatic	Local System		
		SSIP Discoury     SSIP Some Boke     SSIF Some From     SSIF Some Some Some Some Some Some Some Some	Discoven networ Part of Microsoft Part of Microsoft Provides required Launches applica Provides enabling Optimizes the pla Maintains and im Synaptics FP WBF	Running Running	Manual Manual Manual Manual Manual Manual (Tingger St., Manual Automatic Automatic	Local Service Local System Local System Local System Local System Local System Local System Local System		
	Estended Standard	Sync Host_1ad545	This service sync	Running	Automatic (Delay	Local System		

3. Click the Log On tab.



- 4. You can use the service's Properties dialog box to create a virtual service account for an existing service. To do so, change the account name to NT SERVICE\servicename in the This Account field and clear both password fields. Note, however, that existing services might not run correctly under a virtual service account because the account might not have access to files or other resources needed by the service.
- 5. If you run Process Explorer and view the Security tab in the Properties dialog box for a service that uses a virtual account, you can observe the virtual account name and its security ID (SID). To try this, in the Properties dialog box of the srvany service, enter the command-line arguments notepad.exe. (srvany can be used to turn normal executables into services, so it must accept some executable on the command line.) Then click the Start button to start the service.

nage	Performance	Performan			d Network	GPU Grap	h Service
Thre	ads	TCP/IP	Securit	y	Environn	nent	Strings
4		ERVICE\srvan 5-80-1566334 Logon Ses Protected:	193-247492 sion: 6800		1888934-11	79947323-34	415500574
	Group	^			Flags		
	BUILTIN\User	s			Manda	tory	
	CONSOLE LO	GON			Manda	tory	
	Everyone				Manda	tory	
	LOCAL				Manda	itory	
	Mandatory La	abel\High Ma	andatory Le	evel	Integri	ty	
	NT AUTHORI	TY\Authentic	Manda	itory			
	NT AUTHORI		sionId_0_1	0905512			
	NT AUTHORI				Manda		
	NT AUTHORI				Manda		
	in service y	the state to be			Manda		
	Group SID: n/	'a					_
ER	Privilege		Flag	5			^
-	SeChangeNo	tifyPrivilege	Defa	ult Enabl	ed		
	SeCreateGlob	alPrivilege	Defa	ult Enabl	ed		
	Selmpersona	tePrivilege	Defa	ult Enabl	ed		
	SelncreaseWo	-	-				
	SeShutdown		Disal				
	SeTimeZoneP		Disal				~
							Permissions

6. The virtual service account can appear in an access control entry for any object (such as a file) the service needs to access. If you click the **Security** tab in a file's Properties dialog box and create an ACL that references the virtual service account, you will find that the account name you typed (for example, NT SERVICE\srvany) is changed to simply the service name (srvany) by the Check Names function, and it appears in the access control list in this shortened form.

Object name: G:\Dev\PEExc	deres .	
Object name: G:\Dev\PEExp	biorer	
Group or user names:		
Authenticated Users		
SYSTEM		
Administrators (ZODIACV	Administrators)	
Srvany		
Care and the second sec		
Users (ZODIAC\Users)		
Users (ZODIAC\Users)		
Users (ZODIAC\Users)	Add	Remove
Permissions for srvany	Add Allow	Remove Deny
Permissions for srvany Full control		Deny
Permissions for srvany Full control Modify		Deny
Permissions for srvany Full control Modify Read & execute		Deny
Permissions for srvany Full control Modify		Deny

7. The virtual service account can be granted permissions (or user rights) via Group Policy. In this example, the virtual account for the srvany service has been granted the right to create a pagefile (using the Local Security Policy editor, secpol.msc).

Local Security Setting Explain				
Create a pagefile				
1				
Administrators NT SERVICE\srvany				1
in schriecenally				
	1			
Add User or Group	Remove	I.,	_	
Add User or Group	Remove	I,		
Add User or Group	Remove			
Add User or Group	Remove.	(		
Add User or Group	Remove	Cancel		

8. You won't see the virtual service account in user-administration tools like lusrmgr.msc because it is not stored in the SAM registry hive. However, if you examine the registry within the context of the built-in System account (as described previously), you will see evidence of the account in the HKLM\Security\Policy\Secrets key:

ile Edit	View Favorites Help					
	PolDnTrN     PolEKList     PolOldSyskey     PolPrDmN     PolPrDmS     PolPrDmS     PolRevision     SecDesc     Secrets     Secrets     Secrets     Outral     Outral     Outral     Outral     Outral     Outral     DefaultPassword     DefaultPassword     DefaultPassword     SecurityInstallationProv     Recovery     Recovery	<	Name	Type REG_DWORD	Data (invalid DWORD (32-bit) value)	
<	>		<			>

C:\>psexec -s -i -d regedit.exe

## Security descriptors and access control

Tokens, which identify a user's credentials, are only part of the object security equation. Another part of the equation is the security information associated with an object, which specifies who can perform what actions on the object. The data structure for this information is called a *security descriptor*. A security descriptor consists of the following attributes:

- **Revision number** This is the version of the SRM security model used to create the descriptor.
- **Flags** These are optional modifiers that define the behavior or characteristics of the descriptor. These flags are listed in Table 7-5 (most are documented in the Windows SDK).
- **Owner SID** This is the owner's SID.
- Group SID This is the SID of the primary group for the object (used only by the POSIX subsystem, now unused since POSIX is no longer supported).
- Discretionary access control list (DACL) This specifies who has what access to the object.
- System access control list (SACL) This specifies which operations by which users should be logged in the security audit log and the explicit integrity level of an object.

#### TABLE 7-5 Security descriptor flags

Flag	Meaning
SE_OWNER_DEFAULTED	This indicates a security descriptor with a default owner security identifier (SID). Use this bit to find all the objects that have default owner permissions set.
SE_GROUP_DEFAULTED	This indicates a security descriptor with a default group SID. Use this bit to find all the objects that have default group permissions set.
SE_DACL_PRESENT	This indicates a security descriptor that has a DACL. If this flag is not set, or if this flag is set and the DACL is NULL, the security descriptor allows full access to everyone.
SE_DACL_DEFAULTED	This indicates a security descriptor with a default DACL. For example, if an object creator does not specify a DACL, the object receives the default DACL from the access token of the creator. This flag can affect how the sys- tem treats the DACL with respect to access control entry (ACE) inheritance. The system ignores this flag if the SE_DACL_PRESENT flag is not set.
SE_SACL_PRESENT	This indicates a security descriptor that has a system access control list (SACL).
SE_SACL_DEFAULTED	This indicates a security descriptor with a default SACL. For example, if an object creator does not specify a SACL, the object receives the default SACL from the access token of the creator. This flag can affect how the system treats the SACL with respect to ACE inheritance. The system ignores this flag if the SE_SACL_PRESENT flag is not set.
SE_DACL_UNTRUSTED	This indicates that the ACL pointed to by the DACL of the security descrip- tor was provided by an untrusted source. If this flag is set and a com- pound ACE is encountered, the system will substitute known valid SIDs for the server SIDs in the ACEs.
SE_SERVER_SECURITY	This requests that the provider for the object protected by the security descriptor be a server ACL based on the input ACL, regardless of its source (explicit or defaulting). This is done by replacing all the GRANT ACEs with compound ACEs granting the current server access. This flag is meaningful only if the subject is impersonating.
SE_DACL_AUTO_INHERIT_REQ	This requests that the provider for the object protected by the security descriptor automatically propagate the DACL to existing child objects. If the provider supports automatic inheritance, the DACL is propagated to any existing child objects, and the SE_DACL_AUTO_INHERITED bit in the security descriptor of the parent and child objects is set.
SE_SACL_AUTO_INHERIT_REQ	This requests that the provider for the object protected by the security descriptor automatically propagate the SACL to existing child objects. If the provider supports automatic inheritance, the SACL is propagated to any existing child objects, and the SE_SACL_AUTO_INHERITED bit in the security descriptors of the parent object and child objects is set.
SE_DACL_AUTO_INHERITED	This indicates a security descriptor in which the DACL is set up to support automatic propagation of inheritable ACEs to existing child objects. The system sets this bit when it performs the automatic inheritance algorithm for the object and its existing child objects.
SE_SACL_AUTO_INHERITED	This indicates a security descriptor in which the SACL is set up to support automatic propagation of inheritable ACEs to existing child objects. The system sets this bit when it performs the automatic inheritance algorithm for the object and its existing child objects.
SE_DACL_PROTECTED	This prevents the DACL of a security descriptor from being modified by inheritable ACEs.
SE_SACL_PROTECTED	This prevents the SACL of a security descriptor from being modified by inheritable ACEs.

TABLE 7-5	Security	descriptor	flags	(continued)

Flag	Meaning
SE_RM_CONTROL_VALID	This indicates that the resource control manager bits in the security descriptor are valid. The resource control manager bits are 8 bits in the security descriptor structure that contains information specific to the resource manager accessing the structure.
SE_SELF_RELATIVE	This indicates a security descriptor in self-relative format, with all the security information in a contiguous block of memory. If this flag is not set, the security descriptor is in absolute format.

Security descriptors (SDs) can be retrieved programmatically by using various functions, such as GetSecurityInfo, GetKernelObjectSecurity, GetFileSecurity, GetNamedSecurityInfo, and other more esoteric functions. After retrieval, the SD can be manipulated and then the relevant Set function called to make the change. Furthermore, a security descriptor can be constructed using a string in a language called Security Descriptor Definition Language (SDDL), which is capable of representing a security descriptor using a compact string. This string can be converted to a true SD by calling ConvertStringSecurityDescriptorToSecurityDescriptor. As you might expect, the converse function exists as well (ConvertSecurityDescriptorToStringSecurityDescriptor). See the Windows SDK for a detailed description of the SDDL.

An access control list (ACL) is made up of a header and zero or more access control entry (ACE) structures. There are two types of ACLs: DACLs and SACLs. In a DACL, each ACE contains a SID and an access mask (and a set of flags, explained shortly), which typically specifies the access rights (read, write, delete, and so forth) that are granted or denied to the holder of the SID. There are nine types of ACEs that can appear in a DACL: access allowed, access denied, allowed object, denied object, allowed callback, denied callback, allowed object callback, denied-object callback, and conditional claims. As you would expect, the access-allowed ACE grants access to a user, and the access-denied ACE denies the access rights specified in the access mask. The callback ACEs are used by applications that make use of the AuthZ API (described later) to register a callback that AuthZ will call when it performs an access check involving this ACE.

The difference between allowed object and access allowed, and between denied object and access denied, is that the object types are used only within Active Directory. ACEs of these types have a globally unique identifier (GUID) field that indicates that the ACE applies only to particular objects or subobjects (those that have GUID identifiers). (A GUID is a 128-bit identifier guaranteed to be universally unique.) In addition, another optional GUID indicates what type of child object will inherit the ACE when a child is created within an Active Directory container that has the ACE applied to it. The conditional claims ACE is stored in a \*-callback type ACE structure and is described in the section on the AuthZ APIs.

The accumulation of access rights granted by individual ACEs forms the set of access rights granted by an ACL. If no DACL is present (a null DACL) in a security descriptor, everyone has full access to the object. If the DACL is empty (that is, it has zero ACEs), no user has access to the object.


The ACEs used in DACLs also have a set of flags that control and specify characteristics of the ACE related to inheritance. Some object namespaces have containers and objects. A container can hold other container objects and leaf objects, which are its child objects. Examples of containers are directories in the file system namespace and keys in the registry namespace. Certain flags in an ACE control how the ACE propagates to child objects of the container associated with the ACE. Table 7-6, reproduced in part from the Windows SDK, lists the inheritance rules for ACE flags.

Flag	Inheritance Rule		
CONTAINER_INHERIT_ACE	Child objects that are containers, such as directories, inherit the ACE as an effective ACE. The inherited ACE is inheritable unless the NO_PROPAGATE_INHERIT_ACE bit flag is also set.		
INHERIT_ONLY_ACE	This flag indicates an inherit-only ACE that doesn't control access to the object it's attached to. If this flag is not set, the ACE controls access to the object to which it is attached.		
INHERITED_ACE	This flag indicates that the ACE was inherited. The system sets this bit when it propagates an inheritable ACE to a child object.		
NO_PROPAGATE_INHERIT_ACE	If the ACE is inherited by a child object, the system clears the OBJECT_INHERIT_ ACE and CONTAINER_INHERIT_ACE flags in the inherited ACE. This action pre- vents the ACE from being inherited by subsequent generations of objects.		
OBJECT_INHERIT_ACE	Non-container child objects inherit the ACE as an effective ACE. For child objects that are containers, the ACE is inherited as an inherit-only ACE unless the NO_PROPAGATE_INHERIT_ACE bit flag is also set.		

TABLE 7-6 Inheritance rules for ACE flags

A SACL contains two types of ACEs: system audit ACEs and system audit-object ACEs. These ACEs specify which operations performed on the object by specific users or groups should be audited. Audit information is stored in the system audit log. Both successful and unsuccessful attempts can be audited. Like their DACL object-specific ACE cousins, system audit-object ACEs specify a GUID indicating the types of objects or sub-objects that the ACE applies to and an optional GUID that controls propagation of the ACE to particular child object types. If a SACL is null, no auditing takes place on the object. (Security auditing is described later in this chapter.) The inheritance flags that apply to DACL ACEs also apply to system audit-object ACEs.

Figure 7-8 is a simplified picture of a file object and its DACL. As shown, the first ACE allows USER1 to read the file. The second ACE denies members of the group TEAM1 write access to the file. The third ACE grants all other users (Everyone) execute access.





### **EXPERIMENT:** Viewing a security descriptor

Most executive subsystems rely on the object manager's default security functionality to manage security descriptors for their objects. The object manager's default security functions use the security descriptor pointer to store security descriptors for such objects. For example, the process manager uses default security, so the object manager stores process and thread security descriptor pointer of process and thread objects, respectively. The security descriptor pointer of events, mutexes, and semaphores also store their security descriptors. You can use live kernel debugging to view the security descriptors of these objects once you locate their object header, as outlined in the following steps. (Note that both Process Explorer and AccessChk can also show security descriptors for processes.)

- 1. Start local kernel debugging.
- 2. Type !process 0 0 explorer.exe to obtain process information about Explorer:

```
lkd> !process 0 0 explorer.exe
PROCESS ffffe18304dfd780
SessionId: 1 Cid: 23e4 Peb: 00c2a000 ParentCid: 2264
DirBase: 2aa0f6000 ObjectTable: ffffcd82c72fcd80 HandleCount:
<Data Not Accessible>
Image: explorer.exe
PROCESS ffffe1830670a080
SessionId: 1 Cid: 27b8 Peb: 00950000 ParentCid: 035c
DirBase: 2cba97000 ObjectTable: ffffcd82c7ccc500 HandleCount:
<Data Not Accessible>
Image: explorer.exe
```

If more than one instance of explorer is listed, choose one. (It doesn't matter which.)
 Type **!object** with the address of the EPROCESS in the output of the previous command as the argument to show the object data structure:

```
lkd> !object ffffel8304dfd780
Object: ffffel8304dfd780 Type: (ffffel82f7496690) Process
    ObjectHeader: ffffel8304dfd750 (new version)
    HandleCount: 15 PointerCount: 504639
```

4. Type dt \_OBJECT\_HEADER and the address of the object header field from the previous command's output to show the object header data structure, including the security descriptor pointer value:

```
1kd> dt nt!_object_header ffffel8304dfd750
+0x000 PointerCount : 0n504448
+0x008 HandleCount : 0n15
+0x008 NextToFree : 0x00000000'0000000f Void
+0x010 Lock : _EX_PUSH_LOCK
+0x018 TypeIndex : 0xe5 ''
+0x019 TraceFlags : 0 ''
+0x019 DbgRefTrace : 0y0
+0x019 DbgTracePermanent : 0y0
```

+0x01a	InfoMask	:	0x88	11
+0x01b	Flags	:	0 ''	
+0x01b	NewObject	:	0y0	
+0x01b	KernelObject	:	0y0	
+0x01b	KernelOnlyAccess	:	0y0	
+0x01b	ExclusiveObject	:	0y0	
+0x01b	PermanentObject	:	0y0	
+0x01b	DefaultSecurityQu	10	ta : 0	)y0
+0x01b	SingleHandleEntry	/	: 0y0	
+0x01b	DeletedInline	:	0y0	
+0x01c	Reserved	:	0x300	003100
+0x020	<pre>ObjectCreateInfo</pre>	:	0xfff	fe183'09e84ac0 _OBJECT_CREATE_INFORMATION
+0x020	QuotaBlockCharge		: 0xff	ffe183'09e84ac0 Void
+0x028	SecurityDescripto	or	: 0xf	fffcd82'cd0e97ed Void
+0x030	Body	:	_QUAD	)

5. Finally, use the debugger's ! sd command to dump the security descriptor. The security descriptor pointer in the object header uses some of the low-order bits as flags, and these must be zeroed before following the pointer. On 32-bit systems there are three flag bits, so use & -8 with the security descriptor address displayed in the object header structure, as follows. On 64-bit systems there are four flag bits, so you use & -10 instead.

```
lkd> !sd 0xffffcd82'cd0e97ed & -10
->Revision: 0x1
->Sbz1 : 0x0
->Control : 0x8814
          SE_DACL_PRESENT
           SE_SACL_PRESENT
           SE_SACL_AUTO_INHERITED
           SE_SELF_RELATIVE
->Owner : S-1-5-21-3537846094-3055369412-2967912182-1001
->Group : S-1-5-21-3537846094-3055369412-2967912182-1001
->Dacl :
->Dacl : ->AclRevision: 0x2
->Dacl : ->Sbz1 : 0x0
->Dacl : ->AclSize : 0x5c
->Dacl : ->AceCount : 0x3
->Dacl : ->Sbz2 : 0x0
->Dac1 : ->Ace[0]: ->AceType: ACCESS_ALLOWED_ACE_TYPE
->Dacl : ->Ace[0]: ->AceFlags: 0x0
->Dacl : ->Ace[0]: ->AceSize: 0x24
->Dacl : ->Ace[0]: ->Mask : 0x001fffff
->Dacl : ->Ace[0]: ->SID: S-1-5-21-3537846094-3055369412-2967912182-1001
->Dacl : ->Ace[1]: ->AceType: ACCESS_ALLOWED_ACE_TYPE
->Dacl : ->Ace[1]: ->AceFlags: 0x0
->Dacl : ->Ace[1]: ->AceSize: 0x14
->Dacl : ->Ace[1]: ->Mask : 0x001fffff
->Dacl : ->Ace[1]: ->SID: S-1-5-18
->Dacl : ->Ace[2]: ->AceType: ACCESS_ALLOWED_ACE_TYPE
```

```
->Dacl : ->Ace[2]: ->AceFlags: 0x0

->Dacl : ->Ace[2]: ->AceSize: 0x1c

->Dacl : ->Ace[2]: ->Mask : 0x00121411

->Dacl : ->Ace[2]: ->SID: S-1-5-5-0-1745560

->Sacl : ->AclRevision: 0x2

->Sacl : ->AclRevision: 0x2

->Sacl : ->AclSize : 0x1c

->Sacl : ->AceCount : 0x1

->Sacl : ->AceCount : 0x1

->Sacl : ->Ace[0]: ->AceType: SYSTEM_MANDATORY_LABEL_ACE_TYPE

->Sacl : ->Ace[0]: ->AceFlags: 0x0

->Sacl : ->Ace[0]: ->AceSize: 0x14

->Sacl : ->Ace[0]: ->AceSize: 0x14

->Sacl : ->Ace[0]: ->SID: S-1-16-8192
```

The security descriptor contains three access-allowed ACEs: one for the current user (S-1-5-21-3537846094-3055369412-2967912182-1001), one for the System account (S-1-5-18), and the last for the Logon SID (S-1-5-5-0-1745560). The system access control list has one entry (S-1-16-8192) labeling the process as medium integrity level.

#### ACL assignment

To determine which DACL to assign to a new object, the security system uses the first applicable rule of the following four assignment rules:

- 1. If a caller explicitly provides a security descriptor when creating the object, the security system applies it to the object. If the object has a name and resides in a container object (for example, a named event object in the \BaseNamedObjects object manager namespace directory), the system merges any inheritable ACEs (ACEs that might propagate from the object's container) into the DACL unless the security descriptor has the SE\_DACL\_PROTECTED flag set, which prevents inheritance.
- 2. If a caller doesn't supply a security descriptor and the object has a name, the security system looks at the security descriptor in the container in which the new object name is stored. Some of the object directory's ACEs might be marked as inheritable, meaning they should be applied to new objects created in the object directory. If any of these inheritable ACEs are present, the security system forms them into an ACL, which it attaches to the new object. (Separate flags indicate ACEs that should be inherited only by container objects rather than by objects that aren't containers.)
- 3. If no security descriptor is specified and the object doesn't inherit any ACEs, the security system retrieves the default DACL from the caller's access token and applies it to the new object. Several subsystems on Windows have hard-coded DACLs that they assign on object creation (for example, services, LSA, and SAM objects).
- **4.** If there is no specified descriptor, no inherited ACEs, and no default DACL, the system creates the object with no DACL, which allows everyone (all users and groups) full access to the object. This rule is the same as the third rule, in which a token contains a null default DACL.

The rules the system uses when assigning a SACL to a new object are similar to those used for DACL assignment, with some exceptions:

- Inherited system audit ACEs don't propagate to objects with security descriptors marked with the SE\_SACL\_PROTECTED flag (similar to the SE\_DACL\_PROTECTED flag, which protects DACLs).
- If there are no specified security audit ACEs and there is no inherited SACL, no SACL is applied to the object. This behavior is different from that used to apply default DACLs because tokens don't have a default SACL.

When a new security descriptor containing inheritable ACEs is applied to a container, the system automatically propagates the inheritable ACEs to the security descriptors of child objects. (Note that a security descriptor's DACL doesn't accept inherited DACL ACEs if its SE\_DACL\_PROTECTED flag is enabled, and its SACL doesn't inherit SACL ACEs if the descriptor has the SE\_SACL\_PROTECTED flag set.) The order in which inheritable ACEs are merged with an existing child object's security descriptor is such that any ACEs that were explicitly applied to the ACL are kept ahead of ACEs that the object inherits. The system uses the following rules for propagating inheritable ACEs:

- If a child object with no DACL inherits an ACE, the result is a child object with a DACL containing only the inherited ACE.
- If a child object with an empty DACL inherits an ACE, the result is a child object with a DACL containing only the inherited ACE.
- For objects in Active Directory only, if an inheritable ACE is removed from a parent object, automatic inheritance removes any copies of the ACE inherited by child objects.
- For objects in Active Directory only, if automatic inheritance results in the removal of all ACEs from a child object's DACL, the child object has an empty DACL rather than no DACL.

As you'll soon discover, the order of ACEs in an ACL is an important aspect of the Windows security model.

ſ					٦
L	2	=	=	=	
L	2	=	=	=	
L	2	=	=	=	
					- 1

**Note** Inheritance is generally not directly supported by the object stores, such as file systems, the registry, or Active Directory. Windows APIs that support inheritance, including SetEntriesInAc1, do so by invoking appropriate functions within the security inheritance support DLL (%SystemRoot%\System32\Ntmarta.dll) that know how to traverse those object stores.

## Trust ACEs

The advent of protected processes and Protected Processes Light (PPL, discussed in Chapter 3) created a need for such a process to make objects as accessible by protected processes only. This is important to protect certain resources such as the KnownD11s registry key from tampering, even by admin-level code. Such ACEs are specified with well-known SIDs that provide the protection level and signer that is required to obtain access. Table 7-7 shows the SIDs and their level and meaning.

#### TABLE 7-7 Trust SIDs

SID	Protection Level	Protection Signer
1-19-512-0	Protected Light	None
1-19-512-4096	Protected Light	Windows
1-19-512-8192	Protected Light	WinTcb
1-19-1024-0	Protected	None
1-19-1024-4096	Protected	Windows
1-19-1024-8192	Protected	WinTcb

A *trust SID* is part of a token object that exists for tokens attached to protected or PPL processes. The higher the SID number, the more powerful the token is. (remember that Protected is higher than Protected Light).

#### **EXPERIMENT: Viewing trust SIDs**

In this experiment, you'll look at trust SIDs in tokens of protected processes.

Start local kernel debugging.

List Csrss.exe processes with basic information:

```
lkd> !process 0 1 csrss.exe
     PROCESS ffff8188e50b5780
         SessionId: 0 Cid: 0358 Peb: b3a9f5e000 ParentCid: 02ec
         DirBase: 1273a3000 ObjectTable: ffffbe0d829e2040 HandleCount:
     <Data Not Accessible>
         Image: csrss.exe
         VadRoot ffff8188e6ccc8e0 Vads 159 Clone 0 Private 324. Modified 4470.
     Locked 0.
         DeviceMap ffffbe0d70c15620
         Token
                                           ffffbe0d829e7060
         . . .
     PROCESS ffff8188e7a92080
         SessionId: 1 Cid: 03d4 Peb: d5b0de4000 ParentCid: 03bc
         DirBase: 162d93000 ObjectTable: ffffbe0d8362d7c0 HandleCount:
     <Data Not Accessible>Modified 462372. Locked 0.
         DeviceMap ffffbe0d70c15620
         Token
                                          ffffbe0d8362d060
         . . .
Select one of the tokens and show its details:
     lkd> !token ffffbe0d829e7060
     _TOKEN 0xffffbe0d829e7060
     TS Session ID: 0
     User: S-1-5-18
     Process Token TrustLevelSid: S-1-19-512-8192
That's a PPL with a WinTcb signer.
```

### **Determining access**

Two methods are used for determining access to an object:

- The mandatory integrity check, which determines whether the integrity level of the caller is high enough to access the resource, based on the resource's own integrity level and its mandatory policy.
- The discretionary access check, which determines the access that a specific user account has to an object.

When a process tries to open an object, the integrity check takes place before the standard Windows DACL check in the kernel's SeAccessCheck function because it is faster to execute and can quickly eliminate the need to perform the full discretionary access check. Given the default integrity policies in its access token (TOKEN\_MANDATORY\_NO\_WRITE\_UP and TOKEN\_MANDATORY\_NEW\_PROCESS\_ MIN, described previously), a process can open an object for write access if its integrity level is equal to or higher than the object's integrity level and the DACL also grants the process the accesses it desires. For example, a low-integrity-level process cannot open a medium-integrity-level process for write access, even if the DACL grants the process write access.

With the default integrity policies, processes can open any object—with the exception of process, thread, and token objects—for read access as long as the object's DACL grants them read access. That means a process running at low integrity level can open any files accessible to the user account in which it's running. Protected Mode Internet Explorer uses integrity levels to help prevent malware that infects it from modifying user account settings, but it does not stop malware from reading the user's documents.

Recall that process, thread, and token objects are exceptions because their integrity policy also includes No-Read-Up. That means a process integrity level must be equal to or higher than the integrity level of the process or thread it wants to open, and the DACL must grant it the access it wants for an attempt to open it to succeed. Assuming the DACLs allow the desired access, Table 7-8 shows the types of access that processes running at various integrity levels have to other processes and objects.

Accessing Process	Access to Objects	Access to Other Processes
High integrity level	Read/write to all objects with integrity level of High or lower Read access to objects with integrity level of System	Read/write access to all processes with High or lower integrity level No read/write access to processes with System integrity level
Medium integrity level	Read/write to all objects with integrity level of Medium or Low Read access to objects with integrity level of High or System	Read/write access to all processes with Medium or Low integrity level No read/write access to processes with High or System integrity level
Low integrity level	Read/write to all objects with integrity level of Low Read access to objects with integrity level of Medium or higher	Read/write access to all processes with Low integrity level No read/write access to processes with Medium or higher integrity level

TABLE 7-8	Accessing objects and	l processes based	on integrity level
-----------	-----------------------	-------------------	--------------------

**Note** The read access to a process described in this section means full read access, such as reading the contents of the process address space. No-Read-Up does not prevent opening a higher-integrity-level process from a lower one for a more limited access, such as PROCESS\_QUERY\_LIMITED\_INFORMATION, which provides only basic information about the process.

#### **User Interface Privilege Isolation**

The Windows messaging subsystem also honors integrity levels to implement User Interface Privilege Isolation (UIPI). The subsystem does this by preventing a process from sending window messages to the windows owned by a process having a higher integrity level, with the following informational messages being exceptions:

WM\_NULL

- WM\_MOVE
- WM\_SIZE
- WM\_GETTEXT
- WM\_GETTEXTLENGTH

- WM\_GETICON
- WM\_RENDERFORMAT
- WM\_DRAWCLIPBOARD
- WM\_CHANGECBCHAIN
- WM\_THEMECHANGED

WM\_GETHOTKEY

This use of integrity levels prevents standard user processes from driving input into the windows of elevated processes or from performing a shatter attack (such as sending the process malformed messages that trigger internal buffer overflows, which can lead to the execution of code at the elevated process's privilege level). UIPI also blocks window hooks (SetWindowsHookEx API) from affecting the windows of higher-integrity-level processes so that a standard user process can't log the keystrokes the user types into an administrative application, for example. Journal hooks are also blocked in the same way to prevent lower-integrity-level processes from monitor-ing the behavior of higher-integrity-level processes.

Processes (running with medium or higher integrity level only) can choose to allow additional messages to pass the guard by calling the ChangeWindowMessageFilterEx API. This function is typically used to add messages required by custom controls to communicate outside native common controls in Windows. An older API, ChangeWindowMessageFilter, performs a similar function, but it is per-process rather than per-window. With ChangeWindowMessageFilter, it is possible for two custom controls inside the same process to be using the same internal window messages, which could lead to one control's potentially malicious window message to be allowed through, simply because it happens to be a query-only message for the other custom control.

Because accessibility applications such as the On-Screen Keyboard (Osk.exe) are subject to UIPI's restrictions (which would require the accessibility application to be executed for each kind of visible integrity-level process on the desktop), these processes can enable UI access. This flag

can be present in the manifest file of the image and will run the process at a slightly higher integrity level than medium (between 0x2000 and 0x3000) if launched from a standard user account, or at high integrity level if launched from an Administrator account. Note that in the second case, an elevation request won't actually be displayed. For a process to set this flag, its image must also be signed and in one of several secure locations, including %SystemRoot% and %ProgramFiles%.

After the integrity check is complete, and assuming the mandatory policy allows access to the object based on the caller's integrity, one of two algorithms is used for the discretionary check to an object, which will determine the outcome of the access check:

- Determine the maximum access allowed to the object, a form of which is exported to user mode using the AuthZ API (described in the section "The AuthZ API" later in this chapter) or the older GetEffectiveRightsFromAc1 function. This is also used when a program specifies a desired access of MAXIMUM\_ALLOWED, which is what the legacy APIs that don't have a desired access parameter use.
- Determine whether a specific desired access is allowed, which can be done with the Windows AccessCheck function or the AccessCheckByType function.

The first algorithm examines the entries in the DACL as follows:

- 1. If the object has no DACL (a null DACL), the object has no protection and the security system grants all access, unless the access is from an AppContainer process (discussed in the "AppContainers" section later in this chapter), which means access is denied.
- 2. If the caller has the take-ownership privilege, the security system grants write-owner access before examining the DACL. (Take-ownership privilege and write-owner access are explained in a moment.)
- **3.** If the caller is the owner of the object, the system looks for an OWNER\_RIGHTS SID and uses that SID as the SID for the next steps. Otherwise, read-control and write-DACL access rights are granted.
- **4.** For each access-denied ACE that contains a SID that matches one in the caller's access token, the ACE's access mask is removed from the granted-access mask.
- 5. For each access-allowed ACE that contains a SID that matches one in the caller's access token, the ACE's access mask is added to the granted-access mask being computed, unless that access has already been denied.

When all the entries in the DACL have been examined, the computed granted-access mask is returned to the caller as the maximum allowed access to the object. This mask represents the total set of access types that the caller will be able to successfully request when opening the object.

The preceding description applies only to the kernel-mode form of the algorithm. The Windows version implemented by GetEffectiveRightsFromAc1 differs in that it doesn't perform step 2, and it considers a single user or group SID rather than an access token.

### **Owner Rights**

Because owners of an object can normally override the security of an object by always being granted read-control and write-DACL rights, a specialized method of controlling this behavior is exposed by Windows: the Owner Rights SID.

The Owner Rights SID exists for two main reasons:

- **To improve service hardening in the operating system** Whenever a service creates an object at run time, the Owner SID associated with that object is the account the service is running in (such as local system or local service) and not the actual service SID. This means that any other service in the same account would have access to the object by being an owner. The Owner Rights SID prevents that unwanted behavior.
- To allow more flexibility for specific usage scenarios For example, suppose an administrator wants to allow users to create files and folders but not to modify the ACLs on those objects. (Users could inadvertently or maliciously grant access to those files or folders to unwanted accounts.) By using an inheritable Owner Rights SID, the users can be prevented from editing or even viewing the ACL on the objects they create. A second usage scenario relates to group changes. Suppose an employee has been part of some confidential or sensitive group, has created several files while a member of that group, and has now been removed from the group for business reasons. Because that employee is still a user, he could continue accessing the sensitive files.

The second algorithm is used to determine whether a specific access request can be granted based on the caller's access token. Each open function in the Windows API that deals with securable objects has a parameter that specifies the desired access mask, which is the last component of the security equation. To determine whether the caller has access, the following steps are performed:


- 1. If the object has no DACL (a null DACL), the object has no protection and the security system grants the desired access.
- 2. If the caller has the take-ownership privilege, the security system grants write-owner access if requested and then examines the DACL. However, if write-owner access was the only access requested by a caller with take-ownership privilege, the security system grants that access and never examines the DACL.
- 3. If the caller is the owner of the object, the system looks for an OWNER\_RIGHTS SID and uses that SID as the SID for the next steps. Otherwise, read-control and write-DACL access rights are granted. If these rights were the only access rights that the caller requested, access is granted without examining the DACL
- **4.** Each ACE in the DACL is examined from first to last. An ACE is processed if one of the following conditions is satisfied:
  - The ACE is an access-deny ACE, and the SID in the ACE matches an enabled SID (SIDs can be enabled or disabled) or a deny-only SID in the caller's access token.


- The ACE is an access-allowed ACE, and the SID in the ACE matches an enabled SID in the caller's token that isn't of type deny-only.
- It is the second pass through the descriptor for restricted-SID checks, and the SID in the ACE matches a restricted SID in the caller's access token.
- The ACE isn't marked as inherit-only.
- 5. If it is an access-allowed ACE, the rights in the access mask in the ACE that were requested are granted. If all the requested access rights have been granted, the access check succeeds. If it is an access-denied ACE and any of the requested access rights are in the denied-access rights, access is denied to the object.
- **6.** If the end of the DACL is reached and some of the requested access rights still haven't been granted, access is denied.
- 7. If all accesses are granted but the caller's access token has at least one restricted SID, the system rescans the DACL's ACEs looking for ACEs with access-mask matches for the accesses the user is requesting and a match of the ACE's SID with any of the caller's restricted SIDs. Only if both scans of the DACL grant the requested access rights is the user granted access to the object.

The behavior of both access-validation algorithms depends on the relative ordering of allow and deny ACEs. Consider an object with only two ACEs: one that specifies that a certain user is allowed full access to an object and one that denies the user access. If the allow ACE precedes the deny ACE, the user can obtain full access to the object, but if the order is reversed, the user cannot gain any access to the object.

Several Windows functions, such as SetSecurityInfo and SetNamedSecurityInfo, apply ACEs in the preferred order of explicit deny ACEs preceding explicit allow ACEs. For example, the security editor dialog boxes with which you edit permissions on NTFS files and registry keys use these functions. SetSecurityInfo and SetNamedSecurityInfo also apply ACE inheritance rules to the security descriptor on which they are applied.

Figure 7-9 shows an example of access validation demonstrating the importance of ACE ordering. In the example, access is denied to a user wanting to open a file even though an ACE in the object's DACL grants the access. This is because the ACE denying the user access (by virtue of the user's membership in the Writers group) precedes the ACE granting access.





As stated, because it wouldn't be efficient for the security system to process the DACL every time a process uses a handle, the SRM makes this access check only when a handle is opened, not each time the handle is used. Thus, once a process successfully opens a handle, the security system can't revoke the access rights that have been granted, even if the object's DACL changes. Also keep in mind that because kernel-mode code uses pointers rather than handles to access objects, the access check isn't performed when the operating system uses objects. In other words, the Windows executive trusts itself (and all loaded drivers) in a security sense.

The fact that an object's owner is always granted write-DACL access to an object means that users can never be prevented from accessing the objects they own. If, for some reason, an object had an empty DACL (no access), the owner would still be able to open the object with write-DACL access and then apply a new DACL with the desired access permissions.

#### A warning regarding the GUI security editors

When you use the GUI permissions editors to modify security settings on a file, a registry, or an Active Directory object, or on another securable object, the main security dialog box shows you a potentially misleading view of the security that's applied to the object. If you allow Full Control to the Everyone group and deny the Administrator group Full Control, the list might lead you to believe that the Everyone group access-allowed ACE precedes the Administrator deny ACE because that's the order in which they appear. However, as we've said, the editors place deny ACEs before allow ACEs when they apply the ACL to the object.

	Dummy.txt Properties	
is Versions	General Security Details Previous Versions	
brt	Object name: G.\Temp\Dummy.bd	
	Group or user names.	
	St Everyone	
	SE Authenticated Users	
	SYSTEM	
inistrators)	Administrators (2001AC)Administrators)	
	Sers (ZODIAC/Users)	
Edit	To change permissions, click Edit.	Edil
Allow Deny	Permissions for Administrators Allow	Deny
~	Full control	~
~ ~	Full control Modify	~
		***
	Modify	>>>>
	Modify Read & execute	>>>>>
	Modify Read & execute Read	>>>>>
	bd inistrators) Edit_	bd Object name: QiTempiDummy bd Group or user names: (응는 Everyone 용, Authenticated Users 용, SYSTEM 역, SYSTEM 8, Users (ZODIACIUSers) To change permissions, click Edit.

The Permissions tab of the Advanced Security Settings dialog box shows the order of ACEs in the DACL. However, even this dialog box can be confusing because a complex DACL can have deny ACEs for various accesses followed by allow ACEs for other access types.

Name: Owner: Permissions			95 0012758 (8 7220960)	x825-02 - 0210/074
For addition Permission e	al information, double-click a permission entry entries:	7. To modify a permission	entry, select the entry and click i	Edit (if available),
Туре	Principal	Access	Inherited from	
SE Deny	Administrators (ZODIAC\Administrators)	Full control	None	
Allow	Everyone	Full control	None	
Allow	Authenticated Users	Modify	None	
Allow	SYSTEM	Full control	None	
Allow	Users (ZODIAC\Users)	Read & execute	None	
Add Enable in	Remove View.			

The only definitive way to know what access a particular user or group will have to an object (other than having that user or a member of the group try to access the object) is to use the **Effective Access** tab of the dialog box that is displayed when you click the **Advanced** button in the Properties dialog box. Enter the name of the user or group you want to check and the dialog box shows you what permissions they are allowed for the object.

Name: G:\Temp\	Dummy.txt	
Owner: Pavel Yos	ifovich (zodiacon@live.com) 🛭 🏶 Change	
Permissions Audit	Ing Effective Access	
domain, you can also eval adding a group, any grou		, group, or device account. If the account is a member of a security token for the account. When you evaluate the impact of sust be added separately.
View effective access		
Effective access	Permission	Access limited by
×	Full control	File Permissions
×	Traverse folder / execute file	File Permissions
×	List folder / read data	File Permissions
	m 1 11 11 1	File Permissions
×	Read attributes	File Permissions
×	Read attributes Read extended attributes	File Permissions
×	Read extended attributes	File Permissions
×	Read extended attributes Create files / write data	File Permissions File Permissions
×	Read extended attributes Create files / write data Create folders / append data	File Permissions File Permissions File Permissions
× × ×	Read extended attributes Create files / write data Create folders / append data Write attributes	File Permissions File Permissions File Permissions File Permissions
× × × × × × ×	Read extended attributes Create files / write data Create folders / append data Write attributes Write extended attributes	File Permissions File Permissions File Permissions File Permissions File Permissions
* * * * *	Read extended attributes Create files / write data Create folders / append data Write attributes Write extended attributes Delete	File Permissions File Permissions File Permissions File Permissions File Permissions

## **Dynamic Access Control**

The discretionary access control mechanism discussed in previous sections has existed since the first Windows NT version and is useful in many scenarios. There are scenarios, however, where this scheme is not flexible enough. For example, consider a requirement that users accessing a shared file should be allowed to do so if they are using a computer in the workplace, but should not be allowed if accessing the file from their computer at home. There is no way to specify such a condition using an ACE.

Windows 8 and Server 2012 introduced Dynamic Access Control (DAC), a flexible mechanism that can be used to define rules based on custom attributes defined in Active Directory. DAC does not replace the existing mechanism, but adds to it. This means that for an operation to be allowed, both DAC and the classic DACL must grant the permission. Figure 7-10 shows the main aspects of Dynamic Access Control.




FIGURE 7-10 Dynamic Access Control components.

A claim is any piece of information about a user, device (computer in a domain), or resource (generic attribute) that has been published by a domain controller. Examples of valid claims are a user's title and department classification of a file. Any combination of claims can be used in expressions for building rules. These rules collectively become the central access policy.

DAC configuration is done in Active Directory and pushed through policy. The Kerberos tickets protocol has been enhanced to support authenticated transport of user and device claims (known as *Kerberos armoring*).

# The AuthZ API

The AuthZ Windows API provides authorization functions and implements the same security model as the security reference monitor (SRM), but it implements the model totally in user mode in the %SystemRoot%\System32\Authz.dll library. This gives applications that want to protect their own private objects, such as database tables, the ability to leverage the Windows security model without incurring the cost of user mode–to–kernel mode transitions that they would make if they relied on the SRM.

The AuthZ API uses standard security descriptor data structures, SIDs, and privileges. Instead of using tokens to represent clients, AuthZ uses AUTHZ\_CLIENT\_CONTEXT. AuthZ includes user-mode equivalents of all access-check and Windows security functions—for example, AuthzAccessCheck is the AuthZ version of the AccessCheck Windows API that uses the SeAccessCheck SRM function.

Another advantage available to applications that use AuthZ is that they can direct AuthZ to cache the results of security checks to improve subsequent checks that use the same client context and security descriptor. AuthZ is fully documented in the Windows SDK.

This type of access checking, using a SID and security group membership in a static, controlled environment, is known as *Identity-Based Access Control (IBAC)*, and it requires that the security system know the identity of every possible accessor when the DACL is placed in an object's security descriptor.

Windows includes support for *Claims Based Access Control (CBAC)*, where access is granted not based upon the accessor's identity or group membership, but upon arbitrary attributes assigned to the accessor and stored in the accessor's access token. Attributes are supplied by an attribute provider, such as AppLocker. The CBAC mechanism provides many benefits, including the ability to create a DACL for a user whose identity is not yet known or dynamically calculated user attributes. The CBAC ACE (also known as a conditional ACE) is stored in a \*-callback ACE structure, which is essentially private to AuthZ and is ignored by the system SeAccessCheck API. The kernel-mode routine SeSrpAccessCheck does not understand conditional ACEs, so only applications calling the AuthZ APIs can make use of CBAC. The only system component that makes use of CBAC is AppLocker, for setting attributes such as path or publisher. Third-party applications can make use of CBAC by taking advantage of the CBAC AuthZ APIs.

Using CBAC security checks allows powerful management policies, such as the following:

- Run only applications approved by the corporate IT department.
- Allow only approved applications to access your Microsoft Outlook contacts or calendar.
- Allow only people in a particular building on a specific floor to access printers on that floor.
- Allow access to an intranet website only to full-time employees (as opposed to contractors).

Attributes can be referenced in what is known as a *conditional ACE*, where the presence, absence, or value of one or more attributes is checked. An attribute name can contain any alphanumeric Unicode characters, as well as the following characters: colon (:), forward slash (/), and underscore (\_). The value of an attribute can be one of the following: 64-bit integer, Unicode string, byte string, or array.

# **Conditional ACEs**

The format of SDDL strings has been expanded to support ACEs with conditional expressions. The new format of an SDDL string is this: AceType;AceFlags;Rights;ObjectGuid;InheritObjectGuid; AccountSid; (ConditionalExpression).

The AceType for a conditional ACE is either XA (for SDDL\_CALLBACK\_ACCESS\_ALLOWED) or XD (for SDDL\_CALLBACK\_ACCESS\_DENIED). Note that ACEs with conditional expressions are used for claims-type authorization (specifically, the AuthZ APIs and AppLocker) and are not recognized by the object manager or file systems.

A conditional expression can include any of the elements shown in Table 7-9.

TABLE 7-9 Acceptable Elements for a Conditional Expression

Expression Element	Description
AttributeName	Tests whether the specified attribute has a non-zero value.
exists AttributeName	Tests whether the specified attribute exists in the client context.
AttributeName Operator Value	Returns the result of the specified operation. The following operators are defined for use in conditional expressions to test the values of attributes. All these are binary operators (as opposed to unary) and are used in the form AttributeName Operator Value. The operators are Contains any_of, ==, !=, <, <=, >, >=.
ConditionalExpression    ConditionalExpression	Tests whether either of the specified conditional expressions is true.
ConditionalExpression && ConditionalExpression	Tests whether both of the specified conditional expressions are true.
!(ConditionalExpression)	The inverse of a conditional expression.
Member_of {SidArray}	Tests whether the SID_AND_ATTRIBUTES array of the client context con- tains all the security identifiers (SIDs) in the comma-separated list specified by SidArray.

A conditional ACE can contain any number of conditions. It is ignored if the resultant evaluation of the condition is false or applied if the result is true. A conditional ACE can be added to an object using the AddConditionalAce API and checked using the AuthzAccessCheck API.

A conditional ACE could specify that access to certain data records within a program should be granted only to a user who meets the following criteria (for example):

- Holds the Role attribute, with a value of Architect, Program Manager, or Development Lead, and the Division attribute with a value of Windows
- Whose ManagementChain attribute contains the value John Smith
- Whose CommissionType attribute is Officer and whose PayGrade attribute is greater than 6 (that is, the rank of General Officer in the US military)

Windows does not include tools to view or edit conditional ACEs.

## Account rights and privileges

Many operations performed by processes as they execute cannot be authorized through object access protection because they do not involve interaction with a particular object. For example, the ability to bypass security checks when opening files for backup is an attribute of an account, not of a particular object. Windows uses both privileges and account rights to allow a system administrator to control what accounts can perform security-related operations.

A *privilege* is the right of an account to perform a particular system-related operation, such as shutting down the computer or changing the system time. An *account right* grants or denies the account to which it's assigned the ability to perform a particular type of logon, such as a local logon or interactive logon, to a computer. A system administrator assigns privileges to groups and accounts using tools such as the Active Directory Users and Groups MMC snap-in for domain accounts or the Local Security Policy editor (%SystemRoot%\System32\secpol.msc). Figure 7-11 shows the User Rights Assignment configuration in the Local Security Policy editor, which displays the complete list of privileges and account rights available on Windows. Note that the tool makes no distinction between privileges and account rights. However, you can differentiate between them: Any user right that does not contain the words *log on* is an account privilege.

ile Action View Help		
Security Settings	Policy	Security Setting
> Account Policies		Secondy Second
Local Policies	Access Credential Manager as a trusted caller	
Audit Policy	Access this computer from the network	Everyone, Administrators, Users, Backup
User Rights Assignment	Act as part of the operating system	
> Cal Security Options	Add workstations to domain	
Windows Firewall with Advanced Sect	Adjust memory quotas for a process	LOCAL SERVICE, NETWORK SERVICE, Ad
Network List Manager Policies	Allow log on locally	Guest, Administrators, Users, Backup Ope
Public Key Policies	Allow log on through Remote Desktop Services	Administrators, Remote Desktop Users
Software Restriction Policies	Back up files and directories	Administrators, Backup Operators
Application Control Policies	Bypass traverse checking	Everyone,LOCAL SERVICE,NETWORK SE
IP Security Policies on Local Compute	Change the system time	LOCAL SERVICE, Administrators
Advanced Audit Policy Configuration	Change the time zone	LOCAL SERVICE, Administrators, Users, Sy.
	Create a pagefile	Administrators
	Create a token object	
	Create global objects	LOCAL SERVICE, NETWORK SERVICE, Ad
	Create permanent shared objects	
	Create symbolic links	Administrators, NT VIRTUAL MACHINE\
	Debug programs	Administrators
	Deny access to this computer from the network	Guest
	Deny log on as a batch job	
	Deny log on as a service	
	E Deny log on locally	Guest
	Deny log on through Remote Desktop Services	
	Enable computer and user accounts to be trusted for delega	
	E Force shutdown from a remote system	Administrators
	Generate security audits	LOCAL SERVICE, NETWORK SERVICE, IIS
	Repersonate a client after authentication	LOCAL SERVICE, NETWORK SERVICE, Ad
	Concrease a process working set	Users, System Managed Group
	C Increase scheduling priority	Administrators
	Load and unload device drivers	Administrators
	Lock pages in memory	
	Log on as a batch job	Administrators, Backup Operators, Perfor
	Log on as a service	NETWORK SERVICE NT SERVICE ALL SE
	Manage auditing and security log	Administrators
	Modify an object label	
	Modify firmware environment values	Administrators
	Obtain an impersonation token for another user in the same	
	Perform volume maintenance tasks	Administrators
	Profile single process	Administrators
	Profile system performance	Administrators, NT SERVICE\WdiService
	Remove computer from docking station	Administrators, Users
	Replace a process level token	LOCAL SERVICE, NETWORK SERVICE, IS
	Restore files and directories	Administrators, Backup Operators
	Shut down the system	Administrators, Users, Backup Operators
	Synchronize directory service data	Administrators
	Take ownership of files or other objects	Administrators

FIGURE 7-11 Local Security Policy editor user rights assignment.

## Account rights

Account rights are not enforced by the SRM, nor are they stored in tokens. The function responsible for logon is LsaLogonUser. Winlogon, for example, calls the LogonUser API when a user logs on interactively to a computer, and LogonUser calls LsaLogonUser. LogonUser takes a parameter that indicates the type of logon being performed, which includes interactive, network, batch, service, and Terminal Server client.

In response to logon requests, the Local Security Authority (LSA) retrieves account rights assigned to a user from the LSA policy database at the time that a user attempts to log on to the system. The LSA checks the logon type against the account rights assigned to the user account logging on and denies the logon if the account does not have the right that permits the logon type or it has the right that denies the logon type. Table 7-10 lists the user rights defined by Windows.

User Right	Role
Deny logon locally, allow logon locally	Used for interactive logons that originate on the local machine
Deny logon over the network, allow logon over the network	Used for logons that originate from a remote machine
Deny logon through Terminal Services, allow logon through Terminal Services	Used for logons through a Terminal Server client
Deny logon as a service, allow logon as a service	Used by the service control manager when starting a service in a particular user account
Deny logon as a batch job, allow logon as a batch job	Used when performing a logon of type batch

	TABLE 7-10	Account	riahts
--	------------	---------	--------

Windows applications can add and remove user rights from an account by using the LsaAdd-AccountRights and LsaRemoveAccountRights functions, and they can determine what rights are assigned to an account with LsaEnumerateAccountRights.

### **Privileges**

The number of privileges defined by the operating system has grown over time. Unlike user rights, which are enforced in one place by the LSA, different privileges are defined by different components and enforced by those components. For example, the debug privilege, which allows a process to by-pass security checks when opening a handle to another process with the OpenProcess Windows API, is checked for by the process manager.

Table 7-11 is a full list of privileges and describes how and when system components check for them. Each privilege has a macro defined in the SDK headers, in the form SE\_privilege\_NAME, where privilege is a privilege constant—for example, SE\_DEBUG\_NAME for the debug privilege. These macros are defined as strings that start with Se and end with Privilege, as in SeDebugPrivilege. This may seem to indicate that privileges are identified by strings, but in fact they are identified by LUIDs, which naturally are unique for the current boot. Every access to a privilege needs to lookup the correct LUID by calling the LookupPrivilegeValue function. Note, however, that Ntdll and kernel code can identify privileges with integer constants directly without going through a LUID.

Privilege	User Right	Privilege Usage
SeAssignPrimaryTokenPrivilege	Replace a process- level token	Checked for by various components, such as NtSetInformationJobObject, that set a process's token.
SeAuditPrivilege	Generate security audits	Required to generate events for the Security event log with the ReportEvent API.

TABLE 7-11	Privileges
IADLE /-II	1 IIVIIEQES

#### TABLE 7-11 Privileges (continued)

Privilege	User Right	Privilege Usage
SeBackupPrivilege	Back up files and directories	Causes NTFS to grant the following access to any file or directory, regardless of the security descriptor that's present: READ_CONTROL, ACCESS_SYSTEM_ SECURITY, FILE_GENERIC_READ, and FILE_ TRAVERSE. Note that when opening a file for backup, the caller must specify the FILE_FLAG_BACKUP_ SEMANTICS flag. Also allows corresponding access to registry keys when using RegSaveKey.
SeChangeNotifyPrivilege	Bypass traverse checking	Used by NTFS to avoid checking permissions on intermediate directories of a multilevel directory lookup. Also used by file systems when applications register for notification of changes to the file system structure.
SeCreateGlobalPrivilege	Create global objects	Required for a process to create section and sym- bolic link objects in the directories of the object manager namespace that are assigned to a different session than the caller.
SeCreatePagefilePrivilege	Create a pagefile	Checked for by NtCreatePagingFile, which is the function used to create a new paging file.
SeCreatePermanentPrivilege	Create permanent shared objects	Checked for by the object manager when creating a permanent object (one that doesn't get deallocated when there are no more references to it).
SeCreateSymbolicLinkPrivilege	Create symbolic links	Checked for by NTFS when creating symbolic links on the file system with the CreateSymbolicLink API.
SeCreateTokenPrivilege	Create a token object	NtCreateToken, the function that creates a token object, checks for this privilege.
SeDebugPrivilege	Debug programs	If the caller has this privilege enabled, the process manager allows access to any process or thread using NtOpenProcess or NtOpenThread, regardless of the process's or thread's security descriptor (except for protected processes).
SeEnableDelegationPrivilege	Enable computer and user accounts to be trusted for delegation	Used by Active Directory services to delegate authenticated credentials.
SeImpersonatePrivilege	Impersonate a client after authentication	The process manager checks for this when a thread wants to use a token for impersonation and the token represents a different user than that of the thread's process token.
SeIncreaseBasePriorityPrivilege	Increase schedul- ing priority	Checked for by the process manager and is required to raise the priority of a process.
SeIncreaseQuotaPrivilege	Adjust memory quotas for a process	Enforced when changing a process's working set thresholds, a process's paged and nonpaged pool quotas, and a process's CPU rate quota.
SeIncreaseWorkingSetPrivilege	Increase a process working set	Required to call SetProcessWorkingSetSize to increase the minimum working set. This indirectly allows the process to lock up to the minimum work- ing set of memory using VirtualLock.

#### TABLE 7-11 Privileges (continued)

Privilege	User Right	Privilege Usage
SeLoadDriverPrivilege	Load and unload device drivers	Checked for by the NtLoadDriver and NtUnloadDriver driver functions.
SeLockMemoryPrivilege	Lock pages in memory	Checked for by NtLockVirtualMemory, the kernel implementation of VirtualLock.
SeMachineAccountPrivilege	Add workstations to the domain	Checked for by the Security Account Manager on a domain controller when creating a machine account in a domain.
SeManageVolumePrivilege	Perform volume maintenance tasks	Enforced by file system drivers during a volume open operation, which is required to perform disk-check- ing and defragmenting activities.
SeProfileSingleProcessPrivilege	Profile single process	Checked by Superfetch and the prefetcher when requesting information for an individual process through the NtQuerySystemInformation API.
SeRelabelPrivilege	Modify an object label	Checked for by the SRM when raising the integrity level of an object owned by another user, or when attempting to raise the integrity level of an object higher than that of the caller's token.
SeRemoteShutdownPrivilege	Force shutdown from a remote system	Winlogon checks that remote callers of the InitiateSystemShutdown function have this privi- lege.
SeRestorePrivilege	Restore files and directories	This privilege causes NTFS to grant the following ac- cess to any file or directory, regardless of the security descriptor that's present: WRITE_DAC, WRITE_OWNER, ACCESS_SYSTEM_SECURITY, FILE_GENERIC_WRITE, FILE_ADD_FILE, FILE_ADD_SUBDIRECTORY, and DELETE. Note that when opening a file for restore, the caller must specify the FILE_FLAG_BACKUP_ SEMANTICS flag. Allows corresponding access to registry keys when using RegSaveKey.
SeSecurityPrivilege	Manage auditing and security log	Required to access the SACL of a security descriptor and to read and clear the security event log.
SeShutdownPrivilege	Shut down the system	Checked for by NtShutdownSystem and NtRaiseHardError, which presents a system error dialog box on the interactive console.
SeSyncAgentPrivilege	Synchronize direc- tory service data	Required to use the LDAP directory synchronization services. It allows the holder to read all objects and properties in the directory, regardless of the protec- tion on the objects and properties.
SeSystemEnvironmentPrivilege	Modify firmware environment vari- ables	Required by NtSetSystemEnvironmentValue and NtQuerySystemEnvironmentValue to modify and read firmware environment variables using the hard- ware abstraction layer (HAL).
SeSystemProfilePrivilege	Profile system per- formance	Checked for by NtCreateProfile, the function used to perform profiling of the system. This is used by the Kernprof tool, for example.
SeSystemtimePrivilege	Change the sys- tem time	Required to change the time or date.

#### TABLE 7-11 Privileges (continued)

Privilege	User Right	Privilege Usage
SeTakeOwnershipPrivilege	Take ownership of files and other objects	Required to take ownership of an object without being granted discretionary access.
SeTcbPrivilege	Act as part of the operating system	Checked for by the SRM when the session ID is set in a token, by the Plug and Play manager for Plug and Play event creation and management, by BroadcastSystemMessageEx when called with BSM_ALLDESKTOPS, by LsaRegisterLogonProcess, and when specifying an application as a VDM with NtSetInformationProcess.
SeTimeZonePrivilege	Change the time zone	Required to change the time zone.
SeTrustedCredManAccessPrivilege	Access Credential Manager as a trusted caller	Checked by the Credential Manager to verify that it should trust the caller with credential information that can be queried in plaintext. It is granted only to Winlogon by default.
SeUndockPrivilege	Remove computer from a docking station	Checked for by the user-mode Plug and Play man- ager when either a computer undock is initiated or a device eject request is made.
SeUnsolicitedInputPrivilege	Receive unsolic- ited data from a terminal device	This privilege isn't currently used by Windows.

When a component wants to check a token to see whether a privilege is present, it uses the Privilege-Check or LsaEnumerateAccountRights APIs if running in user mode and SeSinglePrivilegeCheck or SePrivilegeCheck if running in kernel mode. The privilege-related APIs are not account-right aware, but the account-right APIs are privilege-aware.

Unlike account rights, privileges can be enabled and disabled. For a privilege check to succeed, the privilege must be in the specified token and it must be enabled. The idea behind this scheme is that privileges should be enabled only when their use is required so that a process cannot inadvertently perform a privileged security operation. Enabling or disabling privileges can be done with the AdjustTokenPrivileges function.

#### **EXPERIMENT:** Seeing a privilege get enabled

By following these steps, you can see that the Date and Time Control Panel applet enables the SeTimeZonePrivilege privilege in response to you using its interface to change the time zone of the computer (Windows 10):

- 1. Run Process Explorer elevated.
- Right-click the clock in the system tray in the taskbar and choose Adjust Date/Time. Alternatively, open the Settings app and search for time to open the Date and Time settings page.

 Right-click the SystemSettings.exe process in Process Explorer and choose Properties. Then click the Security tab in the Properties dialog box. You should see that the SeTimeZonePrivilege privilege is disabled.

Image Threads	Performance TCP/IP	Performance Security	Graph Environ	Disk and ment	Network Job	GPU Graph Strings
	Session: 1 1	CS35010 -3537846094-3 .ogon Session: Protected:		29679121	82-1001	
	Group BUILTINVAdminis BUILTINV4per-V BUILTINVeform BUILTINVerform BUILTINVerform BUILTINVerform BUILTINVerform LOCAL Mandatory Label MicrosoftAccourn NT AUTHORITVV NT AUTHORITVV NT AUTHORITVN NT AUTHORITVN	Administrator ance Log Usen N (Medium Man (Vzodiacon@li Authenticated Joud Account NTERACTIVE	datory Leve ve.com Users		Flags Deny Mandato Mandato Mandato Mandato Mandato Mandato Mandato Mandato Mandato Mandato Mandato Mandato	
đ	Group SID: n/a Privilege SeChangeNotifyF SeIncreaseWorkir SeShutdownPrivil SeT mcZonePrivil SeUndockPrivileg	ngSetPrivilege lege ege	Flags Default En Disabled Disabled Disabled Disabled	abled		
					p	ermissions

4. Change the time zone, close the Properties dialog box, and then open it again. On the Security tab, you should now see that the SeTimeZonePrivilege privilege is enabled:

Image Thread	Performance Is TCP/IP	Performance Security		Disk and onment	Network Job	GPU Gr Strin	
-	Session: 1 L	CS35010 3537846094-3 ogon Session: Yrotected:		2-2967912	182-1001		
	Group BUILTIN\Adminis	rators			Flags		^
	BUILTIN/Hyper-V				Mandat	2002	
	BUILTIN\Perform				Mandat		
	BUILTIN\Users				Mandat		
	CONSOLE LOGO	N I			Mandat	ory	
	Everyone				Mandat	ory	
	LOCAL				Mandat	ory	
	Mandatory Label	Medium Man	datory Le	evel	Integrity		
	MicrosoftAccount				Mandat	ory	
	NT AUTHORITY				Mandat		
	NT AUTHORITY\C		Authenti	cation	Mandat		
	NT AUTHORITY\I				Mandat		
	NT AUTHORITY\L Group SID: n/a	ocal account			Mandat	ory	~
-1	Privilege		Flags				
20	SeChangeNotifyP	rivilege	Default 8	nabled			
	SelncreaseWorkin		Disabled				
	SeShutdownPrivil	ege	Disabled				
	SeTimeZonePrivile	ege	Enabled			8	
	SeUndockPrivileg	e	Disabled				
		с. 					
					_	Permissio	15
				-	OK	Cano	d

### EXPERIMENT: The Bypass Traverse Checking privilege

If you are a systems administrator, you must be aware of the Bypass Traverse Checking privilege (internally called SeNotifyPrivilege) and its implications. This experiment demonstrates that not understanding its behavior can lead to improperly applied security.

- 1. Create a folder and, within that folder, a new text file with some sample text.
- 2. Navigate in Explorer to the new file, open its Properties dialog box, and click the **Security** tab.
- 3. Click the Advanced button.
- 4. Deselect the Inheritance check box.
- 5. Select **Copy** when you are prompted as to whether you want to remove or copy inherited permissions.
- Modify the security of the new folder so that your account does not have any access to the folder. To do so, select your account and check all the **Deny** boxes in the permissions list.
- 7. Run Notepad. Then open the **File** menu, choose **Open**, and browse to the new directory in the dialog box that appears. You should be denied access to the directory.
- **8.** In the File Name field of the Open dialog box, type the full path of the new file. The file should open.

If your account does not have the Bypass Traverse Checking privilege, NTFS performs an access check on each directory of the path to a file when you try to open a file, which results in you being denied access to the file in this example.

## Super privileges

Several privileges are so powerful that a user to which they are assigned is effectively a "super user" who has full control over a computer. These privileges can be used in an infinite number of ways to gain unauthorized access to otherwise off-limit resources and to perform unauthorized operations. However, we'll focus on using the privilege to execute code that grants the user privileges not assigned to the user, with the knowledge that this capability can be leveraged to perform any operation on the local machine that the user desires.

This section lists the privileges and discusses some of the ways they can be exploited. Other privileges, such as Lock Pages in Physical Memory (SeLockMemoryPrivilege), can be exploited for denialof-service attacks on a system, but these are not discussed. Note that on systems with UAC enabled, these privileges will be granted only to applications running at high integrity level or higher, even if the account possesses them:

- Debug programs (SeDebugPrivilege) A user with this privilege can open any process on the system (except for a protected process) without regard to the security descriptor present on the process. For example, the user could implement a program that opens the Lsass process, copy executable code into its address space, and then inject a thread with the CreateRemoteThread Windows API to execute the injected code in a more-privileged security context. The code could grant the user additional privileges and group memberships.
- Take ownership (SeTakeOwnershipPrivilege) This privilege allows a holder to take ownership of any securable object (even protected processes and threads) by writing his own SID into the owner field of the object's security descriptor. Recall that an owner is always granted permission to read and modify the DACL of the security descriptor, so a process with this privilege could modify the DACL to grant itself full access to the object and then close and reopen the object with full access. This would allow the owner to see sensitive data and to even replace system files that execute as part of normal system operation, such as Lsass, with his own programs that grant a user elevated privileges.
- Restore files and directories (SeRestorePrivilege) A user assigned this privilege can replace any file on the system with her own. She could exploit this power by replacing system files as described in the preceding paragraph.
- Load and unload device drivers (SeLoadDriverPrivilege) A malicious user could use this privilege to load a device driver into the system. Device drivers are considered trusted parts of the operating system that can execute within it with System account credentials, so a driver could launch privileged programs that assign the user other rights.
- Create a token object (SeCreateTokenPrivilege) This privilege can be used in the obvious way to generate tokens that represent arbitrary user accounts with arbitrary group membership and privilege assignment.
- Act as part of operating system (SeTcbPrivilege) LsaRegisterLogonProcess, the function a process calls to establish a trusted connection to Lsass, checks for this privilege. A malicious user with this privilege can establish a trusted-Lsass connection and then execute LsaLogonUser, a function used to create new logon sessions. LsaLogonUser requires a valid user name and password and accepts an optional list of SIDs that it adds to the initial token created for a new logon session. The user could therefore use her own user name and password to create a new logon session that includes the SIDs of more privileged groups or users in the resulting token.

**Note** The use of an elevated privilege does not extend past the machine boundary to the network because any interaction with another computer requires authentication with a domain controller and validation of domain passwords. Domain passwords are not stored on a computer either in plaintext or encrypted form, so they are not accessible to malicious code.

Figure 7-12 brings together the concepts covered so far in this chapter by illustrating the basic process and thread security structures. In the figure, notice that the process object and the thread objects have ACLs, as do the access token objects themselves. Also in this figure, thread 2 and thread 3 each have an impersonation token, whereas thread 1 uses the default process access token.




FIGURE 7-12 Process and thread security structures.

## **Security auditing**

The object manager can generate audit events as a result of an access check, and Windows functions available to user applications can generate them directly. Kernel-mode code is always allowed to generate an audit event. Two privileges, SeSecurityPrivilege and SeAuditPrivilege, relate to auditing. A process must have the SeSecurityPrivilege privilege to manage the security event log and to view or set an object's SACL. Processes that call audit system services, however, must have the SeAuditPrivilege privilege to successfully generate an audit record.

The audit policy of the local system controls the decision to audit a particular type of security event. The audit policy, also called the Local Security Policy, is one part of the security policy Lsass maintains on the local system. It is configured with the Local Security Policy editor as shown in Figure 7-13. The audit policy configuration (both the basic settings under Local Policies and the Advanced Audit Policy Configuration) is stored in the registry as a bitmapped value in the HKEY\_LOCAL\_MACHINE\SECURITY\ Policy\PolAdtEv key.




FIGURE 7-13 Local Security Policy editor audit policy configuration.

Lsass sends messages to the SRM to inform it of the auditing policy at system-initialization time and when the policy changes. Lsass is responsible for receiving audit records generated based on the audit events from the SRM, editing the records, and sending them to the event logger. Lsass (instead of the SRM) sends these records because it adds pertinent details, such as the information needed to more completely identify the process that is being audited.

The SRM sends audit records via its ALPC connection to Lsass. The event logger then writes the audit record to the security event log. In addition to audit records the SRM passes, both Lsass and the SAM generate audit records that Lsass sends directly to the event logger, and the AuthZ APIs allow for applications to generate application-defined audits. Figure 7-14 depicts this overall flow.




FIGURE 7-14 Flow of security audit records.

Audit records are put on a queue to be sent to the LSA as they are received. They are not submitted in batches. The audit records are moved from the SRM to the security subsystem in one of two ways. If the audit record is small (less than the maximum ALPC message size), it is sent as an ALPC message. The audit records are copied from the address space of the SRM to the address space of the Lsass process. If the audit record is large, the SRM uses shared memory to make the message available to Lsass and simply passes a pointer in an ALPC message.

## **Object access auditing**

An important use of the auditing mechanism in many environments is to maintain a log of accesses to secured objects—in particular, files. To do this, the Audit object access policy must be enabled, and there must be audit ACEs in system access control lists that enable auditing for the objects in question.

When an accessor attempts to open a handle to an object, the SRM first determines whether the attempt is allowed or denied. If object access auditing is enabled, the SRM then scans the system ACL of the object. There are two types of audit ACEs: access allowed and access denied. An audit ACE must match any of the security IDs held by the accessor, it must match any of the access methods requested, and its type (access allowed or access denied) must match the result of the access check to generate an object access audit record.

Object access audit records include not just the fact of access allowed or denied, but also the reason for the success or failure. This "reason for access" reporting generally takes the form of an access control entry, specified in Security Descriptor Definition Language (SDDL), in the audit record. This allows for a diagnosis of scenarios in which an object to which you believe access should be denied is being permitted, or vice versa, by identifying the specific access control entry that caused the attempted access to succeed or fail.

As was shown in Figure 7-13, object access auditing is disabled by default (as are all other auditing policies).

#### **EXPERIMENT: Object access auditing**

You can observe object access auditing by following these steps:

- In Explorer, navigate to a file to which you would normally have access (such as a text file), open its Properties dialog box, click the Security tab, and then select the Advanced settings.
- 2. Click the **Auditing** tab and click through the administrative privileges warning. The resulting dialog box allows you to add auditing of access control entries to the file's system access control list.

Vame:	G:\Temp\test.t	st.			
Dwnen	Pavel Vosifovic	h (zodiacon@live.com)	Change		
Permissions	Auditing	Effective Access			
or additional i	information, dou	ble-click an audit entry.	. To modify an audit entr	ry, select the entry and click Edit (if a	vailable).
Auditing entrie					
Туре	Principal		Access	Inherited from	
Add	Ramitue	View			

- 3. Click the Add button and choose Select a Principal.
- 4. In the resulting Select User or Group dialog box, enter your own user name or a group to which you belong, such as **Everyone**. Click **Check Names** and then click **OK**. This presents a dialog box for creating an Audit access control entry for this user or group for this file.

, manning a	Entry for test.bat	
rincipale	Everyone Select a principal	
ype:	Success ~	
asic pern	nissions:	Show advanced permission
	Full control	
	✓ Modify ✓ Read & execute	
	Read	
	Write	
	Special permissions	
		Clear all
		OK Cancel

- 5. Click **OK** three times to close the file Properties dialog box.
- **6.** In Explorer, double-click the file to open it with its associated program (for example, Notepad for a text file).
- 7. Click the **Start** menu, type **event**, and choose **Event Viewer**.

- **8.** Navigate to the Security log. Note that there is no entry for access to the file. This is because the audit policy for object access is not yet configured.
- 9. In the Local Security Policy editor, navigate to Local Policies and choose Audit Policy.
- **10.** Double-click **Audit Object Access** and click **Success** to enable auditing of successful access to files.
- **11.** In Event Viewer, click **Action** (from the menu) and **Refresh**. Note that the changes to audit policy resulted in audit records.
- **12.** In Explorer, double-click the file to open it again.
- **13.** In Event Viewer, click **Action** and **Refresh**. Note that several file access audit records are now present.
- **14.** Find one of the file access audit records for event ID 4656. This shows up as "a handle to an object was requested." (You can use the Find option to search for the file name you opened.)
- 15. Scroll down in the text box to find the Access Reasons section. The following example shows that two access methods, READ\_CONTROL, SYNCHRONIZE, and ReadAttributes, ReadEA (extended attributes), and ReadData were requested. READ\_CONTROL was granted because the accessor was the owner of the file. The others were granted because of the indicated access control entry.

Event Viewer (Local)	Security Number	r of events: 25,861 (()	Actions	-			
Content Messer (Local)     Content Mess     Content Messer     Content Messer	Security         Number of events 23:345 (1) None events sublidit           Kaywenit         Date and Time         Source           Madd Socress         11-Dec-16 11:41:34         Microsoft Windows recently autility.           Cenet 805, Microsoft Windows recently audility.         Microsoft Windows recently audility.           Cenet 805, Microsoft Windows recently audility.         C/Window/Papierer.cee           Process 10         C/Window/Papierer.cee           Process 10         C/Window/Papierer.cee			Windows tecurity auditing. Windows serviny soliting. Windows tecurity auditing. Windows tecurity auditing. Windows tecurity auditing. Windows tecurity auditing. Windows construct auditing.	××	Actions           Security         Open Swed Log           Open Swed Log         Open Swed Log           We create Custom View         Import Custom View           Import Custom View         Open Custom View           Open Castom View         Open Custom View           Properties         Properties           Weiw         Refrash           Import         Holgo           Neurol Motors Minimous security a         Security Security Security a           Match Task To This Event         Security	
	Log Name Source Event ID: Levet User OpCode	Security	ReadAttributes: Granted b lows security Logged: Task Category: Keywords: Computer	9 Dr(Å;;0x1301bf;;AU) Granted by Dr Dr(Å;;0x1301bf;;AU) y Dr(Å;;0x1301bf;;AU) 11-Dec-16 18:41:34		nn Save Selected Events ≩ Refrach ₽ Help	,

# **Global audit policy**

In addition to object-access ACEs on individual objects, a global audit policy can be defined for the system that enables object-access auditing for all file-system objects, all registry keys, or for both. A security auditor can therefore be certain that the desired auditing will be performed, without having to set or examine SACLs on all the individual objects of interest.

An administrator can set or query the global audit policy via the AuditPol command with the /resourceSACL option. This can also be done programmatically by calling the AuditSetGlobalSacl and AuditQueryGlobalSacl APIs. As with changes to objects' SACLs, changing these global SACLs requires SeSecurityPrivilege.

### **EXPERIMENT:** Setting global audit policy

You can use the AuditPol command to enable global audit policy.

- If you didn't already do so in the previous experiment, open the Local Security Policy editor, navigate to the Audit Policy settings (refer to Figure 7-13), double-click Audit Object Access, and enable auditing for both success and failure. On most systems, SACLs specifying object access auditing are uncommon, so few if any object-access audit records will be produced at this point.
- 2. In an elevated command prompt window, enter the following command. This will produce a summary of the commands for setting and querying global audit policy.

C:\> auditpol /resourceSACL

3. In the same elevated command prompt window, enter the following commands. On a typical system, each of these commands will report that no global SACL exists for the respective resource type. (Note that the File and Key keywords are case-sensitive.)

```
C:\> auditpol /resourceSACL /type:File /view
C:\> auditpol /resourceSACL /type:Key /view
```

4. In the same elevated command prompt window, enter the following command. This will set a global audit policy such that all attempts to open files for write access (FW) by the indicated user will result in audit records, whether the open attempts succeed or fail. The user name can be a specific user name on the system, a group such as Everyone, a domain-qualified user name such as domainname\username, or a SID.

```
C:\> auditpol /resourceSACL /set /type:File /user:yourusername /success
/failure /access:FW
```

- **5.** While running under the user name indicated, use Explorer or other tools to open a file. Then look at the security log in the system event log to find the audit records.
- 6. At the end of the experiment, use the auditpol command to remove the global SACL you created in step 4, as follows:

```
C:\> auditpol /resourceSACL /remove /type:File /user:yourusername
```

The global audit policy is stored in the registry as a pair of system access control lists in HKLM\ SECURITY\Policy\GlobalSaclNameFile and HKLM\SECURITY\Policy\GlobalSaclNameKey. You can examine these keys by running Regedit.exe under the System account, as described in the "Security system components" section earlier in this chapter. These keys will not exist until the corresponding global SACLs have been set at least once.

The global audit policy cannot be overridden by SACLs on objects, but object-specific SACLs can allow for additional auditing. For example, global audit policy could require auditing of read access by all users to all files, but SACLs on individual files could add auditing of write access to those files by specific users or by more specific user groups.

Global audit policy can also be configured via the Local Security Policy editor in the Advanced Audit Policy settings, described in the next section.

## **Advanced Audit Policy settings**

In addition to the Audit Policy settings described previously, the Local Security Policy editor offers a much more fine-grained set of audit controls under the Advanced Audit Policy Configuration heading, shown in Figure 7-15.




FIGURE 7-15 The Local Security Policy editor's Advanced Audit Policy Configuration settings.

Each of the nine audit policy settings under Local Policies (refer to Figure 7-13) maps to a group of settings here that provide more detailed control. For example, while the Audit Object Access settings under Local Policies allow access to all objects to be audited, the settings here allow auditing of access to various types of objects to be controlled individually. Enabling one of the audit policy settings under Local Policies implicitly enables all the corresponding advanced audit policy events, but if finer control over the contents of the audit log is desired, the advanced settings can be set individually. The standard settings then become a product of the advanced settings. However, this is not visible in the Local Security Policy editor. Attempts to specify audit settings by using both the basic and the advanced options can cause unexpected results.

You can use the Global Object Access Auditing option under Advanced Audit Policy Configuration to configure the global SACLs described in the previous section, using a graphical interface identical to that seen in Explorer or the Registry editor for security descriptors in the file system or the registry.

### **AppContainers**

Windows 8 introduced a new security sandbox called an *AppContainer*. Although it was created primarily to host UWP processes, AppContainers can actually be used for "normal" processes as well (although there is no built-in tool to do that). This section will mostly cover the attributes of packaged AppContainers, which is the term that refers to AppContainers associated with UWP processes and their resulting .Appx format. A complete treatment of UWP apps is beyond the scope of this chapter. You can find more information in Chapter 3 of this book, and in Chapters 8 and 9 in Part 2. Here we'll concentrate on the security aspects of AppContainers and their typical usage as hosts of UWP apps.

**Note** The term *Universal Windows Platform (UWP) app* is the latest used to describe processes that host the Windows Runtime. Older names include *immersive app, modern app, metro app,* and sometimes simply *Windows app.* The *Universal* part indicates the ability of such apps to be deployed and run on various Windows 10 editions and form factors, from IoT core, to mobile, to desktop, to Xbox, to HoloLens. However, they are essentially the same as the ones first introduced in Windows 8. Therefore, the concept of AppContainers discussed in this section is relevant to Windows 8 and later versions of Windows. Note that Universal Application Platform (UAP) is sometimes used instead of UWP; it's the same thing.

**Note** The original codename for AppContainer was *LowBox*. You may see this term come up in many of the API names and data structures throughout this section. They refer to the same concept.

## **Overview of UWP apps**

The mobile device revolution established new ways of obtaining and running software. Mobile devices normally get their applications from a central store, with automatic installation and updates, all with little user intervention. Once a user selects an app from the store, she can see the permissions the app requires to function correctly. These permissions are called *capabilities* and are declared as part of the package when it's submitted to the store. This way, the user can decide whether these capabilities are acceptable.

Figure 7-16 shows an example of a capabilities list for a UWP game (*Minecraft*, Windows 10 beta edition). The game requires internet access as a client and as a server and access to the local home or work network. Once the user downloads the game, she implicitly agrees the game may exercise these capabilities. Conversely, the user can be confident that the game uses *only* those capabilities. That is, there is no way the game could use other unapproved capabilities, such as accessing the camera on the device.


- Store Home Apps	Games				Search	د ۵ – م
System Requ	uirements			Recommended		
OS	Windows 10 version 10 required	240.0 or higher	~	OS	Not specified	Get more info
Architecture	X64 required		~	Architecture	Not specified	Get more info
Microsoft Studios Published by Microsoft Studios © 2015 Microsoft ( Category Action & adventur Approximate size 177.9 MB	Corporation and Mojang	This app has pe	ce ten Win ermissio iternet c	dows 10 devices. In to do the following connection and act as a work networks	Chinese (Simplified), Chin English (United States), Fr German, Italian, Japanese More Learn more Minecraft: Windows 10 Ec Minecraft: Windows 10 Ec Privacy and terms Minecraft: Windows 10 Ec policy Terms of transaction	ench, French (Canada), , Korean , lition Beta support dition Beta website
					Report this product	

FIGURE 7-16 Part of an app's page in the store, showing capabilities, among other things.

To get a sense of the differences between UWP apps and desktop (classic) apps at a high level, consult Table 7-12. From a developer's perspective, the Windows platform can be seen as shown in Figure 7-17.

	UWP App	Desktop (Classic) App
Device Support	Runs on all Windows device families	Runs on PCs only
APIs	Can access WinRT, subset of COM, and subset of Win32 APIs	Can access COM, Win32, and subset of WinRT APIs
Identity	Strong app identity (static and dynamic)	Raw EXEs and processes
Information	Declarative APPX manifest	Opaque binaries
Installation	Self-contained APPX package	Loose files or MSI
App Data	Isolated per-user/per-app storage (local and roaming)	Shared user profile
Lifecycle	Participates in app resource management and PLM	Process-level lifecycle
Instancing	Single instance only	Any number of instances







A few items in Figure 7-17 are worth elaborating on:

- UWP apps can produce normal executables, just like desktop apps. Wwahost.exe (%SystemRoot%\ System32\wwahost.exe) is used to host HTML/JavaScript-based UWP apps, as those produce a DLL, not an executable.
- The UWP is implemented by the Windows Runtime APIs, which are based on an enhanced version of COM. Language projections are provided for C++ (through proprietary language extensions known as C++/CX), .NET languages, and JavaScript. These projections make it relatively easy to access WinRT types, methods, properties, and events from developers' familiar environments.
- Several bridging technologies are available, which can transform other types of applications into UWP. See the MSDN documentation for more information on utilizing these technologies.
- The Windows Runtime is layered on top of the Windows subsystem DLLs, just like the .NET Framework. It has no kernel components and is not part of a different subsystem because it still leverages the same Win32 APIs that the system offers. However, some policies are implemented in the kernel, as well as the general support for AppContainers.

The Windows Runtime APIs are implemented in DLLs residing in the %SystemRoot%\System32 directory, with names in the form *Windows.Xxx.Yyy...*Dll, where the file name usually indicates the Windows Runtime API namespace implemented. For example, Windows.Globalization.Dll implements the classes residing in the Windows.Globalization namespace. (See the MSDN documentation for the complete WinRT API reference.)

## The AppContainer

We've seen the steps required to create processes back in Chapter 3; we've also seen some of the extra steps required to create UWP processes. The initiation of creation is performed by the DCOMLaunch service, because UWP packages support a set of protocols, one of which is the Launch protocol. The resulting process gets to run inside an AppContainer. Here are several characteristics of packaged processes running inside an AppContainer:

- The process token integrity level is set to Low, which automatically restricts access to many objects and limits access to certain APIs or functionality for the process, as discussed earlier in this chapter.
- UWP processes are always created inside a job (one job per UWP app). This job manages the UWP process and any background processes that execute on its behalf (through nested jobs). The jobs allow the Process State Manager (PSM) to suspend or resume the app or background processing in a single stroke.
- The token for UWP processes has an AppContainer SID, which represents a distinct identity based on the SHA-2 hash of the UWP package name. As you'll see, this SID is used by the system and other applications to explicitly allow access to files and other kernel objects. This SID is part of the APPLICATION PACKAGE AUTHORITY instead of the NT AUTHORITY you've mostly seen so far in this chapter. Thus, it begins with S-1-15-2 in its string format, corresponding to SECURITY\_ APP\_PACKAGE\_BASE\_RID (15) and SECURITY\_APP\_PACKAGE\_BASE\_RID (2). Because a SHA-2 hash is 32 bytes, there are a total of eight RIDs (recall that a RID is the size of a 4-byte ULONG) in the remainder of the SID.
- The token may contain a set of capabilities, each represented with a SID. These capabilities are declared in the application manifest and shown on the app's page in the store. Stored in the capability section of the manifest, they are converted to SID format using rules we'll see shortly, and belong to the same SID authority as in the previous bullet, but using the well-known SECURITY\_ CAPABILITY\_BASE\_RID (3) instead. Various components in the Windows Runtime, user-mode device-access classes, and kernel can look for capabilities to allow or deny certain operations.
- The token may only contain the following privileges: SeChangeNotifyPrivilege, SeIncrease-WorkingSetPrivilege, SeShutdownPrivilege, SeTimeZonePrivilege, and SeUndockPrivilege. These are the default set of privileges associated with standard user accounts. Additionally, the AppContainerPrivilegesEnabledExt function part of the ms-win-ntos-ksecurity API Set contract extension can be present on certain devices to further restrict which privileges are enabled by default.

- The token will contain up to four security attributes (see the section on attribute-based access control earlier in this chapter) that identify this token as being associated with a UWP packaged application. These attributes are added by the DcomLaunch service as indicated earlier, which is responsible for the activation of UWP applications. They are as follows:
  - WIN://PKG This identifies this token as belonging to a UWP packaged application. It contains an integer value with the application's origin as well as some flags. See Table 7-13 and Table 7-14 for these values.
  - WIN://SYSAPPID This contains the application identifiers (called *package monikers* or *string names*) as an array of Unicode string values.
  - WIN://PKGHOSTID This identifies the UWP package host ID for packages that have an explicit host through an integer value.
  - WIN://BGKD This is only used for background hosts (such as the generic background task host BackgroundTaskHost.exe) that can store packaged UWP services running as COM providers. The attribute's name stands for *background* and contains an integer value that stores its explicit host ID.

The TOKEN\_LOWBOX (0x4000) flag will be set in the token's Flags member, which can be queried with various Windows and kernel APIs (such as GetTokenInformation). This allows components to identity and operate differently under the presence of an AppContainer token.

**Note** A second type of AppContainer exists: a child AppContainer. This is used when a UWP AppContainer (or parent AppContainer) wishes to create its own nested AppContainer to further lock down the security of the application. Instead of eight RIDs, a child AppContainer has four additional RIDs (the first eight match the parents') to uniquely identify it.

Origin	Meaning
Unknown (0)	The package origin is unknown.
Unsigned (1)	The package is unsigned.
Inbox (2)	The package is associated with a built-in (inbox) Windows application.
Store (3)	The package is associated with a UWP application downloaded from the store. This origin is validated by checking if the DACL of the file associated with the main UWP application's executable contains a trust ACE.
Developer Unsigned (4)	The package is associated with an unsigned developer key.
Developer Signed (5)	The package is associated with a signed developer key.
Line-of-Business (6)	The package is associated with a side-loaded line-of-business (LOB) application.

TABLE 7-13 Pac	kage origins
----------------	--------------

Flag	Meaning
PSM_ACTIVATION_TOKEN_PACKAGED_APPLICATION (0x1)	This indicates that the AppContainer UWP ap- plication is stored in AppX packaged format. This is the default.
PSM_ACTIVATION_TOKEN_SHARED_ENTITY (0x2)	This indicates that this token is being used for multiple executables all part of the same AppX packaged UWP application.
PSM_ACTIVATION_TOKEN_FULL_TRUST (0x4)	This indicates that this AppContainer token is being used to host a Project Centennial (Windows Bridge for Desktop) converted Win32 application.
PSM_ACTIVATION_TOKEN_NATIVE_SERVICE (0x8)	This indicates that this AppContainer token is being used to host a packaged service cre- ated by the Service Control Manager (SCM)'s Resource Manager. See Chapter 9 in Part 2 for more information on services.
PSM_ACTIVATION_TOKEN_DEVELOPMENT_APP (0x10)	This indicates that this is an internal develop- ment application. Not used on retail systems.
BREAKAWAY_INHIBITED (0x20)	The package cannot create a process that is not itself packaged as well. This is set by using the PROC_THREAD_ATTRIBUTE_DESKTOP_ APP_POLICY process-creation attribute. (See Chapter 3 for more information.)

#### **EXPERIMENT: Viewing UWP process information**

There are several ways to look at UWP processes, some more obvious than others. Process Explorer can highlight processes that use the Windows Runtime in color (cyan by default). To see this in action, open Process Explorer, open the **Options** menu, and choose **Configure Colors**. Then make sure the **Immersive Processes** check box is selected.



*Immersive process* is the original term used to describe WinRT (now UWP) apps in Windows 8. (They were mostly full screen, and therefore "immersive.") This distinction is available by calling the IsImmersiveProcess API.

Run Calc.exe and switch to Process Explorer. You should see several processes highlighted in cyan, including Calculator.exe. Now minimize the Calculator app and notice that the cyan highlight has turned gray. This is because Calculator has been suspended. Restore Calculator's window, and it's back to cyan.

You should have similar experiences with other apps—for example, Cortana (SearchUI.exe). Click or tap the **Cortana** icon on the taskbar and then close it. You should see the gray to cyan and back to gray transition. Or, click or tap the **Start** button. ShellExperienceHost.exe highlights in a similar fashion.

The presence of some cyan-highlighted processes might surprise you, such as Explorer.exe, TaskMgr.Exe, and RuntimeBroker.exe. These are not really apps, but use Windows Runtime APIs, and so are classified as immersive. (The role of RuntimeBroker will be discussed shortly.)

Finally, make sure the Integrity column is visible in Process Explorer and sort by that column. You'll find processes such as Calculator.exe and SearchUI.exe with AppContainer integrity level. Notice that Explorer and TaskMgr are not there, clearly showing they are not UWP processes, and so live under different rules.

		1.1	9.14 Jan			18
Process	PID	CPU	Integrity	Private Bytes	Working Set	Description
Interrupts	n/a	0.74		0 K	0 K	Hardware Interrupt
Calculator.exe	11128		AppContainer	13,420 K	36,712 K	
Microsoft.Msn.Weather.exe	3040	Suspended	AppContainer	45,600 K	15,764 K	Weather
SearchUI.exe	3728	Suspended	AppContainer	43,508 K	102,564 K	Search and Cortan
ShellExperienceHost.exe	1872	Suspended	AppContainer	79,872 K	130,636 K	Windows Shell Exp
SkypeHost.exe	9624	Suspended	AppContainer	33,084 K	26,844 K	Microsoft Skype Pr
System Idle Process	0	92.57		0 K	4 K	
Twitter.Windows.exe	2084	Suspended	AppContainer	33,348 K	8,576 K	Twitter.Windows
Video.UI.exe	8772	Suspended	AppContainer	19,900 K	37,444 K	Video Application
🕑 firefox.exe	11856	0.31	Low	571,804 K	615,372 K	Firefox
- 🛄 ApntEx.exe	1060		Medium	1,844 K	5,960 K	Alps Pointing-devi
- Consist aug	0024	0.01	Madium	J CAA V	17 776 V	Also Deleting david

### **EXPERIMENT:** Viewing an AppContainer token

You can look at the properties of an AppContainer hosted process with several tools. In Process Explorer, the Security tab shows the capabilities associated with the token. Here's the Security tab for Calculator.exe:

Image TCP/	Perform		Performa	nce Graph Envi	Disk an	d Network Job	GPU Graph	Thread Strings
-		S-1-5-2 1	\CS35010 I-35378460 Logon Sess Protected:			912182-1001		
	Microsoft NT AUTH NT AUTH NT AUTH NT AUTH NT AUTH NT AUTH S-1-15-2	ICRITY IORITY IORITY IORITY IORITY IORITY IORITY IORITY -46676 -46676	INTERACT Local acco Local acco LogonSes This Organ 7348-373 7348-373	on@live.co ated Users count Auth IVE ount ount and n sionId_0_1 nization 9614953-2	m nember of 786264 270083639	Administra 12-1801644 12-1801644	Mandatory Mandatory AppContair	her
	Group SID	): n/a						
£	Privilege SeChang SeIncreas SeShutdo SeTimeZo SeUndoo	eNotify eWork ownPriv onePriv	ingSetPrivi ilege ilege		ult Enabled bled bled bled	i		
							P	ermissions

Notice two interesting pieces of information: the AppContainer SID, shown in the Flags column as AppContainer, and a single capability, right underneath the AppContainer SID. Except for the base RID (SECURITY\_APP\_PACKAGE\_BASE\_RID versus SECURITY\_CAPABILITY\_BASE\_RID), the remaining eight RIDs are identical, and both refer to the package name in SHA-2 format as discussed. This shows you that there will always be one implicit capability, the capability of being the package itself, which really means Calculator requires no capabilities at all. The upcoming capabilities section covers a much more complex example.

#### **EXPERIMENT: Viewing AppContainer token attributes**

You can obtain similar information on the command line by using the AccessChk Sysinternals tool while also adding a full list of all of the token's attributes. For example, running AccessChk with the -p -fl switches followed by the process ID for SearchUI.exe, which hosts Cortana, shows the following:

```
C:\ >accesschk -p -f 3728
Accesschk v6.10 - Reports effective permissions for securable objects
Copyright (C) 2006-2016 Mark Russinovich
Sysinternals - www.sysinternals.com
[7416] SearchUI.exe
```

```
RW DESKTOP-DD6KTPM\aione
  RW NT AUTHORITY\SYSTEM
  RW Package
\S-1-15-2-1861897761-1695161497-2927542615-642690995-327840285-2659745135-2630312742
  Token security:
  RW DESKTOP-DD6KTPM\aione
  RW NT AUTHORITY\SYSTEM
  RW DESKTOP-DD6KTPM\aione-S-1-5-5-0-459087
  RW Package
\$-1-15-2-1861897761-1695161497-2927542615-642690995-327840285-2659745135-2630312742
  R BUILTIN\Administrators
  Token contents:
   User:
      DESKTOP-DD6KTPM\aione
   AppContainer:
      Package
\$-1-15-2-1861897761-1695161497-2927542615-642690995-327840285-2659745135-2630312742
    Groups:
      Mandatory Label\Low Mandatory Level
                                                       INTEGRITY
      Everyone
                                                       MANDATORY
      NT AUTHORITY\Local account and member of Administrators group DENY
      Security Attributes:
      WIN://PKGHOSTID
         TOKEN_SECURITY_ATTRIBUTE_TYPE_UINT64
          [0] 1794402976530433
      WIN://SYSAPPID
         TOKEN_SECURITY_ATTRIBUTE_TYPE_STRING
          [0] Microsoft.Windows.Cortana_1.8.3.14986_neutral_neutral_cw5n1h2txyewy
          [1] CortanaUI
          [2] Microsoft.Windows.Cortana_cw5n1h2txyewy
      WIN://PKG
          TOKEN_SECURITY_ATTRIBUTE_TYPE_UINT64
          [0] 131073
      TSA://ProcUnique
          [TOKEN_SECURITY_ATTRIBUTE_NON_INHERITABLE]
          [TOKEN_SECURITY_ATTRIBUTE_COMPARE_IGNORE]
          TOKEN_SECURITY_ATTRIBUTE_TYPE_UINT64
          [0] 204
          [1] 24566825
```

First is the package host ID, converted to hex: 0x660000000001. Because all package host IDs begin with 0x66, this means Cortana is using the first available host identifier: 1. Next are the system application IDs, which contain three strings: the strong package moniker, the friendly application name, and the simplified package name. Finally, you have the package claim, which is 0x20001 in hex. Based on the Table 7-13 and Table 7-14 fields you saw, this indicates an origin of Inbox (2) and flags set to PSM\_ACTIVATION\_TOKEN\_PACKAGED\_APPLICATION, confirming that Cortana is part of an AppX package.

### AppContainer security environment

One of the biggest side-effects caused by the presence of an AppContainer SID and related flags is that the access check algorithm you saw in the "Access checks" section earlier in this chapter is modified to essentially ignore all regular user and group SIDs that the token may contain, essentially treating them as deny-only SIDs. This means that even though Calculator may be launched by a user John Doe belonging to the Users and Everyone groups, it will fail any access checks that grant access to John Doe's SID, the Users group SID, or the Everyone group SID. In fact, the only SIDs that are checked during the discretionary access check algorithm will be that of the AppContainer SID, followed by the capability access check algorithm, which will look at any capability SIDs part of the token.

Taking things even further than merely treating the discretionary SIDs as deny-only, AppContainer tokens effect one further critical security change to the access check algorithm: a NULL DACL, typically treated as an allow-anyone situation due to the lack of any information (recall that this is different from an empty DACL, which is a deny-everyone situation due to explicit allow rules), is ignored and treated as a deny situation. To make matters simple, the only types of securable objects that an AppContainer can access are those that explicitly have an allow ACE for its AppContainer SID or for one of its capabilities. Even unsecured (NULL DACL) objects are out of the game.

This situation causes compatibility problems. Without access to even the most basic file system, registry, and object manager resources, how can an application even function? Windows takes this into account by preparing a custom execution environment, or "jail" if you will, specifically for each AppContainer. These jails are as follows:

**Note** So far we've implied that each UWP packaged application corresponds to one AppContainer token. However, this doesn't necessarily imply that only a single executable file can be associated with an AppContainer. UWP packages can contain multiple executable files, which all belong to the same AppContainer. This allows them to share the same SID and capabilities and exchange data between each other, such as a micro-service back-end executable and a foreground front-end executable.

- The AppContainer SID's string representation is used to create a subdirectory in the object manager's namespace under \Sessions\x\AppContainerNamedObjects. This becomes the private directory of named kernel objects. This specific subdirectory object is then ACLed with the AppContainer SID associated with the AppContainer that has an allow-all access mask. This is in contrast to desktop apps, which all use the \Sessions\x\BaseNamedObjects subdirectory (within the same session x). We'll discuss the implications of that shortly, as well as the requirement for the token to now store handles.
- The token will contain a LowBox number, which is a unique identifier into an array of LowBox Number Entry structures that the kernel stores in the g\_SessionLowboxArray global variable. Each of these maps to a SEP\_LOWBOX\_NUMBER\_ENTRY structure that, most importantly, contains an atom table unique to this AppContainer, because the Windows Subsystem Kernel Mode Driver (Win32k.sys) does not allow AppContainers access to the global atom table.

- The file system contains a directory in %LOCALAPPDATA% called Packages. Inside it are the package monikers (the string version of the AppContainer SID—that is, the package name) of all the installed UWP applications. Each of these application directories contains application-specific directories, such as TempState, RoamingState, Settings, LocalCache, and others, which are all ACLed with the specific AppContainer SID corresponding to the application, set to an allow-all access mask.
- Within the Settings directory is a Settings.dat file, which is a registry hive file that is loaded as an application hive. (You will learn more about application hives in Chapter 9 in Part 2.) The hive acts as the local registry for the application, where WinRT APIs store the various persistent state of the application. Once again, the ACL on the registry keys explicitly grants allow-all access to the associated AppContainer SID.

These four jails allow AppContainers to securely, and locally, store their file system, registry, and atom table without requiring access to sensitive user and system areas on the system. That being said, what about the ability to access, at least in read-only mode, critical system files (such as Ntdll.dll and Kernel32.dll) or registry keys (such as the ones these libraries will need), or even named objects (such as the \RPC Control\DNSResolver ALPC port used for DNS lookups)? It would not make sense, on each UWP application or uninstallation, to re-ACL entire directories, registry keys, and object namespaces to add or remove various SIDs.

To solve this problem, the security subsystem understands a specific group SID called ALL APPLICATION PACKAGES, which automatically binds itself to any AppContainer token. Many critical system locations, such as %SystemRoot%\System32 and HKLM\Software\Microsoft\Windows\CurrentVersion, will have this SID as part of their DACL, typically with a read or read-and-execute access mask. Certain objects in the object manager namespace will have this as well, such as the DNSResolver ALPC port in the \RPC Control object manager directory. Other examples include certain COM objects, which grant the execute right. Although not officially documented, third-party developers, as they create non-UWP applications, can also allow interactions with UWP applications by also applying this SID to their own resources.


Unfortunately, because UWP applications can technically load almost any Win32 DLL as part of their WinRT needs (because WinRT is built on top of Win32, as you saw), and because it's hard to predict what an individual UWP application might need, many system resources have the ALL APPLICATION PACKAGES SID associated with their DACL as a precaution. This now means there is no way for a UWP developer, for example, to prevent DNS lookups from their application. This greater-than-needed access is also helpful for exploit writers, which could leverage it to escape from the AppContainer sandbox. Newer versions of Windows 10, starting with version 1607 (Anniversary Update), contain an additional element of security to combat this risk: Restricted AppContainers.

By using the PROC\_THREAD\_ATTRIBUTE\_ALL\_APPLICATION\_PACKAGES\_POLICY process attribute and setting it to PROCESS\_CREATION\_ALL\_APPLICATION\_PACKAGES\_OPT\_OUT during process creation (see Chapter 3 for more information on process attributes), the token will not be associated with any ACEs that specify the ALL APPLICATION PACKAGES SID, cutting off access to many system resources that would otherwise be accessible. Such tokens can be identified by the presence of a fourth token attribute named WIN://NOALLAPPPKG with an integer value set to 1. Of course, this takes us back to the same problem: How would such an application even be able to load Ntdll.dll, which is key to any process initialization? Windows 10 version 1607 introduces a new group, called ALL RESTRICTED APPLICATION PACKAGES, which takes care of this problem. For example, the System32 directory now also contains this SID, also set to allow read and execute permissions, because loading DLLs in this directory is key even to the most sandboxed process. However, the DNSResolver ALPC port does not, so such an AppContainer would lose access to DNS.

#### **EXPERIMENT: Viewing AppContainer security attributes**

In this experiment, we'll look at the security attributes of some of the directories mentioned in the previous section.

- **1.** Make sure Calculator is running.
- 2. Open WinObj elevated from Sysinternals and navigate to the object directory corresponding to Calculator's AppContainer SID. (You saw it in a previous experiment.)



3. Right-click the directory, select Properties, and click the Security tab. You should see something like the following screenshot. Calculator's AppContainer SID has permission to list, add object, and add subdirectory (among others scrolled out of view), which simply means Calculator can create kernel objects under this directory.

Everyone		
Account Unknown(S-1-15-2-466767348-3	739614953-7700	136392-1
CREATOR OWNER		
RESTRICTED		
SYSTEM		
Pavel Yosfovich (zodiacon@ive.com)		~
	Add	Bemove
emissions for Account nknown(S-1-15-2-466767348-3739614953-2	Allow	Deny
List		
Add Object		E1 -
Add Subdirectory	$\square$	
Read		
Write		
TTING.		
List Add Object Add Subdirectory Read	NNN	

4. Open Calculator's local folder by navigating to %LOCALAPPDATA%\Packages\ Microsoft.WindowsCalculator\_8wekyb3d8bbwe. Then right-click the Settings subdirectory, select Properties, and click the Security tab. You should see Calculator's AppContainer SID having full permissions for the folder:

eneral Sharing Security Previous Ve	rsions Custom	iiZ0
Object name: C:\Users\ADMIN,AppD	ata\Local\Pack	cages Microsof
Group or user names:		
Account Unknown(S-1-15-2-4667673	48-3739614953-	2700536392-1
SYSTEM		
2 Pavel Yosifovich (zodiacon@live co	m)	
Administrators (ZODIAC)Administrate	ors)	
To change permissions, click Edit		Edt.
Permissions for Account		Eost_
Lemissions for Account Unknown(S-1-15-2-466767348-3739	Allow	Deny
Full control	~	^
Modéy	~	
Read & execute	****	
List folder contents	~	
Read	~	
Write	~	~
For special permissions or advanced set click Advanced	tings,	Adyanced

5. In Explorer, open the %SystemRoot% directory (for example, C:\Windows), right-click the System32 directory, select Properties, and click the Security tab. You should see the read and execute permissions for all application packages and all restricted application packages (if using Windows 10 version 1607 or later):

	Security Previous Vers				
Object name:	C:\Windows\System32				
Group or user na	mes				
ALL APPLIC	ATION PACKAGES				
ALL RESTR	ICTED APP PACKAGES				
E CREATOR	OWNER				
RR SYSTEM					
<			,		
To change permissions, click Edit.					
Permissions for A PACKAGES	ALL APPLICATION	Allow	Deny		
Full control					
Modify					
Read & execu	Ale .	~			
List folder cont	tents	~			
Read		~			
Write					

As an alternative, you can use the AccessChk Sysinternals command-line tool to view the same information.

### **EXPERIMENT:** Viewing the AppContainer atom table

An atom table is a hash table of integers to strings that's used by the windowing system for various identification purposes, such as Window Class registration (RegisterClassEx) and custom Windows messages. The AppContainer private atom table can be viewed with the kernel debugger:

- **1.** Run Calculator, open WinDbg, and start local kernel debugging.
- 2. Find the Calculator process:

```
lkd> !process 0 1 calculator.exe
PROCESS ffff828cc9ed1080
SessionId: 1 Cid: 4bd8 Peb: d040bbc000 ParentCid: 03a4
DeepFreeze
DirBase: 5fccaa000 ObjectTable: ffff950ad9fa2800 HandleCount:
<Data Not Accessible>
Image: Calculator.exe
VadRoot ffff828cd2c9b6a0 Vads 168 Clone 0 Private 2938. Modified 3332.
Locked 0.
DeviceMap ffff950aad2cd2f0
Token ffff950adb313060
...
```

3. Use the token value with the following expressions:

```
lkd> r? @$t1 = @$t0->NumberOfBuckets
lkd> r? @$t0 = (nt!_RTL_ATOM_TABLE*)((nt!_token*)0xffff950adb313060)-
>LowboxNumberEntry->AtomTable
lkd> .for (r @$t3 = 0; @$t3 < @$t1; r @$t3 = @$t3 + 1) { ?? (wchar_t*)@$t0-</pre>
```

```
>Buckets[@$t3]->Name }
wchar t * 0xffff950a'ac39b78a
 "Protocols"
wchar_t * 0xffff950a'ac17b7aa
 "Topics"
wchar_t * 0xffff950a'b2fd282a
 "TaskbarDPI Deskband"
wchar_t * 0xffff950a'b3e2b47a
 "Static"
wchar_t * 0xffff950a'b3c9458a
 "SvsTreeView32"
wchar_t * 0xffff950a'ac34143a
 "UxSubclassInfo"
wchar t * 0xffff950a'ac5520fa
 "StdShowItem"
wchar t * 0xffff950a'abc6762a
 "SysSetRedraw"
wchar_t * 0xffff950a'b4a5340a
 "UIA_WindowVisibilityOverridden"
wchar_t * 0xffff950a'ab2c536a
"True"
. . .
wchar_t * 0xffff950a'b492c3ea
"tooltips class"
wchar_t * 0xffff950a'ac23f46a
 "Save"
wchar_t * 0xffff950a'ac29568a
 "MSDraw"
wchar_t * 0xffff950a'ac54f32a
 "StdNewDocument"
wchar t * 0xffff950a'b546127a
 "{FB2E3E59-B442-4B5B-9128-2319BF8DE3B0}"
wchar_t * 0xffff950a'ac2e6f4a
 "Status"
wchar_t * 0xffff950a'ad9426da
 "ThemePropScrollBarCtl"
wchar_t * 0xffff950a'b3edf5ba
"Edit"
wchar_t * 0xffff950a'ab02e32a
 "Svstem"
wchar_t * 0xffff950a'b3e6c53a
 "MDIClient"
wchar_t * 0xffff950a'ac17a6ca
 "StdDocumentName"
wchar t * 0xffff950a'ac6cbeea
 "StdExit"
wchar_t * 0xffff950a'b033c70a
 "{C56C5799-4BB3-7FAE-7FAD-4DB2F6A53EFF}"
wchar_t * 0xffff950a'ab0360fa
 "MicrosoftTabletPenServiceProperty"
wchar_t * 0xffff950a'ac2f8fea
 "OLEsystem"
```

### AppContainer capabilities

As you've just seen, UWP applications have very restricted access rights. So how, for example, is the Microsoft Edge application able to parse the local file system and open PDF files in the user's Documents folder? Similarly, how can the Music application play MP3 files from the Music directory? Whether done directly through kernel access checks or by brokers (which you'll see in the next section), the key lies in capability SIDs. Let's see where these come from, how they are created, and when they are used.

First, UWP developers begin by creating an application manifest that specifies many details of their application, such as the package name, logo, resources, supported devices, and more. One of the key elements for capability management is the list of capabilities in the manifest. For example, let's take a look at Cortana's application manifest, located in %SystemRoot%\SystemApps\Microsoft.Windows. Cortana\_cw5n1h2txywey\AppxManifest.xml:

```
<Capabilities>
```

```
<wincap:Capability Name="packageContents"/>
<!-- Needed for resolving MRT strings -->
<wincap:Capability Name="cortanaSettings"/>
<wincap:Capability Name="cloudStore"/>
<wincap:Capability Name="visualElementsSystem"/>
<wincap:Capability Name="perceptionSystem"/>
<Capability Name="internetClient"/>
<Capability Name="internetClientServer"/>
<Capability Name="privateNetworkClientServer"/>
<uap:Capability Name="enterpriseAuthentication"/>
<uap:Capability Name="musicLibrary"/>
<uap:Capability Name="phoneCall"/>
<uap:Capability Name="picturesLibrary"/>
<uap:Capability Name="sharedUserCertificates"/>
<rescap:Capability Name="locationHistory"/>
<rescap:Capability Name="userDataSystem"/>
<rescap:Capability Name="contactsSystem"/>
<rescap:Capability Name="phoneCallHistorySystem"/>
<rescap:Capability Name="appointmentsSystem"/>
<rescap:Capability Name="chatSystem"/>
<rescap:Capability Name="smsSend"/>
<rescap:Capability Name="emailSystem"/>
<rescap:Capability Name="packageQuery"/>
<rescap:Capability Name="slapiQueryLicenseValue"/>
<rescap:Capability Name="secondaryAuthenticationFactor"/>
<DeviceCapability Name="microphone"/>
<DeviceCapability Name="location"/>
<DeviceCapability Name="wiFiControl"/>
```

</Capabilities>

You'll see many types of entries in this list. For example, the Capability entries contain the wellknown SIDs associated with the original capability set that was implemented in Windows 8. These begin with SECURITY\_CAPABILITY\_—for example, SECURITY\_CAPABILITY\_INTERNET\_CLIENT, which is part of the capability RID under the APPLICATION PACKAGE AUTHORITY. This gives us a SID of S-1-15-3-1 in string format. Other entries are prefixed with uap, rescap, and wincap. One of these (rescap) refers to restricted capabilities. These are capabilities that require special onboarding from Microsoft and custom approvals before being allowed on the store. In Cortana's case, these include capabilities such as accessing SMS text messages, emails, contacts, location, and user data. Windows capabilities, on the other hand, refer to capabilities that are reserved for Windows and system applications. No store application can use these. Finally, UAP capabilities refer to standard capabilities that anyone can request on the store. (Recall that UAP is the older name for UWP.)

Unlike the first set of capabilities, which map to hard-coded RIDs, these capabilities are implemented in a different fashion. This ensures a list of well-known RIDs doesn't have to be constantly maintained. Instead, with this mode, capabilities can be fully custom and updated on the fly. To do this, they simply take the capability string, convert it to full upper-case format, and take a SHA-2 hash of the resulting string, much like AppContainer package SIDs are the SHA-2 hash of the package moniker. Again, since SHA-2 hashes are 32 bytes, this results in 8 RIDs for each capability, following the wellknown SECURITY\_CAPABILITY\_BASE\_RID (3).

Finally, you'll notice a few DeviceCapability entries. These refer to device classes that the UWP application will need to access, and can be identified either through well-known strings such as the ones you see above or directly by a GUID that identifies the device class. Rather than using one of the two methods of SID creation already described, this one uses yet a third! For these types of capabilities, the GUID is converted into a binary format and then mapped out into four RIDs (because a GUID is 16 bytes). On the other hand, if a well-known name was specified instead, it must first be converted to a GUID. This is done by looking at the HKLM\Software\Microsoft\Windows\CurrentVersion\DeviceAccess\CapabilityMappings registry key, which contains a list of registry keys associated with device capabilities and a list of GUIDs that map to these capabilities. The GUIDs are then converted to a SID as you've just seen.

**Note** For an up-to-date list of supported capabilities, see *https://msdn.microsoft.com/en-us/windows/uwp/packaging/app-capability-declarations*.

As part of encoding all of these capabilities into the token, two additional rules are applied:

- As you may have seen in the earlier experiment, each AppContainer token contains its own package SID encoded as a capability. This can be used by the capability system to specifically lock down access to a particular app through a common security check instead of obtaining and validating the package SID separately.
- Each capability is re-encoded as a group SID through the use of the SECURITY\_CAPABILITY\_APP\_ RID (1024) RID as an additional sub-authority preceding the regular eight-capability hash RIDs.

After the capabilities are encoded into the token, various components of the system will read them to determine whether an operation being performed by an AppContainer should be permitted. You'll note most of the APIs are undocumented, as communication and interoperability with UWP applications is not officially supported and best left to broker services, inbox drivers, or kernel components. For example, the kernel and drivers can use the RtlCapabilityCheck API to authenticate access to certain hardware interfaces or APIs.

As an example, the Power Manager checks for the ID\_CAP\_SCREENOFF capability before allowing a request to shut off the screen from an AppContainer. The Bluetooth port driver checks for the bluetoothDiagnostics capability, while the application identity driver checks for Enterprise Data Protection (EDP) support through the enterpriseDataPolicy capability. In user mode, the documented CheckTokenCapability API can be used, although it must know the capability SID instead of providing the name (the undocumented RtlDeriveCapabilitySidFromName can generate this, however). Another option is the undocumented CapabilityCheck API, which does accept a string.

Finally, many RPC services leverage the RpcClientCapabilityCheck API, which is a helper function that takes care of retrieving the token and requires only the capability string. This function is very commonly used by many of the WinRT-enlightened services and brokers, which utilize RPC to communicate with UWP client applications.

#### **EXPERIMENT: Viewing AppContainer capabilities**

To clearly demonstrate all these various capability combinations and their population in the token, let's look at the capabilities for a complex app such as Cortana. You've already seen its manifest, so you can use that output to compare with the UI. First, looking at the Security tab for SearchUI.exe shows the following (sorted by the Flags column):

Image TCP	Perform /IP		Performa	nce Graph Enviro	Disk and I	Network Job	GPU Graph	Thread
-	User:	5-1-5-2 1	\CS35010 I-353784609 Logon Sessio Protected:		2-29679121	32-1001		
	APPLICA APPLICA APPLICA APPLICA APPLICA APPLICA S-1-15-3 S-1-15-3 S-1-15-3 S-1-15-3 S-1-15-3 S-1-15-3	TION P, TION P, TION P, TION P, TION P, TION P, TION P, -1024- -1024- -1024- -1024- -1024- -1024- -1024- -1024-	97761-1695 ACKAGE AUT ACKAGE AUT ACKAGE AUT ACKAGE AUT ACKAGE AUT ACKAGE AUT ACKAGE AUT ACKAGE AUT 210835722- 1962849891 2210865643 2257373614 2442212349	THORITY\Sc THORITY\Yo THORITY\Yo THORITY\Yo THORITY\Yo THORITY\Yo THORITY\Yo -11452189 850430189 -68848726 -35159871 -17179146	oftware and our home or our internet our internet our music lib our pictures our Window 9-39776405 -152938482 2-35714178 49-1329579 93-1151184	hardware c., work net., connection, rary library s credentials 88-13431., 5-139260., 121-36286., 1022-3761., 1220-2820.,	Capability Capability Capability Capability Capability Capability Capability Capability Capability Capability Capability Capability	ner
đ	Group SIE Privilege SeChang SeIncreas SeShutdo SeTimeZo SeUndoc	eNotify seWork ownPriv	ingSetPrivile ilege ilege	Flags Default ge Disablec Disablec Disablec	i i			
								Permissions

Clearly, Cortana has obtained many capabilities—all the ones in its manifest. Some are those that were originally in Windows 8 and are known to functions like IsWellKnownSid, for which Process Explorer shows a friendly name. Other capabilities are just shown using their SID, as they represent either hashes or GUIDs, as discussed.

To get the details of the package from which the UWP process was created, you can use the UWPList tool provided with the downloadable resources for this book. It can show all immersive processes on the system or a single process based on its ID:

```
C:\WindowsInternals>UwpList.exe 3728
List UWP Processes - version 1.1 (C)2016 by Pavel Yosifovich
Building capabilities map... done.
Process ID: 3728
_____
Image name: C:\Windows\SystemApps\Microsoft.Windows.Cortana_cw5n1h2txyewy\SearchUI.exe
Package name: Microsoft.Windows.Cortana
Publisher: CN=Microsoft Windows, O=Microsoft Corporation, L=Redmond, S=Washington, C=US
Published ID: cw5n1h2txyewy
Architecture: Neutral
Version: 1.7.0.14393
AppContainer SID: S-1-15-2-1861897761-1695161497-2927542615-642690995-327840285-
2659745135-2630312742
Lowbox Number: 3
Capabilities: 32
cortanaSettings (S-1-15-3-1024-1216833578-114521899-3977640588-1343180512-
2505059295-473916851-3379430393-3088591068) (ENABLED)
visualElementsSystem (S-1-15-3-1024-3299255270-1847605585-2201808924-710406709-
3613095291-873286183-3101090833-2655911836) (ENABLED)
perceptionSystem (S-1-15-3-1024-34359262-2669769421-2130994847-3068338639-
3284271446-2009814230-2411358368-814686995) (ENABLED)
internetClient (S-1-15-3-1) (ENABLED)
internetClientServer (S-1-15-3-2) (ENABLED)
privateNetworkClientServer (S-1-15-3-3) (ENABLED)
enterpriseAuthentication (S-1-15-3-8) (ENABLED)
musicLibrary (S-1-15-3-6) (ENABLED)
phoneCall (S-1-15-3-1024-383293015-3350740429-1839969850-1819881064-1569454686-
4198502490-78857879-1413643331) (ENABLED)
picturesLibrary (S-1-15-3-4) (ENABLED)
sharedUserCertificates (S-1-15-3-9) (ENABLED)
locationHistory (S-1-15-3-1024-3029335854-3332959268-2610968494-1944663922-
1108717379-267808753-1292335239-2860040626) (ENABLED)
userDataSystem (S-1-15-3-1024-3324773698-3647103388-1207114580-2173246572-
4287945184-2279574858-157813651-603457015) (ENABLED)
contactsSystem (S-1-15-3-1024-2897291008-3029319760-3330334796-465641623-3782203132-
742823505-3649274736-3650177846) (ENABLED)
phoneCallHistorySystem (S-1-15-3-1024-2442212369-1516598453-2330995131-3469896071-
605735848-2536580394-3691267241-2105387825) (ENABLED)
appointmentsSystem (S-1-15-3-1024-2643354558-482754284-283940418-2629559125-
2595130947-547758827-818480453-1102480765) (ENABLED)
chatSystem (S-1-15-3-1024-2210865643-3515987149-1329579022-3761842879-3142652231-
371911945-4180581417-4284864962) (ENABLED)
smsSend (S-1-15-3-1024-128185722-850430189-1529384825-139260854-329499951-
1660931883-3499805589-3019957964) (ENABLED)
emailSystem (S-1-15-3-1024-2357373614-1717914693-1151184220-2820539834-3900626439-
4045196508-2174624583-3459390060) (ENABLED)
```

packageQuery (S-1-15-3-1024-1962849891-688487262-3571417821-3628679630-802580238-1922556387-206211640-3335523193) (ENABLED) slapiQueryLicenseValue (S-1-15-3-1024-3578703928-3742718786-7859573-1930844942-2949799617-2910175080-1780299064-4145191454) (ENABLED)  $\mathtt{S-1-15-3-1861897761-1695161497-2927542615-642690995-327840285-2659745135-2630312742}$ (ENABLED) S-1-15-3-787448254-1207972858-3558633622-1059886964 (ENABLED) S-1-15-3-3215430884-1339816292-89257616-1145831019 (ENABLED) S-1-15-3-3071617654-1314403908-1117750160-3581451107 (ENABLED) S-1-15-3-593192589-1214558892-284007604-3553228420 (ENABLED) S-1-15-3-3870101518-1154309966-1696731070-4111764952 (ENABLED) S-1-15-3-2105443330-1210154068-4021178019-2481794518 (ENABLED) S-1-15-3-2345035983-1170044712-735049875-2883010875 (ENABLED) S-1-15-3-3633849274-1266774400-1199443125-2736873758 (ENABLED) S-1-15-3-2569730672-1095266119-53537203-1209375796 (ENABLED) S-1-15-3-2452736844-1257488215-2818397580-3305426111 (ENABLED)

The output shows the package full name, executable directory, AppContainer SID, publisher information, version, and list of capabilities. Also shown is the LowBox number, which is just a local index of the app.

Lastly, you can inspect these properties in the kernel debugger with the !token command.

Some UWP apps are called *trusted*, and although they use the Windows Runtime platform like other UWP apps, they do not run inside an AppContainer, and have an integrity level higher than Low. The canonical example is the System Settings app (%SystemRoot%\ImmersiveControlPanel\ SystemSettings.exe); this seems reasonable, as the Settings app must be able to make changes to the system that would be impossible to do from an AppContainer-hosted process. If you look at its token, you will see the same three attributes—PKG, SYSAPPID, and PKGHOSTID—which confirm that it's still a packaged application, even without the AppContainer token present.

#### AppContainer and object namespace

Desktop applications can easily share kernel objects by name. For example, suppose process A creates an event object by calling CreateEvent(Ex) with the name MyEvent. It gets back a handle it can later use to manipulate the event. Process B running in the same session can call CreateEvent(Ex) or OpenEvent with the same name, MyEvent, and (assuming it has appropriate permissions, which is usually the case if running under the same session) get back another handle to the same underlying event object. Now if process A calls SetEvent on the event object while process B was blocked in a call to WaitForSingleObject on its event handle, process B's waiting thread would be released because it's the same event object. This sharing works because named objects are created in the object manager directory \Sessions\x\BaseNamedObjects, as shown in Figure 7-18 with the WinObj Sysinternals tool.

Furthermore, desktop apps can share objects between sessions by using a name prefixed with Global\. This creates the object in the session 0 object directory located in \BaseNamedObjects (refer to Figure 7-18).




FIGURE 7-18 Object manager directory for named objects.

AppContainer-based processes have their root object namespace under \Sessions\x\AppContainer NamedObjects\<AppContainerSID>. Since every AppContainer has a different AppContainer SID, there is no way two UWP apps can share kernel objects. The ability to create a named kernel object in the session 0 object namespace is not allowed for AppContainer processes. Figure 7-19 shows the object manager's directory for the Windows UWP Calculator app.

UWP apps that want to share data can do so using well-defined contracts, managed by the Windows Runtime. (See the MSDN documentation for more information.)

Sharing kernel objects between desktop apps and UWP apps is possible, and often done by broker services. For example, when requesting access to a file in the Documents folder (and getting the right capability validated) from the file picker broker, the UWP app will receive a file handle that it can use for reads and writes directly, without the cost of marshalling requests back and forth. This is achieved by having the broker duplicate the file handle it obtained directly in the handle table of the UWP application. (More information on handle duplication appears in Chapter 8 in Part 2.) To simplify things even further, the ALPC subsystem (also described in Chapter 8) allows the automatic transfer of handles in this way through ALPC handle attributes. and the Remote Procedure Call (RPC) services that use ALPC as their underlying protocol can use this functionality as part of their interfaces. Marshallable handles in the IDL file will automatically be transferred in this way through the ALPC subsystem.

<u>Yiew</u> <u>Help</u>			
	Name /	Туре	SymLink
- Driver	CoreUI]-PID(11128)-TID(13008) 4567ada3-1560-4691-aab0-5f212242	ALPC Port	
> - FileSystem	CoreUI]-PID(11128)-TID(13008) 57622c35-efae-4ac6-a0fc-a2f288e76		
GLOBAL??	1 AnimationsComplete	Event	
KernelObjects	App CE 00002b78	Event	
- KnownDils	App QS 00002b78	Semaphore	
KnownDils32	ApplicationService:2b78Microsoft.WindowsCalculator_8wekyb3d8b	Section	
- INLS	BuildTreeServiceDrained	Event	
Ubjectivpes	ComTaskPool:11128	Semaphore	
ALC CONTO	DeferredAnimationOperationsComplete	Event	
accurry	FontDownloadsidle	Event	
- Jessions	Global	SymbolicLink	\BaseNamedObjects
1 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2	HasAnimations	Event	(beschanned objects
	HasBuildTreeWorks	Event	
	1 HasDeferredAnimationOperations	Event	
	HWNDInterface:60ca8	Section	
	1 ImageDecodingIdle	Event	
	1. KeyboardInputReceived	Event	
	Local	SymbolicLink	\Sessions\1\AppContai
	PageNavigationComplete	Event	(sessions) i supposinai
> - S-1-15-2-2246530975-808720366-1776470054-2.	PopupMenuCommandInvoked	Event	
>	RootVisualReset	Event	
> - S-1-15-2-2967553933-3217682302-2494645345-	Session	SymbolicLink	\Sessions\1\AppConta
> - 5-1-15-2-350187224-1905355452-1037786396-3	SessionImmersiveColorMutex	Mutant	(acasionati addresina
>	SessionImmersiveColorPreference	Section	
> 1-10-2-400/0/348-3/39014903-2/00830392-1	SM0:11128:120:WilError_01	Mutant	
AFC CONTON	SM0:11128:120:WilError_01_p0	Semaphore	
	SM0:11128:120:WilError_01_p0h	Semaphore	
- DosDevices	- super restriction of point	Semoprore	
BNOLINKS			
> Windows			
> Windows			

FIGURE 7-19 Object manager directory for Calculator.

Outside of official broker RPC services, a desktop app can create a named (or even unnamed) object normally, and then use the DuplicateHandle function to inject a handle to the same object into the UWP process manually. This works because desktop apps typically run with medium integrity level and there's nothing preventing them from duplicating handles into UWP processes—only the other way around.

**Note** Communication between a desktop app and a UWP is not usually required because a store app cannot have a desktop app companion, and cannot rely on such an app to exist on the device. The capability to inject handles into a UWP app may be needed in specialized cases such as using the desktop bridge (Centennial) to convert a desktop app to a UWP app and communicate with another desktop app that is known to exist.

### **AppContainer handles**

In a typical Win32 application, the presence of the session-local and global BaseNamedObjects directory is guaranteed by the Windows subsystem, as it creates this on boot and session creation. Unfortunately, the AppContainerBaseNamedObjects directory is actually created by the launch application itself. In the case of UWP activation, this is the trusted DComLaunch service, but recall that not all AppContainers are necessarily tied to UWP. They can also be manually created through the right process-creation attributes. (See Chapter 3 for more information on which ones to use.) In this case, it's possible for an untrusted application to have created the object directory (and required symbolic links within it), which would result

in the ability for this application to close the handles from underneath the AppContainer application. Even without malicious intent, the original launching application might exit, cleaning up its handles and destroying the AppContainer-specific object directory. To avoid this situation, AppContainer tokens have the ability to store an array of handles that are guaranteed to exist throughout the lifetime of any application using the token. These handles are initially passed in when the AppContainer token is being created (through NtCreateLowBoxToken) and are duplicated as kernel handles.

Similar to the per-AppContainer atom table, a special SEP\_CACHED\_HANDLES\_ENTRY structure is used, this time based on a hash table that's stored in the logon session structure for this user. (See the "Logon" section later in this chapter for more information on logon sessions.) This structure contains an array of kernel handles that have been duplicated during the creation of the AppContainer token. They will be closed either when this token is destroyed (because the application is exiting) or when the user logs off (which will result in tearing down the logon session).

### **EXPERIMENT:** Viewing token stored handles

To view token stored handles, follow these steps:

- **1.** Run Calculator and launch local kernel debugging.
- 2. Search for the calculator process:

```
lkd> !process 0 1 calculator.exe
PROCESS ffff828cc9ed1080
    SessionId: 1 Cid: 4bd8 Peb: d040bbc000 ParentCid: 03a4
DeepFreeze
   DirBase: 5fccaa000 ObjectTable: ffff950ad9fa2800 HandleCount:
<Data Not Accessible>
    Image: Calculator.exe
   VadRoot ffff828cd2c9b6a0 Vads 168 Clone 0 Private 2938. Modified 3332.
Locked 0.
    DeviceMap ffff950aad2cd2f0
   Token
                                      ffff950adb313060
                                      1 Day 08:01:47.018
    ElapsedTime
    UserTime
                                     00:00:00.015
    KernelTime
                                      00:00:00.031
    QuotaPoolUsage[PagedPool]
                                     465880
    QuotaPoolUsage[NonPagedPool]
                                      23288
    Working Set Sizes (now, min, max) (7434, 50, 345) (29736KB, 200KB, 1380KB)
    PeakWorkingSetSize
                                     11097
    VirtualSize
                                      303 Mb
    PeakVirtualSize
                                      314 Mb
    PageFaultCount
                                      21281
    MemoryPriority
                                      BACKGROUND
    BasePriority
                                      8
    CommitCharge
                                      4925
    Job
                                      ffff828cd4914060
```

Dump the token using the dt command. (Remember to mask the lower 3 or 4 bits if they are not zero.)
 1kd> dt nt!\_token ffff950adb313060
 202000 Taker Sauras

```
+0x000 TokenSource : _TOKEN_SOURCE
+0x010 TokenId : _LUID
  +0x018 AuthenticationId : _LUID
  +0x020 ParentTokenId : _LUID
  . . .
  +0x0c8 TokenFlags : 0x4a00
  +0x0cc TokenInUse : 0x1 ''
  +0x0d0 IntegrityLevelIndex : 1
  +0x0d4 MandatoryPolicy : 1
  +0x0d8 LogonSession : 0xfff950a'b4bb35c0 _SEP_LOGON_SESSION_REFERENCES
  +0x0e0 OriginatingLogonSession : _LUID
  +0x0e8 SidHash : _SID_AND_ATTRIBUTES_HASH
  +0x1f8 RestrictedSidHash : _SID_AND_ATTRIBUTES_HASH
  +0x308 pSecurityAttributes : 0xfff950a'e4ff57f0 _AUTHZBASEP_SECURITY_
ATTRIBUTES_INFORMATION
                   : 0xffff950a'e00ed6d0 Void
  +0x310 Package
  +0x318 Capabilities : 0xffff950a'e8e8fbc0 _SID_AND_ATTRIBUTES
  +0x320 CapabilityCount : 1
  +0x328 CapabilitiesHash : _SID_AND_ATTRIBUTES_HASH
  +0x438 LowboxNumberEntry : 0xffff950a'b3fd55d0 _SEP_LOWBOX_NUMBER_ENTRY
  +0x440 LowboxHandlesEntry : 0xffff950a'e6ff91d0 _SEP_LOWBOX_HANDLES_ENTRY
  +0x448 pClaimAttributes : (null)
   . . .
```

4. Dump the LowboxHandlesEntry member:

```
1kd> dt nt!_sep_lowbox_handles_entry 0xffff950a'e6ff91d0
+0x000 HashEntry : _RTL_DYNAMIC_HASH_TABLE_ENTRY
+0x018 ReferenceCount : 0n10
+0x020 PackageSid : 0xffff950a'e6ff9208 Void
+0x028 HandleCount : 6
+0x030 Handles : 0xffff950a'e91d8490 -> 0xffffffff*800023cc Void
```

5. There are six handles. Let's dump their values:

lkd> dq 0xffff950ae91d8490 L6
ffff950a'e91d8490 fffffff'800023cc ffffffff'80001e80
ffff950a'e91d84a0 fffffff'80004214 ffffffff'8000425c
ffff950a'e91d84b0 fffffff'800028c8 ffffffff'80001834

6. You can see that these handles are kernel handles—that is, handle values starting with 0xffffffff (64 bit). Now you can use the !handle command to look at individual handles. Here are two examples from the six handles above:

```
lkd> !handle ffffffff'80001e80
PROCESS ffff828cd71b3600
SessionId: 1 Cid: 27c4 Peb: 3fdfb2f000 ParentCid: 2324
```

```
DirBase: 80bb85000 ObjectTable: ffff950addabf7c0 HandleCount:
<Data Not Accessible>
   Image: windbg.exe
Kernel handle Error reading handle count.
80001e80: Object: ffff950ada206ea0 GrantedAccess: 0000000f (Protected)
(Inherit) (Audit) Entry: ffff950ab5406a00
Object: ffff950ada206ea0 Type: (ffff828cb66b33b0) Directory
   ObjectHeader: ffff950ada206e70 (new version)
       HandleCount: 1 PointerCount: 32770
       Directory Object: ffff950ad9a62950 Name: RPC Control
       Hash Address
                             Туре
                                                       Name
        ____ ____
                              _ _ _ _
        23 ffff828cb6ce6950 ALPC Port
OLE376512B99BCCA5DE4208534E7732
lkd> !handle ffffffff'800028c8
PROCESS ffff828cd71b3600
   SessionId: 1 Cid: 27c4 Peb: 3fdfb2f000 ParentCid: 2324
   DirBase: 80bb85000 ObjectTable: ffff950addabf7c0 HandleCount: <Data
Not Accessible>
   Image: windbg.exe
Kernel handle Error reading handle count.
800028c8: Object: ffff950ae7a8fa70 GrantedAccess: 000f0001 (Audit) Entry:
ffff950acc426320
Object: ffff950ae7a8fa70 Type: (ffff828cb66296f0) SymbolicLink
   ObjectHeader: ffff950ae7a8fa40 (new version)
       HandleCount: 1 PointerCount: 32769
       Directory Object: ffff950ad9a62950 Name: Session
        Flags: 00000000 ( Local )
       Target String is '\Sessions\1\AppContainerNamedObjects
\S-1-15-2-466767348-3739614953-2700836392-1801644223-4227750657
-1087833535-2488631167'
```

Finally, because the ability to restrict named objects to a particular object directory namespace is a valuable security tool for sandboxing named object access, the upcoming (at the time of this writing) Windows 10 Creators Update includes an additional token capability called *BNO isolation* (where *BNO* refers to BaseNamedObjects). Using the same SEP\_CACHE\_HANDLES\_ENTRY structure, a new field, BnoIsolationHandlesEntry, is added to the TOKEN structure, with the type set to SepCachedHandlesEntryBnoIsolation instead of SepCachedHandlesEntryLowbox. To use this feature, a special process attribute must be used (see Chapter 3 for more information), which contains an isolation prefix and a list of handles. At this point, the same LowBox mechanism is used, but instead of an AppContainer SID object directory, a directory with the prefix indicated in the attribute is used.

### Brokers

Because AppContainer processes have almost no permissions except for those implicitly granted with capabilities, some common operations cannot be performed directly by the AppContainer and require help. (There are no capabilities for these, as these are too low level to be visible to users in the store, and difficult to manage.) Some examples include selecting files using the common File Open dialog box or printing with a Print dialog box. For these and other similar operations, Windows provides helper processes, called *brokers*, managed by the system broker process, RuntimeBroker.exe.

An AppContainer process that requires any of these services communicates with the Runtime Broker through a secure ALPC channel and Runtime Broker initiates the creation of the requested broker process. Examples are %SystemRoot%\PrintDialog\PrintDialog.exe and %SystemRoot%\System32\PickerHost.exe.

### **EXPERIMENT: Brokers**

The following steps show how broker processes are launched and terminated:

- Click the Start button, type Photos, and select the Photos option to run the built-in Windows 10 Photos application.
- 2. Open Process Explorer, switch the process list to a tree view, and locate the Microsoft. Photos.exe process. Place both windows side by side.
- 3. In the Photos app, select a picture file, and click **Print** in the top ellipsis menu or right-click the picture and choose **Print** from the menu that appears. The Print dialog box should open, and Process Explorer should show the newly created broker (PrintDialog. exe). Notice they are all children of the same Svchost process. (All UWP processes are launched by the DCOMLaunch service hosted inside that process.)

8 8 5 5 5 5 5 A O	- Courses			auto a surger	
hocess	PID	CPU Integrity	Private Bytes	Working Set Description	Compa
E services.exe	500	< 0.01 System	4,376 K	7,964 K Services and Controller app	Microse
- svchost.exe	920	0.02 System	10,284 K	37,952 K Host Process for Windows	Microsc
WmiPrvSE.exe	2904	System	6,572 K	13,584 K WMI Provider Host	Microsc
WmiPrvSE.exe	3388	System	3,952 K	11,504 KWMI Provider Host	Microsc
III unsecapp.exe	6772	System	1,556 K	4,936 K Sink to receive asynchrono	Microso
RuntimeBroker.exe	8404	0.01 Medium	45,188 K	98,520 K Runtime Broker	Microso
I unsecapp.exe	1416	High	1,480 K	5,416 K Sink to receive asynchrono	Microso
ShellExperienceHost.exe	1872	Suspended AppContainer	95,396 K	147,300 K Windows Shell Experience	Microse
SkypeHost.exe	9624	Suspended AppContainer	32,828 K	26,932 K Microsoft Skype Preview	Microso
+ a explorer.ese					
SettingSyncHost.exe	10404	< 0.01 Medium	19,156 K	3,208 K Host Process for Setting Sy.	Microso
III unsecapp.exe	11780	Medium	1,728 K	5,908 K Sink to receive asynchrono	Microso
G UcMapi.exe	13152	0.02 Medium	19,844 K	35,176 K Skype for Business	Microso
III dilhost.exe	12612	Medium	2,840 K	9,668 K COM Surrogate	Microso
ApplicationFrameHost.exe	11960	0.01 Medium	25,320 K	44,976 X Application Frame Host	Microso
Witter.Windows.ass	2084	Suspended AppContainer	33,348 K	6,956 K Ewitter.Windows	
Calculator.exe	11128	AppContainer	13,924 K	34,740 K	
Tel dilhost.exe	14916	High	1,620 K	5,108 K COM Surrogate	Microso
FileCoAuth.exe	32	Medium	2.064 K	6.972 K Microsoft OneDriveFile Co	Microso
Uphynchitmiconw.exe	17000	0.02 Medium	17,560 K	28,116 K Microsoft Lync	Microso
Video ULexe	22712	Suspended AppContainer	14,388 K	15,272 K Mideo Application	Microso
HxCalendarAppimm.exe	18476	Suspended AppContainer	14,984 K	36,004 K Microsoft Outlook Calendar	Microse
HaTar.exe	24420	Suspended AppContainer	14,624 K	38,760 K Microsoft Outlook Commu.	Microso
XDesProc.exe	17156	0.53 AppContainer	189,236 K	209,748 K Microsoft Visual Studio XA	Microso
Microsoft.Photos.exe	17008	2,45 AppContainer	459,204 K	527.372 K	
SearchULexe	14604	Suspended AppContainer	75,904 K	134,236 K Search and Cortana applica.	
SystemSettingsBroker.exe	21748	0.02 Medium	4,776 K	20,964 K System Settings Broker	Microso
#PrintDialog.exe	arono	8.8. at	40.477.8	ED TOC & BOAR PRODUCT	
TWI much and some	< .				>

4. Close the Print dialog box. The PrintDialog.exe process should exit.

# Logon

Interactive logon (as opposed to network logon) occurs through the interaction of the following:

- The logon process (Winlogon.exe)
- The logon user interface process (LogonUI.exe) and its credential providers
- Lsass.exe
- One or more authentication packages
- SAM or Active Directory

Authentication packages are DLLs that perform authentication checks. Kerberos is the Windows authentication package for interactive logon to a domain. MSV1\_0 is the Windows authentication package for interactive logon to a local computer, for domain logons to trusted pre–Windows 2000 domains, and for times when no domain controller is accessible.

Winlogon is a trusted process responsible for managing security-related user interactions. It coordinates logon, starts the user's first process at logon, and handles logoff. It also manages various other operations relevant to security, including launching LogonUI for entering passwords at logon, changing passwords, and locking and unlocking the workstation. The Winlogon process must ensure that operations relevant to security aren't visible to any other active processes. For example, Winlogon guarantees that an untrusted process can't get control of the desktop during one of these operations and thus gain access to the password.

Winlogon relies on the credential providers installed on the system to obtain a user's account name or password. Credential providers are COM objects located inside DLLs. The default providers are authui. dll, SmartcardCredentialProvider.dll, and FaceCredentialProvider.dll, which support password, smartcard PIN, and face-recognition authentication, respectively. Allowing other credential providers to be installed enables Windows to use different user-identification mechanisms. For example, a third party might supply a credential provider that uses a thumbprint-recognition device to identify users and extract their passwords from an encrypted database. Credential providers are listed in HKLM\SOFTWARE\Microsoft\ Windows\CurrentVersion\Authentication\Credential Providers, where each subkey identifies a credential provider class by its COM CLSID. (The CLSID itself must be registered at HKCR\CLSID like any other COM class.) You can use the CPlist.exe tool provided with the downloadable resources for this book to list the credential providers with their CLSID, friendly name, and implementation DLL.

To protect Winlogon's address space from bugs in credential providers that might cause the Winlogon process to crash (which, in turn, will result in a system crash, because Winlogon is considered a critical system process), a separate process, LogonUI.exe, is used to actually load the credential providers and display the Windows logon interface to users. This process is started on demand whenever Winlogon needs to present a user interface to the user, and it exits after the action has finished. It also allows Winlogon to simply restart a new LogonUI process should it crash for any reason.

Winlogon is the only process that intercepts logon requests from the keyboard. These are sent through an RPC message from Win32k.sys. Winlogon immediately launches the LogonUI application to

display the user interface for logon. After obtaining a user name and password from credential providers, Winlogon calls Lsass to authenticate the user attempting to log on. If the user is authenticated, the logon process activates a logon shell on behalf of that user. The interaction between the components involved in logon is illustrated in Figure 7-20.




FIGURE 7-20 Components involved in logon.

In addition to supporting alternative credential providers, LogonUI can load additional network provider DLLs that need to perform secondary authentication. This capability allows multiple network providers to gather identification and authentication information all at one time during normal logon. A user logging on to a Windows system might simultaneously be authenticated on a Linux server. That user would then be able to access resources of the UNIX server from the Windows machine without requiring additional authentication. Such a capability is known as one form of single sign-on.

# Winlogon initialization

During system initialization, before any user applications are active, Winlogon performs the following steps to ensure that it controls the workstation once the system is ready for user interaction:

- It creates and opens an interactive window station (for example, \Sessions\1\Windows\ WindowStations\WinSta0 in the object manager namespace) to represent the keyboard, mouse, and monitor. Winlogon creates a security descriptor for the station that has one and only one ACE containing only the system SID. This unique security descriptor ensures that no other process can access the workstation unless explicitly allowed by Winlogon.
- 2. It creates and opens two desktops: an application desktop (\Sessions\1\Windows\WinSta0\ Default, also known as the interactive desktop) and a Winlogon desktop (\Sessions\1\Windows\ WinSta0\Winlogon, also known as the Secure Desktop). The security on the Winlogon desktop is created so that only Winlogon can access that desktop. The other desktop allows both

Winlogon and users to access it. This arrangement means that any time the Winlogon desktop is active, no other process has access to any active code or data associated with the desktop. Windows uses this feature to protect the secure operations that involve passwords and locking and unlocking the desktop.

- 3. Before anyone logs on to a computer, the visible desktop is Winlogon's. After a user logs on, pressing the SAS sequence (by default, Ctrl+Alt+Del) switches the desktop from Default to Winlogon and launches LogonUI. (This explains why all the windows on your interactive desktop seem to disappear when you press Ctrl+Alt+Del, and then return when you dismiss the Windows Security dialog box.) Thus, the SAS always brings up a Secure Desktop controlled by Winlogon.
- 4. It establishes an ALPC connection with Lsass. This connection will be used for exchanging information during logon, logoff, and password operations, and is made by calling LsaRegisterLogonProcess.
- It registers the Winlogon RPC message server, which listens for SAS, logoff, and workstation lock notifications from Win32k. This measure prevents Trojan horse programs from gaining control of the screen when the SAS is entered.

Note	The Wininit process performs steps similar to steps 1 and 2 to allow legacy
interac	tive services running on session 0 to display windows, but it does not per-
form a	ny other steps because session 0 is not available for user logon.

### How SAS is implemented

The SAS is secure because no application can intercept the Ctrl+Alt+Del keystroke combination or prevent Winlogon from receiving it. Win32k.sys reserves the Ctrl+Alt+Del key combination so that whenever the Windows input system (implemented in the raw input thread in Win32k) sees the combination, it sends an RPC message to Winlogon's message server, which listens for such notifications. The keystrokes that map to a registered hot key are not sent to any process other than the one that registered it, and only the thread that registered a hot key can unregister it, so a Trojan horse application cannot deregister Winlogon's ownership of the SAS.

A Windows function, SetWindowsHookEx, enables an application to install a hook procedure that's invoked every time a keystroke is pressed, even before hot keys are processed, and allows the hook to squash keystrokes. However, the Windows hot key processing code contains a special case for Ctrl+Alt+Del that disables hooks so that the keystroke sequence can't be intercepted. In addition, if the interactive desktop is locked, only hot keys owned by Winlogon are processed.

Once the Winlogon desktop is created during initialization, it becomes the active desktop. When the Winlogon desktop is active, it is always locked. Winlogon unlocks its desktop only to switch to the application desktop or the screen-saver desktop. (Only the Winlogon process can lock or unlock a desktop.)

# User logon steps

Logon begins when a user presses the SAS (Ctrl+Alt+Del). After the SAS is pressed, Winlogon starts LogonUI, which calls the credential providers to obtain a user name and password. Winlogon also creates a unique local logon SID for this user, which it assigns to this instance of the desktop (keyboard, screen, and mouse). Winlogon passes this SID to Lsass as part of the LsaLogonUser call. If the user is successfully logged on, this SID will be included in the logon process token—a step that protects access to the desktop. For example, another logon to the same account but on a different system will be unable to write to the first machine's desktop because this second logon won't be in the first logon's desktop token.

When the user name and password have been entered, Winlogon retrieves a handle to a package by calling the Lsass function LsaLookupAuthenticationPackage. Authentication packages are listed in the registry under HKLM\SYSTEM\CurrentControlSet\Control\Lsa. Winlogon passes logon information to the authentication package via LsaLogonUser. Once a package authenticates a user, Winlogon continues the logon process for that user. If none of the authentication packages indicates a successful logon, the logon process is aborted.

Windows uses two standard authentication packages for interactive username/password-based logons:

- MSV1\_0 The default authentication package on a stand-alone Windows system is MSV1\_0 (Msv1\_0.dll), an authentication package that implements LAN Manager 2 protocol. Lsass also uses MSV1\_0 on domain-member computers to authenticate to pre–Windows 2000 domains and computers that can't locate a domain controller for authentication. (Computers that are disconnected from the network fall into this latter category.)
- Kerberos The Kerberos authentication package, Kerberos.dll, is used on computers that are members of Windows domains. The Windows Kerberos package, with the cooperation of Kerberos services running on a domain controller, supports the Kerberos protocol. This protocol is based on Internet RFC 1510. (Visit the Internet Engineering Task Force [IETF] website at http://www.ietf.org for detailed information on the Kerberos standard.)

### MSV1\_0

The MSV1\_0 authentication package takes the user name and a hashed version of the password and sends a request to the local SAM to retrieve the account information, which includes the hashed password, the groups to which the user belongs, and any account restrictions. MSV1\_0 first checks the account restrictions, such as hours or type of accesses allowed. If the user can't log on because of the restrictions in the SAM database, the logon call fails and MSV1\_0 returns a failure status to the LSA.

MSV1\_0 then compares the hashed password and user name to that obtained from the SAM. In the case of a cached domain logon, MSV1\_0 accesses the cached information by using Lsass functions that store and retrieve "secrets" from the LSA database (the SECURITY hive of the registry). If the information matches, MSV1\_0 generates a LUID for the logon session and creates the logon session by calling Lsass, associating this unique identifier with the session and passing the information needed to ultimately create an access token for the user. (Recall that an access token includes the user's SID, group SIDs, and assigned privileges.)

**Note** MSV1\_0 does not cache a user's entire password hash in the registry because that would enable someone with physical access to the system to easily compromise a user's domain account and gain access to encrypted files and to network resources the user is authorized to access. Instead, it caches half of the hash. The cached half-hash is sufficient to verify that a user's password is correct, but it isn't sufficient to gain access to EFS keys and to authenticate as the user on a domain because these actions require the full hash.

If MSV1\_0 needs to authenticate using a remote system, as when a user logs on to a trusted pre– Windows 2000 domain, MSV1\_0 uses the Netlogon service to communicate with an instance of Netlogon on the remote system. Netlogon on the remote system interacts with the MSV1\_0 authentication package on that system, passing back authentication results to the system on which the logon is being performed.

#### Kerberos

The basic control flow for Kerberos authentication is the same as the flow for MSV1\_0. However, in most cases, domain logons are performed from member workstations or servers rather than on a domain controller, so the authentication package must communicate across the network as part of the authentication process. The package does so by communicating via the Kerberos TCP/IP port (port 88) with the Kerberos service on a domain controller. The Kerberos Key Distribution Center service (Kdcsvc.dll), which implements the Kerberos authentication procesl, runs in the Lsass process on domain controllers.

After validating hashed user-name and password information with Active Directory's user account objects (using the Active Directory server Ntdsa.dll), Kdcsvc returns domain credentials to Lsass, which returns the result of the authentication and the user's domain logon credentials (if the logon was successful) across the network to the system where the logon is taking place.

**Note** This description of Kerberos authentication is highly simplified, but it highlights the roles of the various components involved. Although the Kerberos authentication protocol plays a key role in distributed domain security in Windows, its details are outside the scope of this book.

After a logon has been authenticated, Lsass looks in the local policy database for the user's allowed access, including interactive, network, batch, or service process. If the requested logon doesn't match the allowed access, the logon attempt will be terminated. Lsass deletes the newly created logon session by cleaning up any of its data structures and then returns failure to Winlogon, which in turn displays an appropriate message to the user. If the requested access is allowed, Lsass adds the appropriate additional security IDs (such as Everyone, Interactive, and the like). It then checks its policy database for any granted privileges for all the SIDs for this user and adds these privileges to the user's access token.

When Lsass has accumulated all the necessary information, it calls the executive to create the access token. The executive creates a primary access token for an interactive or service logon and an impersonation token for a network logon. After the access token is successfully created, Lsass duplicates the token, creating a handle that can be passed to Winlogon, and closes its own handle. If necessary, the logon operation is audited. At this point, Lsass returns success to Winlogon along with a handle to the access token, the LUID for the logon session, and the profile information, if any, that the authentication package returned.

### **EXPERIMENT: Listing active logon sessions**

As long as at least one token exists with a given logon session LUID, Windows considers the logon session to be active. You can use the LogonSessions tool from Sysinternals, which uses the LsaEnumerateLogonSessions function (documented in the Windows SDK) to list the active logon sessions:

```
C:\WINDOWS\system32>logonsessions
LogonSessions v1.4 - Lists logon session information
Copyright (C) 2004-2016 Mark Russinovich
Sysinternals - www.sysinternals.com
[0] Logon session 00000000:000003e7:
   User name: WORKGROUP\ZODIAC$
   Auth package: NTLM
   Logon type: (none)
   Session: 0
Sid: S-1-5-18
   Logon time: 09-Dec-16 15:22:31
   Logon server:
   DNS Domain:
   UPN:
[1] Logon session 0000000:0000cdce:
   User name:
   Auth package: NTLM
   Logon type: (none)
   Session: 0
Sid: (none)
   Logon time: 09-Dec-16 15:22:31
   Logon server:
   DNS Domain:
   UPN:
[2] Logon session 00000000:000003e4:
   User name: WORKGROUP\ZODIAC$
   Auth package: Negotiate
   Logon type: Service
   Session: 0
Sid: S-1-5-20
   Logon time: 09-Dec-16 15:22:31
   Logon server:
   DNS Domain:
   UPN:
```

```
[3] Logon session 0000000:00016239:
   User name: Window Manager\DWM-1
   Auth package: Negotiate
   Logon type: Interactive
   Session:
               1
   Sid:
               S-1-5-90-0-1
   Logon time: 09-Dec-16 15:22:32
   Logon server:
   DNS Domain:
   UPN:
[4] Logon session 0000000:00016265:
   User name: Window Manager\DWM-1
   Auth package: Negotiate
   Logon type: Interactive
   Session:
              1
   Sid:
               S-1-5-90-0-1
   Logon time: 09-Dec-16 15:22:32
   Logon server:
   DNS Domain:
   UPN:
[5] Logon session 00000000:000003e5:
   User name:
               NT AUTHORITY\LOCAL SERVICE
   Auth package: Negotiate
   Logon type: Service
   Session:
              0
   Sid:
                S-1-5-19
   Logon time: 09-Dec-16 15:22:32
   Logon server:
   DNS Domain:
   UPN:
. . .
[8] Logon session 00000000:0005c203:
   User name:
               NT VIRTUAL MACHINE\AC9081B6-1E96-4BC8-8B3B-C609D4F85F7D
   Auth package: Negotiate
   Logon type: Service
   Session:
               0
   Sid:
                S-1-5-83-1-2895151542-1271406230-163986315-2103441620
   Logon time: 09-Dec-16 15:22:35
   Logon server:
   DNS Domain:
   UPN:
[9] Logon session 0000000:0005d524:
   User name:
                 NT VIRTUAL MACHINE\B37F4A3A-21EF-422D-8B37-AB6B0A016ED8
   Auth package: Negotiate
   Logon type: Service
   Session:
                 0
   Sid:
                S-1-5-83-1-3011463738-1110254063-1806382987-3631087882
   Logon time: 09-Dec-16 15:22:35
```

```
Logon server:

DNS Domain:

UPN:

[12] Logon session 0000000:0429ab2c:

User name: IIS APPPOOL\DefaultAppPool

Auth package: Negotiate

Logon type: Service

Session: 0

Sid: S-1-5-82-3006700770-424185619-1745488364-794895919-4004696415

Logon time: 09-Dec-16 22:33:03

Logon server:

DNS Domain:

UPN:
```

Information reported for a session includes the SID and name of the user associated with the session, as well as the session's authentication package and logon time. Note that the Negotiate authentication package, seen in logon sessions 2 and 9 in the preceding output, will attempt to authenticate via Kerberos or NTLM, depending on which is most appropriate for the authentication request.

The LUID for a session is displayed on the Logon Session line of each session block. Using the Handle.exe utility (also from Sysinternals), you can find the tokens that represent a particular logon session. For example, to find the tokens for logon session 8 in the output just shown, you could enter this command:

```
C:\WINDOWS\system32>handle -a 5c203
```

```
Nthandle v4.1 - Handle viewer
Copyright (C) 1997-2016 Mark Russinovich
Sysinternals - www.sysinternals.com
```

System	pid: 4	type: Directory	1274: $Sessions 0$	4: \Sessions\0\
DosDevices\0000000	0-0005c203			
lsass.exe	pid: 496	type: Token	D7C: NT VIRTUAL MACHINE\	C: NT VIRTUAL MACHINE\
AC9081B6-1E96-4BC8	8-8B3B-C609D4	F85F7D:5c203		
lsass.exe	pid: 496	type: Token	2350: NT VIRTUAL MACHINE\	D: NT VIRTUAL MACHINE\
AC9081B6-1E96-4BC8	8-8B3B-C609D4	F85F7D:5c203		
lsass.exe	pid: 496	type: Token	2390: NT VIRTUAL MACHINE\	D: NT VIRTUAL MACHINE\
AC9081B6-1E96-4BC8	8-8B3B-C609D4	F85F7D:5c203		
svchost.exe	pid: 900	type: Token	804: NT VIRTUAL MACHINE\	4: NT VIRTUAL MACHINE\
AC9081B6-1E96-4BC8	8-8B3B-C609D4	F85F7D:5c203		
svchost.exe	pid: 1468	type: Token	10EC: NT VIRTUAL MACHINE\	C: NT VIRTUAL MACHINE\
AC9081B6-1E96-4BC8	8-8B3B-C609D4	F85F7D:5c203		
vmms.exe	pid: 4380	type: Token	A34: NT VIRTUAL MACHINE\	4: NT VIRTUAL MACHINE\
AC9081B6-1E96-4BC8	8-8B3B-C609D4	F85F7D:5c203		
vmcompute.exe	pid: 6592	type: Token	200: NT VIRTUAL MACHINE\	D: NT VIRTUAL MACHINE\
AC9081B6-1E96-4BC8	8-8B3B-C609D4	F85F7D:5c203		
vmwp.exe	pid: 7136	type: WindowStatior	n 168: \Windows\WindowStations	8: \Windows\WindowStat
Service-0x0-5c203\$	5			
vmwp.exe	pid: 7136	type: WindowStatior	n 170: \Windows\WindowStations	D: \Windows\WindowStat
Service-0x0-5c203\$	5			

CHAPTER 7 Security 717

Winlogon then looks in the registry at the value HKLM\SOFTWARE\Microsoft\Windows NT\Current Version\Winlogon\Userinit and creates a process to run whatever the value of that string is. (This value can be several EXEs separated by commas.) The default value is Userinit.exe, which loads the user profile and then creates a process to run whatever the value of HKCU\SOFTWARE\Microsoft\Windows NT\Current Version\Winlogon\Shell is, if that value exists. That value does not exist by default, however. If it doesn't exist, Userinit.exe does the same for HKLM\SOFTWARE\Microsoft\Windows NT\Current Version\Winlogon\Shell, which defaults to Explorer.exe. Userinit then exits (which is why Explorer.exe shows up as having no parent when examined in Process Explorer). For more information on the steps followed during the user logon process, see Chapter 11 in Part 2.

### Assured authentication

A fundamental problem with password-based authentication is that passwords can be revealed or stolen and used by malicious third parties. Windows includes a mechanism that tracks the authentication strength of how a user authenticated with the system, which allows objects to be protected from access if a user did not authenticate securely. (Smartcard authentication is considered to be a stronger form of authentication than password authentication.)

On systems that are joined to a domain, the domain administrator can specify a mapping between an object identifier (OID) (a unique numeric string representing a specific object type) on a certificate used for authenticating a user (such as on a smartcard or hardware security token) and a SID that is placed into the user's access token when the user successfully authenticates with the system. An ACE in a DACL on an object can specify such a SID be part of a user's token in order for the user to gain access to the object. Technically, this is known as a *group claim*. In other words, the user is claiming membership in a particular group, which is allowed certain access rights on specific objects, with the claim based upon the authentication mechanism. This feature is not enabled by default, and it must be configured by the domain administrator in a domain with certificate-based authentication.

Assured authentication builds on existing Windows security features in a way that provides a great deal of flexibility to IT administrators and anyone concerned with enterprise IT security. The enterprise decides which OIDs to embed in the certificates it uses for authenticating users and the mapping of particular OIDs to Active Directory universal groups (SIDs). A user's group membership can be used to identify whether a certificate was used during the logon operation. Different certificates can have different issuance policies and, thus, different levels of security, which can be used to protect highly sensitive objects (such as files or anything else that might have a security descriptor).

Authentication protocols (APs) retrieve OIDs from certificates during certificate-based authentication. These OIDs must be mapped to SIDs, which are in turn processed during group membership expansion, and placed in the access token. The mapping of OID to universal group is specified in Active Directory.

As an example, an organization might have several certificate-issuance policies named Contractor, Full Time Employee, and Senior Management, which map to the universal groups Contractor-Users, FTE-Users, and SM-Users, respectively. A user named Abby has a smartcard with a certificate issued using the Senior Management issuance policy. When she logs in using her smartcard, she receives an additional group membership (which is represented by a SID in her access token) indicating that she is a member of the SM-Users group. Permissions can be set on objects (using an ACL) such that only members of the FTE-Users or SM-Users group (identified by their SIDs within an ACE) are granted access. If Abby logs in using her smartcard, she can access those objects, but if she logs in with just her user name and password (without the smartcard), she cannot access those objects because she will not have either the FTE-Users or SM-Users group in her access token. A user named Toby who logs in with a smartcard that has a certificate issued using the Contractor issuance policy would not be able to access an object that has an ACE requiring FTE-Users or SM-Users group membership.

## Windows Biometric Framework

Windows provides a standardized mechanism for supporting certain types of biometric devices, such as fingerprint scanners, used to enable user identification via a fingerprint swipe: the Windows Biometric Framework (WBF). Like many other such frameworks, the WBF was developed to isolate the various functions involved in supporting such devices, so as to minimize the code required to implement a new device.

The primary components of the WBF are shown in Figure 7-21. Except as noted in the following list, all of these components are supplied by Windows:

- The Windows Biometric Service (%SystemRoot%\System32\Wbiosrvc.dll This provides the process-execution environment in which one or more biometric service providers can execute.
- The Windows Biometric Driver Interface (WBDI) This is a set of interface definitions (IRP major function codes, DeviceIoControl codes, and so forth) to which any driver for a biometric scanner device must conform if it is to be compatible with the Windows Biometric Service. WBDI drivers can be developed using any of the standard driver frameworks (UMDF, KMDF and WDM). However, UMDF is recommended to reduce code size and increase reliability. WBDI is described in the Windows Driver Kit documentation.
- The Windows Biometric API This allows existing Windows components such as Winlogon and LogonUI to access the biometric service. Third-party applications have access to the Windows Biometric API and can use the biometric scanner for functions other than logging in to Windows. An example of a function in this API is WinBioEnumServiceProviders. The Biometric API is exposed by %SystemRoot%\System32\Winbio.dll.
- The fingerprint biometric service provider This wraps the functions of biometric-type-specific adapters to present a common interface, independent of the type of biometric, to the Windows Biometric Service. In the future, additional types of biometrics, such as retinal scans or voiceprint analyzers, might be supported by additional biometric service providers. The biometric service provider in turn uses three adapters, which are user-mode DLLs:
  - **The sensor adapter** This exposes the data-capture functionality of the scanner. The sensor adapter usually uses Windows I/O calls to access the scanner hardware. Windows provides a sensor adapter that can be used with simple sensors, those for which a WBDI driver exists. For more complex sensors, the sensor adapter is written by the sensor vendor.
  - **The engine adapter** This exposes processing and comparison functionality specific to the scanner's raw data format and other features. The actual processing and comparison might be performed within the engine adapter DLL, or the DLL might communicate with some other module. The engine adapter is always provided by the sensor vendor.

CHAPTER 7 Security 719

- **The storage adapter** This exposes a set of secure storage functions. These are used to store and retrieve templates against which scanned biometric data is matched by the engine adapter. Windows provides a storage adapter using Windows cryptography services and standard disk file storage. A sensor vendor might provide a different storage adapter.
- The functional device driver for the actual biometric scanner device This exposes the WBDI at its upper edge. It usually uses the services of a lower-level bus driver, such as the USB bus driver, to access the scanner device. This driver is always provided by the sensor vendor.

Win32 Application	UWP App					
Windows Biometric Fra	Windows Biometric Framework API (WinBio.Dll)					
Windows Bior	netric Service					
Biometric Ser	vice Provider					
Sensor Adapter Engine Adapter Storage Adapter						
Windows Biometr	ic Driver Interface					
Dri	Driver					
Provided by Microsoft						
Provided by IHV/ISV	Provided by IHV/ISV					
Provided by Microsoft or	Provided by Microsoft or IHV/ISV					



A typical sequence of operations to support logging in via a fingerprint scan might be as follows:

- After initialization, the sensor adapter receives from the service provider a request for capture data. The sensor adapter in turn sends a DeviceIoControl request with the IOCTL\_ BIOMETRIC\_CAPTURE\_DATA control code to the WBDI driver for the fingerprint scanner device.
- 2. The WBDI driver puts the scanner into capture mode and queues the IOCTL\_BIOMETRIC\_ CAPTURE\_DATA request until a fingerprint scan occurs.
- 3. A prospective user swipes a finger across the scanner. The WBDI driver receives notification of this, obtains the raw scan data from the sensor, and returns this data to the sensor driver in a buffer associated with the IOCTL\_BIOMETRIC\_CAPTURE\_DATA request.
- **4.** The sensor adapter provides the data to the fingerprint biometric service provider, which in turn passes the data to the engine adapter.
- 5. The engine adapter processes the raw data into a form compatible with its template storage.
- 6. The fingerprint biometric service provider uses the storage adapter to obtain templates and corresponding security IDs from secure storage. It invokes the engine adapter to compare each template to the processed scan data. The engine adapter returns a status indicating whether it's a match or not a match.

**7.** If a match is found, the Windows Biometric Service notifies Winlogon, via a credential provider DLL, of a successful login and passes it the security ID of the identified user. This notification is sent via an ALPC message, providing a path that cannot be spoofed.

# Windows Hello

Windows Hello, introduced in Windows 10, provides new ways to authenticate users based on biometric information. With this technology, users can log in effortlessly just by showing themselves to the device's camera or swiping their finger.

At the time of this writing, Windows Hello supports three types of biometric identification:

- Fingerprint
- Face
- Iris

The security aspect of biometrics needs to be considered first. What is the likelihood of someone being identified as you? What is the likelihood of you *not* being identified as you? These questions are parameterized by two factors:

- **False accept rate (uniqueness)** This is the probability of another user having the same biometric data as you. Microsoft's algorithms make sure the likelihood is 1 in 100,000.
- False reject rate (reliability) This is the probability of you not being correctly recognized as you (for example, in abnormal lighting conditions for face or iris recognition). Microsoft's implementation makes sure there is less than 1 percent chance of this happening. If it does happen, the user can try again or use a PIN code instead.

Using a PIN code may seem less secure than using a full-blown password (the PIN can be as simple as a four-digit number). However, a PIN is more secure than a password for two main reasons:

- The PIN code is local to the device and is never transmitted across the network. This means that even if someone gets a hold of the PIN, they cannot use it to log in as the user from any other device. Passwords, on the other hand, travel to the domain controller. If someone gets hold of the password, they can log in from another machine into the domain.
- The PIN code is stored in the Trusted Platform Module (TPM)—a piece of hardware that also plays a part in Secure Boot (discussed in detail in Chapter 11 in Part 2)—so is difficult to access. In any case, it requires physical access to the device, raising the bar considerably for a potential security compromise.

Windows Hello is built upon the Windows Biometric Framework (WBF) (described in the previous section). Current laptop devices support fingerprint and face biometrics, while iris is only supported on the Microsoft Lumia 950 and 950 XL phones. (This will likely change and expand in future devices.) Note that face recognition requires an infrared (IR) camera as well as a normal (RGB) one, and is supported on devices such as the Microsoft Surface Pro 4 and the Surface Book.

# **User Account Control and virtualization**

User Account Control (UAC) is meant to enable users to run with standard user rights as opposed to administrative rights. Without administrative rights, users cannot accidentally (or deliberately) modify system settings, malware can't normally alter system security settings or disable antivirus software, and users can't compromise the sensitive information of other users on shared computers. Running with standard user rights can thus mitigate the impact of malware and protect sensitive data on shared computers.

UAC had to address a couple of problems to make it practical for a user to run with a standard user account. First, because the Windows usage model has been one of assumed administrative rights, software developers assumed their programs would run with those rights and could therefore access and modify any file, registry key, or operating system setting. Second, users sometimes need administrative rights to perform such operations as installing software, changing the system time, and opening ports in the firewall.

The UAC solution to these problems is to run most applications with standard user rights, even though the user is logged in to an account with administrative rights. At the same time, UAC makes it possible for standard users to access administrative rights when they need them—whether for legacy applications that require them or for changing certain system settings. As described, UAC accomplishes this by creating a filtered admin token as well as the normal admin token when a user logs in to an administrative account. All processes created under the user's session will normally have the filtered admin token in effect so that applications that can run with standard user rights will do so. However, the administrative user can run a program or perform other functions that require full Administrator rights through UAC elevation.

Windows also allows certain tasks that were previously reserved for administrators to be performed by standard users, enhancing the usability of the standard user environment. For example, Group Policy settings exist that can enable standard users to install printers and other device drivers approved by IT administrators and to install ActiveX controls from administrator-approved sites.

Finally, when software developers test in the UAC environment, they are encouraged to develop applications that can run without administrative rights. Fundamentally, non-administrative programs should not need to run with administrator privileges; programs that often require administrator privileges are typically legacy programs using old APIs or techniques, and they should be updated.

Together, these changes obviate the need for users to run with administrative rights all the time.

## File system and registry virtualization

Although some software legitimately requires administrative rights, many programs needlessly store user data in system-global locations. When an application executes, it can be running in different user accounts, and it should therefore store user-specific data in the per-user %AppData% directory and save per-user settings in the user's registry profile under HKEY\_CURRENT\_USER\Software. Standard user accounts don't have write access to the %ProgramFiles% directory or HKEY\_LOCAL\_MACHINE\ Software, but because most Windows systems are single-user and most users have been administrators until UAC was implemented, applications that incorrectly saved user data and settings to these locations worked anyway.

Windows enables these legacy applications to run in standard user accounts through the help of file system and registry namespace virtualization. When an application modifies a system-global location in the file system or registry and that operation fails because access is denied, Windows redirects the operation to a per-user area. When the application reads from a system-global location, Windows first checks for data in the per-user area and, if none is found, permits the read attempt from the global location.

Windows will always enable this type of virtualization unless:

- The application is 64-bit Because virtualization is purely an application-compatibility technology meant to help legacy applications, it is enabled only for 32-bit applications. The world of 64-bit applications is relatively new and developers should follow the development guidelines for creating standard user-compatible applications.
- The application is already running with administrative rights In this case, there is no need for any virtualization.
- The operation came from a kernel-mode caller
- The operation is being performed while the caller is impersonating For example, any operations not originating from a process classified as legacy according to this definition, including network file-sharing accesses, are not virtualized.
- The executable image for the process has a UAC-compatible manifest Specifying a requestedExecutionLevel setting, described in the next section.
- The administrator does not have write access to the file or registry key This exception exists to enforce backward compatibility because the legacy application would have failed before UAC was implemented even if the application was run with administrative rights.

#### Services are never virtualized

You can see the virtualization status (the process virtualization status is stored as a flag in its token) of a process by adding the UAC Virtualization column to Task Manager's Details page, as shown in Figure 7-22. Most Windows components—including the Desktop Window Manager (Dwm.exe), the Client Server Run-Time Subsystem (Csrss.exe), and Explorer—have virtualization disabled because they have a UAC-compatible manifest or are running with administrative rights and so do not allow virtualization. However, 32-bit Internet Explorer (iexplore.exe) has virtualization enabled because it can host multiple ActiveX controls and scripts and must assume that they were not written to operate correctly with standard user rights. Note that, if required, virtualization can be completely disabled for a system using a Local Security Policy setting.

In addition to file system and registry virtualization, some applications require additional help to run correctly with standard user rights. For example, an application that tests the account in which it's running for membership in the Administrators group might otherwise work, but it won't run if it's not in that group. Windows defines a number of application-compatibility shims to enable such applications to work anyway. The shims most commonly applied to legacy applications for operation with standard user rights are shown in Table 7-15.

File Options View							
Processes Perform	nance A	pp history	Startup U	sers	Details	Services	
Name	PID	Status	CPU	J Pla	tform	UAC virtualiz	-
W EegoService	3792	Running	00	32	bit	Not allowed	
WEpePcMonito	13724	Running	00	32	bit	Disabled	
esif_assist_64	3728	Running	00	64	bit	Disabled	
<pre>esif_uf.exe</pre>	3636	Running	00	64	bit	Not allowed	
EvtEng.exe	3816	Running	00	64	bit	Not allowed	- 6
a explorer.exe	9188	Running	00	64	bit	Disabled	
explorer.exe	10168	Running	00	64	bit	Disabled	- 1
FileCoAuth.exe	18216	Running	00	32	bit	Enabled	- 1
🕑 firefox.exe	17376	Running	00	32	bit	Disabled	
firefox.exe	2876	Running	00	32	bit	Disabled	
fontdrvhost	16400	Running	00	64	bit		
fpCSEvtSvc.e	3500	Running	00	64	bit	Not allowed	
hidfind.exe	7288	Running	00	64	bit	Disabled	
HidMonitorS	3492	Running	00	64	bit	Not allowed	
HlpViewer.exe	13132	Running	00	32	bit	Disabled	
HPNotificati	11304	Running	00	64	bit	Disabled	
hpgwmiex.exe	8792	Running	00	32	bit	Not allowed	
hpgwmiex.exe	7420	Running	00	32	bit	Not allowed	
HPSupportS	14984	Running	00	64	bit	Not allowed	
IAStorDataM	15288	Running	00	32	bit	Not allowed	
IAStoricon.exe	14920	Running	00	32	bit	Disabled	
ibtsiva.exe	3516	Running	00	64	bit	Not allowed	
🥘 iexplore.exe	12652	Running	00	64	bit	Disabled	
🧉 iexplore.exe	16460	Running	00	32	bit	Enabled	
■ igfxCUIServic	1748	Running	00	64	bit	Not allowed	
IpOverUsbSv	3532	Running	00	32	bit	Not allowed	
Ilet and the same	4204	Demaine	00	22	la ta	N -+ - II	`

FIGURE 7-22 Using Task Manager to view virtualization status.

TABLE 7-15	UAC virtualization	shims
------------	--------------------	-------

Flag	Meaning
ElevateCreateProcess	This changes CreateProcess to handle ERROR_ELEVATION_REQUIRED errors by calling the application information service to prompt for elevation.
ForceAdminAccess	This spoofs queries of Administrator group membership.
VirtualizeDeleteFile	This spoofs successful deletion of global files and directories.
LocalMappedObject	This forces global section objects into the user's namespace.
VirtualizeHKCRLite	This redirects global registration of COM objects to a per-user location.
VirtualizeRegisterTypeLib	This converts per-machine typelib registrations to per-user registrations.

### **File virtualization**

The file system locations that are virtualized for legacy processes are %ProgramFiles%, %ProgramData%, and %SystemRoot%, excluding some specific subdirectories. However, any file with an executable extension—including .exe, .bat, .scr, .vbs, and others—is excluded from virtualization. This means that programs that update themselves from a standard user account fail instead of creating private versions of their executables that aren't visible to an administrator running a global updater.

**Note** To add extensions to the exception list, enter them in the HKLM\System\Current-ControlSet\Services\Luafv\Parameters\ExcludedExtensionsAdd registry key and reboot. Use a multistring type to delimit multiple extensions, and do not include a leading dot in the extension name.

Modifications to virtualized directories by legacy processes are redirected to the user's virtual root directory, %LocalAppData%\VirtualStore. The Local component of the path highlights the fact that virtualized files don't roam with the rest of the profile when the account has a roaming profile.

The UAC File Virtualization filter driver (%SystemRoot%\System32\Drivers\Luafv.sys) implements file system virtualization. Because this is a file system filter driver, it sees all local file system operations, but it implements functionality only for operations from legacy processes. As shown in Figure 7-23, the filter driver changes the target file path for a legacy process that creates a file in a system-global location but does not for a non-virtualized process with standard user rights. Default permissions on the \Windows directory deny access to the application written with UAC support, but the legacy process acts as though the operation succeeds when it really created the file in a location fully accessible by the user.




FIGURE 7-23 UAC File Virtualization filter driver operation.

### **EXPERIMENT:** File virtualization behavior

In this experiment, you will enable and disable virtualization on the command prompt and see several behaviors to demonstrate UAC file virtualization:

- Open a non-elevated command prompt (you must have UAC enabled for this to work) and enable virtualization for it. You can change the virtualization status of a process by right-clicking the process in the Task Manager Details tab and selecting UAC Virtualization from the shortcut menu that appears.
- 2. Navigate to the C:\Windows directory and use the following command to write a file: echo hello-1 > test.txt
- 3. List the contents of the directory. You'll see that the file appears.


dir test.txt


4. Disable virtualization by right-clicking the process in the Task Manager Details tab and deselecting UAC Virtualization. Then list the directory as in step 3. Notice that the file is gone. However, a directory listing of the VirtualStore directory will reveal the file:

dir %LOCALAPPDATA%\VirtualStore\Windows\test.txt

- 5. Enable virtualization again for this process.
- **6.** To look at a more complex scenario, create a new command prompt window, but elevated this time. Then repeat steps 2 and 3 using the string hello-2.
- **7.** Examine the text inside these files by using the following command in both command prompts. The screenshots that follow show the expected output.

type test.txt





8. From your elevated command prompt, delete the test.txt file:

del test.txt

9. Repeat step 3 of the experiment in both windows. Notice that the elevated command prompt cannot find the file anymore, while the standard user command prompt shows the old contents of the file again. This demonstrates the failover mechanism described earlier: Read operations look in the per-user virtual store location first, but if the file doesn't exist, read access to the system location will be granted.

### **Registry virtualization**

Registry virtualization is implemented slightly differently from file system virtualization. Virtualized registry keys include most of the HKEY\_LOCAL\_MACHINE\Software branch, but there are numerous exceptions, such as the following:

- HKLM\Software\Microsoft\Windows
- HKLM\Software\Microsoft\Windows NT
- HKLM\Software\Classes

Only keys that are commonly modified by legacy applications, but that don't introduce compatibility or interoperability problems, are virtualized. Windows redirects modifications of virtualized keys by a legacy application to a user's registry virtual root at HKEY\_CURRENT\_USER\Software\Classes\ VirtualStore. The key is located in the user's Classes hive, %LocalAppData%\Microsoft\Windows\ UsrClass.dat, which, like any other virtualized file data, does not roam with a roaming user profile. Instead of maintaining a fixed list of virtualized locations as Windows does for the file system, the virtualization status of a key is stored as a combination of flags, shown in Table 7-16.

You can use the Reg.exe utility included in Windows, with the flags option, to display the current virtualization state for a key or to set it. In Figure 7-24, note that the HKLM\Software key is fully virtualized, but the Windows subkey (and all its children) have only silent failure enabled.

#### TABLE 7-16 Registry virtualization flags

Flag	Meaning
REG_KEY_DONT_VIRTUALIZE	This specifies whether virtualization is enabled for this key. If the flag is set, virtu- alization is disabled.
REG_KEY_DONT_SILENT_FAIL	If the REG_KEY_DONT_VIRTUALIZE flag is set (virtualization is disabled), this key specifies that a legacy application that would be denied access performing an operation on the key is instead granted MAXIMUM_ALLOWED rights to the key (any access the account is granted) instead of the rights the application requested. If this flag is set, it implicitly disables virtualization as well.
REG_KEY_RECURSE_FLAG	This determines whether the virtualization flags will propagate to the child keys (subkeys) of this key.




FIGURE 7-24 UAC registry virtualization flags on the Software and Windows keys.

Unlike file virtualization, which uses a filter driver, registry virtualization is implemented in the configuration manager. (See Chapter 9 in Part 2 for more information on the registry and the configuration manager.) As with file system virtualization, a legacy process creating a subkey of a virtualized key is redirected to the user's registry virtual root, but a UAC-compatible process is denied access by default permissions. This is shown in Figure 7-25.




FIGURE 7-25 UAC registry virtualization operation.

# Elevation

Even if users run only programs that are compatible with standard user rights, some operations still require administrative rights. For example, the vast majority of software installations require administrative rights to create directories and registry keys in system-global locations or to install services or device drivers. Modifying system-global Windows and application settings also requires administrative rights, as does the parental controls feature. It would be possible to perform most of these operations by switching to a dedicated administrator account, but the inconvenience of doing so would likely result in most users remaining in the administrator account to perform their daily tasks, most of which do not require administrative rights.

It's important to be aware that UAC elevations are conveniences and not security boundaries. A security boundary requires that security policy dictate what can pass through the boundary. User accounts are an example of a security boundary in Windows because one user can't access the data belonging to another user without having that user's permission.

Because elevations aren't security boundaries, there's no guarantee that malware running on a system with standard user rights can't compromise an elevated process to gain administrative rights. For example, elevation dialog boxes only identify the executable that will be elevated; they say nothing about what it will do when it executes.

### Running with administrative rights

Windows includes enhanced "run as" functionality so that standard users can conveniently launch processes with administrative rights. This functionality requires giving applications a way to identify operations for which the system can obtain administrative rights on behalf of the application, as necessary (we'll say more on this topic shortly).

To enable users acting as system administrators to run with standard user rights but not have to enter user names and passwords every time they want to access administrative rights, Windows makes use of a mechanism called *Admin Approval Mode* (*AAM*). This feature creates two identities for the user at logon: one with standard user rights and another with administrative rights. Since every user on a Windows system is either a standard user or acting for the most part as a standard user in AAM, developers must assume that all Windows users are standard users, which will result in more programs working with standard user rights without virtualization or shims.

Granting administrative rights to a process is called *elevation*. When elevation is performed by a standard user account (or by a user who is part of an administrative group but not the actual Administrators group), it's referred to as an *over-the-shoulder* (*OTS*) *elevation* because it requires the entry of credentials for an account that's a member of the Administrators group, something that's usually completed by a privileged user typing over the shoulder of a standard user. An elevation performed by an AAM user is called a *consent elevation* because the user simply has to approve the assignment of his administrative rights.

Stand-alone systems, which are typically home computers, and domain-joined systems treat AAM access by remote users differently because domain-connected computers can use domain administrative groups in their resource permissions. When a user accesses a stand-alone computer's file share, Windows requests the remote user's standard user identity. But on domain-joined systems, Windows honors all the user's domain group memberships by requesting the user's administrative identity. Executing an image that requests administrative rights causes the application information service (AIS, contained in %SystemRoot%\System32\Appinfo.dll), which runs inside a standard service host process (SvcHost.exe), to launch %SystemRoot%\System32\Consent.exe. Consent captures a bitmap of the screen, applies a fade effect to it, switches to a desktop that's accessible only to the local system account (the Secure Desktop), paints the bitmap as the background, and displays an elevation dialog box that contains information about the executable. Displaying this dialog box on a separate desktop prevents any application present in the user's account from modifying the appearance of the dialog box.

If an image is a Windows component digitally signed (by Microsoft or another entity), the dialog box displays a light blue stripe across the top, as shown at the left of Figure 7-26 (the distinction between Microsoft signed images and other signers has been removed in Windows 10). If the image is unsigned, the stripe becomes yellow, and the prompt stresses the unknown origin of the image (see the right of Figure 7-26). The elevation dialog box shows the image's icon, description, and publisher for digitally signed images, but it shows only the file name and "Publisher: Unknown" for unsigned images. This difference makes it harder for malware to mimic the appearance of legitimate software. The Show More Details link at the bottom of the dialog box expands it to show the command line that will be passed to the executable if it launches.

User Account Control X	User Account Control >
Do you want to allow this app to make changes to your device?	Do you want to allow this app from an unknown publisher to make changes to your device?
Registry Editor Verified publisher: Microsoft Windows Show more details	SystemFormatter.exe Publisher: Unknown File origin: Hard drive on this computer Show more details
Yes No	Yes No

FIGURE 7-26 AAC UAC elevation dialog boxes based on image signature.

The OTS consent dialog box, shown in Figure 7-27, is similar, but prompts for administrator credentials. It will list any accounts with administrator rights.

Do ye	ount Control ou want to allow t ges to your device	
DN	Windows Comman	id Processor
Verifie	d publisher: Microsoft V	lindows
Show	more details	
To con	tinue, enter an admin u	ser name and password.
0	Pavel	
0	Password	
	WIN10X86VM\Pavel	
	Yes	No

FIGURE 7-27 OTS consent dialog box.

If a user declines an elevation, Windows returns an access-denied error to the process that initiated the launch. When a user agrees to an elevation by either entering administrator credentials or clicking Yes, AIS calls CreateProcessAsUser to launch the process with the appropriate administrative identity. Although AIS is technically the parent of the elevated process, AIS uses new support in the CreateProcessAsUser API that sets the process's parent process ID to that of the process that originally launched it. That's why elevated processes don't appear as children of the AIS service-hosting process in tools such as Process Explorer that show process trees. Figure 7-28 shows the operations involved in launching an elevated process from a standard user account.




FIGURE 7-28 Launching an administrative application as a standard user.

### **Requesting administrative rights**

There are a number of ways the system and applications identify a need for administrative rights. One that shows up in the Explorer user interface is the Run as Administrator context menu command and shortcut option. These items also include a blue and gold shield icon that should be placed next to any button or menu item that will result in an elevation of rights when it is selected. Choosing the Run as Administrator command causes Explorer to call the ShellExecute API with the runas verb.

The vast majority of installation programs require administrative rights, so the image loader, which initiates the launch of an executable, includes installer-detection code to identify likely legacy installers. Some of the heuristics it uses are as simple as detecting internal version information or whether the image has the words *setup*, *install*, or *update* in its file name. More sophisticated means of detection involve scanning for byte sequences in the executable that are common to third-party installation wrapper utilities. The image loader also calls the application-compatibility library to see if the target executable requires administrator rights. The library looks in the application-compatibility database to see whether the executable has the RequireAdministrator or RunAsInvoker compatibility flag associated with it.

The most common way for an executable to request administrative rights is for it to include a requestedExecutionLevel tag in its application manifest file. The element's level attribute can have one of the three values shown in Table 7-17.

Elevation Level	Meaning	Usage
As invoker	No need for administrative rights; never ask for elevation.	Typical user applications that don't need administrative privileges—for example, Notepad.
Highest available	Request approval for highest rights available. If the user is logged on as a standard user, the process will be launched as invoker; other- wise, an AAM elevation prompt will appear, and the process will run with full administra- tive rights.	Applications that can function without full administrative rights but expect users to want full access if it's easily accessible. For example, the Registry Editor, Microsoft Management Console, and the Event Viewer use this level.
Require administrator	Always request administrative rights. An OTS elevation dialog box prompt will be shown for standard users; otherwise, AAM.	Applications that require administrative rights to work, such as the Firewall Settings Editor, which affects system-wide security.

 TABLE 7-17
 Requested elevation levels

The presence of the trustInfo element in a manifest (which you can see in the manifest dump of eventvwr.exe) denotes an executable that was written with support for UAC and the requestedExecutionLevel element nests within it. The uiAccess attribute is where accessibility applications can use the UIPI bypass functionality mentioned earlier.

```
C:\>sigcheck -m c:\Windows\System32\eventvwr.exe
. . .
<trustInfo xmlns="urn:schemas-microsoft-com:asm.v3">
    <security>
        <requestedPrivileges>
            <requestedExecutionLevel
                level="highestAvailable"
                uiAccess="false"
            />
        </requestedPrivileges>
    </security>
</trustInfo>
<asmv3:application>
   <asmv3:windowsSettings xmlns="http://schemas.microsoft.com/SMI/2005/WindowsSettings">
        <autoElevate>true</autoElevate>
   </asmv3:windowsSettings>
</asmv3:application>
. . .
```

#### **Auto-elevation**

In the default configuration (see the next section for information on changing this), most Windows executables and control panel applets do not result in elevation prompts for administrative users, even if they need administrative rights to run. This is because of a mechanism called *auto-elevation*. Auto-elevation is intended to preclude administrative users from seeing elevation prompts for most of their work; the programs will automatically run under the user's full administrative token.

Auto-elevation has several requirements. One is that the executable in question must be considered as a Windows executable. This means it must be signed by the Windows publisher (not just by Microsoft; oddly, they are not the same—Windows-signed is considered more privileged than Microsoft-signed). It must also be in one of several directories considered secure: %SystemRoot% System32 and most of its subdirectories, %Systemroot%\Ehome, and a small number of directories under %ProgramFiles% (for example, those containing Windows Defender and Windows Journal).

There are additional requirements, depending on the type of executable. EXE files other than Mmc. exe auto-elevate if they are requested via an autoElevate element in their manifest. The manifest shown earlier of eventvwr.exe in the previous section illustrates this.

Mmc.exe is treated as a special case because whether it should auto-elevate or not depends on which system management snap-ins it is to load. Mmc.exe is normally invoked with a command line specifying an MSC file, which in turn specifies which snap-ins are to be loaded. When Mmc.exe is run from a protected administrator account (one running with the limited administrator token), it asks Windows for administrative rights. Windows validates that Mmc.exe is a Windows executable and then checks the MSC. The MSC must also pass the tests for a Windows executable, and furthermore must be on an internal list of auto-elevate MSCs. This list includes nearly all MSC files in Windows.

Finally, COM (out-of-process server) classes can request administrative rights within their registry key. To do so requires a subkey named Elevation with a DWORD value named Enabled, having a value of 1. Both the COM class and its instantiating executable must meet the Windows executable requirements, although the executable need not have requested auto-elevation.

### **Controlling UAC behavior**

UAC can be modified via the dialog box shown in Figure 7-29. This dialog box is available under Change User Account Control Settings. Figure 7-29 shows the control in its default position.

Alwa	ys notify	
-	-	Notify me only when apps try to make changes to my computer (default)
-	2	<ul> <li>Don't notify me when I make changes to Windows settings</li> </ul>
-	-	
-		Recommended if you use familiar apps and visit familiar websites.
Neve	r notify	

FIGURE 7-29 User Account Control Settings dialog box.

The four possible settings have the effects described in Table 7-18.

The third position is not recommended because the UAC elevation prompt appears not on the Secure Desktop but on the normal user's desktop. This could allow a malicious program running in the same session to change the appearance of the prompt. It is intended for use only in systems where the video subsystem takes a long time to dim the desktop or is otherwise unsuitable for the usual UAC display.

#### TABLE 7-18 UAC options

Slider Position	When administrative user not run	Remarks	
	attempts to change Windows settings (for example, use cer- tain Control Panel applets)	attempts to install software or run a program whose manifest calls for elevation, or uses Run as Administrator	
Highest position (Always Notify)	A UAC elevation prompt appears on the Secure Desktop.	A UAC elevation prompt appears on the Secure Desktop.	This was the Windows Vista behavior.
Second position	UAC elevation occurs automatically with no prompt or notification.	A UAC elevation prompt appears on the Secure Desktop.	Windows default setting.
Third position	UAC elevation occurs automatically with no prompt or notification.	A UAC elevation prompt appears on the user's normal desktop.	Not recommended.
Lowest position (Never Notify)	UAC is turned off for administrative users.	UAC is turned off for administrative users.	Not recommended.

The lowest position is strongly discouraged because it turns UAC off completely as far as administrative accounts are concerned. Prior to Windows 8, all processes run by a user with an administrative account are run with the user's full administrative rights in effect; there is no filtered admin token. Starting with Windows 8, UAC cannot be turned off completely, because of the AppContainer model. Admin users won't be prompted for elevation, but processes will not elevate unless required to do so by the manifest or launched from an elevated process.

The UAC setting is stored in four values in the registry under HKLM\SOFTWARE\Microsoft\ Windows\CurrentVersion\Policies\System, as shown in Table 7-19. ConsentPromptBehaviorAdmin controls the UAC elevation prompt for administrators running with a filtered admin token, and ConsentPromptBehaviorUser controls the UAC prompt for users other than administrators.

Slider Position	ConsentPrompt BehaviorAdmin	ConsentPrompt BehaviorUser	EnableLUA	PromptOnSecureDesktop
Highest position (Always Notify)	2 (display AAC UAC elevation prompt)	3 (display OTS UAC elevation prompt)	1 (enabled)	1 (enabled)
Second position	5 (display AAC UAC elevation prompt, except for changes to Windows settings)	3	1	1
Third position	5	3	1	0 (disabled; UAC prompt appears on user's normal desktop)
Lowest position (Never Notify)	0	3	0 (disabled; logins to administrative accounts do not create a restricted admin access token)	0

# **Exploit mitigations**

Throughout this chapter, we've seen a number of technologies that help protect the user, guarantee the code-signing properties of executable code, and lock down access to resources through sandboxing. At the end of the day, however, all secure systems have failure points, all code has bugs, and attackers leverage increasingly complex attacks to exploit them. A security model in which all code is assumed to be bug-free, or in which a software developer assumes all bugs will eventually be found and fixed, is destined to fail. Additionally, many security features that provide code-execution "guarantees" do so at a cost of performance or compatibility, which may be unacceptable in such scenarios.

A much more successful approach is to identify the most common techniques used by attackers, as well as employ an internal "red team" (that is, an internal team attacking its own software) to discover new techniques before attackers do and to implement mitigations against such techniques. (These mitigations can be as simple as moving some data around or as complex as employing Control Flow Integrity [CFI] techniques.) Because vulnerabilities can number in the thousands in a complex code base such as Windows, but exploit techniques are limited, the idea is to make large classes of bugs very difficult (or in some cases, impossible) to exploit, without worrying about finding all the bugs.

# **Process-mitigation policies**

While individual applications can implement various exploit mitigations on their own (such as Microsoft Edge, which leverages a mitigation called *MemGC* to avoid many classes of memory-corruption attacks), this section will cover mitigations that are provided by the operating system to all applications or to the system itself to reduce exploitable bug classes. Table 7-20 describes all mitigations in the latest version of Windows 10 Creators Update, the type of bug class they mitigate against, and mechanisms to activate them.

Mitigation Name	Use Case	Enabling Mechanism
ASLR Bottom Up Randomization	This makes calls to VirtualAlloc subject to ASLR with 8-bit entropy, including stack-base randomization.	This is set with the PROCESS_ CREATION_MITIGATION_POLICY_ BOTTOM_UP_ASLR_ALWAYS_ON process-creation attribute flag.
ASLR Force Relocate Images	This forces ASLR even on binaries that do not have the /DYNAMICBASE linker flag.	This is set with SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_FORCE_ RELOCATE_IMAGES_ALWAYS_ON process-creation flag.
High Entropy ASLR (HEASLR)	This significantly increases entropy of ASLR on 64-bit images, increasing bottom-up randomization to up to 1 TB of variance (that is, bottom-up allo- cations may start anywhere between 64 KB and 1 TB into the address space, giving 24 bits of entropy).	Must be set through /HIGHENTROPYVA at link time or the PROCESS_CREATION_MITIGATION_ POLICY_HIGH_ENTROPY_ASLR_ ALWAYS_ON process-creation attribute flag.

TABLE 7-20	Process	mitigation	options
			0 0 0 0 0 0 0

Mitigation Name	Use Case	Enabling Mechanism
ASLR Disallow Stripped Images	This blocks the load of any library without relocations (linked with the / FIXED flag) when combined with ASLR Force Relocate Images.	This is set with SetProcessMitigationPolicy or with the PROCESS_CREATION_ MITIGATION_POLICY_FORCE_ RELOCATE_IMAGES_ALWAYS_ON_REQ_ RELOCS process-creation flag.
DEP: Permanent	This prevents the process from dis- abling DEP on itself. Only relevant on x86. Only relevant on 32-bit applica- tions (and/or under WoW64)	This is set with the SetProcessMitigationPolicy, process-creation attribute or with SetProcessDEPPolicy.
DEP: Disable ATL Thunk Emulation	This prevents legacy ATL library code from executing ATL thunks in the heap, even if a known compatibility issue. Only relevant on 32-bit applica- tions (and/or under WoW64)	This is set with the SetProcessMitigationPolicy, process-creation attribute or with SetProcessDEPPolicy.
SEH Overwrite Protection (SEHOP)	This prevents structure exception handlers from being overwritten with incorrect ones, even if the image was not linked with Safe SEH (/SAFESEH). Only relevant on 32-bit applications (and/or under WoW64).	This can be set with SetProcessDEPPolicy or with the PROCESS_CREATION_MITIGATION_ POLICY_SEHOP_ENABLE process- creation flag.
Raise Exception on Invalid Handle	This helps catch handle reuse (use- after-handle-close) attacks in which a process uses a handle that is no longer the handle it expected (for example: SetEvent on a mutex) by crashing the process instead of returning a failure that the process might ignore.	This is set with SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_STRICT_ HANDLE_CHECKS_ALWAYS_ON process-creation attribute flag.
Raise Exception on Invalid Handle Close	This helps catch handle reuse (double- handle-close) attacks in which a pro- cess is attempting to close a handle that has already been closed, sug- gesting that a different handle may potentially be used in other scenarios, in which an exploit would be success- ful, ultimately limiting its universal effectiveness.	Undocumented, and can only be set through an undocumented API.
Disallow Win32k System Calls	This disables all access to the Win32 kernel-mode subsystem driver, which implements the Window Manager (GUI) and Graphics Device Interface (GDI) and DirectX. No system calls to this component will be possible.	This is set with SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_WIN32K_ SYSTEM_CALL_DISABLE_ALWAYS_ON process-creation attribute flag.
Filter Win32k System Calls	This filters access to the Win32k kernel-mode subsystem driver only to certain APIs allowing simple GUI and Direct X access, mitigating many of the possible attacks, without com- pletely disabling availability of the GUI/GDI services.	This is set through an internal process- creation attribute flag, which can define one out of three possible sets of Win32k filters that are enabled. However, because the filter sets are hard-coded, this mitigation is re- served for Microsoft internal usage.

Mitigation Name	Use Case	Enabling Mechanism
Disable Extension Points	This prevents a process from loading an input method editor (IME), a Windows hook DLL (SetWindowsHookEx), an app- initialization DLL (AppInitDlls value in the registry), or a Winsock layered service provider (LSP).	This is set with SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_EXTENSION_ POINT_DISABLE_ALWAYS_ON process-creation attribute flag.
Arbitrary Code Guard (CFG)	This prevents a process from allocating executable code or from changing the permission of existing executable code to make it writeable. It can be config- ured to allow a particular thread inside the process to request this capability or to allow a remote process from disabling this mitigation, which are not supported from a security point of view.	This is set with SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_PROHIBIT_ DYNAMIC_CODE_ALWAYS_ON and PROCESS_CREATION_MITIGATION_ POLICY_PROHIBIT_DYNAMIC_ CODE_ALWAYS_ON_ALLOW_OPT_OUT process-creation attribute flags.
Control Flow Guard (CFG)	This helps prevent memory corruption vulnerabilities from being used to hijack control flow by validating the target of any indirect CALL or JMP instruction against a list of valid expected target functions. Part of Control Flow Integrity (CFI) mechanisms described in the next section.	The image must be compiled with the /guard: cf option, and linked with the /guard: cf option. It can be set with the PROCESS_ CREATION_MITIGATION_POLICY_ CONTROL_FLOW_GUARD_ALWAYS_ON process-creation attribute flag in case the image does not support it, but CFG enforcement is still desirable for other images loading in the process.
CFG Export Suppression	This strengthens CFG by suppressing indirect calls to the exported API table of the image.	The image must be compiled with /guard: exportsuppress, and can also be configured through SetProcessMitigationPolicy or with the PROCESS_CREATION_ MITIGATION_POLICY_CONTROL_ FLOW_GUARD_EXPORT_SUPPRESSION process-creation attribute flag.
CFG Strict Mode	This prevents the loading of any image library within the current process that was not linked with the /guard:cf option.	This is set through SetProcessMitigationPolicy or with the PROCESS_CREATION_ MITIGATION_POLICY2_STRICT_ CONTROL_FLOW_GUARD_ALWAYS_ON process-creation attribute flag.
Disable Non System Fonts	This prevents the loading of any font files that have not been registered by Winlogon at user logon time, after being installed in the C:\windows\fonts directory.	This is set through SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_ FONT_DISABLE_ALWAYS_ON process-creation attribute flag.
Microsoft-Signed Binaries Only	This prevents the loading of any image library within the current process that has not been signed by a Microsoft CA—issued certificate.	This is set through the PROCESS_CREATION_ MITIGATION_POLICY_BLOCK_NON_ MICROSOFT_BINARIES_ALWAYS_ON process-attribute flag at startup time.

TABLE 7-20	Process mitigation options	(continued)
------------	----------------------------	-------------

Mitigation Name	Use Case	Enabling Mechanism
Store-Signed Binaries Only	This prevents the loading of any image library within the current process that has not been signed by the Microsoft Store CA.	This is set through the PROCESS_CREATION_ MITIGATION_POLICY_BLOCK_NON_ MICROSOFT_BINARIES_ALLOW_STORE process attribute flag at startup time.
No Remote Images	This prevents the loading of any im- age library within the current process that is present on a non-local (UNC or WebDAV) path.	This is set through SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_IMAGE_ LOAD_NO_REMOTE_ALWAYS_ON process-creation attribute flag.
No Low IL Images	This prevents the loading of any image library within the current process that has a mandatory label below medium (0x2000).	This is set through SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_IMAGE_ LOAD_NO_LOW_LABEL_ALWAYS_ON process-creation flag. It can also be set through a resource claim ACE called IMAGELOAD on the file of the process being loaded.
Prefer System32 Images	This modifies the loader's search path to always look for the given image library being loaded (through a rela- tive name) in the %SystemRoot%\ System32 directory, regardless of the current search path.	This is set through SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY_IMAGE_LOAD_ PREFER_SYSTEM32_ALWAYS_ON process-creation attribute flag.
Return Flow Guard (RFG)	This helps prevent additional classes of memory-corruption vulnerabilities that affect control flow by validating, before the execution of a RET instruc- tion, that the function was not called through a return-oriented program- ming (ROP) exploit by not having begun its execution correctly or by executing on an invalid stack. This is part of the Control Flow Integrity (CFI) mechanisms.	Currently still being implemented in a robust and performant way, this mitigation is not yet available, but is included here for completeness.
Restrict Set Thread Context	This restricts the modification of the current thread's context.	Currently disabled pending the availability of RFG, which makes the mitigation more robust, this mitiga- tion may appear in a future version of Windows. It is included here for completeness.
Loader Continuity	This prohibits the process from dy- namically loading any DLLs that do not have the same integrity level as the process, in cases where a signature policy mitigation above could not be enabled at startup time due to com- patibility concerns. This specifically targets cases of DLL planting attacks.	This is set through SetProcessMitigationPolicy or the PROCESS_CREATION_ MITIGATION_POLICY2_LOADER_ INTEGRITY_CONTINUITY_ALWAYS_ON process-creation attribute flag.

Mitigation Name	Use Case	Enabling Mechanism
Heap Terminate On Corruption	This disables the Fault Tolerant Heap (FTH) and the raising of a continuable exception in the case of heap cor- ruption by terminating the process instead. This prevents the use of heap corruption as a way to force an attacker-controlled exception handler from executing, or in cases where the program ignores the heap exception, or cases where the exploit only some- times causes heap corruption (limiting its universal effectiveness or reliability).	This is set through HeapSetInformation or by using the PROCESS_CREATION_MITIGATION_ POLICY_HEAP_TERMINATE_ALWAYS_ ON process-creation attribute flag.
Disable Child Process Creation	This prohibits the creation of child processes by marking the token with a special restriction, which should stop any other component from creating a process while impersonating the to- ken of this process (for example, WMI process creation, or a kernel compo- nent creating the process).	This is set through the PROCESS_ CREATION_CHILD_PROCESS_ RESTRICTED process-creation attribute flag. It can be overridden to allow packaged (UWP) applica- tions with the PROCESS_CREATION_ DESKTOP_APPX_OVERRIDE flag.
All Application Packages Policy	This makes an application running under an AppContainer unable to access resources that have an ALL APPLICATION PACKAGES SID pres- ent, as was explained earlier in the "AppContainers" section. The presence of an ALL RESTRICTED APPLICATION PACKAGES SID will be required in- stead. Sometimes referred to as Less Privileged App Container (LPAC).	This is set through the PROC_THREAD_ ATTRIBUTE_ALL_APPLICATION_ PACKAGES_POLICY process-creation attribute.

TABLE 7-20 Process mitigation options (continued)

Note that it is also possible to some of these mitigations on a per-application or per-system basis without the cooperation of the application developer. To do so, open the Local Group Policy Editor. Then expand **Computer Configuration**, then **Administrative Templates**, then **System**, and finally **Mitigation Options** (see Figure 7-30). In the Process Mitigation Options dialog box, enter the appropriate bit-number value that corresponds to the mitigations being enabled, using **1** to enable a mitigation, **0** to disable it, or **?** to leave it to its default or process-requested value (again, see Figure 7-30). The bit numbers are taken from the PROCESS\_MITIGATION\_POLICY enumeration found in the Winnt.h header file. This will result in the appropriate registry value being written in the Image File Execution Options (IFEO) key for the entered image name. Unfortunately the current version of Windows 10 Creators Update and earlier will strip out many of the newer mitigations. You can avoid this by manually setting the REG\_DWORD MitigationOptions registry value.

🔶 📶 📾 📓 📷 🐨						
Local Computer Policy			sted Font ss Mitigat	Blocking ion Options	State Not configured Not configured	Comment No No
Administrative Templates	Process	Mitigation	Options			- 0
Control Panel		Mitigation			Previous Setting Mexibelin	8
Start Menu and Taskbar	O Not Con	figured	Comme	it		
Comparison      Compariso	Enabled					
App-V     Audit Process Creation     Credentials Delegation     Device Guard	O Disabled		Support	ed on: At least Window	s Server 2016, Windows 10	
Device Installation     Device Redirection     Disk NV Cache	Options:				Help:	
Disk Quotas Distributed COM	Process Mit	The second se		Show		individua
Driver Installation     Early Laurch Antimalware     Enhanced Storage Access			how Cont Process N	ents itigation Options	- 0	× penforce he ing es of flag
File Classification Infrastructure		ſ	1	alue name	Value	g is forced
File Share Shadow Copy Provider Filesystem			./ m	paint.exe	22222212222122221112222112222	ire
Folder Redirection			•			NABLE
<ul> <li>Group Policy</li> <li>Internet Communication Manageme</li> </ul>						ild
> iscsi						
MDC KDC						
Kerberos Locale Services						HUNK_EN
Logon						ocess.
Mitigation Options						pt NX ATL)
	1.1	-	2		provide a second second second	
> I Net Logon > I Power Management					OK Cance	4 11

FIGURE 7-30 Customizing process-mitigation options.

# **Control Flow Integrity**

Data Execution Prevention (DEP) and Arbitrary Code Guard (ACG) make it hard for exploits to place executable code on the heap or stack, to allocate new executable code, or to change existing executable code. As a result, memory/data-only attacks have become more interesting. Such attacks allow the modification of portions of memory to redirect control flow, such as modifying return addresses on the stack or indirect function pointers stored in memory. Techniques such as return-oriented-programming (ROP) and jump-oriented-programming (JOP) are often used to violate the regular code flow of the program and redirect it to known locations of interesting code snippets ("gadgets").

Because such snippets are often present in the middle or end of various functions, when control flow is redirected in this way, it must be redirected into the middle or end of a legitimate function. By employing Control Flow Integrity (CFI) technologies—which can, for example, validate that the target of an indirect JMP or CALL instruction is the beginning of a real function, or that a RET instruction is pointing to an expected location, or that a RET instruction is issued after the function was entered through its beginning—the operating system and compiler can detect and prevent most classes of such exploits.

## **Control Flow Guard**

Control Flow Guard (CFG) is an exploit-mitigation mechanism first introduced in Windows 8.1 Update 3 that exists in enhanced version in Windows 10 and Server 2016, with further improvements released on various updates (up to and including the latest Creators Update). Originally implemented only for user-mode code, CFG now also exists as Kernel CFG (KCFG) on the Creators Update. CFG addresses the indirect CALL/JMP part of CFI by verifying that the target of an indirect call is at the start of a known function (more on that momentarily). If the target is not at the start of a known function, the process is simply terminated. Figure 7-31 shows the conceptual operation of CFG.




FIGURE 7-31 Conceptual view of Control Flow Guard.

CFG requires the cooperation of a supported compiler that will add the call to the validation code before indirect changes in control flow. The Visual C++ compiler has an option, /guard:cf, that must be set for images (or even on a C/C++ source file level) to be built with CFG support (this option is also available in Visual Studio's GUI in the C/C++/Code Generation/Control Flow Guard setting in the project's properties). This setting should also be set in the linker settings, as both components of Visual Studio are required to collaborate to support CFG.

Once those settings are present, images (EXEs and DLLs) that are compiled with CFG-enabled indicate this in their PE header. In addition, they contain a list of functions that are the valid indirect control flow targets in a .gfids PE section (by default merged by the linker with the .rdata section). This list is built by the linker and contains the relative virtual address (RVA) of all functions in the image. This includes those that might not be called by an indirect call by the code present in the image because there's no way of knowing if outside code does not somehow legitimately know the address of a function and is attempting to call it. This can be especially true of exported functions, which can be called after obtaining their pointer through GetProcAddress.

That being said, programmers can use a technique called *CFG suppression*, which is supported through the DECLSPEC\_GUARD\_SUPRESS annotation, and which marks the function in the table of valid functions with a special flag indicating that the programmer never expects such a function to be the target of any indirect call or jump.

Now that a table of valid function targets exists, all that a simple validation function would need to do is to compare the target of the CALL or JMP instruction with one of the functions in the table. Algorithmically, this would result in an O(n) algorithm, where the number of functions needed to check would be equivalent, in the worst case, to the number of functions in the table. Clearly, linearly scanning an entire array during every single indirect change in control flow would bring a program to its knees, so operating system support is needed to perform CFG checks efficiently. We'll see in the next section how Windows can achieve this.

## **EXPERIMENT: Control Flow Guard information**

The DumpBin Visual Studio tool can show some basic CFG information. The following dumps header and loader configuration information for Smss:

```
c:\> dumpbin /headers /loadconfig c:\windows\system32\smss.exe
Microsoft (R) COFF/PE Dumper Version 14.00.24215.1
Copyright (C) Microsoft Corporation. All rights reserved.
Dump of file c:\windows\system32\smss.exe
PE signature found
File Type: EXECUTABLE IMAGE
FILE HEADER VALUES
            8664 machine (x64)
               6 number of sections
        57899A7D time date stamp Sat Jul 16 05:22:53 2016
               O file pointer to symbol table
               0 number of symbols
              FO size of optional header
              22 characteristics
                   Executable
                   Application can handle large (>2GB) addresses
OPTIONAL HEADER VALUES
             20B magic # (PE32+)
           14.00 linker version
           12800 size of code
            EC00 size of initialized data
               0 size of uninitialized data
            1080 entry point (0000000140001080) NtProcessStartupW
            1000 base of code
       140000000 image base (0000000140000000 to 000000140024FFF)
            1000 section alignment
             200 file alignment
           10.00 operating system version
           10.00 image version
           10.00 subsystem version
               0 Win32 version
           25000 size of image
             400 size of headers
           270FD checksum
              1 subsystem (Native)
            4160 DLL characteristics
```

High Entropy Virtual Addresses Dvnamic base NX compatible Control Flow Guard Section contains the following load config: 000000D0 size O time date stamp 0.00 Version 0 GlobalFlags Clear 0 GlobalFlags Set O Critical Section Default Timeout 0 Decommit Free Block Threshold 0 Decommit Total Free Threshold 000000000000000 Lock Prefix Table O Maximum Allocation Size 0 Virtual Memory Threshold O Process Heap Flags 0 Process Affinity Mask 0 CSD Version 0800 Dependent Load Flag 00000000000000 Edit List 000000140020660 Security Cookie 00000001400151C0 Guard CF address of check-function pointer 00000001400151C8 Guard CF address of dispatch-function pointer 00000001400151D0 Guard CF function table 2A Guard CF function count 00010500 Guard Flags CF Instrumented FID table present Long jump target table present 0000 Code Integrity Flags 0000 Code Integrity Catalog 00000000 Code Integrity Catalog Offset 00000000 Code Integrity Reserved 000000000000000 Guard CF address taken IAT entry table 0 Guard CF address taken IAT entry count 000000000000000 Guard CF long jump target table 0 Guard CF long jump target count 00000000000000 Dynamic value relocation table Guard CF Function Table Address \_\_\_\_\_ 0000000140001010 \_TlgEnableCallback 0000000140001070 SmpSessionComplete 0000000140001080 NtProcessStartupW 0000000140001B30 SmscpLoadSubSystemsForMuSession 0000000140001D10 SmscpExecuteInitialCommand 000000140002FB0 SmpExecPgm

0000000140003620 SmpStartCsr 00000001400039F0 SmpApiCallback 0000000140004E90 SmpStopCsr

. . .

The CFG-related information is marked in bold in the preceding output. We will discuss that shortly. For now, open Process Explorer, right-click the process column header, choose **Select Columns.** Then, in the Process Image tab, select the **Control Flow Guard** check box. Also select **Virtual Size** in the Process Memory tab. You should see something like this:

File Options View Process Fil		Help				A
Process	PID	CPU	Control Flow Guard	Virtual Size	Private Bytes	Working Set
Architect Manager.exe	4380			100,208 K	3,748 K	6,768 K M
armsvc.exe	4164			58,232 K	1,280 K	1,376 K A
audiodg.exe	9560		CFG	2,147,533,904 K	6,128 K	11,015 K V
BrcmMgmtAgent.exe	4444			57,836 K	4,364 K	4,864 K E
Calculator.exe	15864	Suspen	S	330,980 K	28,464 K	580 K
CfgTest.exe	16284	102203	CFG	6,442,495,355 K	780 K	224 K
conhost.exe	2512		CFG	2,147,545,712 K	1,156 K	956 K C
conhost.exe	9284		CFG	2,147,574,076 K	1,904 K	1,764 K K
conhost.exe	14428	< 0.01	CFG	2,147,574,276 K	1,924 K	2,252 K
conhost.exe	6636		CFG	2,147,574,275 K	1,944 K	1,804 K (
conhost.exe	12632		CFG	2,147,575,300 K	2,012 K	2,720 K
conhost.exe	19064		CFG	2,147,562,792 K	1,412 K	5,576 K (
Creator-ws.exe	4388	< 0.01		72,084 K	2,536 K	4,320 K F
CSrss.exe	860		CFG	2,147,549,860 K	1,688 K	1,872 K (
CSTSS.exe	980	0.24	CFG	2,147,585,704 K	2,816 K	3,948 K (
CxMonSvc.exe	3564			525,916 K	26.880 K	3.288 K
CxUtilSvc.exe	4112			64.412 K	1.668 K	2.240 K L
asHost.exe	3488		CFG	2,147,531,188 K	5,992 K	7,940 K I
devenv.exe	7000	0.28		1,140,960 K	429,576 K	178,516 K
C devenv.exe	14900	1.15		1,573,600 K	789,588 K	427,936 K I
devenv.exe	1900	0.93		1,203,272 K	466,780 K	314,560 K
C devenv.exe	22048	0.96		1,380,848 K	555,288 K	408,700 K I
devenv.exe	22780	0.90		1,433,360 K	583,436 K	603,836 K I
I dllhost.exe	3240		CFG	2,147,829,064 K	5,060 K	6,976 K (
DPAgent.exe	9552			277,984 K	26,756 K	9,880 K I
Q DpAgent.exe	10000			44.712.14	07.4 17	200 V 1

You should see most Microsoft-provided processes were built with CFG (including Smss, Csrss, Audiodg, Notepad, and many others). The virtual size for CFG-built processes is surprisingly high. Recall that the virtual size indicates the total address space used in the process, whether that memory is committed or reserved. In contrast, the Private Bytes column shows the private committed memory and is not even remotely close to the virtual size (although the virtual size includes non-private memory as well). For 64-bit processes, the virtual size is at least 2 TB, which we will shortly be able to rationalize.

## The CFG bitmap

As you saw earlier, forcing the program to iterate through a list of function calls every few instructions would not be practical. Therefore, instead of an algorithm that requires linear time O(n), performance requirements dictate that an O(1) algorithm be used instead—one where a constant lookup time is used, regardless of how many functions are present in the table. This constant lookup time should be as small as possible. A clear winner of such a requirement would be an array that is indexable by the target function's address, which is an indication if this address is valid or not (such as a simple BOOL). With a 128 TB of possible addresses, though, such an array would itself have to be 128 TB \* sizeof(BOOL), which is an unacceptable storage size—bigger than the address space itself. Can we do better?

First, we can leverage the fact that compilers ought to generate x64 function code on 16-byte boundaries. This reduces the size to the required array to only 8 TB \* sizeof(BOOL). But using an entire BOOL (which is 4 bytes in the worst case or 1 byte in the best) is extremely wasteful. We only need one state, valid or invalid, which only needs to use 1 bit. This makes the calculation 8 TB / 8, or simply 1 TB. Unfortunately, however, there's a snag. There's no guarantee that the compiler will generate *all* functions on a 16-byte binary. Hand-crafted assembly code and certain optimizations might violate this rule. As such, we'll have to figure out a solution. One possible option is to simply use another bit to indicate if the function begins *somewhere* on the next 15 bytes instead of on the 16-byte boundary itself. Thus, we have the following possibilities:

- **{0, 0}** No valid function begins inside this 16-byte boundary.
- {1, 0} A valid function begins exactly on this aligned 16-byte address.
- {1, 1} A valid function begins somewhere inside of this 16-byte address.

Thanks to this setup, if the attacker attempts to call inside a function that was marked as 16-byte aligned by the linker, the 2-bit state will be {1, 0}, while the required bits (that is, bits 3 and 4) in the address will be {1, 1} as the address won't be 16-byte aligned. Therefore, an attacker will only be able to call an arbitrary instruction in the first 16 bytes of the function if the linker did not generate the function aligned in the first place (bits would then be {1, 1}, as shown above). Even then, this instruction must somehow be useful to the attacker without crashing the function (typically some sort of stack pivot or gadget that ends in a ret instruction).

With this understanding in mind, we can apply the following formulas to compute the size of the CFG bitmap:

- **32-bit application on x86 or x64** 2 GB / 16 \* 2 = 32 MB
- 32-bit application with /LARGEADDRESSAWARE, booted in 3 GB mode on x86 3 GB / 16 \*
   2 = 48 MB
- **64-bit application** 128 TB / 16 \* 2 = 2 TB
- 32-bit application with /LARGEADDRESSAWARE, on x64 4 GB / 16 \* 2 = 64 MB, plus the size of the 64-bit bitmap, which is needed to protect 64-bit Ntdll.dll and WoW64 components, so 2 TB + 64MB

Allocating and filling out 2 TB of bits on every single process execution is still a tough performance overhead to swallow. Even though we have fixed the execution cost of the indirect call itself, process startup cannot be allowed to take so long, and 2 TB of committed memory would exhaust the commit limit instantly. Therefore, two memory-saving and performance-helping tricks are used.

First, the memory manager will only reserve the bitmap, basing itself on the assumption that the CFG validation function will treat an exception during CFG bitmap access as an indication that the bit state is {0,0}. As such, as long as the region contains 4 KB of bit states that are all {0, 0}, it can be left as reserved, and only pages with at least one bit set {1, X} need to be committed.

Next, as described in the ASLR section of Chapter 5, "Memory management," the system performs the randomization/relocation of libraries typically only once at boot, as a performance-saving measure to avoid

CHAPTER 7 Security 745

From the Library of Octavian Mustafa

repeated relocations. As such, after a library that supports ASLR has been loaded once at a given address, it will always be loaded at that same address. This also therefore means that once the relevant bitmap states have been calculated for the functions in that library, they will be identical in all other processes that also load the same binary. As such, the memory manager treats the CFG bitmap as a region of pagefile-backed shareable memory, and the physical pages that correspond to the shared bits only exist in RAM once.

This reduces the cost of the committed pages in RAM and means that only the bits corresponding to private memory need to be calculated. In regular applications, private memory is not executable except in the copy-on-write case where someone has patched a library (but this will not happen at image load), so the cost of loading an application, if it shares the same libraries as other previously launched applications, is almost nil. The next experiment demonstrates this.

## **EXPERIMENT: Control Flow Guard bitmap**

Open the VMMap tool and select a Notepad process. You should see a large reserved block in the Sharable section like so:

File Edit View	w Tools Options He	elp									
Process: PID:	notepad.exe 17588										
Committed:										126,1	192
Private Bytes:			_	_						2,5	-
											Ē
Working Set:										5,3	.,
trocking sets										910	197
Туре	Size	Committed	Prh	ate	Total WS	Private WS	Shareable WS	Shared	WS	Locked	N
otal	2.147.611.772 K	126,192 K		24 K	5.372 K	1,496 K	3,8761		52 K		
nage	65,652 K	65,652 K		68 K	3,176 K	412 K	2,764 1		52 K		
lapped File	22,196 K	22,196 K									
hateable					1,104 K				95 K		
enp	3,104 K	856 K	7	92 K	616 K	612 K	41	ç			
lanaged Heap											
tack	512 K	80 K		BD K	12 K	12 K					
tvate Data	3,280 K	40 K		40 K	20 K	16 K	41	(	4 K		
age Table	444 K	544 K	4	64 K	444 K	444 K					
nusable	3,088 K										
ree	135,291,342,080 K										
	۲.										
	12		-			10200000		12	725		
kddress .	Туре		Size	Committed	Private	Total WS	Private WS	Shareable WS	Share	Lock	
	40000 Shareable	2,147,4	183,648 K	25,496 K		208 K		208 K			
	A0000 Shamable		20,480 K	4,380 K		100 K		100 K	100 K		
	10000 Shareable		4.092 K	4,092 K							
	80000 Shareable		1,568 K	252 K		60 K		60 K			
	10000 Shamable		1,540 K	1.540 K		504 K		504 K			
	10000 Shareable		1.024 K	20 K		4 K		4 K			
	C0000 Shareable		812 K	812 K		168 K		168 K			
	10000 Shamable 70000 Shareable		140 K	140 K		8K		8 K			
	70000 Shareable		88 K 16 K	88 K 16 K		20 K 12 K		20 K 12 K			
	90000 Shareable		16 K	16 K		SK		12 K			
	50000 Shareable		16 K	16 K		88		8 K	88		
0.000095030410	> <		10 0	10 /5							
	2.6										
						Tesleo.	Heap Aloc		Dige	Trace.	

You can sort the lower pane by size and quickly locate the large chunk used for the CFGBitmap, as shown. Additionally, if you attach to the process and use the !address command on the process, you will see WinDBG identifying the CFG bitmap for you:

```
+ 7df5'ff530000 7df6'0118a000 0'01c5a000 MEM_MAPPED MEM_RESERVE
Other [CFG Bitmap]
7df6'0118a000 7df6'011fb000 0'00071000 MEM_MAPPED MEM_COMMIT PAGE_NOACCESS
Other [CFG Bitmap]
7df6'011fb000 7ff5'df530000 1ff'de335000 MEM_MAPPED MEM_RESERVE
Other [CFG Bitmap]
```

7ff5'df530000 7ff5'df532000 0'00002000 MEM\_MAPPED MEM\_COMMIT PAGE\_READONLY Other [CFG Bitmap]

Note how large regions are marked as MEM\_RESERVE, in between regions that are MEM\_COMMIT, representing that at least one valid bit state {1, X} is set. Also, all (or almost all) the regions will be MEM\_MAPPED, since they belong to the shared bitmap.

## CFG bitmap construction

Upon system initialization, the MiInitializeCfg function is called to initialize support for CFG. The function creates one or two section objects (MmCreateSection) as reserved memory with size appropriate for the platform, as shown earlier. For 32-bit platforms, one bitmap is enough. For x64 platforms, two bitmaps are required—one for 64-bit processes and the other for Wow64 processes (32-bit applications). The section objects' pointers are stored in a substructure within the MiState global variable.

After a process is created, the appropriate section is securely mapped into the process's address space. *Securely* here means that the section cannot be unmapped by code running within the process or have its protection changed. (Otherwise, malicious code could just unmap the memory, reallocate, and fill everything with 1 bits, effectively disabling CFG, or simply modify any bits by marking the region read/write.)

The user mode CFG bitmap(s) are populated in the following scenarios:

- During image mapping, images that have been dynamically relocated due to ASLR (see Chapter 5, for more on ASLR) will have their indirect call target metadata extracted. If an image does not have indirect call target metadata, meaning it was not compiled with CFG, it is assumed that every address within the image can be called indirectly. As explained, because dynamically relocated images are expected to load at the same address in every process, their metadata is used to populate the shared section that is used for the CFG bitmap.
- During image mapping, special care is needed for non-dynamically relocated images and images not being mapped at their preferred base. For these image mappings, the relevant pages of the CFG bitmap are made private and are populated using the CFG metadata from the image. For images whose CFG bits are present in the shared CFG bitmap, a check is made to ensure that all the relevant CFG bitmap pages are still shared. If this is not the case, the bits of the private CFG bitmap pages are populated using the CFG metadata from the image.
- When virtual memory is allocated or re-protected as executable, the relevant pages of the CFG bitmap are made private and initialized to all 1s by default. This is needed for cases such as just-in-time (JIT) compilation, where code is generated on the fly and then executed (for example, .NET or Java).

## Strengthening CFG protection

Although CFG does an adequate job to prevent types of exploits that leverage indirect calls or jumps, it could be bypassed through the following ways:

- If the process can be tricked or an existing JIT engine abused to allocate executable memory, all the corresponding bits will be set to {1, 1}, meaning that all memory is considered a valid call target.
- For 32-bit applications, if the expected call target is \_\_stdcall (standard calling convention), but an attacker is able to change the indirect call target to \_\_cdecl (C calling convention), the stack will become corrupt, as the C call function will not perform cleanup of the caller's arguments, unlike a standard call function. Because CFG cannot differentiate between the different calling conventions, this results in a corrupt stack, potentially with an attacker-controlled return address, bypassing the CFG mitigation.
- Similarly, compiler-generated setjmp/longjmp targets behave differently from true indirect calls. CFG cannot differentiate between the two.
- Certain indirect calls are harder to protect, such as the Import Address Table (IAT) or Delay-Load Address Table, which is typically in a read-only section of the executable.
- Exported functions may not be desirable indirect function calls.

Windows 10 introduces advancements to CFG that address all these issues. The first is to introduce a new flag to the VirtualAlloc function called PAGE\_TARGETS\_INVALID and one to VirtualProtect called PAGE\_TARGETS\_NO\_UPDATE. With these flags set, JIT engines that allocate executable memory will not see all their allocations' bits set to the {1, 1} state. Instead, they must manually call the SetProcess-ValidCallTargets function (which calls the native NtSetInformationVirtualMemory function), which will allow them to specify the actual function start addresses of their JITed code. Additionally, this function is marked as a suppressed call with DECLSPEC\_GUARD\_SUPPRESS, making sure that attackers cannot use an indirect CALL or JMP to redirect into it, even at its function start. (Because it's an inherently dangerous function, calling it with a controlled stack or registers could result in the bypassing of CFG.)

Next, improved CFG changes the default flow you saw in the beginning of this section with a more refined flow. In this flow, the loader does not implement a simple "verify target, return" function, but rather a "verify target, call target, check stack, return" function, which is used in a subset of places on 32-bit applications (and/or running under WoW64). This improved execution flow is shown in Figure 7-32.

Next, improved CFG adds additional tables inside of the executable, such as the Address Taken IAT table and the Long Jump Address table. When longjmp and IAT CFG protection are enabled in the compiler, these tables are used to store destination addresses for these specific types of indirect calls, and the relevant functions are *not* placed in the regular function table, therefore not figuring in the bitmap. This means that if code is attempting to indirect jump/call to one of these functions, it will be treated as an illegal transition. Instead, the C Runtime and linker will validate the targets of, say, the longjmp function, by manually checking this table. Although it's more inefficient than a bitmap, there should be little to no functions in these tables, making the cost bearable.

Finally, improved CFG implements a feature called *export suppression*, which must be supported by the compiler and enabled by process-mitigation policy. (See the section "Process-mitigation policies" for more on process level mitigations.) With this feature enabled, a new bit state is implemented (recall that bulleted list had {0, 1} as an undefined state). This state indicates that the function is valid but export-suppressed, and it will be treated differently by the loader.




FIGURE 7-32 Improved CFG.

You can determine which features are present in a given binary by looking at the guard flags in the Image Load Configuration Directory, which the DumpBin application used earlier can decode. For reference, they are listed in Table 7-21.

TABLE 7-21	Control	Flow	Guard	flags
------------	---------	------	-------	-------

Flag Symbol	Value	Description
IMAGE_GUARD_CF_INSTRUMENTED	0x100	This indicates CFG support is present for this module.
IMAGE_GUARD_CFW_INSTRUMENTED	0x200	This module performs CFG and write integrity checks.
IMAGE_GUARD_CF_FUNCTION_TABLE_PRESENT	0x400	This module contains CFG-aware function lists.
IMAGE_GUARD_SEURITY_COOKIE_UNUSED	0x800	This module does not make use of the security cookie emitted with the compiler /GS flag.
IMAGE_GUARD_PROTECT_DELAYLOAD_IAT	0x1000	This module supports read- only delay-load Import Address Tables (IATs).
IMAGE_GUARD_DELAYLOAD_IAT_IN_ITS_OWN_SECTION	0x2000	Delay-load IAT is its own section, so it can be re-protected if desired.
IMAGE_GUARD_CF_EXPORT_SUPPRESSION_INFO_PRESENT	0x4000	This module contains suppressed export information.
IMAGE_GUARD_CF_ENABLE_EXPORT_SUPPRESSION	0x8000	This module enables suppression of exports.
IMAGE_GUARD_CF_LONGJUMP_TABLE_PRESENT	0x10000	This module contains longjmp target information.

## Loader interaction with CFG

Although it is the memory manager that builds the CFG bitmap, the user-mode loader (see Chapter 3 for more information) serves two purposes. The first is to dynamically enable CFG support only if the feature is enabled (for example, the caller may have requested no CFG for the child process, or the process itself might not have CFG support). This is done by the LdrpCfgProcessLoadConfig loader function, which is called to initialize CFG for each loaded module. If the module D11Characteristics flags in the optional header of the PE does not have the CFG flag set (IMAGE\_DLLCHARACTERISTICS\_ GUARD\_CF), the GuardF1ags member of IMAGE\_LOAD\_CONFIG\_DIRECTORY structure does not have the IMAGE\_GUARD\_CF\_INSTRUMENTED flag set, or the kernel has forcibly turned off CFG for this module, then there is nothing to do.

Second, if the module is indeed using CFG, LdrpCfgProcessLoadConfig gets the indirect checking function pointer retrieved from the image (the GuardCFCheckFunctionPointer member of IMAGE\_LOAD\_CONFIG\_DIRECTORY structure) and sets it to either LdrpValidateUserCallTarget or LdrpValidateUserCallTargetES in Ntdll, depending on whether export suppression is enabled. Additionally, the function first makes sure the indirect pointer has not been somehow modified to point outside the module itself.

Furthermore, if improved CFG was used to compile this binary, a second indirect routine is available, called the *dispatch CFG routine*. It is used to implement the enhanced execution flow described earlier. If the image includes such a function pointer (in the GuardCFDispatchFunctionPointer member of the abovementioned structure), it is initialized to LdrpDispatchUserCallTarget, or LdrpDispatchUserCallTargetES if export suppression is enabled.

**Note** In some cases, the kernel itself can emulate or perform indirect jumps or calls on behalf of user mode. In situations where this is a possibility, the kernel implements its own MmValidateUserCallTarget routine, which performs the same work as LdrpValidate-UserCallTarget.

The code generated by the compiler when CFG is enabled issues an indirect call that lands in the LdrpValidateCallTarget(ES) or LdrpDispatchUserCallTarget(ES) functions in Ntdll. This function uses the target branch address and checks the bit state value for the function:

- If the bit state is {0, 0}, the dispatch is potentially invalid.
- If the bit state is {1, 0}, and the address is 16-byte aligned, the dispatch is valid. Otherwise, it is potentially invalid.
- If the bit state is {1, 1}, and the address is not 16-byte aligned, the dispatch is valid. Otherwise, it is potentially invalid.
- If the bit state is {0, 1}, the dispatch is potentially invalid.

If the dispatch is potentially invalid, the RtlpHandleInvalidUserCallTarget function will execute to determine the appropriate action. First, it checks if suppressed calls are allowed in the process, which

is an unusual application-compatibility option that might be set if Application Verifier is enabled, or through the registry. If so, it will check if the address is suppressed, which is why it was not inserted into the bitmap (recall that a special flag in the guard function table entry indicates this). If this is the case, the call is allowed through. If the function is not valid at all (meaning it's not in the table), then the dispatch is aborted and the process terminated.

Second, a check is made to see if export suppression is enabled. If it is, the target address is checked against the list of export-suppressed addresses, which is once again indicated with another flag that is added in the guard function table entry. If this is the case, the loader validates that the target address is a forwarder reference to the export table of another DLL, which is the only allowed case of an indirect call toward an image with suppressed exports. This is done by a complex check that makes sure the target address is in a different image, that its image load directory has enabled export suppression, and that this address is in the import directory of that image. If these checks match, the kernel is called through the NtSetInformationVirtualMemory call described earlier, to change the bit state to {1, 0}. If any of these checks fail, or export suppression is not enabled, then the process is terminated.

For 32-bit applications, an additional check is performed if DEP is enabled for the process. (See Chapter 5 for more on DEP.) Otherwise, because there are no execution guarantees to begin with, the incorrect call is allowed, as it may be an older application calling into the heap or stack for legitimate reasons.

Finally, because large sets of {0, 0} bit states are not committed to save space, if checking the CFG bitmap lands on a reserved page, an access violation exception occurs. On x86, where exception handling setup is expensive, instead of being handled as part of the verification code, it is left to propagate normally. (See Chapter 8 in Part 2 for more on exception dispatching.) The user-mode dispatcher handler, KiUserExceptionDispatcher, has specific checks for recognizing CFG bitmap access violation exceptions within the validation function and will automatically resume execution if the exception code was STATUS\_IN\_PAGE\_ERROR. This simplifies the code in LdrpValidateUserCallTarget(ES) and LdrpDispatchUserCallTarget(ES), which don't have to include exception handling code. On x64, where exception handlers are simply registered in tables, the LdrpICallHandler handler runs instead, with the same logic as above.

## **Kernel CFG**

Although drivers compiled with Visual Studio and /guard: cf also ended up with the same binary properties as user-mode images, the first versions of Windows 10 did not do anything with this data. Unlike the user-mode CFG bitmap, which is protected by a higher, more trusted entity (the kernel), there is nothing that can truly "protect" the kernel CFG bitmap if one were to be created. A malicious exploit could simply edit the PTE that corresponded to the page containing the desired bits to modify, mark it as read/write, and proceed with the indirect call or jump. Therefore, the overhead of setting up such a trivially bypassable mitigation was simply not worth it.

With a greater number of users enabling VBS features, once again, the higher security boundary that VTL 1 provides can be leveraged. The SLAT page table entries come to the rescue by providing a second boundary against PTE page protection changes. While the bitmap is readable to VTL 0 because the SLAT entries are marked as read only, if a kernel attacker attempts to change the PTEs to mark them read/write, they cannot do the same to the SLAT entries. As such, this will be detected as an invalid

KCFG bitmap access which HyperGuard can act on (for telemetry reasons alone—since the bits can't be changed anyway).

KCFG is implemented almost identically to regular CFG, except that export suppression is not enabled, nor is longjmp support, nor is the ability to dynamically request additional bits for JIT purposes. Kernel drivers should not be doing any of these things. Instead, the bits are set in the bitmap based on the "address taken IAT table" entries, if any are set; by the usual function entries in the guard table each time a driver image is loaded; and for the HAL and kernel during boot by MiInitializeKernelCfg. If the hypervisor is not enabled, and SLAT support is not present, then none of this will be initialized, and Kernel CFG will be kept disabled.

Just like in the user-mode case, a dynamic pointer in the load configuration data directory is updated, which in the enabled case will point to \_\_guard\_check\_icall for the check function and \_\_guard\_dispatch\_icall for the dispatch function in enhanced CFG mode. Additionally, a variable named guard\_icall\_bitmap will hold the virtual address of the bitmap.

One last detail on Kernel CFG is that unfortunately, dynamic Driver Verifier settings will not be configurable (for more information on Driver Verifier, see Chapter 6, "I/O system"), as this would require adding dynamic kernel hooks and redirecting execution to functions that may not be in the bitmap. In this case, STATUS\_VRF\_CFG\_ENABLED (0xC000049F) will be returned, and a reboot is required (at which time the bitmap can be built with the Verifier Driver hooks in place).

# Security assertions

Earlier, we described how Control Flow Guard will terminate the process. We also explained how certain other mitigations or security features will raise an exception to kill the process. It is important to be accurate with what *exactly* happens during these security violations because both these descriptions hide important details about the mechanism.

In fact, when a security-related breach occurs, such as when CFG detects an incorrect indirect call or jump, terminating the process through the standard TerminateProcess mechanism would not be an adequate path. There would be no crash generated, and no telemetry sent to Microsoft. These are both important tools for the administrator to understand that a potential exploit has executed or that an application compatibility issue exists, as well as for Microsoft to track zero-day exploitation in the wild. On the flip side, while raising an exception would achieve the desired result, exceptions are callbacks, which can be:

- Potentially hooked by attackers if /SAFESEH and SEHOP mitigations are not enabled, causing the security check to be the one that gives control to an attacker in the first place—or an attacker can simply "swallow" the exception.
- Potentially hooked by legitimate parts of the software through an unhandled exception filter or vectored exception handler, both of which might accidentally swallow the exception.
- Same as above, but intercepted by a third-party product that has injected its own library into the process. Common to many security tools, this can also lead in the exception not being correctly delivered to Windows Error Reporting (WER).

- A process might have an application recovery callback registered with WER. This might then display a less clear UI to the user, and might restart the process in its current exploited state, leading anywhere from a recursive crash/start loop to the exception being swallowed whole.
- Likely in a C++-based product, caught by an outer exception handler as if "thrown" by the program itself, which, once again, might swallow the exception or continue execution in an unsafe manner.

Solving these issues requires a mechanism that can raise an exception that cannot be intercepted by any of the process's components outside of the WER service, which must itself be guaranteed to receive the exception. This is where security assertions come into play.

## **Compiler and OS support**

When Microsoft libraries, programs, or kernel components encounter unusual security situations, or when mitigations recognize dangerous violations of security state, they now use a special compiler intrinsic supported by Visual Studio, called \_\_fastfai1, which takes one parameter as input. Alternatively, they can call a runtime library (Rt1) function in Ntdll called Rt1Fai1Fast2, which itself contains a \_\_fastfai1 intrinsic. In some cases, the WDK or SDK contain inline functions that call this intrinsic, such as when using the LIST\_ENTRY functions InsertTai1List and RemoveEntryList. In other situations, it is the Universal CRT (uCRT) itself that has this intrinsic in its functions. In yet others, APIs will do certain checks when called by applications and may use this intrinsic as well.

Regardless of the situation, when the compiler sees this intrinsic, it generates assembly code that takes the input parameter, moves it into the RCX (x64) or ECX (x86) register, and then issues a software interrupt with the number 0x29. (For more information on interrupts, see Chapter 8 in Part 2.)

In Windows 8 and later, this software interrupt is registered in the Interrupt Dispatch Table (IDT) with the handler KiRaiseSecurityCheckFailure, which you can verify on your own by using the !idt 29 command in the debugger. This will result (for compatibility reasons) in KiFastFailDispatch being called with the STATUS\_STACK\_BUFFER\_OVERRUN status code (0xC0000409). This will then do regular exception dispatching through KiDispatchException, but treat this as a second-chance exception, which means that the debugger and process won't be notified.

This condition will be specifically recognized and an error message will be sent to the WER error ALPC port as usual. WER will claim the exception as non-continuable, which will then cause the kernel to terminate the process with the usual ZwTerminateProcess system call. This, therefore, guarantees that once the interrupt is used, no return to user mode will ever be performed within this process again, that WER will be notified, and that the process will be terminated (additionally, the error code will be the exception code). When the exception record is generated, the first exception argument will be the input parameter to \_\_fastfail.

Kernel-mode code can also raise exceptions, but in this case KiBugCheckDispatch will be called instead, which will result in a special kernel mode crash (bugcheck) with code 0x139 (KERNEL\_SECURITY\_ CHECK\_FAILURE), where the first argument will be the input parameter to \_\_fastfail.

## Fast fail/security assertion codes

Because the \_\_fastfail intrinsic contains an input argument that is bubbled up to the exception record or crash screen, it allows the failing check to identify what part of the system or process is not working correctly or has encountered a security violation. Table 7-22 shows the various failure conditions and their meaning or significance.

Code	Meaning
Legacy OS Violation (0x0)	An older buffer security check present in a legacy binary has failed, and has been converted to a security assertion instead.
V-Table Guard Failure (0x1)	The Virtual Table Guard Mitigation in Internet Explorer 10 and higher has en- countered a corrupted virtual function table pointer.
Stack Cookie Check Failure (0x2)	The stack cookie generated with the /GS compiler option (also called a stack canary) has been corrupted.
Corrupt List Entry (0x3)	One of the macros for manipulating LIST_ENTRY structures has detected an inconsistent linked list, where the grandparent or grandchild entry does not point to the parent or child entry of the item being manipulated.
Incorrect Stack (0x4)	A user-mode or kernel-mode API that is often potentially called from ROP- based exploits while operating on an attacker-controlled stack has been called, and the stack is therefore not the expected one.
Invalid Argument (0x5)	A user-mode CRT API (typically) or other sensitive function has been called with an invalid argument, suggesting potential ROP-based use or an otherwise cor- rupted stack.
Stack Cookie Init Failure (0x6)	The initialization of the stack cookie has failed, suggesting image patching or corruption.
Fatal App Exit (0x7)	The application has used the FatalAppExit user-mode API, which has been converted into a security assertion to grant it the advantages this has.
Range Check Failure (0x8)	Additional validation checks in certain fixed array buffers to check if the array element index is within expected bounds.
Unsafe Registry Access (0x9)	A kernel-mode driver is attempting to access registry data from a user-control- lable hive (such as an application hive or user profile hive) and is not using the RTL_QUERY_REGISTRY_TYPECHECK flag to protect itself.
CFG Indirect Call Failure (0xA)	Control Flow Guard has detected an indirect CALL or JMP instruction to a tar- get address that is not a valid dispatch per the CFG bitmap.
CFG Write Check Failure (0xB)	Control Flow Guard with write protection has detected an invalid write to pro- tected data. This feature (/guard:cfw) is not supported outside of testing at Microsoft.
Invalid Fiber Switch (0xC)	The SwitchToFiber API was used on an invalid fiber or from a thread which has not been converted to a fiber.
Invalid Set of Context (0xD)	An invalid context record structure was detected while attempting to restore it (due to an exception or SetThreadContext API), in which the stack pointer is not valid. Checked only when CFG is active on the process.
Invalid Reference Count (0xE)	A reference countered object (such as the OBJECT_HEADER in kernel-mode or a Win32k.sys GDI object) has underflowed its reference count below 0 or overflowed beyond its maximum capacity back to 0.
Invalid Jump Buffer (0x12)	A longjmp attempt is being made with a jump buffer that contains an invalid stack address or invalid instruction pointer. Checked only when CFG is active on the process.

TABLE 7-22	fastfail	failure	codes
------------	----------	---------	-------

#### TABLE 7-22 \_\_\_\_\_fastfail failure codes (continued)

Code	Meaning
MRDATA Modified (0x13)	The mutable read-only data heap/section of the loader has been modified. Checked only when CFG is active on the process.
Certification Failure (0x14)	One or more Cryptographic Services APIs has encountered an issue parsing a certificate or an invalid ASN.1 stream.
Invalid Exception Chain (0x15)	An image linked with /SAFESEH, or with the SEHOP mitigation, has encountered an invalid exception handler dispatch.
Crypto Library (0x16)	CNG.SYS, KSECDD.SYS, or their equivalent APIs in user mode have encountered some critical failure.
Invalid Call in DLL Callout (0x17)	An attempt to call dangerous functions while in the user-mode loader's notification callback has occurred.
Invalid Image Base (0x18)	An invalid value forImageBase (IMAGE_DOS_HEADER structure) was detected by the user-mode image loader.
Delay Load Protection Failure (0x19)	The delay-loaded IAT has been found to be corrupted while delay-loading an imported function. Checked only when CFG is active on the process, and delay-load IAT protection is enabled.
Unsafe Extension Call (0x1A)	Checked when certain kernel-mode extension APIs are called, and the caller state is incorrect.
Deprecated Service Called (0x1B)	Checked when certain no-longer supported, and undocumented system calls, are called.
Invalid Buffer Access (0x1C)	Checked by the runtime library functions in Ntdll and the kernel when a generic buffer structure is corrupt in some way.
Invalid Balanced Tree (0x1D)	Checked by the runtime library functions in Ntdll and the kernel when an RTL_RB_TREE or RTL_AVL_TABLE structure has invalid nodes (where siblings and/or parent nodes do not match up with the grandparent's, similar to the LIST_ENTRY checks).
Invalid Next Thread (0x1E)	Checked by the kernel scheduler when the next thread to schedule in the KPRCB is invalid in some way.
CFG Call Suppressed (0x1F)	Checked when CFG is allowing a suppressed call due to compatibility concerns. In this situation, WER will mark the error as handled, and the kernel will not terminate the process, but telemetry will still be sent to Microsoft.
APCs Disabled (0x20)	Checked by the kernel when returning to user-mode and kernel APCs are still disabled.
Invalid Idle State (0x21)	Checked by the kernel power manager when the CPU is attempting to enter an invalid C-state.
MRDATA Protection Failure (0x22)	Checked by the user-mode loader when the Mutable Read-Only Heap Section has already been unprotected outside of the expected code path.
Unexpected Heap Exception (0x23)	Checked by the heap manager whenever the heap is corrupted in ways that indicate potential exploitation attempts.
Invalid Lock State (0x24)	Checked by the kernel when certain locks are not in their expected state, such as if an acquired lock is already in a released state.
Invalid Longjmp (0x25)	Checked by longjmp when called, and CFG is active on the process with Longjmp Protection enabled, but the Longjmp Table is corrupt or missing in some way.
Invalid Longjmp Target (0x26)	Same conditions as above, but the Longjmp Table indicates that this is not a valid Longjmp target function.

#### TABLE 7-22 \_\_\_\_fastfail failure codes (continued)

Code	Meaning
Invalid Dispatch Context (0x27)	Checked by the exception handler in kernel-mode when an exception is at- tempted to be dispatched with an incorrect CONTEXT record.
Invalid Thread (0x28)	Checked by the scheduler in kernel-mode when the KTHREAD structure is cor- rupt during certain scheduling operations.
Invalid System Call Number (0x29)	Similar to Deprecated Service Called, but WER will mark the exception as han- dled, resulting in the process continuing and therefore only used for telemetry.
Invalid File Operation (0x2A)	Used by the I/O Manager and certain file systems, as another telemetry-type failure as above.
LPAC Access Denied (0x2B)	Used by the SRM's access check function when a lower-privilege AppContainer attempts to access an object that does not have the ALL RESTRICTED APPLICATION PACKAGES SID and tracing of such failures is enabled. Once more, results only in telemetry data, not a process crash.
RFG Stack Failure (0x2C)	Used by Return Flow Guard (RFG), although this feature is currently disabled.
Loader Continuity Failure (0x2D)	Used by the process-mitigation policy of the same name, shown earlier, to in- dicate that an unexpected image with a different signature or no signature has been loaded.
CFG Export Suppression Failure (0x2D)	Used by CFG when enabled with export suppression to indicate that a suppressed export has been the target of an indirect branch.
Invalid Control Stack (0x2E)	Used by RFG, although this feature is currently disabled.
Set Context Denied (0x2F)	Used by the process-mitigation policy of the same name, shown earlier, al- though this feature is currently disabled.

# **Application Identification**

Historically, security decisions in Windows have been based on a user's identity (in the form of the user's SID and group membership), but a growing number of security components (AppLocker, firewall, antivirus, anti-malware, Rights Management Services, and others) need to make security decisions based on what code is to be run. In the past, each of these security components used their own proprietary method for identifying applications, which led to inconsistent and overly complicated policy authoring. The purpose of Application Identification (AppID) is to bring consistency to how the security components recognize applications by providing a single set of APIs and data structures.

**Note** This is not the same as the AppID used by DCOM/COM+ applications, where a GUID represents a process that is shared by multiple CLSIDs, nor is it related to UWP application ID.

Just as a user is identified when she logs in, an application is identified just before it is started by generating the main program's AppID. An AppID can be generated from any of the following attributes of the application:

**Fields** Fields within a code-signing certificate embedded within the file allow for different combinations of publisher name, product name, file name, and version. APPID://FQBN is a

fully qualified binary name, and it is a string in the following form: {Publisher\Product\ Filename, Version}. Publisher is the Subject field of the x.509 certificate used to sign the code, using the following fields:

- O Organization
- L Locality
- S State or province
- C Country
- File hash there are several methods that can be used for hashing. The default is APPID:// SHA256HASH. However, for backward compatibility with SRP and most x.509 certificates, SHA-1 (APPID://SHA1HASH) is still supported. APPID://SHA256HASH specifies the SHA-256 hash of the file.
- The partial or complete path to the file APPID://Path specifies a path with optional wildcard characters (\*).

**Note** An AppID does not serve as a means for certifying the quality or security of an application. An AppID is simply a way of identifying an application so that administrators can reference the application in security policy decisions.

The AppID is stored in the process access token, allowing any security component to make authorization decisions based on a single consistent identification. AppLocker uses conditional ACEs (described earlier) for specifying whether a particular program is allowed to be run by the user.

When an AppID is created for a signed file, the certificate from the file is cached and verified to a trusted root certificate. The certificate path is reverified daily to ensure the certificate path remains valid. Certificate caching and verification are recorded in the system event log at Application and Services Logs\Microsoft\Windows\AppID\Operational.

# AppLocker

Windows 8.1 and Windows 10 (Enterprise editions) and Windows Server 2012/R2/2016 support a feature known as *AppLocker*, which allows an administrator to lock down a system to prevent unauthorized programs from being run. Windows XP introduced Software Restriction Policies (SRP), which was the first step toward this capability, but SRP was difficult to manage, and it couldn't be applied to specific users or groups. (All users were affected by SRP rules.) AppLocker is a replacement for SRP, and yet co-exists alongside SRP, with AppLocker's rules being stored separately from SRP's rules. If both AppLocker and SRP rules are in the same Group Policy object (GPO), only the AppLocker rules will be applied.

Another feature that makes AppLocker superior to SRP is AppLocker's auditing mode, which allows an administrator to create an AppLocker policy and examine the results (stored in the system event log) to determine whether the policy will perform as expected—without actually performing the restrictions. AppLocker auditing mode can be used to monitor which applications are being used by one or more users on a system.

AppLocker allows an administrator to restrict the following types of files from being run:

- Executable images (EXE and COM)
- Dynamic-link libraries (DLL and OCX)
- Microsoft Software Installer (MSI and MSP) for both install and uninstall
- Scripts
- Windows PowerShell (PS1)
- Batch (BAT and CMD)
- VisualBasic Script (VBS)
- Java Script (JS)

AppLocker provides a simple GUI rule-based mechanism, which is very similar to network firewall rules, for determining which applications or scripts are allowed to be run by specific users and groups, using conditional ACEs and AppID attributes. There are two types of rules in AppLocker:

- Allow the specified files to run, denying everything else.
- Deny the specified files from being run, allowing everything else. Deny rules take precedence over allow rules.

Each rule can also have a list of exceptions to exclude files from the rule. Using an exception, you could create a rule to, for example, allow everything in the C:\Windows or C:\Program Files directories to be run except RegEdit.exe.

AppLocker rules can be associated with a specific user or group. This allows an administrator to support compliance requirements by validating and enforcing which users can run specific applications. For example, you can create a rule to allow users in the Finance security group to run the finance line-of-business applications. This blocks everyone who is not in the Finance security group from running finance applications (including administrators) but still provides access for those who have a business need to run the applications. Another useful rule would be to prevent users in the Receptionists group from installing or running unapproved software.

AppLocker rules depend upon conditional ACEs and attributes defined by AppID. Rules can be created using the following criteria:

Fields within a code-signing certificate embedded within the file, allowing for different combinations of publisher name, product name, file name, and version For example, a rule could be created to allow all versions greater than 9.0 of Contoso Reader to run or allow anyone in the Graphics group to run the installer or application from Contoso for GraphicsShop as long as the version is 14.\*. For example, the following SDDL string denies execute access to

any signed programs published by Contoso for the RestrictedUser user account (identified by the user's SID):

D:(XD;;FX;;;S-1-5-21-3392373855-1129761602-2459801163-1028;((Exists APPID://FQBN) && ((APPID://FQBN) >= ({"O=CONTOSO, INCORPORATED, L=REDMOND, S=CWASHINGTON, C=US\\*\\*",0})))

Directory path, allowing only files within a particular directory tree to run This can also be used to identify specific files. For example, the following SDDL string denies execute access to the programs in the directory C:\Tools for the RestrictedUser user account (identified by the user's SID):

D:(XD;;FX;;;S-1-5-21-3392373855-1129761602-2459801163-1028;(APPID://PATH Contains "%OSDRIVE%\TOOLS\\*"))

 File hash Using a hash will also detect if a file has been modified and prevent it from running. This can also be a weakness if files are changed frequently because the hash rule will need to be updated frequently. File hashes are often used for scripts because few scripts are signed. For example, this SDDL string denies execute access to programs with the specified hash values for the RestrictedUser user account (identified by the user's SID):

D:(XD;;FX;;S-1-5-21-3392373855-1129761602-2459801163-1028;(APPID://SHA256HASH Any\_of {#7a334d2b99d48448eedd308dfca63b8a3b7b44044496ee2f8e236f5997f1b647, #2a782f76cb94ece307dc52c338f02edbbfdca83906674e35c682724a8a92a76b}))

AppLocker rules can be defined on the local machine using the Security Policy MMC snap-in (secpol. msc, see Figure 7-33) or a Windows PowerShell script, or they can be pushed to machines within a domain using Group Policy. AppLocker rules are stored in multiple locations within the registry:

- HKLM\Software\Policies\Microsoft\Windows\SrpV2 This key is also mirrored to HKLM\SOFTWARE\Wow6432Node\Policies\Microsoft\Windows\SrpV2. The rules are stored in XML format.
- HKLM\SYSTEM\CurrentControlSet\Control\Srp\Gp\Exe The rules are stored as SDDL and a binary ACE.
- HKEY\_CURRENT\_USER\Software\Microsoft\Windows\CurrentVersion\Group Policy
   Objects\{GUID}Machine\Software\Policies\Microsoft\Windows\SrpV2 AppLocker policy
   pushed down from a domain as part of a GPO are stored here in XML format.

Certificates for files that have been run are cached in the registry under the key HKLM\SYSTEM\ CurrentControlSet\Control\AppID\CertStore. AppLocker also builds a certificate chain (stored in HKLM\SYSTEM\CurrentControlSet\Control\AppID\CertChainStore) from the certificate found in a file back to a trusted root certificate.

There are also AppLocker-specific PowerShell commands (cmdlets) to enable deployment and testing via scripting. After using the Import-Module AppLocker to get AppLocker cmdlets into PowerShell, several cmdlets are available. These include Get-AppLockerFileInformation, Get-AppLockerPolicy, New-AppLockerPolicy, Set-AppLockerPolicy, and Test-AppLockerPolicy.





FIGURE 7-33 AppLocker configuration page in Local Security Policy.

The AppID and SRP services coexist in the same binary (AppIdSvc.dll), which runs within an SvcHost process. The service requests a registry change notification to monitor any changes under that key, which is written by either a GPO or the AppLocker UI in the Local Security Policy MMC snap-in. When a change is detected, the AppID service triggers a user-mode task (AppIdPolicyConverter.exe), which reads the new rules (described with XML) and translates them into binary format ACEs and SDDL strings, which are understandable by both the user-mode and kernel-mode AppID and AppLocker components. The task stores the translated rules under HKLM\SYSTEM\CurrentControlSet\Control\Srp\Gp. This key is writable only by System and Administrators, and it is marked read-only for authenticated users. Both user-mode and kernel-mode AppID components read the translated rules from the registry directly. The service also monitors the local machine trusted root certificate store, and it invokes a user-mode task (AppIdCertStoreCheck.exe) to reverify the certificates at least once per day and whenever there is a change to the certificate store. The AppID kernel-mode driver (%SystemRoot%\System32\ drivers\AppId.sys) is notified about rule changes by the AppID service through an APPID\_POLICY\_ CHANGED DeviceIoControl request.

An administrator can track which applications are being allowed or denied by looking at the system event log using Event Viewer (once AppLocker has been configured and the service started). See Figure 7-34.

Event Viewer (Local)	EXE and DLL Number of events: 6					Actions		
Cutom Views     Windews (sgs)     Active Trictory Web Services     Corp Septications and Services     Corp Septication     Windews     Windews     Windews     Windews     Advice Trictory Meb Service     Windews     Advice Trictory Meb Service     Windews     Advice Trictory Meb Service     Advice Trictory Meb Se	Level (2) Information (2) Information (3) Information (3) Information (4) Information (4) Information	Date and Time 12/12/2015 52438 PM 12/12/2015 5248 PM 12/12/2015 52407 PM 12/12/2015 52408 PM 12/12/2015 52258 PM 12/12/2015 52238 PM	Source Applacker Applacker Applacker Applacker Applacker	8002 8004 8001 8001 8001 8001	Task Category None None None None None None	EXE and DLL         Open Swed Log           Control Swed Log         Impart Custom View           Impart Custom View         Impart Custom View           Clar Log         Properties           Drabble Log         Impart Custom View           Swe All Events Ac         Attach a Task To this Log           Wei         Swe All Events Ac           Attach a Task To this Log         Event NOD4, Applancker           Start Task To This Event         Selected Forest		
Packaged app-Deployment Packaged app-Execution AppModel-Runtime	Event 8004, AppLocke	r -				🗙 🔂 Сору		
Approduct rotation     Approaches     Approx     Appprox     Approx     Appprox     Appprox     Appprox     Appprox	General Details	Error geywords MYDOMAIN/Pavel Compute Info	12/12/2016 5:24:10 PM gory: None			🧟 Refresh		



The implementations of AppID, AppLocker, and SRP are somewhat blurred and violate strict layering, with various logical components coexisting within the same executables, and the naming is not as consistent as one would like.

The AppID service runs as Local Service so that it has access to the Trusted Root Certificate Store on the system. This also enables it to perform certificate verification. The AppID service is responsible for the following:

- Verification of publisher certificates
- Adding new certificates to the cache
- Detecting AppLocker rule updates and notifying the AppID driver

The AppID driver performs the majority of the AppLocker functionality and relies on communication (via DeviceIoControl requests) from the AppID service, so its device object is protected by an ACL, granting access only to the NT SERVICE\AppIDSvc, LOCAL SERVICE and BUILTIN\Administrators groups. Thus, the driver cannot be spoofed by malware.

When the AppID driver is first loaded, it requests a process-creation callback by calling PsSetCreateProcessNotifyRoutineEx. When the notification routine is called, it is passed a PPS\_ CREATE\_NOTIFY\_INFO structure (describing the process being created). It then gathers the AppID attributes that identify the executable image and writes them to the process's access token. Then it calls the undocumented routine SeSrpAccessCheck, which examines the process token and the conditional ACE AppLocker rules, and determines whether the process should be allowed to run. If the process should not be allowed to run, the driver writes STATUS\_ACCESS\_DISABLED\_BY\_POLICY\_OTHER to the Status field of the PPS\_CREATE\_NOTIFY\_INFO structure, which causes the process creation to be canceled (and sets the process's final completion status).

To perform DLL restriction, the image loader sends a DeviceIoControl request to the AppID driver whenever it loads a DLL into a process. The driver then checks the DLL's identity against the AppLocker conditional ACEs, just like it would for an executable.

**Note** Performing these checks for every DLL load is time-consuming and might be noticeable to end users. For this reason, DLL rules are normally disabled, and they must be specifically enabled via the Advanced tab in the AppLocker properties page in the Local Security Policy snap-in.

The scripting engines and the MSI installer have been modified to call the user-mode SRP APIs whenever they open a file, to check whether a file is allowed to be opened. The user-mode SRP APIs call the AuthZ APIs to perform the conditional ACE access check.

# **Software Restriction Policies**

Windows contains a user-mode mechanism called *Software Restriction Policies (SRP)* that enables administrators to control what images and scripts execute on their systems. The Software Restriction Policies node of the Local Security Policy editor, shown in Figure 7-35, serves as the management interface for a machine's code execution policies, although per-user policies are also possible using domain group policies.



FIGURE 7-35 Software Restriction Policy configuration.

Several global policy settings appear beneath the Software Restriction Policies node:

- Enforcement This policy configures whether restriction policies apply to libraries, such as DLLs, and whether policies apply to users only or to administrators as well.
- Designated File Types This policy records the extensions for files that are considered executable code.
- Trusted Publishers This policy controls who can select which certificate publishers are trusted.

When configuring a policy for a particular script or image, an administrator can direct the system to recognize it using its path, its hash, its Internet zone (as defined by Internet Explorer), or its cryptographic certificate, and can specify whether it is associated with the Disallowed or Unrestricted security policy.

Enforcement of SRPs takes place within various components where files are treated as containing executable code. Some of these components are listed here:

- The user-mode Windows CreateProcess function in Kernel32.dll enforces it for executable images.
- The DLL loading code in Ntdll enforces it for DLLs.
- The Windows command prompt (Cmd.exe) enforces it for batch file execution.
- Windows Scripting Host components that start scripts—Cscript.exe (for command-line scripts), Wscript.exe (for UI scripts), and Scrobj.dll (for script objects)—enforce it for script execution.
- The PowerShell host (PowerShell.exe) enforces it for PowerShell script execution.

Each of these components determines whether the restriction policies are enabled by reading the TransparentEnabled registry value in the HKLM\Software\Policies\Microsoft \Windows\Safer\ Codeldentifiers key, which if set to 1 indicates that policies are in effect. Then it determines whether the code it's about to execute matches one of the rules specified in a subkey of the Codeldentifiers key and, if so, whether the execution should be allowed. If there is no match, the default policy, as specified in the DefaultLevel value of the Codeldentifiers key, determines whether the execution is allowed.

Software Restriction Policies are a powerful tool for preventing the unauthorized access of code and scripts, but only if properly applied. Unless the default policy is set to disallow execution, a user can make minor changes to an image that's been marked as disallowed so that he can bypass the rule and execute it. For example, a user can change an innocuous byte of a process image so that a hash rule fails to recognize it, or copy a file to a different location to avoid a path-based rule.

## **EXPERIMENT: Watching Software Restriction Policy enforcement**

You can indirectly see SRPs being enforced by watching accesses to the registry when you attempt to execute an image that you've disallowed.

- **1.** Run secpol.msc to open the Local Security Policy editor and navigate to the Software Restriction Policies node.
- 2. Choose **Create New Policies** from the context menu if no policies are defined.
- **3.** Create a path-based disallow restriction policy (under the Additional Rules node) for %SystemRoot%\System32\Notepad.exe.
- 4. Run Process Monitor and set an include a Path filter for Safer.
- 5. Open a command prompt and run Notepad from the prompt.

Your attempt to run Notepad should result in a message telling you that you cannot execute the specified program, and Process Monitor should show the command prompt (cmd.exe) querying the local machine restriction policies.

# **Kernel Patch Protection**

Some device drivers modify the behavior of Windows in unsupported ways. For example, they patch the system call table to intercept system calls or patch the kernel image in memory to add functionality to specific internal functions. Such modifications are inherently dangerous and can reduce system stability and security. Additionally, it is also possible for such modifications to be made with malicious intent, either by rogue drivers or through exploits due to vulnerabilities in Windows drivers.

Without the presence of a more privileged entity than the kernel itself, detecting and protecting against kernel-based exploits or drivers from within the kernel itself is a tricky game. Because both the detection/protection mechanism and the unwanted behavior operate in ring 0, it is not possible to define a security boundary in the true sense of the word, as the unwanted behavior could itself be used to disable, patch, or fool the detection/prevention mechanism. That being said, even in such conditions, a mechanism to react to such unwanted operations can still be useful in the following ways:

By crashing the machine with a clearly identifiable kernel-mode crash dump, both users and administrators can easily see that an unwanted behavior has been operating inside of their kernel and they can take action. Additionally, it means that legitimate software vendors will not want to take the risk of crashing their customers' systems and will find supported ways of extending kernel functionality (such as by using the filter manager for file system filters or other callback-based mechanisms).

- Obfuscation (which is not a security boundary) can make it costly—either in time or in complexity—for the unwanted behavior to disable the detection mechanism. This added cost means that the unwanted behavior is more clearly identified as potentially malicious, and that its complexity results in additional costs to a potential attacker. By shifting the obfuscation techniques, it means that legitimate vendors will be better off taking the time to move away from their legacy extension mechanisms and implement supported techniques instead, without the risk of looking like malware.
- Randomization and non-documentation of which specific checks the detection/prevention mechanism makes to monitor kernel integrity, and non-determinism of when such checks are executed, cripple the ability of attackers to ensure their exploits are reliable. It forces them to account for every possible non-deterministic variable and state transition that the mechanism has through static analysis, which obfuscation makes nearly impossible within the timeframe required before another obfuscation shift or feature change is implemented in the mechanism.
- Because kernel mode crash dumps are automatically submitted to Microsoft, it allows the company to receive telemetry of in-the-wild unwanted code, and to either identify software vendors whose code is unsupported and is crashing systems, or to track the progress of malicious drivers in the wild, or even zero-day kernel-mode exploitations, and fix bugs that may not have been reported, but are actively exploited.

# PatchGuard

Shortly after the release of 64-bit Windows for x64 and before a rich third-party ecosystem had developed, Microsoft saw an opportunity to preserve the stability of 64-bit Windows, and to add telemetry and exploit-crippling patch detection to the system, through a technology called *Kernel Patch Protection (KPP)*, also referred to as *PatchGuard*. When Windows Mobile was released, which operates on a 32-bit ARM processor core, the feature was ported to such systems, too, and it will be present in 64-bit ARM (AArch64) systems as well. Due to the existence of too many legacy 32-bit drivers that still use unsupported and dangerous hooking techniques, however, this mechanism is not enabled on such systems, even on Windows 10 operating systems. Fortunately, usage of 32-bit systems is almost coming to an end, and server versions of Windows no longer support this architecture at all.

Although both *Guard* and *Protection* imply that this mechanism will protect the system, it is important to realize that the only guard/protection offered is the crashing of the machine, which prevents further execution of the unwanted code. The mechanism does not *prevent* the attack in the first place, nor mitigate against it, nor undo it. Think of KPP as an Internet-connected video security system, or CCTV, with a loud alarm (the crash) inside the vault (the kernel), not as an impenetrable lock on the vault.

KPP has a variety of checks that it makes on protected systems, and documenting them all would both be impractical (due to the difficulty of static analysis) and valuable to potential attackers (reducing their research time). However, Microsoft does document certain checks, which we generalize in Table 7-23. When, where, and how KPP makes these checks, and which specific functions or data structures are affected, is outside of the scope of this analysis.

Component	Legitimate Usage	Potential Unwanted Usage
Executable code in the kernel, its dependencies, and core drivers, as well as the Import Address Table (IAT) of these components	Standard Windows components key to operation of kernel-mode usage.	Patching code in these components can modify their behavior and in- troduce unwanted back doors to the system, hide data or unwanted com- munications from the system, as well as reduce the stability of the system, or even add additional vulnerabilities through buggy third-party code.
Global Descriptor Table (GDT)	CPU hardware protection for the im- plementation of ring privilege levels (ring 0 versus ring 3).	Modification of expected permissions and mappings between code and ring levels, allowing ring 3 code ring 0 access.
Interrupt Descriptor Table (IDT) or Interrupt Vector Table	Table read by the CPU to deliver inter- rupt vectors to the correct handling routine.	Hooking of keystrokes, network pack- ets, paging mechanism, system calls, hypervisor communication, and more, which can be used for back-dooring, hiding malicious data or communica- tions, or accidentally adding vulner- abilities through buggy third-party code.
System Service Descriptor Table (SSDT)	Table containing the array of pointers for each system call handler.	Hooking of all user-mode communi- cations with the kernel. Same issues as above.
Critical CPU registers such as Control Registers, Vector Base Address Register, and Model Specific Registers	Used for system calls, virtualization, enabling CPU security features such as SMEP, and more.	Same as above, plus disabling of key CPU security features or hypervisor protection.
Various function pointers in the kernel	Used as indirect calls to various inter- nal functionality.	Can be used to hook certain internal kernel operations, leading to back doors and/or instability.
Various global variables in the kernel	Used to configure various parts of the kernel, including certain security features.	Malicious code would disable these security features, such as through an exploit from user mode allowing arbi- trary memory overwrites.
Process and module list	Used to show the user, in tools such as Task Manager, Process Explorer, and the Windows Debugger, which processes are active, and which drivers are loaded.	Malicious code can hide the existence of certain processes or drivers on the machine, making them invisible to the user and most applications such as security software.
Kernel stacks	Store function arguments, the call stack (where a function should return), and variables.	Operating on a non-standard kernel stack is often the sign of a return- oriented programming (ROP) exploit operating on a pivoted stack as part of the attack.
Window Manager, graphical system calls, callbacks, and more	Provides the GUI, GDI, and DirectX services.	Same hooking abilities as described earlier, but specifically targeting the graphics and window-management stack. Same issues as other types of hooks.
Object types	Definitions for the various objects (such as processes and files) that the system supports through the object manager.	Can be used as another hooking tech- nique, which does not target indirect function pointers in binaries' data sections, nor patching code directly. Same issues.

TABLE 7-23	Generalized description	of elements	protected by K	(PP	(continued)
INCOLE / LO	ocheranzea acscription	or cicilicities	protected by n		(continucu)

Component	Legitimate Usage	Potential Unwanted Usage
Local APIC	Used to receive hardware interrupts on the processor, receive timer inter- rupts, and inter-processor interrupts (IPI).	Can be used to hook timer execu- tion, IPIs, or interrupts, or as a way for persistent code to covertly maintain liveness on the machine, executing on a periodic basis.
Filter and third-party notification callbacks	Used by legitimate third-party secu- rity software (and Windows Defender) to receive notifications about system actions, and in some cases even block/ defend against certain actions. Exists as the supported way to achieve much of what KPP prevents.	Could be used by malicious code to hook all the filterable operations, as well as maintain liveness on a ma- chine, executing on a periodic basis.
Specialized configuration and flags	Various data structures, flags, and ele- ments of legitimate components that provide security and/or mitigation guarantees to them.	Could be used by malicious code to bypass certain mitigations or violate certain guarantees or expectations that user-mode processes might have, such as unprotecting a protected process.
KPP engine itself	Code related to bug-checking the system during a KPP violation, execut- ing the callbacks associated with KPP, and more.	By modifying certain parts of the sys- tem used by KPP, unwanted compo- nents could attempt to silence, ignore, or otherwise cripple KPP.

As mentioned, when KPP detects unwanted code on the system, it crashes the system with an easily identifiable code. This corresponds to bugcheck code 0x109, which stands for CRITICAL\_STRUCTURE\_ CORRUPTION, and the Windows Debugger can be used to analyze this crash dump. (See Chapter 15, "Crash dump analysis," in Part 2 for more information.) The dump information will contain *some* information about the corrupted or scrumptiously modified part of the kernel, but any additional data must be analyzed by Microsoft's Online Crash Analysis (OCA) and/or Windows Error Reporting (WER) teams and is not exposed to users.

For third-party developers who use techniques that KPP deters, the following supported techniques can be used:

- File system (mini) filters Use these to hook all file operations, including loading image files and DLLs, that can be intercepted to purge malicious code on-the-fly or block reading of known bad executables or DLLs. (See Chapter 13, "File systems," in Part 2 for more information on these.)
- Registry filter notifications Use these to hook all registry operations. (See Chapter 9 in Part 2 for more information on these notifications.) Security software can block modification of critical parts of the registry, as well as heuristically determine malicious software by registry access patterns or known bad registry keys.
- Process notifications Security software can monitor the execution and termination of all processes and threads on the system, as well as DLLs being loaded or unloaded. With the enhanced notifications added for antivirus and other security vendors, they also can block process launch. (See Chapter 3 for more information on these notifications.)

- Object manager filtering Security software can remove certain access rights being granted to processes and/or threads to defend their own utilities against certain operations. (These are discussed in Chapter 8 in Part 2.)
- NDIS Lightweight Filters (LWF) and Windows Filtering Platform (WFP) filters Security software can intercept all socket operations (accept, listen, connect, close, and so on) and even the packets themselves. With LWF, security vendors have access to the raw Ethernet frame data that is going from the network card (NIC) to the wire.
- Event Tracing for Windows (ETW) Through ETW, many types of operations that have interesting security properties can be consumed by a user-mode component, which can then react to data in near real-time. In certain cases, special secure ETW notifications are available to anti-malware-protected processes under NDA with Microsoft and participation in various security programs, which give access to a greater set of tracing data. (ETW is discussed in Chapter 8 in Part 2.)

# HyperGuard

On systems that run with virtualization-based security (described earlier in this chapter in the section "Virtualization-based security"), it is no longer true that attackers with kernel-mode privileges are essentially running at the same security boundary as a detection/prevention mechanism. In fact, such attackers would operate at VTL 0, while a mechanism could be implemented in VTL 1. In the Anniversary Update of Windows 10 (version 1607), such a mechanism does indeed exist, which is appropriately named *HyperGuard*. HyperGuard has a few interesting properties that set it apart from PatchGuard:

- It does not need to rely on obfuscation. The symbol files and function names that implement HyperGuard are available for anyone to see, and the code is not obfuscated. Complete static analysis is possible. This is because HyperGuard is a true security boundary.
- It does not need to operate non-deterministically because this would provide no advantage due to the preceding property. In fact, by operating deterministically, HyperGuard can crash the system at the precise time unwanted behavior is detected. This means crash data will contain clear and actionable data for the administrator (and Microsoft's analysis teams), such as the kernel stack, which will show the code that performed the undesirable behavior.
- Due to the preceding property, it can detect a wider variety of attacks, because the malicious code does not have the chance to restore a value back to its correct value during a precise time window, which is an unfortunate side-effect of PatchGuard's non-determinism.

HyperGuard is also used to extend PatchGuard's capabilities in certain ways, and to strengthen its ability to run undetected by attackers trying to disable it. When HyperGuard detects an inconsistency, it too will crash the system, albeit with a different code: 0x18C (HYPERGUARD\_VIOLATION). As before, it might be valuable to understand, at a generic level, what kind of things HyperGuard will detect, which you can see in Table 7-24.

Component	Legitimate Usage	Potential Unwanted Usage
Executable code in the kernel, its dependencies, and core drivers, as well as the Import Address Table (IAT) of these components	Refer to Table 7-23.	Refer to Table 7-23.
Global Descriptor Table (GDT)	Refer to Table 7-23.	Refer to Table 7-23.
Interrupt Descriptor Table (IDT) or Interrupt Vector Table	Refer to Table 7-23.	Refer to Table 7-23.
Critical CPU registers such as Control Registers, GDTR, IDTR, Vector Base Address Register, and Model Specific Registers	Refer to Table 7-23.	Refer to Table 7-23.
Executable code, callbacks, and data regions in the Secure Kernel and its dependencies, including HyperGuard itself	Standard Windows components key to operation of VTL 1 and secure kernel-mode usage.	Patching code in these components implies the attacker has access to some sort of vulnerability in VTL 1, either through hardware or the hyper- visor. Could be used to subvert Device Guard, HyperGuard, and Credential Guard.
Structures and features used by Trustlets	Sharing data between one Trustlet to another, or Trustlets and the kernel, or Trustlets and VTL 0.	Implies that some vulnerability might exist in one or more Trustlets, which could be used to hamper features such as Credential Guard or Shielded Fabric/vTPM.
Hypervisor structures and regions	Used by the hypervisor to communicate with VTL 1.	Implies a potential vulnerability in a VTL 1 com- ponent or the hypervisor itself, which may be accessible from ring 0 in VTL 0.
Kernel CFG bitmap	Used to identify valid kernel functions that are the subject of indirect function calls or jumps, as described earlier.	Implies that an attacker has been able to per- form a modification to the VTL 1-protected KCFG bitmap through some sort of hardware or hypervisor exploit.
Page verification	Used to implement HVCI-related work for Device Guard.	Implies that an attacker has somehow attacked SKCI, which could result in Device Guard com- promise or non-authorized IUM Trustlets.
NULL page	None.	Implies that an attacker has somehow coerced the kernel and/or secure kernel to allocate vir- tual page 0, which can be used to exploit NULL- page vulnerabilities in either VTL 0 or VTL 1.

On systems with VBS enabled, there is another security-related feature that is worth describing, which is implemented in the hypervisor itself: Non-Privileged Instruction Execution Prevention (NPIEP). This mitigation targets specific x64 instructions that can be used to leak the kernel-mode addresses of the GDT, IDT, and LDT, which are SGDT, SIDT, and SLDT. With NPIEP, these instructions are still allowed to execute (due to compatibility concerns), but will return a per-processor unique number that is not actually the kernel address of these structures. This serves as a mitigation against Kernel ASLR (KASLR) information leaks from local attackers.

Finally, note that there is no way to disable PatchGuard or HyperGuard once they are enabled. However, because device-driver developers might need to make changes to a running system as part of debugging, PatchGuard is not enabled when the system boots in debugging mode with an active remote kernel-debugging connection. Similarly, HyperGuard is disabled if the hypervisor boots in debugging mode with a remote debugger attached.

# Conclusion

Windows provides an extensive array of security functions that meet the key requirements of both government agencies and commercial installations. In this chapter, we've taken a brief tour of the internal components that are the basis of these security features. In Chapter 8 of Part 2, we'll look at various mechanisms that are spread out throughout the Windows system.

# Index

### **Symbols**

! (exclamation points), 40 .NET Framework, 6–7 64-bit address space layouts, 357–359 64-bit extended systems, 50

## Α

AAM (Admin Approval Mode), 729 access access checks, 621-624 access masks, 624 access tokens, 20, 677 ACEs (access control entries). See ACEs ACLs (access control lists). See ACLs object access auditing, 679-681 access checks, 621-624 access control entries. See ACEs access control lists. See ACLs access masks, 624 access tokens, 20, 677 accounting (quantums), 233 accounts privileges, 668-675 Bypass Traverse Checking privilege, 675 super privileges, 675-676 rights, 668-670 User Account Control. See UAC ACEs (access control entries) conditional ACEs, 667-668 GUI security editors, 664-665 overview, 650-653 trust SIDs, 657-658 ACLs (access control lists) assigning, 656-657 determining access, 659-665 GUI security editors, 664-665 inheritance, 656-657 overview, 650-653 Owner Rights SIDs, 662 activation contexts, 163 address spaces 64-bit address space layouts, 357-359 ARM address space layouts, 356-357 canonical addresses, 359 creating processes, 140-142 dynamic allocation, 359-365 image bias, 368 PTEs, 355-356 quotas, 364-365 sessions, 353-355 setting address limits, 363-364 types of data, 348-349

user address spaces. See user address spaces viewing address usage, 361-363 x64 virtual address limitations, 359 x86 address space layouts, 349-352 x86 session space, 353-355 x86 system address space layouts, 352-353 address translation ARM virtual address translation, 381-382 overview, 371 page tables, 375-376 PTEs, 375-376 TLB, 377-378 viewing, 378-380 write bits, 376-377 x64 virtual address translation, 380-381 x86 virtual address translation, 371-375 Address Windowing Extensions (AWE), 22, 323-324 addresses, canonical, 359 Admin Approval Mode (AAM), 729 administrative rights (UAC), 729-732 advanced audit policy, 683-684 affinity manager, 336 affinity masks extended affinity masks, 276-277 symmetric multiprocessing, 53 threads. 275-277 allocating address spaces dynamic allocation, 359-365 quotas, 364-365 memory, 310-315 API Sets (image loader), 173-176 APIs (application programming interfaces) API Sets (image loader), 173-176 AuthZ, 666-667 COM (component object model), 5 .NET Framework, 6-7 overview, 4 Windows Runtime, 5-6 **AppContainers** brokers, 709 capabilities, 699-703 handles, 705-708 lowboxes, defined, 134 object namespaces, 703-705 overview, 684 security environment. See security environment tokens, 690-692 UWP apps, 685-687 UWP processes, 687-692 AppIDs, 756-757 application programming interfaces. See APIs applications. See also processes APIs. See APIs AppContainers. See AppContainers AppIDs, 756-757 AppLocker, 757-762 classic apps, 103 desktop apps, 103 immersive apps, 103 large address spaces, 351 modern apps, 103 UWP apps, 685-687 AppLocker, 757–762 applying priority boosts, 249 architecture components, 61-62 kernel mode, 47-49 overview, 47-49, 61-62 user mode, 47-49 VBS, 59-61 ARM address space layouts, 356-357 ARM virtual address translation, 381-382 ASLR. See address spaces assertions compilers, 753 fast fail failure codes, 754-756 operating system, 753 overview, 752-753 assigning ACLs, 656-657 processors (groups), 271-273 assured authentication, 718-719 asymmetric multiprocessing, 51 asynchronous I/O, 511 atom tables, 697-698 attributes AppContainer security, 695–697 converting, 131-135 trustlets, 125 auditing (security) advanced audit policy, 683-684 global audit policy, 682-683 object access auditing, 679-681 overview, 677-679 authentication policies (Credential Guard), 616-617 users, 713-718 Kerberos, 714-715 MSV1\_0, 713-714 viewing active logon sessions, 715-717 AuthZ API, 666–667 Autoboost, 254 auto-elevation (UAC), 732-733 AWE (Address Windowing Extensions), 22, 323-324

#### balance set manager-cores (threads)

#### В

balance set manager priority boosts, 247 working sets, 421–422 bandwidth, reserving, 551–552 binary planting, 160 bitmaps (CFG), 744–747 BNO isolation, 708 brokers (AppContainers), 709 buckets (heaps), 335 built-in trustlets, 125 bumps, 549, 551 bus drivers, 493 Bypass Traverse Checking Privilege, 675

#### С

caching files, 513 calculating load address, 368-369 cancelling I/O overview, 537 thread termination, 539 users, 537-538 canonical addresses, 359 catalog files (Plug and Play), 574 CBAC (Claims-Based Access Control), 667 CC (Common Criteria), 607 CFG (Control Flow Guard), 741 bitmaps, 744-747 image loader, 750-751 kernel CFG, 751-752 overview, 741-742 strengthening, 747-749 suppression, 741, 748 viewing, 742-744 CFI (control flow integrity), 740 checked build (kernel debugging), 57-58 checking large address space support, 351 Claims-Based Access Control (CBAC), 667 class drivers, 494 classic apps, 103 classification, memory combining, 461 clients, memory limits, 447-449 clock cycles, 233-234 clock interval, 232 clustered page faults, 387-388 collided page faults, 387 COM (component object model), 5 combining memory classification, 461 combined pages release, 464-465 creating shared PTEs, 462-464 overview, 459-460 page combining, 462 searching, 460 viewing, 465-467 command prompt windows, opening, 13 commands ! (exclamation points), 40 laddress, 746 !ca, 408, 411 !cpuinfo, 233 Idbaprint, 58

Idd 380 !devnode, 562-563 !devobj, 504-506, 524 ldevstack, 521 !dg, 379 !drvobj, 504-506, 512, 517 !file, 408 !fileobj, 509 !handle, 109, 408, 707 !heap, 338 !heap -i, 341-343 !heap -s, 340 lirp, 519, 522, 541 lirpfind, 521 ljob, 180-182, 265, 294 list, 167 llookaside, 331 Imemusage, 410 Inuma, 270 lobject, 502–504 !partition, 448 !pcr, 77, 260 !peb, 109-110, 166 !pfn, 443 !poolused, 328 !popcaps, 597 !popolicy, 598 lprcb, 77s !process, 109, 180-181, 197, 261, 518 !pte, 375, 379, 466 !ready, 230-231 !runas, 180 !sd, 655 !session, 353 !silo, 189 !smt, 268 lsysptes, 355 !teb. 201-205 !thread, 109, 197-199, 201, 261, 518 Itoken, 637 lvad, 402 lverifier, 557 lvm. 307 !vm 4, 355 !wdfkd.wdfldr, 580 !wmiprint, 58 !wsle, 420 .process, 109–110 ~, 202, 209 at, 8 AuditPol, 682 bang commands, 40 cron, 8 dd, 380 docker, 190 dt. 40-42, 78, 108, 182 dump, 40 a, 70, 265 k. 70, 210 lm, 112 poolmon, 327 powercfg /a, 592 powercfg /h, 591 powercfg /list, 598

q, 43 runas, 101 schtacks, 8 start, 218-219 u, 71 ver, 3 winver, 3 commit charge memory manager, 313 page faults. See page faults commit limit commit charge, 394-396 memory manager, 313 committed pages (private pages), 310-313 Common Criteria (CC), 607 communication, secure, 614-615 compilers, assertions, 753 completion ports, 541-546 component object model (COM), 5 components architecture, 61-62 I/O, 483-488 memory manager, 302-303 security, 608-611 SuperFetch, 473-474 compression (memory), 449-456 concurrency (threads), 542 conditional ACEs, 667-668 configuring DFSS, 290-292 guantum, 237–238 Connected Standby, 594 consent elevation (UAC), 729 consoles, 67 container notification (I/O), 552 containers (silos) ancillary functionality, 189-190 containers, 190–191 contexts, 186-188 creating, 188-189 isolation, 184-186 monitors, 187-188 objects, 183-184 overview, 183 context switches, 215 context switching, 255-256 contexts activation contexts, 163 context switches, 215 context switching, 255-256 Direct Switch, 255-256 directed context switch, 19 image loader, 163 jobs (silos), 186-188 threads, 18 Control Flow Guard. See CFG control flow integrity (CFI), 740 controlling power, 599-600 quantums, 234-235 converting attributes, 131–135 copy-on-write, 321-323 cores (threads), 52

**CPU-executive process object** 

CPU rate limits, 292–295 sets, 278–283 starvation, 246–248 Credential Guard authentication policies, 616–617 Kerberos armoring, 616–617 NTOWF/TGT key, 613–614 overview, 612–613 passwords, 613 secure communication, 614–615 UEFI, 616 credential providers (DLLs), 98 CSR\_PROCESS data structure, 105, 111–112 CSR\_THREAD data structure, 195, 205–206

#### D

DAC (Dynamic Access Control), 666 DACLs. See ACLs data address spaces, 348-349 loading, 471-472 Data Execution Protection (DEP), 319-321 data structures PFN, 440-443 processes !process command, 109 CSR\_PROCESS, 105, 111-112 DXGPROCESS, 105 EPROCESS, 105-108 ETHREAD, 105 KPROCESS, 106-107 W32PROCESS, 105, 113 threads CSR\_THREAD, 195, 205, 206 ETHREAD, 194-201 KTHREAD, 194-201 databases dispatcher database, 228-230 image loader, 164-168 loaded modules database, 164-168 deadline scheduling, 254 debuggers kernel-mode debugger, 210–212 user-mode debugger, 209-210 debugging DebugActiveProcess function, 39 DebugBreak function, 194 heaps, 342-346 kernel-mode debugger, 210–212 kernel debugging. See kernel debugging unkillable processes, 539-541 user-mode debugger, 209-210 Debugging Tools for Windows (kernel debugging), 38-42 kernel-mode debugging, 39-40 user-mode debugging, 39 viewing type information, 41-42 Deferred Procedure Calls (DPCs) 1/0.490-492 stacks, 401 demand paging, 413

DEP (Data Execution Protection), 319-321 **Dependency Walker** exported functions, 34-35 HAL image dependencies, 80-82 subsystems, 62-63 design goals (Windows), 45-46 desktop apps, 103 determining access (ACLs), 659-665 device drivers bus drivers, 493 class drivers, 494 device objects, 500-507 dispatch routines, 504, 517-518 driver objects, 500-507 Driver Verifier. See Driver Verifier file objects, 507-510 filter drivers, 493 function drivers, 493 installing, 571-575, 577 IRPs dispatch routines, 517-518 layered drivers, 533-536 overview, 525-528 user address spaces, 528-531 KMDF, 578-587 layered drivers IRPs, 533-536 overview, 494-496 loading, 575-577 opening devices, 507-510 overview, 82-83, 492-496 port drivers, 494-495 power manager, 596 routines, 498-500 support, 560-561, 569-571 types, 492-496 UMDF, 578-581, 587-590 Universal Windows Drivers, 85 viewing, 85-88, 496-498 WDF. See WDF WDK (Windows Driver Kit), 43-44 WDM, 83-84, 493-494 Device Guard, 617-619 device objects (device drivers), 500-507 devices drivers. See device drivers device stacks, 563-569 devnodes, 563-569 enumeration, 561-563 opening, 507-510 support, 560-561 trees, 561-563 DFSS (dynamic fair share scheduling), 289-292 Direct Swit0ch, 255-256 directed context switch, 19 dispatch events, 239-240 dispatch routines device drivers, 504 IRPs. 517-518 dispatcher database, 228-230 dispatchers, 215 displaying. See viewing

DIIS credential providers, 98 DIIMain function, 154 image loader import parsing, 168-170 name redirection, 162-163 name resolution, 160–162 safe DLL search mode, 160 viewing DLL load search order, 163-164 Ntdll.dll, 70-72 overview, 8 subsystem DLLs, 48 subsystems, 62-63 DPCs (Deferred Procedure Calls) 1/0.490-492 stacks, 401 driver objects (device drivers), 500-507 Driver Verifier I/O, 554-555 memory IRQL checking, 557 low resources simulation, 557–558 miscellaneous checks, 558-559 pool tracking, 556-557 special pool, 555-556 overview, 552-554 drivers. See device drivers dumping device trees, 562-563 dump command, 40 ETHREAD structure, 197-198 KTHREAD structure, 197–198 silo contexts, 187-188 DXGPROCESS data structure, 105 Dynamic Access Control (DAC), 666 dynamic allocation (address spaces), 359-365 dynamic fair share scheduling (DFSS), 289-292 dynamic processors, 295-296

## E

editions (Windows), 54-57 EMET (Enhanced Mitigation Experience Toolkit), 370 enclaves (memory), 467-472 Enhanced Mitigation Experience Toolkit (EMET), 370 entries (PFN), 443 enumeration (devices), 561–563 environment (AppContainers security) overview, 693-695 viewing atom table, 697-698 viewing security attributes, 695-697 EPROCESS data structure, 105–108 EPROCESS object, 138-140 ETHREAD data structure, 105, 194-201 events dispatch events, 239-240 notification events, 423-425 examining. See viewing exclamation points (!), 40 executing initial thread, 148 executive, 72-75 executive process object, 138-143

#### executive resources (priority boosts)-free pages

executive resources (priority boosts), 242-243 exiting threads, 260 experiments allocating memory, 311-313 Bypass Traverse Checking Privilege, 675 calculating load address, 368-369 checked build, 57-58 checking large address space support, 351 configuring quantums, 237-238 creating maximum number of threads, 399 debugging unkillable processes, 539-541 dumping device trees, 562-563 ETHREAD structure, 197-198 KTHREAD structure, 197–198 silo contexts, 187-188 identifying trustlets, 129 launching programs at low integrity levels, 641-642 Performance Monitor kernel mode/user mode comparison, 26-27 setting address limits, 363-364 tracing process startup, 149-154 troubleshooting pool leaks, 329-330 using virtual service accounts, 647-650 viewina access masks, 624 active logon sessions, 715-717 address translation, 378-380 address usage, 361-363 AppContainer atom table, 697-698 AppContainer capabilities, 701-703 AppContainer security attributes, 695-697 AppContainer tokens, 690-692 brokers, 709 CFG, 742-744 CFG bitmaps, 746-747 clock cycles per quantum, 233-234 control areas, 408-412 CPU rate limits, 293-295 CPU sets. 279-283 CPU starvation, 247-248 CSR PROCESS structure, 112 CSR\_THREAD structure, 206 DEP, 321 device drivers, 85-88 device objects, 502-506 devnodes, 568-569 DLL load search order, 163-164 driver catalog files, 574 driver dispatch routines, 517-518 driver INF files, 573 driver objects, 504-506 driver power mappings, 596 drivers, 496-498 DSS. 290-292 enabling privileges, 673-675 EPROCESS data structure, 107–108 ETHREAD structure, 196–201 exported functions, 34-35 fast I/O, 512-513 file objects, 508-509 file virtualization, 726-727

filtered admin tokens, 645-646 foreground boosts, 243-245 free page lists, 429-430 global audit policy, 682 GUI boosts, 245-246 HAL image dependencies, 80-82 heaps, 338-341 idle threads, 260-262 image loader, 156-157 integrity levels, 628-631 I/O priority boosting/bumping, 551 I/O priority throughput, 549-551 IRPs, 518-519, 521-524 jobs, 180-183 kernel stacks, 400-401 kernel type information, 41-42 KMDF drivers, 580-581 KPCR, 77-78 KPRCB. 77-78 KTHREAD structure, 196-201 loaded modules database, 166-167 look-aside lists, 331–332 memory, 305-308 memory compression, 455-456 memory partitions, 458 memory-mapped files, 316-317 MMCSS priority boosting, 252-253 modified page lists, 430-435 notification events, 424-425 NUMA processors, 270-271 object access auditing, 679-681 page files, 390-392, 397-398 page priorities, 437 pageheap, 344-346 PEB, 110-111 PFN, 427-428 PFN entries, 443 pool size, 326-327 power availability requests, 603 power states, 592-593 prefetch file reads and writes, 415-416 processes, affinity, 275-276 processes, data structures, 109 processes, process tree, 12-13 processes, Process Explorer, 16-18 processes, Task Manager, 9–11 protected processes, 118-119 PTEs, 355-356 ready threads, 230-231 section objects, 406-407 security descriptors, 654-656 service processes, 97-98 services, 97 sessions, 353-355 SIDs, 626-627 SMT processors, 268-269 SRPs, 764 stacks, 521 standby page lists, 430-435 subsystems, 62-63 swap files, 393 system power capabilities, 597-599 system service dispatcher, 70-71 TEB, 201-205

thread freezing, 265-266 thread pools, 299-300 thread priorities, 219–222 thread states, 224-228 threads, clock interval, 232 threads, kernel-mode debugger, 210-212 threads, protected processes, 213 threads, user-mode debugger, 209–210 token stored handles, 706-708 tokens, 635-640 trust SIDs, 658 UMDF drivers, 580-581 user address spaces, 366-367 UWP processes, 689-690 VADs, 402-403 virtual page files, 393 Windows edition enabled features, 56-57 working sets, 418-421 zero page lists, 429-430 exploit mitigation assertions. See assertions CFG. See CFG control flow integrity, 740 overview, 735 process mitigation policies, 735-740 extended affinity masks, 276-277

#### F

facilities (Windows edition enabled features), 56 - 57fast fail failure codes, 754–756 fast I/O, 511-513 fast user switching, 30, 475 fault-tolerant heaps (FTH), 347-348 fibers, 19 file mapping objects, 20 file objects (device driv0ers), 507-510 files caching, 513 catalog files, 574 file mapping objects, 20 INF files, 573 mapped-file I/O, 513 memory-mapped files, 315–317 page files. See page files virtualization (UAC), 722-727 filter drivers, 493 filtered admin tokens (SIDs), 645-646 filters (function drivers), 493 firmware, 29 flags, converting, 131-135 flow (IRPs), 519-520 foreground threads, 243-245 frameworks .NET Framework, 6-7 power management framework, 600-601 WBF (Windows Biometric Framework), 719-721 free pages lists, 429-430 memory manager, 310-313

### freezing threads-hypervisor GUI security editors, 664–665

security editors, 664–665 threads (priority boosts), 245–246 GUIDs (Switchback), 171–173

### Н

HAL (hardware abstraction layer) overview, 79-82 viewing image dependencies, 80-82 handles AppContainers, 705-708 token stored handles. 706-708 hardware firmware, 29 HAL. See HAL kernel support, 78–79 hashes (AppContainer atom tables), 697–698 heaps/pools affinity manager, 336 buckets, 335 debugging, 342-346 FTH (fault tolerant heaps), 347-348 HeapAlloc function, 332 HeapCreate function, 332 HeapDestroy function, 332 HeapFree function, 332 HeapLock function, 332 HeapReAlloc function, 332 HeapUnlock function, 332 HeapWalk function, 332 leaks, 329-330 LFH (low-fragmentation heaps), 335-336 look-aside lists, 331-332 NT heaps, 334 non-paged pools, 325 overview, 324-325, 332 paged pools, 325 pageheap, 343-346 poolmon command, 327 processes, 333 randomizing (user address spaces), 369 security, 341-342 segment heaps, 336-337 size, 325-327 special pools, 325, 555-556 synchronization, 334-335 thread pools, 297-300 tracking, 556-557 types, 334 usage, 327-329 viewing, 338-341 heterogenous multiprocessing, 52 heterogenous scheduling, 286–287 hibernation, 475 hiding. See viewing hierarchies (jobs), 179–180 host (consoles), 67 hybrid jobs, 183 HyperGuard, 768–769 hypervisor, 27–28

freezing threads, 264-266 FTH (fault-tolerant heaps), 347-348 functions AllocConsole, 63 AvTaskIndexYield, 254 BaseThreadInit, 160, 170 ConvertThreadToFiber, 19 CreateFiber, 19 CreateFile, 34 CreateProcess, 101-104, 129-131, 134, 157 CreateProcessAsUser, 101-103, 139 CreateProcessInternal, 101-103 CreateProcessInternalW, 129, 131, 134-138, 146-147, 150 CreateProcessWithLogonW, 101-103 CreateProcessWithTokenW, 101-103 CreateRemoteThread, 193-194 CreateRemoteThreadEx, 194, 206-207 CreateThread, 193-194, 199, 208 Csr, 71-72 DbgUi, 72 DebugActiveProcess, 39 DebugBreak, 194 DeviceIoControl, 73 DgbPrintEx, 58 DllMain, 154 drivers, 493 Etw, 72 Ex, 73 ExitProcess, 154 exported, 34-35 GetQueueCompletionStatus, 176 GetSystemTimeAdjustment, 232 GetThreadContext, 18 GetVersionEx, 2 HeapAlloc, 332 HeapCreate, 332 HeapDestroy, 332 HeapFree, 332 HeapLock, 332 HeapReAlloc, 332 HeapUnlock, 332 HeapWalk, 332 Inbv, 73 lo, 73 IoCompleteRequest, 241 lop, 73 Ke, 75 KeStartDynamicProcessor, 295 KiConvertDynamicHeteroPolicy, 287 KiDeferredReadyThread, 274, 284 KiDirectSwitchThread, 256 KiExitDispatcher, 241, 256 KiProcessDeferredReadyList, 274 KiRemoveBoostThread, 241, 250 KiSearchForNewThreadOnProcessor, 283 KiSelecthreadyThreadEx, 267 KiSelectNextThread, 266-267 Ldr, 70-71 LdrApplyFileNameRedirection, 175 Mi, 73 MiZeroInParallel, 303 NtCreateProcessEx, 104, 120 NtCreateThreadEx, 207

NtCreateUserProcess, 104 NtCreateWorkerFactory, 298 OpenProcess, 39 overview, 7-8 PopInitializeHeteroProcessors, 286 prefixes, list of, 87-88 PsCreateSystemThread, 194 PspAllocateProcess, 104, 138 PspComputeQuantum, 235 PspCreatePicoProcess, 104 PspInitializeApiSetMap, 175 PspInsertProcess, 104, 143 PsTerminateSystemThread, 194 QueryInformationJobObject, 179 ReadFile, 25 ReadProcessMemory, 20 ResumeThread, 264 Rtl. 72 RtlAssert, 58 RtlCreateUserProcess, 104 RtlGetVersion, 55 RtlUserThreadStart, 208 RtlVerifyVersionInfo, 55 secure system calls, 71 SetInformationJobObject, 275 SetPriorityClass, 218 SetProcessAffinityMask, 275 SetProcessWorkingSetSize, 222 SetThreadAffinityMask, 275 SetThreadIdealProcessor, 278 SetThreadSelectedCpuSets, 279 subsystem DLLs, 63 SuspendThread, 264 SwitchToFiber, 19 system services, 72 SystemParametersInfo, 178 TerminateJobObject, 179 TerminateProcess, 154 TermsrvGetWindowsDirectoryW, 170 TimeBeginPeriod, 232 TimeSetEvent, 232 TpAllocJobNotification, 176 UserHandleGrantAccess, 176 VerifyVersionInfo, 2, 55 VirtualLock, 314 WaitForMultipleObjects, 256 WaitForSingleObject, 256 Wow64GetThreadContext, 19 WriteProcessMemory, 20 ZwUserGetMessage, 210

## G

games (priority boosts), 251–254 global audit policy, 682–683 granularity (memory), 314–315 groups claims, 718 processors, 271–273 scheduling CPU rate limits, 292–295 DFSS, 289–292 dynamic processors, 295–296 overview, 287–289

#### IBAC (Identity-Based Access Control)-KMDF (WDF)

#### I

IBAC (Identity-Based Access Control), 667 ideal node, 278 ideal processor, 277-278 identification AppIDs, 756-757 trustlets, 129 identities (trustlets), 125-126 Identity-Based Access Control (IBAC), 667 Idle process, 89-90 idle threads, 260-263, 267 image bias, 368 image loader activation contexts, 163 API Sets, 173-176 binary planting, 160 CFG, 750-751 DLL import parsing, 168-170 DLL load search order, 163-164 DLL name redirection, 162–163 DLL name resolution, 160–162 early initialization, 157-160 loaded modules database, 164-168 overview, 155-156 post-import process initialization, 170 safe DLL search mode, 160 Switchback, 171-173 viewing, 156-157 images HAL, 80-82 image bias, 368 loading. See image loader native images (subsystems), 72 opening, 135-138 randomizing (user address spaces), 367-369 immersive applications, 103 immersive processes, 103-104 impersonation (SIDs), 642-644 implementation (SAS), 712 importing DLLs, 168-170 INF files, 573 inheritance (ACLs), 656-657 initial thread creating, 144-146 executing, 148 initializing memory enclaves, 469, 472 processes creating processes, 148-149 image loader, early, 157-160 image loader, post-import process, 170 subsystem, 146-147 Winlogon, 711-712 in-paging I/O, 386-387 input. See I/O installing drivers, 571-575, 577 integrity levels (SIDs), 628-631, 641-642 interfaces (APIs) API Sets (image loader), 173-176 AuthZ, 666-667 COM (component object model), 5 .NET Framework, 6-7

overview, 4 Windows Runtime, 5-6 internal synchronization, 308 Interrupt Request Levels (IRQLs), 488-490, 557 invalid PTEs, 384-385 inversion I/O priorities, 549 priority boosts, 246 1/0 asynchronous, 511 cancelling overview, 537 thread termination, 539 users, 537-538 completion ports, 541-546 components, 483-488 concurrency, 542 container notifications, 552 device drivers. See device drivers DPCs, 490-492 Driver Verifier, 554-555, 557 fast I/O. 511-513 file caching, 513 in-paging I/O, 386-387 I/O manager, 485-486 IRPs (I/O request packets). See IRPs (I/O request packets) IRQLs, 488-490, 557 mapped-file I/O, 513 overview, 483-488 Plug and Play catalog files, 574 device enumeration, 561-563 device stacks, 563-569 device support, 560-561 device trees, 561-563 devnodes. 563-569 driver installation, 571-575 driver support, 560-561, 569-571 INF files, 573 overview, 559-560 power manager controlling power, 599-600 drivers, 596 overview, 590-594 performance states, 601 power availability requests, 602-603 power management framework, 600-601 power mappings, 595 power states, 590-594 system capabilities, 597-599 priorities. See priorities priority boosts, 241-242 processing, 486-488 scatter/gather I/O, 513 synchronous, 511 thread-agnostic I/O, 536-537 WDF. See WDF I/O manager, 485-486 I/O request packets. See IRPs IoCompletion object, 542 IRPs (I/O request packets), 513

cancelling 537–539 dispatch routines, 517–518 flow, 519–520 layered drivers, 533–536 overview, 513–515, 525–528 stacks, 515–519, 521 synchronization, 531–533 user address spaces, 528–531 viewing, 518–519, 521–524 IRQLs (Interrupt Request Levels), 488–490, 557 isolation (jobs), 184–186

#### J

jobs creating, 178–179 hierarchies, 179–180 hybrid jobs, 183 limits, 177–178 overview, 20–21, 176–177 silos. *See* silos (jobs) viewing, 180–183

### Κ

Kerberos armoring, 616-617 authentication, 714-715 kernel debugging checked build, 57-58 Debugging Tools for Windows, 38-42 kernel-mode debugging, 39-40 LiveKd, 43 overview, 38 symbols, 38 threads, 210-212 type information, 41-42 user-mode debugging, 39 hardware support, 78-79 jobs. See jobs kernel CFG, 751-752 kernel mode. See kernel mode KPCR, 76-78 KPRCB, 76-78 objects, 75 overview, 75 patches processes defined, 106 structure, 141 secure kernel, 59-61 stacks, 400-401 user address spaces, 369 kernel mode architecture, 47-49 user mode comparison, 23-27, 46 kernel patches HyperGuard, 768-769 overview, 764-765 PatchGuard, 765–768 kernel processor control block (KPRCB), 76-78 kernel processor control region (KPCR), 76-78 KMDF (WDF), 578-587

KPCR (kernel processor control region), 76–78 KPRCB (kernel processor control block), 76–78 KPROCESS data structure, 106–107 KTHREAD data structure, 194–201

#### L

large address spaces, checking support, 351 large pages (memory manager), 303-304 last processor, 277-278 launching programs at low integrity levels, 641-642 layered drivers IRPs, 533-536 overview, 494-496 lavouts 64-bit address space layouts, 357-359 ARM address space layouts, 356-357 user address spaces, 365–367 x86 address space layouts, 349-352 x86 system address space layouts, 352-353 lazy evaluation, 323 leaks (pools), 329-330 Legacy Standby, 594 levels SID integrity levels, 628-631, 641-642 thread priorities, 215-219 LFH, 335-336 (low-fragmentation heaps), 335-336 lightweight threads, 19 Linux subsystems, 68-70 lists look-aside lists (pools), 331-332 minimum TCB list, 117 page lists, 429-435 LiveKd, 43 load address (user address spaces), 368-369 loading data (memory enclaves), 471-472 drivers, 575-577 images. See image loader load address (user address spaces), 368-369 locking/locks memory, 314 priority boosts, 241 logging (SuperFetch), 474-475 logical prefetcher (working sets), 413-416 logon assured authentication, 718-719 group claims, 718 overview, 710-711 SAS implementation, 712 user authentication, 713-718 Kerberos, 714-715 MSV1 0, 713-714 viewing active logon sessions, 715-717 WBF, 719-721 Windows Hello, 721 Windows logon process, 98-99 Winlogon initialization, 711-712 look-aside lists, 331-332 low resources simulation, 557-558

LowBox. See AppContainers low-fragmentation heaps (LFH), 335–336

#### Μ

managing power. See power manager working sets, 417-421 mandatory labels (SIDs), 630 mapped page writer, 438-439 mapped-file I/O, 513 mappings (power), 595 masks access masks, 624 affinity masks. See affinity masks memory address spaces. See address spaces address translation. See address translation AWE (Address Windowing Extensions), 22, 323-324 combining, 459-467 compression, 449-456 **Driver Verifier** IRQL checking, 557 low resources simulation, 557-558 miscellaneous checks, 558-559 pool tracking, 556-557 special pool, 555-556 enclaves, 467-472 heaps/pools. See heaps/pools limits physical memory, 446-447 Windows clients, 447-449 Memory Compression process, 91 memory manager. See memory manager NUMA (non-uniform memory architecture). See NUMA page faults. See page faults partitions, 456-458 PFN. See PFN section objects, 405-412 stacks, 398 SuperFetch. See SuperFetch VADs (virtual address descriptors). See VADs (virtual address descriptors) virtual memory, 21-23 working sets WSRM, 222-223 Memory Compression process, 91 memory manager allocating memory, 310-315 attaching to the process, 310 AWE, 323-324 commit charge, 313 commit limit, 313 committed pages, 310-313 components, 302-303 copy-on-write, 321-323 DEP, 319-321 free pages, 310-313 granularity, 314-315 internal synchronization, 308 large pages, 303-304 lazy evaluation, 323

#### KPCR (kernel processor control region)-nodes

locking memory, 314 memory-mapped files, 315-317 NX page protection, 319 overview, 301-302 pages, defined, 304 protecting memory, 317-319 reserved pages, 310-313 services overview, 309-310 shareable pages, 310-313 shared memory, 315 small pages, 303-304 viewing memory, 305-308 memory-mapped files, 315-317 minimal processes, 104, 120 minimum TCB list, 117 miscellaneous checks (Device Driver), 558–559 mitigating exploits. See exploit mitigation mitigations (security), 370 MMCSS (Multimedia Class Scheduler Service), 239, 251-254 model (operating system), 46-47 modern apps, 103 modern processes, 103-104 Modern Standby, 594 modified page lists, 430-435 modified page writer, 438-439 modules (image loader), 164-168 monitors (silos), 187–188 MSV1\_0 authentication, 713-714 Multimedia Class Scheduler Service (MMCSS), 239, 251-254 multiple sessions, 29-30 multiprocessor systems affinity masks, 53, 275-276 asymmetric, 51 CPU sets, 278-283 extended affinity masks, 276-277 heterogenous, 52 ideal node, 278 ideal processor, 277-278 last processor, 277-278 NUMA systems, 269-271 overview, 268 processors groups, 53, 271-273 number per group, 273 selecting, 284-286 state, 274 scheduler scalability, 274 selecting, 283-284 SMT systems, 268-269 symmetric, 51-53 multitasking (operating system), 51

### Ν

namespaces, 703–705 native images, 72 native processes, 104 .NET Framework, 6–7 nodes devnodes, 563–569 ideal node, 278 processors, 52

#### no-execute (NX) page protection-policies

no-execute (NX) page protection, 319 non-paged pools, 325 non-uniform memory architecture. See NUMA notification events, 423-425 NT heaps, 334 Ntdll.dll, 70–72 NTOWF/TGT key, 613-614 NUMA (non-uniform memory architecture) overview, 404 processors, 270-271 systems, 269-271 numbers processors per group, 273 threads, creating maximum, 399 NX (no-execute) page protection, 319

## 0

obiects device drivers device objects, 500-507 file objects, 507-510 driver objects device drivers, 500-507 dispatch routines, 504 EPROCESS object, 138-140 executive process object, 138-143 file mapping objects, 20 loCompletion, 542 jobs. See jobs kernel objects, 75 namespaces (AppContainers), 703-705 object access auditing, 679-681 overview, 30-31 section objects, 405-412 security access checks, 621-624 ACEs. See ACEs ACLs. See ACLs DAC, 666 overview, 619-621 security descriptors, 650-656 SIDs. See SIDs virtual service accounts, 646-650 OneCore, 3-4 opening command prompt windows, 13 devices, 507-510 images, 135-138 operating system (OS) assertions, 753 model, 46-47 multitasking, 51 scalability, 53 OTS (over-the-shoulder) elevation, 729 output. See I/O over-the-shoulder (OTS) elevation, 729 Owner Rights SIDs, 662

#### Ρ

packets. See IRPs PAE (Physical Address Extension), 371 page directory entry (PDE), 374

page directory pointer entry (PDPE), 374 page directory pointer table (PDPT), 372 page faults clustered page faults, 387-388 collided page faults, 387 commit charge commit limit, 394-396 page file size, 397-398 in-paging I/O, 386-387 overview, 383-384 page files overview, 389-390 swap files, 392-393 viewing, 390-392 virtual page files, 393 PTEs invalid PTEs, 384-385 prototype PTEs, 385-386 soft page faults, 384 page files overview, 389-390 reservations (PFNs), 443-446 size (commit charge), 397-398 swap files, 392-393 viewing, 390-392 virtual page files, 393 page frame number. See PFN page lists, 428-435 page table entries. See PTEs page tables, address translation, 375-376 paged pools, 325 pageheap, 343-346 pages combining memory combining, 462 releasing, 464-465 committed pages, 310-313 defined, 304 faults. See page faults files. See page files free pages, 310-313 mapped page writer, 438-439 memory manager, 310-313 modified page writer, 438-439 page frame number. See PFN page lists. See page lists page tables, address translation, 375-376 paged pools, 325 pageheap, 343-346 PDE (page directory entry), 374 PDPE (page directory pointer entry), 374 PDPT (page directory pointer table), 372 PFN. See PFN priorities, 436-437, 476-478 PTEs (page table entries). See PTEs reserved pages, 310-313 shareable pages, 310-313 states, 425-428 SuperFetch, 476-478 parameters, validating, 131–135 parsing DLLs, 168-170 partitions, 456-458 passwords (Credential Guard), 613

patches (kernel). See patches (kernels) HyperGuard, 768-769 overview, 764-765 PatchGuard, 765-768 PatchGuard, 765-768 PCB (process control block), 106 PCR (processor control region), 260 PDE (page directory entry), 374 PDPE (page directory pointer entry), 374 PDPT (page directory pointer table), 372 PEB (Process Environmental Block), 105 overview, 105 setting up, 143 viewing, 110-111 performance Performance Monitor. See Performance Monitor robust performance, 478-479 states, 601 SuperFetch, 478–479 Performance Monitor kernel mode/user mode comparison, 26-27 overview, 36-38 PFN (page frame number) data structures, 440-443 entries, 443 mapped page writer, 438-439 modified page writer, 438-439 overview, 425-428 page files (reservations), 443-446 page lists, 428-435 page priorities, 436-437 page states, 425-428 viewing, 427-428 Physical Address Extension (PAE), 371 physical memory limits, 446-447 Pico creating processes, 104 overview, 121-122 subsystems, 68-70 placement policies (working sets), 416-417 Plug and Play (PnP) devices catalog files, 574 device stacks, 563-569 devnodes, 563-569 driver installation, 571-575 driver support, 569-571 enumeration, 561-563 INF files, 573 support, 560-561 trees, 561-563 drivers, 560-561 overview, 559-560 policies advanced audit policy, 683-684 authentication policies, 616-617 Credential Guard, 616-617 global audit policy, 682-683 process mitigation policies, 735-740 SRPs (software restriction policies), 757. 762-764

#### policies-quotas (address spaces)

trustlets, 124-125 Windows edition enabled features, 56-57 pools size, 326-327 threads, 299-300 usage, 327-329 port drivers, 494-495 portability (Windows), 50-51 ports completion ports, 541-546 port drivers, 494–495 power manager Connected Standy, 594 controlling power, 599-600 drivers, 596 Legacy Standy, 594 Modern Standy, 594 overview, 590-594 performance states, 601 power availability requests, 602-603 power management framework, 600-601 power mapings, 595 power states, 590-594 system capabilities, 597-599 PPL (Protected Processes Light), 115-120 preemption (threads), 257-258 prefetcher (working sets), 413-416 prefixes (functions), 87-88 priorities. See also priority boosts 1/0 bandwidth reservation, 551-552 boosts, 549, 551 bumps, 549, 551 inversion, 549 overview, 546 strategies, 547-548 viewing throughput, 549-551 pages, 436-437 SuperFetch, 476-478 threads levels, 215-219 real-time, 218-219 viewing, 219-222 priority boosts. See also priorities applying, 249 Autoboost, 254 balance set manager, 247 CPU starvation, 246-248 deadline scheduling, 254 dispatch events, 239-240 executive resources, 242-243 foreground threads, 243-245 games, 251-254 GUI threads. 245-246 1/0, 241-242 locks, 241 MMCSS, 239, 251-254 multimedia, 251-254 overview, 238-239 priority inversion, 246 removing, 250 scheduling category, 251 unwait boosts, 240-241

private pages (committed pages), 310-313 privileges (accounts), 668-675 Bypass Traverse Checking privilege, 675 super privileges, 675-676 .process, 109-110 process control block (PCB), 106 Process Environmental Block (PEB), 105 overview, 105 setting up, 143 viewing, 110-111 Process Explorer, 14–18 process reflection (SuperFetch), 480-482 process tree, viewing, 12-14 process VADs, 402-403 processes. See also applications access tokens, 677 attaching to the process, 310 console host, 67 creating address space, 140-142 converting attributes, 131-135 converting flags, 131-135 executing initial thread, 148 executive process object, 138-143 initial thread, 144-146 initializing process, 148-149 initializing subsystem, 146-147 kernel process structure, 141 opening images, 135-138 overview, 101-104, 129-130 setting up EPROCESS object, 138-140 setting up PEB, 143 tracing startup, 149–154 validating parameters, 131-135 data structures !process command, 109 CSR PROCESS, 105, 111-112 DXGPROCESS, 105 EPROCESS, 105-108 ETHREAD, 105 KPROCESS, 106-107 W32PROCESS, 105, 113 debugging unkillable processes, 539-541 heaps, 333 image loader. See image loader immersive processes, 103-104 jobs. See jobs kernel processes, 106 minimal processes, 104, 120 minimum TCB list, 117 mitigation policies, 735-740 modern processes, 103-104 native processes, 104 overview, 8-18 PCB (process control block), 106 PEB (Process Environmental Block), See PEB (Process Environmental Block) Pico. See Pico protected processes. See protected processes reflection (SuperFetch), 480-482 secure processes. See trustlets system processes. See system processes

terminating, 154-155 trustlets. See trustlets UWP processes, 687-692 VADs, 402-403 viewing DLL load search order, 163-164 image loader, 156-157, 163-164 PEB, 110-111 Process Explorer, 14-18, 118-119 process tree, 12-14 protected processes, 118-119, 212-213 Task Manager, 9-11 processing I/O, 486–488 processor control region (PCR), 260 processors groups assigning, 271-273 number of processors per group, 273 scheduling (dynamic processors), 295-296 symmetric multiprocessing, 53 ideal processor, 277-278 KPCR, 76-78 KPRCB, 76-78 last processor, 277-278 nodes, 52 multiprocessor systems. See multiprocessing/multiprocessor systems NUMA, 270-271 PCR (processor control region), 260 selecting, 284-286 SMT, 268-269 state, 274 programs. See applications Protected Process Light (PPL), 115–120 protected processes overview, 113-115 PPLs, 115-120 viewing Process Explorer, 118-119 threads, 212-213 protecting memory, 317-319 prototype PTEs, 385–386 PspInsertProcess function, 104, 143 PTEs (page table entries) address spaces, 355-356 address translation, 375-376 creating shared PTEs, 462-464 defined, 372 invalid PTEs, 384-385 prototype PTEs, 385-386

## Q

quantums (threads), 258–260 accounting, 233 clock cycles, 233–234 clock interval, 232 configuring, 237–238 controlling, 234–235 overview, 231–232 registry value, 236–237 variable quantums, 235–236 quotas (address spaces), 364–365

#### randomization-SIDs (security identifiers)

threads

#### R

randomization (user address spaces) heap, 369 images, 367-369 stacks, 369 viewing support, 370-371 ratings (security) CC. 607 TCSEC, 605-607 ready threads, 230-231 ReadyBoost, 479-480 ReadyBoot, 413-416 ReadyDrive, 480 real-time priorities (threads), 218-219 reflection (process reflection), 480-482 registry overview, 32-33 threads (guantum), 236-237 viewing (security keys), 610 virtualization (UAC), 722-724, 727-728 releasing combined pages, 464-465 removing priority boosts, 250 requests. See IRPs reservations (PFNs), 443-446 reserved pages (memory manager), 310-313 reserving bandwidth, 551-552 Resource Monitor, 36-38 resources Driver Verifier, 557-558 low resources simulation, 557-558 Resource Monitor, 36-38 restricted tokens (SIDs), 644-645 rights (accounts), 668-670 robust performance, 478-479 rotate VADs. 403 routines device drivers, 498-500 dispatch routines. See dispatch routines overview, 7-8

#### S

SACLs. See ACLs safe DLL search mode, 160 sandboxes (lowboxes), 134 SAS implementation, 712 saturation values, 216 scalability operating system, 53 scheulers, 274 scatter/gather I/O, 513 scenarios (SuperFetch), 475-476 schedulers (scalability), 274 scheduling groups CPU rate limits. 292-295 DFSS, 289-292 dynamic processors, 295-296 overview, 287-289 priority boosts deadline scheduling, 254 scheduling category, 251 schedulers (scalability), 274

context switches, 215 dispatchers, 215 exiting, 260 heterogenous, 286-287 preemption, 257-258 guantums, 258-260 terminating, 260 voluntary switching, 256-257 scheduling category, 251 SDK (software development kit), 43 searching image loader, 160 memory combining, 460 safe DLL search mode, 160 section objects, 405-412 secure communication (Credential Guard), 614-615 secure kernel, 59-61 secure processes (trustlets) attributes, 125 built-in, 125 identifying, 129 identities, 125-126 overview, 61, 123-124 policies, 124-125 services, 127-128 system calls, 128 Secure System process, 91 security access tokens. See access tokens accounts privileges, 668-675 privileges, Bypass Traverse Checking privilege, 675 privileges, super privileges, 675-676 rights, 668-670 AppContainers. See AppContainers AppIDs, 756-757 AppLocker, 757–762 auditing. See auditing (security) AuthZ API, 666-667 CBAC, 667 components, 608-611 Credential Guard. See Credential Guard Device Guard, 617-619 exploit mitigation. See exploit mitigation GUI security editors, 664-665 heaps, 341-342 IBAC, 667 kernel patches. See kernel patches logon. See logon mitigations (user address spaces), 370 objects access checks, 621-624 ACEs. See ACEs ACLs. See ACLs DAC, 666 overview, 619-621 security descriptors. See security descriptors, 650 SIDs. See SIDs, 625 virtual service accounts, 646-650 overview, 31-32, 605

ratings. See ratings (security) secure communication (Credential Guard), 614-615 secure kernel, 59-61 secure processes. See secure processes (trustlets) secure system calls (functions), 71 Secure System process, 91 security descriptors. See security descriptors SIDs (security identifiers). See SIDs SRPs, 757, 762-764 trustlets. See trustlets UAC (User Account Control), See UAC (User Account Control) UIPI, 660-661 VBS (virtualization-based security). See VBS (virtualization-based security) architecture, 59-61 hypervisor, 28 viewing (registry keys), 610 virtualization files. 722-727 overview, 611-612, 722 registry, 722-724, 727-728 VSM. See VSB security descriptors overview, 650-653 viewing, 654-656 security identifiers. See SIDs segment heaps, 336-337 selectina processors, 284-286 threads, 266-267, 283-284 server silos. See silos Service Control Manager, 96 service processes, 97-98 services memory manager, 309-310 overview, 7-8 Service Control Manager, 96 service processes, 97-98 system service dispatcher, 70-71 trustlets, 127-128 viewing, 97 Session Manager process, 92-95 sessions multiple, 29-30 viewing, 353-355 Session Manager process, 92–95 x86 session space, 353-355 setting address limits, 363-364 EPROCESS object, 138-140 PEB, 143 UAC, 733-734 shareable pages, 310-313 shared memory, 315 sharing PTEs, 462-464 showing. See viewing SIDs (security identifiers) filtered admin tokens, 645-646 impersonation, 642-644

SIDs (security identifiers)-thread pools

integrity levels, 628-631, 641-642 mandatory labels, 630 overview, 625-626 Owner Rights SIDs, 662 restricted tokens, 644-645 tokens, 632-640 trust SIDs. 657-658 viewing, 626-627 silos (jobs) ancillary functionality, 189-190 containers, 190-191 contexts, 186-188 creating, 188-189 isolation, 184-186 monitors, 187-188 objects, 183-184 overview, 183 simulating low resources, 557-558 size large address spaces, checking support, 351 page files commit charge, 397-398 memory manager, 303-304 pools, 325-327 small pages (memory manager), 303-304 SMT systems, 268-269 soft page faults, 384 software development kit (SDK), 43 software PTEs, 384-385 software restriction policies (SRPs), 757, 762-764 special pools, 325, 555-556 SRPs (software restriction policies), 757, 762-764 stacks device stacks, 563-569 DPC stacks, 401 IRPs, 515-519, 521 kernel stacks, 400-401 overview, 398 Plug and Play, 563-569 randomizing, 369 user address spaces, 369 user stacks, 399 standby SuperFetch, 475 page lists, 430-435 startup (subsystems), 63-64 states pages (PFN), 425-428 processors, 274 threads, 223-228 storage (TLS), 18 strategies (I/O priorities), 547-548 strengthening CFG, 747-749 structures data structures. See data structures kernel process structure, 141 subsystems console host, 67 DLLs, 62-63 initializing, 146-147 Linux, 68-70 native images, 72

Ntdll.dll, 70-72 overview, 62-63 Pico providers, 68-70 startup, 63-64 subsystem DLLs, 48 viewing types, 62-63 Windows subsystem, 64-67 super privileges, 675-676 SuperFetch components, 473-474 fast user switching, 475 hibernation, 475 logging, 474-475 overview, 472-474 page priorities, 476-478 process reflection, 480-482 ReadyBoost, 479-480 ReadvDrive, 480 robust performance, 478-479 scenarios, 475-476 standby, 475 tracing, 474-475 support (Plug and Play), 560-561, 569-571 suppression (CFG), 741, 748 suspending threads, 264 swap files, 392-393 swapper (working sets), 421-422 switches/switching context switches/switching, 215, 255-256 Direct Switch, 255-256 directed context switch, 19 voluntary switching, 256-257 symbols kernel debugging, 38 viewing kernel type information, 41-42 symmetric multiprocessing, 51-53 synchronization heaps, 334-335 internal synchronization, 308 IRPs, 531-533 memory, 308 synchronous I/O, 511 Sysinternals, 44 system address space layouts (x86), 352-353 System and Compressed Memory process, 90 system calls (trustlets), 128 system capabilities (power manager), 597-599 System process, 90-91 system processes Idle process, 89-90 Memory Compression process, 91 overview, 88-89 Secure System process, 91 Service Control Manager, 96 service processes, 97-98 Session Manager process, 92-95 System and Compressed Memory process, 90 System process, 90-91 system thread, 90-91 Windows Initialization process, 95–96 Windows logon process, 98-99

system PTEs (page table entries) address spaces, 355-356 address translation, 375-376 creating shared PTEs, 462-464 defined, 372 invalid PTEs, 384-385 prototype PTEs, 385-386 system services (functions), 72 system thread, 90-91 system working sets, 422-423 systems PTEs (page table entries). See PTEs (page table entries) subsystems. See subsystems Sysinternals, 44 system address space layouts (x86), 352-353 System and Compressed Memory process, 90 system calls (trustlets), 128 system capabilities (power manager), 597-599 System process, 90-91 system processes. See system processes system services (functions), 72 system thread, 90-91 system working sets, 422-423 SystemParametersInfo function, 178 viewing (system service dispatcher), 70-71

#### Т

tables (PTEs, page table entries) address spaces, 355-356 address translation, 375-376 creating shared PTEs, 462-464 defined, 372 invalid PTEs, 384-385 prototype PTEs, 385-386 Task Manager, 9–11 TCB (thread control block) minimum TCB list, 117 overview, 196 TCSEC (Trusted Computer System Evaluation Criteria), 605-607 TEB (thread environment block) overview, 194, 198 viewing, 201-205 Terminal Services, 29-30 terminating I/O, 539 processes, 154-155 TerminateJobObject function, 179 threads, 260, 539 thread-agnostic I/O, 536-537 thread control block (TCB) minimum TCB list, 117 overview, 196 thread environment block (TEB) overview, 194, 198 viewing, 201-205 Thread Information Block (TIB), 201 thread local storage (TLS), 18 thread pools, 297-300

#### threads-user stacks

threads access tokens, 20, 677 cancelling I/O, 539 concurrency, 542 context, 18 context switching, 255-256 contexts, 18 cores, 52 creating, 193-194, 206-207, 399 data structures CSR THREAD, 195, 205-206 ETHREAD, 194-201 KTHREAD, 194-201 Direct Switch, 255-256 directed context switch, 19 dispatcher database, 228-230 fibers, 19 file mapping objects, 20 freezing, 264-266 group scheduling CPU rate limits, 292–295 DFSS, 289-292 dynamic processors, 295-296 overview, 287-289 idle threads, 260-263, 267 initial thread, 144, 145-146, 148 maximum number, 399 multiprocessor systems. See multiprocessor systems overview, 18-19 PCR, 260 priorities levels, 215-219 real-time, 218-219 viewing, 219-222 priority boosts applying, 249 Autoboost, 254 balance set manager, 247 CPU starvation, 246-248 deadline scheduling, 254 dispatch events, 239-240 executive resources, 242-243 foreground threads, 243-245 games, 251-254 GUI threads, 245-246 I/O, 241-242 locks, 241 MMCSS, 239, 251-254 multimedia, 251-254 overview, 238-239 priority inversion, 246 removing, 250 scheduling category, 251 unwait boosts, 240-241 quantums. See quantums (threads) ready, 230-231 saturation values. 216 scheduling context switches, 215 dispatchers, 215 exiting, 260 heterogenous, 286-287 preemption, 257-258

quantums, 258-260 terminating, 260 voluntary switching, 256-257 scheduling overview, 214-215 selecting, 266-267, 283-284 states, 223-228 suspending, 264 system thread, 90-91 TCB (thread control block). See TCB (thread control block) TEB (thread environment block). See TEB (thread environment block) terminating, 539 thread-agnostic I/O, 536-537 thread pools, 297-300 TIB (Thread Information Block), 201 TLS (thread local storage), 18 UMS threads, 19-20 VADs (virtual address descriptors), 20 viewing kernel-mode debugger, 210–212 overview, 207-209 protected processes, 212-213 ready, 230-231 TEB. 201-205 user-mode debugger, 209-210 worker factories, 297-300 throughput (I/O priorities), 549-551 TIB (Thread Information Block), 201 TLB (translation look-aside buffer), 377–378 TLS (thread local storage), 18 tokens access tokens, 677 AppContainters, 690-692 BNO isolation, 708 SIDs, 632-640 stored handles, 706-708 tools Debugging Tools for Windows (kernel debugging), 38-42 Windows, viewing internals, 35-36 tracing process startup, 149-154 SuperFetch, 474–475 tracking pools (Device Driver), 556-557 translating addresses ARM virtual address translation, 381–382 overview, 371 page tables, 375-376 PTEs, 375-376 TLB, 377-378 viewing, 378-380 write bits. 376-377 x64 virtual address translation, 380–381 x86 virtual address translation, 371-375 translation look-aside buffer (TLB), 377-378 trees (Plug and Play), 561–563 troubleshooting pools, 329-330 trust SIDs. 657-658 Trusted Computer System Evaluation Criteria (TCSEC), 605-607 trustlets attributes, 125 built-in, 125

identifying, 129 identities, 125–126 overview, 61, 123–124 policies, 124–125 services, 127–128 system calls, 128 types device drivers, 492–496 heaps, 334 kernels, 41–42 subsystems, 62–63

#### U

UAC (User Account Control) elevation Admin Approval Mode (AAM), 729 administrative rights, 729-732 auto-elevation, 732-733 consent, 729 over-the-shoulder (OTS), 729 overview, 729 settings, 733-734 overview, 722 virtualization files, 722-727 registry, 722-724, 727-728 UEFI (Credential Guard), 616 UIPI (User Interface Privilege Isolation), 660-661 UMDF (WDF), 578, 580-581, 587-590 UMS threads (user mode scheduling threads), 19 - 20Unicode, 33-35 Universal Windows Drivers, 85 unkillable processes, debugging, 539-541 unwait boosts, 240-241 updating Windows, 3 usage (pools), 327-329 User Account Control. See UAC user address spaces calculating load address, 368-369 EMET, 370 heap randomization, 369 image randomization, 367-369 IRPs, 528-531 kernel, 369 layouts, 365-367 overview, 365-367 security mitigations, 370 stack randomization, 369 viewing, 366-367 viewing randomization support, 370-371 User Interface Privilege Isolation (UIPI), 660-661 user mode architecture, 47-49 kernel mode comparison, 23-27, 46 user-mode debugging Debugging Tools for Windows, 39 viewing threads, 209-210 user mode scheduling threads (UMS threads), 19–20 user stacks, 399

#### users-viewing

licorc authentication, 713-718 Kerberos, 714-715 MSV1\_0, 713-714 viewing active logon sessions, 715-717 cancelling I/O, 537-538 fast user switching, 30, 475 multiple sessions, 29-30 SuperFetch, 475 UAC. See UAC user address spaces. See user address spaces using virtual service accounts, 647-650 UWP apps, 685-687 UWP processes, 687-692

### V

VADs (virtual address descriptors) overview, 20, 401 process VADs, 402-403 rotate VADs, 403 validating parameters (processes), 131-135 values (saturation values), 216 variable quantums, 235-236 VBS (virtualization-based security) architecture, 59-61 hypervisor, 28 versions (Windows) OneCore, 3-4 overview, 1-3 updating, 3 viewing access masks, 624 active logon sessions, 715-717 addresses randomization support, 370-371 translation, 378-380 usage, 361-363 user address spaces, 366-367, 370-371 VADs (virtual address descriptors), 402 - 403AppContainer atom table, 697-698 capabilities, 701-703 security attributes, 695-697 tokens, 690-692 brokers, 709 CFG, 742-744 CFG bitmaps, 746-747 control areas, 408-412 CPU. See CPU CSR\_PROCESS data structure, 112 CSR THREAD structure, 206 DEP. 321 device drivers, 85-88 device objects, 502-506 devnodes, 568-569 DFSS (dynamic fair share scheduling), 290-292 drivers, 496-498 catalog files, 574

device drivers, 85-88 dispatch routines, 517-518 INF files, 573 KMDF drivers, 580-581 objects, 504-506 power mappings, 596 UMDF drivers, 580-581 dumping. See dumping enabling privileges, 673-675 EPROCESS data structure, 107–108 ETHREAD structure, 196-201 files catalog files, 574 file objects, 508-509 INF files, 573 memory-mapped files, 316-317 page files, 390-392, 397-398 prefetch file reads and writes, 415-416 swap files, 393 virtual page files, 393 virtualization, 726-727 free page lists, 429-430 functions, exported, 34-35 global audit policy, 682 HAL image dependencies, 80-82 heaps, 338-341 image loader, 156-157 DLL load search order, 163-164 loaded modules database, 166-167 integrity levels, 628-631 I/O fast I/O, 512-513 IRPs. 518-519, 521-524 priority boosting/bumping, 551 priority throughput, 549-551 IRPs, 518-519, 521-524 jobs, 180–183 kernel kernel-mode debugger, 210-212 KPRCB (kernel processor control block), 77-78 KPCR (kernel processor control region), 77-78 stacks, 400-401 type information, 41-42 KTHREAD structure, 196-201 look-aside lists, 331-332 memory, 305-308 combining, 465-467 compression, 455-456 memory-mapped files, 316-317 partitions, 458 modified page lists, 430-435 notification events, 424-425 NUMA processors, 270-271 object access auditing, 679-681 pages files, 390-392, 397-398 free page lists, 429-430 modified page lists, 430-435 pageheap, 344-346 PFN (Page Frame Number), 427-428, 443

priorities, 437 PTEs (page table entries), 355-356 standby page lists, 430-435 virtual page files, 393 zero page lists, 429-430 PEB (Process Environmental Block), 110-111 PFN (Page Frame Number), 427-428, 443 pools. See pools power availability requests, 603 driver power mappings, 596 states, 592-593 system capabilities, 597-599 prefetch file reads and writes, 415-416 priority boosts bumping (I/O), 551 CPU starvation, 247-248 foreground threads, 243-245 GUI threads, 245-246 MMCSS (Multimedia Class Scheduler Service), 252-253 processes affinity, 275-276 data structures, 109 PEB (Process Environmental Block), 110-111 Process Explorer, 14-18, 118-119 process tree, 12-14 protected processes, 118-119, 212-213 service processes, 97–98 Task Manager, 9-11 UWP processes, 689-690 PTEs (page table entries), 355-356 section objects, 406-407 security AppContainer, 695-697 descriptors, 654-656 registry keys, 610 SIDs (security identifiers), 626-627 trust SIDs. 658 services, 97 MMCSS (Multimedia Class Scheduler Service), 252-253 service processes, 97-98 system service dispatcher, 70-71 sessions, 353-355, 715-717 SMT processors, 268-269 SRPs (software restriction policies), 764 stacks, 400-401, 521 standby page lists, 430-435 swap files, 393 systems power capabilities, 597-599 subsystems, 62-63 system service dispatcher, 70-71 threads clock cycles per quantum, 233-234 clock interval, 232 foreground threads, 243-245 freezing, 265-266 GUI threads, 245-246 idle threads, 260-262 kernel-mode debugger, 210-212 KTHREAD structure, 196-201

#### 783

#### From the Library of Octavian Mustafa

#### viewing-zero page lists

viewing, threads (continued) overview, 207-209 pools, 299-300 priorities, 219-222 protected processes, 118-119, 212-213 ready, 230-231 states, 224-228 user-mode debugger, 209-210 tokens, 635-640 AppContainers, 690-692 filtered admin tokens, 645-646 token stored handles, 706-708 virtual page files, 393 Windows enabled features. 56-57 tools, 35-36 working sets, 418-421 zero page lists, 429-430 virtual address descriptors (VADs). See VADs (virtual address descriptors) virtual address spaces. See address spaces virtual memory, 21-23 virtual page files, 393 Virtual Secure Mode. See VBS virtual service accounts, 646-650 Virtual Trust Levels (VTLs), 59-61 virtualization security authentication policies, 616-617 Device Guard, 617-619 files, 722-727 Kerberos armoring, 616-617 NTOWF/TGT key, 613-614 overview, 611-613, 722 passwords, 613 registry, 722-724, 727-728 secure communication, 614-615 UEFI, 616 VBS (virtualization-based security). See VBS (virtualization-based security) virtualization-based security (VBS): See VBS (virtualization-based security) voluntary switching, 256-257 VSM. See VBS VTLs (Virtual Trust Levels), 59-61

#### W

W32PROCESS data structure, 105, 113 WBF (Windows Biometric Framework), 719-721 WDF (Windows Driver Foundation) KMDF, 578-587 overview, 84, 578-579 UMDF, 578, 580-581, 587-590 WDK (Windows Driver Kit), 43-44 WDM (Windows Driver Model), 83-84, 493-494 windows, opening command prompts, 13 Windows client memory limits, 447-449 design goals, 45-46 editions comparison, 54-56 viewing enabled features, 56-57 operating system model, 46-47 portability, 50-51 SDK (software development kit), 43 versions OneCore, 3-4 overview, 1-3 updating, 3 viewing internals, 35-36 W32PROCESS data structure, 105, 113 WBF (Windows Biometric Framework), 719-721 WDF (Windows Driver Foundation). See WDF Windows Driver Foundation) WDK (Windows Driver Kit), 43-44 WDM (Windows Driver Model), 83-84, 493-494 Windows API. See APIs Windows Hello, 721 Windows Initialization process, 95-96 Windows logon process, 98-99 Windows Runtime, 5-6 Windows subsystem, 64-67 Winlogon initialization, 711-712 winver command, 3 WSRM (Windows System Resource Manager ), 222–223

Windows Biometric Framework (WBF), 719-721 Windows Driver Foundation (WDF) KMDF, 578-587 overview, 84, 578-579 UMDF, 578, 580-581, 587-590 Windows Driver Kit (WDK), 43-44 Windows Driver Model (WDM), 83-84, 493-494 Windows Hello, 721 Windows Initialization process, 95-96 Windows logon process, 98-99 Windows Runtime, 5-6 Windows System Resource Manager (WSRM), 222-223 Winlogon initialization, 711-712 worker factories, 297-300 working sets balance set manager, 421-422 demand paging, 413 managing, 417-421 memory, 412 notification events, 423-425 overview, 413 placement policies, 416-417 prefetcher, 413–416 ReadyBoot, 413-416 swapper, 421-422 system working sets, 422-423 viewing, 418-421 write bits, 376-377 WSRM (Windows System Resource Manager), 222-223

## X–Z

x64 systems, 50 x64 virtual address limitations, 359 x64 virtual address translation, 380–381 x86 address space layouts, 349–352 x86 session space, 353–355 x86 system address space layouts, 352–353 x86 virtual address translation, 371–375 zero page lists, 429–430